

---

# The Python/C API

*Δημοσίευση 3.11.14*

**Guido van Rossum and the Python development team**

Οκτωβρίου 15, 2025

Python Software Foundation  
Email: [docs@python.org](mailto:docs@python.org)



<b>1</b>	<b>Introduction</b>	<b>3</b>
1.1	Coding standards	3
1.2	Include Files	3
1.3	Useful macros	4
1.4	Objects, Types and Reference Counts	7
1.4.1	Reference Counts	7
1.4.2	Types	10
1.5	Exceptions	10
1.6	Embedding Python	12
1.7	Debugging Builds	13
<b>2</b>	<b>C API Stability</b>	<b>15</b>
2.1	Stable Application Binary Interface	15
2.1.1	Limited C API	15
2.1.2	Stable ABI	16
2.1.3	Limited API Scope and Performance	16
2.1.4	Limited API Caveats	16
2.2	Platform Considerations	17
2.3	Contents of Limited API	17
<b>3</b>	<b>The Very High Level Layer</b>	<b>41</b>
<b>4</b>	<b>Reference Counting</b>	<b>47</b>
<b>5</b>	<b>Exception Handling</b>	<b>49</b>
5.1	Printing and clearing	49
5.2	Raising exceptions	50
5.3	Issuing warnings	53
5.4	Querying the error indicator	53
5.5	Signal Handling	56
5.6	Exception Classes	57
5.7	Exception Objects	57
5.8	Unicode Exception Objects	58
5.9	Recursion Control	59
5.10	Standard Exceptions	59
5.11	Standard Warning Categories	61
<b>6</b>	<b>Utilities</b>	<b>63</b>
6.1	Operating System Utilities	63
6.2	System Functions	66
6.3	Process Control	68

6.4	Importing Modules . . . . .	68
6.5	Data marshalling support . . . . .	72
6.6	Parsing arguments and building values . . . . .	73
6.6.1	Parsing arguments . . . . .	73
6.6.2	Building values . . . . .	79
6.7	String conversion and formatting . . . . .	81
6.8	PyHash API . . . . .	83
6.9	Reflection . . . . .	83
6.10	Codec registry and support functions . . . . .	84
6.10.1	Codec lookup API . . . . .	84
6.10.2	Registry API for Unicode encoding error handlers . . . . .	85
<b>7</b>	<b>Abstract Objects Layer</b>	<b>87</b>
7.1	Object Protocol . . . . .	87
7.2	Call Protocol . . . . .	91
7.2.1	The <i>tp_call</i> Protocol . . . . .	92
7.2.2	The Vectorcall Protocol . . . . .	92
7.2.3	Object Calling API . . . . .	94
7.2.4	Call Support API . . . . .	96
7.3	Number Protocol . . . . .	96
7.4	Sequence Protocol . . . . .	99
7.5	Mapping Protocol . . . . .	101
7.6	Iterator Protocol . . . . .	102
7.7	Buffer Protocol . . . . .	103
7.7.1	Buffer structure . . . . .	104
7.7.2	Buffer request types . . . . .	106
7.7.3	Complex arrays . . . . .	108
7.7.4	Buffer-related functions . . . . .	109
7.8	Old Buffer Protocol . . . . .	110
<b>8</b>	<b>Concrete Objects Layer</b>	<b>111</b>
8.1	Fundamental Objects . . . . .	111
8.1.1	Type Objects . . . . .	111
8.1.2	The <code>None</code> Object . . . . .	115
8.2	Numeric Objects . . . . .	115
8.2.1	Integer Objects . . . . .	115
8.2.2	Boolean Objects . . . . .	118
8.2.3	Floating Point Objects . . . . .	119
8.2.4	Complex Number Objects . . . . .	121
8.3	Sequence Objects . . . . .	122
8.3.1	Bytes Objects . . . . .	122
8.3.2	Byte Array Objects . . . . .	124
8.3.3	Unicode Objects and Codecs . . . . .	125
8.3.4	Tuple Objects . . . . .	143
8.3.5	Struct Sequence Objects . . . . .	144
8.3.6	List Objects . . . . .	146
8.4	Container Objects . . . . .	147
8.4.1	Dictionary Objects . . . . .	147
8.4.2	Set Objects . . . . .	150
8.5	Function Objects . . . . .	152
8.5.1	Function Objects . . . . .	152
8.5.2	Instance Method Objects . . . . .	153
8.5.3	Method Objects . . . . .	153
8.5.4	Cell Objects . . . . .	154
8.5.5	Code Objects . . . . .	154
8.6	Other Objects . . . . .	156
8.6.1	File Objects . . . . .	156
8.6.2	Module Objects . . . . .	157

8.6.3	Iterator Objects . . . . .	164
8.6.4	Descriptor Objects . . . . .	165
8.6.5	Slice Objects . . . . .	165
8.6.6	MemoryView objects . . . . .	167
8.6.7	Weak Reference Objects . . . . .	168
8.6.8	Capsules . . . . .	169
8.6.9	Frame Objects . . . . .	170
8.6.10	Generator Objects . . . . .	172
8.6.11	Coroutine Objects . . . . .	172
8.6.12	Context Variables Objects . . . . .	172
8.6.13	DateTime Objects . . . . .	174
8.6.14	Objects for Type Hinting . . . . .	177
<b>9</b>	<b>Initialization, Finalization, and Threads</b>	<b>179</b>
9.1	Before Python Initialization . . . . .	179
9.2	Global configuration variables . . . . .	180
9.3	Initializing and finalizing the interpreter . . . . .	182
9.4	Process-wide parameters . . . . .	183
9.5	Thread State and the Global Interpreter Lock . . . . .	187
9.5.1	Releasing the GIL from extension code . . . . .	187
9.5.2	Non-Python created threads . . . . .	188
9.5.3	Cautions about fork() . . . . .	188
9.5.4	High-level API . . . . .	189
9.5.5	Low-level API . . . . .	191
9.6	Sub-interpreter support . . . . .	194
9.6.1	Bugs and caveats . . . . .	195
9.7	Asynchronous Notifications . . . . .	195
9.8	Profiling and Tracing . . . . .	196
9.9	Advanced Debugger Support . . . . .	197
9.10	Thread Local Storage Support . . . . .	198
9.10.1	Thread Specific Storage (TSS) API . . . . .	198
9.10.2	Thread Local Storage (TLS) API . . . . .	199
<b>10</b>	<b>Python Initialization Configuration</b>	<b>201</b>
10.1	Example . . . . .	201
10.2	PyWideStringList . . . . .	202
10.3	PyStatus . . . . .	203
10.4	PyPreConfig . . . . .	204
10.5	Preinitialize Python with PyPreConfig . . . . .	206
10.6	PyConfig . . . . .	207
10.7	Initialization with PyConfig . . . . .	217
10.8	Isolated Configuration . . . . .	218
10.9	Python Configuration . . . . .	219
10.10	Python Path Configuration . . . . .	219
10.11	Py_RunMain() . . . . .	220
10.12	Py_GetArgcArgv() . . . . .	220
10.13	Multi-Phase Initialization Private Provisional API . . . . .	221
<b>11</b>	<b>Memory Management</b>	<b>223</b>
11.1	Overview . . . . .	223
11.2	Allocator Domains . . . . .	224
11.3	Raw Memory Interface . . . . .	224
11.4	Memory Interface . . . . .	225
11.5	Object allocators . . . . .	226
11.6	Default Memory Allocators . . . . .	227
11.7	Customize Memory Allocators . . . . .	228
11.8	Debug hooks on the Python memory allocators . . . . .	229
11.9	The pymalloc allocator . . . . .	230
11.9.1	Customize pymalloc Arena Allocator . . . . .	231

11.10	tracemalloc C API . . . . .	231
11.11	Examples . . . . .	231
<b>12</b>	<b>Object Implementation Support</b>	<b>233</b>
12.1	Allocating Objects on the Heap . . . . .	233
12.2	Common Object Structures . . . . .	234
12.2.1	Base object types and macros . . . . .	234
12.2.2	Implementing functions and methods . . . . .	236
12.2.3	Accessing attributes of extension types . . . . .	239
12.3	Type Objects . . . . .	241
12.3.1	Quick Reference . . . . .	241
12.3.2	PyTypeObject Definition . . . . .	246
12.3.3	PyObject Slots . . . . .	247
12.3.4	PyVarObject Slots . . . . .	248
12.3.5	PyTypeObject Slots . . . . .	248
12.3.6	Static Types . . . . .	266
12.3.7	Heap Types . . . . .	266
12.4	Number Object Structures . . . . .	266
12.5	Mapping Object Structures . . . . .	268
12.6	Sequence Object Structures . . . . .	269
12.7	Buffer Object Structures . . . . .	270
12.8	Async Object Structures . . . . .	271
12.9	Slot Type typedefs . . . . .	271
12.10	Examples . . . . .	273
12.11	Supporting Cyclic Garbage Collection . . . . .	275
12.11.1	Controlling the Garbage Collector State . . . . .	277
<b>13</b>	<b>API and ABI Versioning</b>	<b>279</b>
<b>A'</b>	<b>Γλωσσάρι</b>	<b>281</b>
<b>B'</b>	<b>About these documents</b>	<b>299</b>
B'.1	Contributors to the Python Documentation . . . . .	299
<b>Γ'</b>	<b>Ιστορία και Άδεια</b>	<b>301</b>
Γ'.1	Η ιστορία του λογισμικού . . . . .	301
Γ'.2	Όροι και προϋποθέσεις για την πρόσβαση ή την χρήση της Python με άλλους τρόπους . . . . .	302
Γ'.2.1	PSF LICENSE AGREEMENT FOR PYTHON 3.11.14 . . . . .	302
Γ'.2.2	ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ BEOPEN.COM ΓΙΑ PYTHON 2.0 . . . . .	303
Γ'.2.3	ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ CNRI ΓΙΑ PYTHON 1.6.1 . . . . .	304
Γ'.2.4	ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ CWI ΓΙΑ PYTHON 0.9.0 ΕΩΣ 1.2 . . . . .	305
Γ'.2.5	ZERO-CLAUSE BSD LICENSE FOR CODE IN THE PYTHON 3.11.14 DOCUMENTATION . . . . .	305
Γ'.3	Άδειες και Ευχαριστίες για Ενσωματωμένο Λογισμικό . . . . .	306
Γ'.3.1	Mersenne Twister . . . . .	306
Γ'.3.2	Sockets . . . . .	307
Γ'.3.3	Ασύγχρονες socket υπηρεσίες . . . . .	307
Γ'.3.4	Διαχείριση Cookie . . . . .	308
Γ'.3.5	Ανίχνευση εκτέλεσης . . . . .	308
Γ'.3.6	Συναρτήσεις UUencode και UUdecode . . . . .	309
Γ'.3.7	Κλήσεις Απομακρυσμένης Διαδικασίας XML . . . . .	309
Γ'.3.8	test_epoll . . . . .	310
Γ'.3.9	Επιλογή kqueue . . . . .	310
Γ'.3.10	SipHash24 . . . . .	311
Γ'.3.11	strtod και dtoa . . . . .	311
Γ'.3.12	OpenSSL . . . . .	312
Γ'.3.13	expat . . . . .	315
Γ'.3.14	libffi . . . . .	315
Γ'.3.15	zlib . . . . .	316

Γ'.3.16	cfuhash . . . . .	316
Γ'.3.17	libmpdec . . . . .	317
Γ'.3.18	W3C C14N σουίτα δοκιμής . . . . .	317
Γ'.3.19	Audioop . . . . .	318
Γ'.3.20	asyncio . . . . .	318
<b>Δ' Copyright</b>		<b>321</b>
<b>Ευρετήριο</b>		<b>323</b>





This manual documents the API used by C and C++ programmers who want to write extension modules or embed Python. It is a companion to `extending-index`, which describes the general principles of extension writing but does not document the API functions in detail.



---

## Introduction

---

The Application Programmer's Interface to Python gives C and C++ programmers access to the Python interpreter at a variety of levels. The API is equally usable from C++, but for brevity it is generally referred to as the Python/C API. There are two fundamentally different reasons for using the Python/C API. The first reason is to write *extension modules* for specific purposes; these are C modules that extend the Python interpreter. This is probably the most common use. The second reason is to use Python as a component in a larger application; this technique is generally referred to as *embedding* Python in an application.

Writing an extension module is a relatively well-understood process, where a «cookbook» approach works well. There are several tools that automate the process to some extent. While people have embedded Python in other applications since its early existence, the process of embedding Python is less straightforward than writing an extension.

Many API functions are useful independent of whether you're embedding or extending Python; moreover, most applications that embed Python will need to provide a custom extension as well, so it's probably a good idea to become familiar with writing an extension before attempting to embed Python in a real application.

### 1.1 Coding standards

If you're writing C code for inclusion in CPython, you **must** follow the guidelines and standards defined in [PEP 7](#). These guidelines apply regardless of the version of Python you are contributing to. Following these conventions is not necessary for your own third party extension modules, unless you eventually expect to contribute them to Python.

### 1.2 Include Files

All function, type and macro definitions needed to use the Python/C API are included in your code by the following line:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

This implies inclusion of the following standard headers: `<stdio.h>`, `<string.h>`, `<errno.h>`, `<limits.h>`, `<assert.h>` and `<stdlib.h>` (if available).

---

**Σημείωση:** Since Python may define some pre-processor definitions which affect the standard headers on some systems, you *must* include `Python.h` before any standard headers are included.

---

It is recommended to always define `PY_SSIZE_T_CLEAN` before including `Python.h`. See [Parsing arguments and building values](#) for a description of this macro.

---

All user visible names defined by `Python.h` (except those defined by the included standard headers) have one of the prefixes `Py` or `_Py`. Names beginning with `_Py` are for internal use by the Python implementation and should not be used by extension writers. Structure member names do not have a reserved prefix.

---

**Σημείωση:** User code should never define names that begin with `Py` or `_Py`. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

---

The header files are typically installed with Python. On Unix, these are located in the directories `prefix/include/pythonversion/` and `exec_prefix/include/pythonversion/`, where `prefix` and `exec_prefix` are defined by the corresponding parameters to Python's **configure** script and `version` is `'%d.%d' % sys.version_info[:2]`. On Windows, the headers are installed in `prefix/include`, where `prefix` is the installation directory specified to the installer.

To include the headers, place both directories (if different) on your compiler's search path for includes. Do *not* place the parent directories on the search path and then use `#include <pythonX.Y/Python.h>`; this will break on multi-platform builds since the platform independent headers under `prefix` include the platform specific headers from `exec_prefix`.

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be `extern "C"`. As a result, there is no need to do anything special to use the API from C++.

## 1.3 Useful macros

Several useful macros are defined in the Python header files. Many are defined closer to where they are useful (e.g. `Py_RETURN_NONE`). Others of a more general utility are defined here. This is not necessarily a complete listing.

### **PyMODINIT\_FUNC**

Declare an extension module `PyInit_` initialization function. The function return type is `PyObject*`. The macro declares any special linkage declarations required by the platform, and for C++ declares the function as `extern "C"`.

The initialization function must be named `PyInit_`*name*, where *name* is the name of the module, and should be the only non-`static` item defined in the module file. Example:

```
static struct PyModuleDef spam_module = {
    PyModuleDef_HEAD_INIT,
    .m_name = "spam",
    ...
};

PyMODINIT_FUNC
PyInit_spam(void)
{
    return PyModule_Create(&spam_module);
}
```

### **Py\_ABS(x)**

Return the absolute value of `x`.

Νέο στην έκδοση 3.3.

### **Py\_ALWAYS\_INLINE**

Ask the compiler to always inline a static inline function. The compiler can ignore it and decides to not inline the function.

It can be used to inline performance critical static inline functions when building Python in debug mode with function inlining disabled. For example, MSC disables function inlining when building in debug mode.

Marking blindly a static inline function with `Py_ALWAYS_INLINE` can result in worse performances (due to increased code size for example). The compiler is usually smarter than the developer for the cost/benefit analysis.

If Python is built in debug mode (if the `Py_DEBUG` macro is defined), the `Py_ALWAYS_INLINE` macro does nothing.

It must be specified before the function return type. Usage:

```
static inline Py_ALWAYS_INLINE int random(void) { return 4; }
```

Νέο στην έκδοση 3.11.

#### **Py\_CHARMASK** (c)

Argument must be a character or an integer in the range [-128, 127] or [0, 255]. This macro returns c cast to an unsigned char.

#### **Py\_DEPRECATED** (version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

Example:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

Άλλαξε στην έκδοση 3.8: MSVC support was added.

#### **Py\_GETENV** (s)

Like `getenv(s)`, but returns NULL if `-E` was passed on the command line (i.e. if `Py_IgnoreEnvironmentFlag` is set).

#### **Py\_MAX** (x, y)

Return the maximum value between x and y.

Νέο στην έκδοση 3.3.

#### **Py\_MEMBER\_SIZE** (type, member)

Return the size of a structure (type) member in bytes.

Νέο στην έκδοση 3.6.

#### **Py\_MIN** (x, y)

Return the minimum value between x and y.

Νέο στην έκδοση 3.3.

#### **Py\_NO\_INLINE**

Disable inlining on a function. For example, it reduces the C stack consumption: useful on LTO+PGO builds which heavily inline code (see [bpo-33720](#)).

Usage:

```
Py_NO_INLINE static int random(void) { return 4; }
```

Νέο στην έκδοση 3.11.

#### **Py\_STRINGIFY** (x)

Convert x to a C string. E.g. `Py_STRINGIFY(123)` returns "123".

Νέο στην έκδοση 3.4.

**Py\_UNREACHABLE()**

Use this when you have a code path that cannot be reached by design. For example, in the `default:` clause in a `switch` statement for which all possible values are covered in `case` statements. Use this in places where you might be tempted to put an `assert(0)` or `abort()` call.

In release mode, the macro helps the compiler to optimize the code, and avoids a warning about unreachable code. For example, the macro is implemented with `__builtin_unreachable()` on GCC in release mode.

A use for `Py_UNREACHABLE()` is following a call a function that never returns but that is not declared `_Py_NO_RETURN`.

If a code path is very unlikely code but can be reached under exceptional case, this macro must not be used. For example, under low memory condition or if a system call returns a value out of the expected range. In this case, it's better to report the error to the caller. If the error cannot be reported to caller, `Py_FatalError()` can be used.

Νέο στην έκδοση 3.7.

**Py\_UNUSED(arg)**

Use this for unused arguments in a function definition to silence compiler warnings. Example: `int func(int a, int Py_UNUSED(b)) { return a; }.`

Νέο στην έκδοση 3.4.

**PyDoc\_STRVAR(name, str)**

Creates a variable with name `name` that can be used in docstrings. If Python is built without docstrings, the value will be empty.

Use `PyDoc_STRVAR` for docstrings to support building Python without docstrings, as specified in [PEP 7](#).

Example:

```
PyDoc_STRVAR(pop_doc, "Remove and return the rightmost element.");

static PyMethodDef deque_methods[] = {
    // ...
    {"pop", (PyCFunction)deque_pop, METH_NOARGS, pop_doc},
    // ...
}
```

**PyDoc\_STR(str)**

Creates a docstring for the given input string or an empty string if docstrings are disabled.

Use `PyDoc_STR` in specifying docstrings to support building Python without docstrings, as specified in [PEP 7](#).

Example:

```
static PyMethodDef sqlite_row_methods[] = {
    {"keys", (PyCFunction)sqlite_row_keys, METH_NOARGS,
     PyDoc_STR("Returns the keys of the row.")},
    {NULL, NULL}
};
```

## 1.4 Objects, Types and Reference Counts

Most Python/C API functions have one or more arguments as well as a return value of type `PyObject*`. This type is a pointer to an opaque data type representing an arbitrary Python object. Since all Python object types are treated the same way by the Python language in most situations (e.g., assignments, scope rules, and argument passing), it is only fitting that they should be represented by a single C type. Almost all Python objects live on the heap: you never declare an automatic or static variable of type `PyObject`, only pointer variables of type `PyObject*` can be declared. The sole exception are the type objects; since these must never be deallocated, they are typically static `PyTypeObject` objects.

All Python objects (even Python integers) have a *type* and a *reference count*. An object's type determines what kind of object it is (e.g., an integer, a list, or a user-defined function; there are many more as explained in types). For each of the well-known types there is a macro to check whether an object is of that type; for instance, `PyList_Check(a)` is true if (and only if) the object pointed to by *a* is a Python list.

### 1.4.1 Reference Counts

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a *strong reference* to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When the last *strong reference* to an object is released (i.e. its reference count becomes zero), the object is deallocated. If it contains references to other objects, those references are released. Those other objects may be deallocated in turn, if there are no more references to them, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is «don't do that.»)

Reference counts are always manipulated explicitly. The normal way is to use the macro `Py_INCREF()` to take a new reference to an object (i.e. increment its reference count by one), and `Py_DECREF()` to release that reference (i.e. decrement the reference count by one). The `Py_DECREF()` macro is considerably more complex than the `Py_INCREF()` one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of releasing references for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming `sizeof(Py_ssize_t) >= sizeof(void*)`). Thus, the reference count increment is a simple operation.

It is not necessary to hold a *strong reference* (i.e. increment the reference count) for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to take a new *strong reference* (i.e. increment the reference count) temporarily. An important situation where this arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without taking a new reference. Some other operation might conceivably remove the object from the list, releasing that reference, and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a code path which allows control to flow back to the user from a `Py_DECREF()`, so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with `PyObject_`, `PyNumber_`, `PySequence_` or `PyMapping_`). These operations always create a new *strong reference* (i.e. increment the reference count) of the object they return. This leaves the caller with the responsibility to call `Py_DECREF()` when they are done with the result; this soon becomes second nature.

## Reference Count Details

The reference count behavior of functions in the Python/C API is best explained in terms of *ownership of references*. Ownership pertains to references, never to objects (objects are not owned: they are always shared). «Owning a reference» means being responsible for calling `Py_DECREF()` on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually releasing it by calling `Py_DECREF()` or `Py_XDECREF()` when it's no longer needed—or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a *new* reference. When no ownership is transferred, the caller is said to *borrow* the reference. Nothing needs to be done for a *borrowed reference*.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are `PyList_SetItem()` and `PyTuple_SetItem()`, which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple `(1, 2, "three")` could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here, `PyLong_FromLong()` returns a new reference which is immediately stolen by `PyTuple_SetItem()`. When you want to keep using an object although the reference to it will be stolen, use `Py_INCREF()` to grab another reference before calling the reference-stealing function.

Incidentally, `PyTuple_SetItem()` is the *only* way to set tuple items; `PySequence_SetItem()` and `PyObject_SetItem()` refuse to do this since tuples are an immutable data type. You should only use `PyTuple_SetItem()` for tuples that you are creating yourself.

Equivalent code for populating a list can be written using `PyList_New()` and `PyList_SetItem()`.

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function, `Py_BuildValue()`, that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

It is much more common to use `PyObject_SetItem()` and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding references is much saner, since you don't have to take a new reference just so you can give that reference away («have it be stolen»). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;

    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
```

(συνέχεια στην επόμενη σελίδα)



(συνεχίζεται από την προηγούμενη σελίδα)

```

PyObject *index = PyLong_FromSsize_t(i);
if (!index)
    return -1;
if (PyObject_SetItem(target, index, item) < 0) {
    Py_DECREF(index);
    return -1;
}
Py_DECREF(index);
}
return 0;
}

```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the only reference to the object. Therefore, the generic functions that return object references, like `PyObject_GetItem()` and `PySequence_GetItem()`, always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only — *the plumage* (the type of the object passed as an argument to the function) *doesn't enter into it!* Thus, if you extract an item from a list using `PyList_GetItem()`, you don't own the reference — but if you obtain the same item from the same list using `PySequence_GetItem()` (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using `PyList_GetItem()`, and once using `PySequence_GetItem()`.

```

long
sum_list(PyObject *list)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;

    n = PyList_Size(list);
    if (n < 0)
        return -1; /* Not a list */
    for (i = 0; i < n; i++) {
        item = PyList_GetItem(list, i); /* Can't fail */
        if (!PyLong_Check(item)) continue; /* Skip non-integers */
        value = PyLong_AsLong(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
    return total;
}

```

```

long
sum_sequence(PyObject *sequence)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;
    n = PySequence_Length(sequence);
    if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {
        item = PySequence_GetItem(sequence, i);

```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

    if (item == NULL)
        return -1; /* Not a sequence, or other failure */
    if (PyLong_Check(item)) {
        value = PyLong_AsLong(item);
        Py_DECREF(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
    else {
        Py_DECREF(item); /* Discard reference ownership */
    }
}
return total;
}

```

## 1.4.2 Types

There are few other data types that play a significant role in the Python/C API; most are simple C types such as `int`, `long`, `double` and `char*`. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

type `Py_ssize_t`

*Μέρος του Σταθερό ABI.* A signed integral type such that `sizeof(Py_ssize_t) == sizeof(size_t)`. C99 doesn't define such a thing directly (`size_t` is an unsigned integral type). See [PEP 353](#) for details. `PY_SSIZE_T_MAX` is the largest positive value of type `Py_ssize_t`.

## 1.5 Exceptions

The Python programmer only needs to deal with exceptions if specific error handling is required; unhandled exceptions are automatically propagated to the caller, then to the caller's caller, and so on, until they reach the top-level interpreter, where they are reported to the user accompanied by a stack traceback.

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented otherwise, this indicator is either `NULL` or `-1`, depending on the function's return type. A few functions return a Boolean `true/false` result, with `false` indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with `PyErr_Occurred()`. These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function `PyErr_Occurred()` can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and `NULL` otherwise. There are a number of functions to set the exception state: `PyErr_SetString()` is the most common (though not the most general) function to set the exception state, and `PyErr_Clear()` clears the exception state.

The full exception state consists of three objects (all of which can be `NULL`): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of `sys.exc_info()`; however, they are not the same: the Python objects represent the last exception being handled by a Python `try ... except` statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to `sys.exc_info()` and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function `sys.exc_info()`, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns, and return an error indicator, but it should *not* set another exception — that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the `sum_sequence()` example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
int
incr_item(PyObject *dict, PyObject *key)
{
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
    int rv = -1; /* Return value initialized to -1 (failure) */

    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;

        /* Clear the error and use zero: */
        PyErr_Clear();
        item = PyLong_FromLong(0L);
        if (item == NULL)
            goto error;
    }
    const_one = PyLong_FromLong(1L);
    if (const_one == NULL)
        goto error;

    incremented_item = PyNumber_Add(item, const_one);
    if (incremented_item == NULL)
        goto error;

    if (PyObject_SetItem(dict, key, incremented_item) < 0)
        goto error;
    rv = 0; /* Success */
    /* Continue with cleanup code */

error:
    /* Cleanup code, shared by success and failure path */

    /* Use Py_XDECREF() to ignore NULL references */
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

Py_XDECREF(item);
Py_XDECREF(const_one);
Py_XDECREF(incremented_item);

return rv; /* -1 for error, 0 for success */
}

```

This example represents an endorsed use of the `goto` statement in C! It illustrates the use of `PyErr_ExceptionMatches()` and `PyErr_Clear()` to handle specific exceptions, and the use of `Py_XDECREF()` to dispose of owned references that may be NULL (note the 'X' in the name; `Py_DECREF()` would crash when confronted with a NULL reference). It is important that the variables used to hold owned references are initialized to NULL for this to work; likewise, the proposed return value is initialized to `-1` (failure) and only set to success after the final call made is successful.

## 1.6 Embedding Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is `Py_Initialize()`. This initializes the table of loaded modules, and creates the fundamental modules `builtins`, `__main__`, and `sys`. It also initializes the module search path (`sys.path`).

`Py_Initialize()` does not set the «script argument list» (`sys.argv`). If this variable is needed by Python code that will be executed later, setting `PyConfig.argv` and `PyConfig.parse_argv` must be set: see [Python Initialization Configuration](#).

On most systems (in particular, on Unix and Windows, although the details are slightly different), `Py_Initialize()` calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named `lib/pythonX.Y` relative to the parent directory where the executable named `python` is found on the shell command search path (the environment variable `PATH`).

For instance, if the Python executable is found in `/usr/local/bin/python`, it will assume that the libraries are in `/usr/local/lib/pythonX.Y`. (In fact, this particular path is also the «fallback» location, used when no executable file named `python` is found along `PATH`.) The user can override this behavior by setting the environment variable `PYTHONHOME`, or insert additional directories in front of the standard path by setting `PYTHONPATH`.

The embedding application can steer the search by calling `Py_SetProgramName(file)` *before* calling `Py_Initialize()`. Note that `PYTHONHOME` still overrides this and `PYTHONPATH` is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of `Py_GetPath()`, `Py_GetPrefix()`, `Py_GetExecPrefix()`, and `Py_GetProgramFullPath()` (all defined in `Modules/getpath.c`).

Sometimes, it is desirable to «uninitialize» Python. For instance, the application may want to start over (make another call to `Py_Initialize()`) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling `Py_FinalizeEx()`. The function `Py_IsInitialized()` returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that `Py_FinalizeEx()` does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

## 1.7 Debugging Builds

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file `Misc/SpecialBuilds.txt` in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently used builds will be described in the remainder of this section.

### **Py\_DEBUG**

Compiling the interpreter with the `Py_DEBUG` macro defined produces what is generally meant by a debug build of Python. `Py_DEBUG` is enabled in the Unix build by adding `--with-pydebug` to the `./configure` command. It is also implied by the presence of the not-Python-specific `_DEBUG` macro. When `Py_DEBUG` is enabled in the Unix build, compiler optimization is disabled.

In addition to the reference count debugging described below, extra checks are performed, see [Python Debug Build](#).

Defining `Py_TRACE_REFS` enables reference tracing (see the `configure --with-trace-refs` option). When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every *PyObject*. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.)

Please refer to `Misc/SpecialBuilds.txt` in the Python source distribution for more detailed information.



Python's C API is covered by the Backwards Compatibility Policy, [PEP 387](#). While the C API will change with every minor release (e.g. from 3.9 to 3.10), most changes will be source-compatible, typically by only adding new API. Changing existing API or removing API is only done after a deprecation period or to fix serious issues.

CPython's Application Binary Interface (ABI) is forward- and backwards-compatible across a minor release (if these are compiled the same way; see [Platform Considerations](#) below). So, code compiled for Python 3.10.0 will work on 3.10.8 and vice versa, but will need to be compiled separately for 3.9.x and 3.11.x.

Names prefixed by an underscore, such as `_Py_InternalState`, are private API that can change without notice even in patch releases.

## 2.1 Stable Application Binary Interface

For simplicity, this document talks about *extensions*, but the Limited API and Stable ABI work the same way for all uses of the API – for example, embedding Python.

### 2.1.1 Limited C API

Python 3.2 introduced the *Limited API*, a subset of Python's C API. Extensions that only use the Limited API can be compiled once and work with multiple versions of Python. Contents of the Limited API are [listed below](#).

#### **Py\_LIMITED\_API**

Define this macro before including `Python.h` to opt in to only use the Limited API, and to select the Limited API version.

Define `Py_LIMITED_API` to the value of `PY_VERSION_HEX` corresponding to the lowest Python version your extension supports. The extension will work without recompilation with all Python 3 releases from the specified one onward, and can use Limited API introduced up to that version.

Rather than using the `PY_VERSION_HEX` macro directly, hardcode a minimum minor version (e.g. `0x030A0000` for Python 3.10) for stability when compiling with future Python versions.

You can also define `Py_LIMITED_API` to 3. This works the same as `0x03020000` (Python 3.2, the version that introduced Limited API).

## 2.1.2 Stable ABI

To enable this, Python provides a *Stable ABI*: a set of symbols that will remain compatible across Python 3.x versions.

The Stable ABI contains symbols exposed in the *Limited API*, but also other ones – for example, functions necessary to support older versions of the Limited API.

On Windows, extensions that use the Stable ABI should be linked against `python3.dll` rather than a version-specific library such as `python39.dll`.

On some platforms, Python will look for and load shared library files named with the `abi3` tag (e.g. `mymodule.abi3.so`). It does not check if such extensions conform to a Stable ABI. The user (or their packaging tools) need to ensure that, for example, extensions built with the 3.10+ Limited API are not installed for lower versions of Python.

All functions in the Stable ABI are present as functions in Python’s shared library, not solely as macros. This makes them usable from languages that don’t use the C preprocessor.

## 2.1.3 Limited API Scope and Performance

The goal for the Limited API is to allow everything that is possible with the full C API, but possibly with a performance penalty.

For example, while `PyList_GetItem()` is available, its “unsafe” macro variant `PyList_GET_ITEM()` is not. The macro can be faster because it can rely on version-specific implementation details of the list object.

Without `Py_LIMITED_API` defined, some C API functions are inlined or replaced by macros. Defining `Py_LIMITED_API` disables this inlining, allowing stability as Python’s data structures are improved, but possibly reducing performance.

By leaving out the `Py_LIMITED_API` definition, it is possible to compile a Limited API extension with a version-specific ABI. This can improve performance for that Python version, but will limit compatibility. Compiling with `Py_LIMITED_API` will then yield an extension that can be distributed where a version-specific one is not available – for example, for prereleases of an upcoming Python version.

## 2.1.4 Limited API Caveats

Note that compiling with `Py_LIMITED_API` is *not* a complete guarantee that code conforms to the *Limited API* or the *Stable ABI*. `Py_LIMITED_API` only covers definitions, but an API also includes other issues, such as expected semantics.

One issue that `Py_LIMITED_API` does not guard against is calling a function with arguments that are invalid in a lower Python version. For example, consider a function that starts accepting `NULL` for an argument. In Python 3.9, `NULL` now selects a default behavior, but in Python 3.8, the argument will be used directly, causing a `NULL` dereference and crash. A similar argument works for fields of structs.

Another issue is that some struct fields are currently not hidden when `Py_LIMITED_API` is defined, even though they’re part of the Limited API.

For these reasons, we recommend testing an extension with *all* minor Python versions it supports, and preferably to build with the *lowest* such version.

We also recommend reviewing documentation of all used API to check if it is explicitly part of the Limited API. Even with `Py_LIMITED_API` defined, a few private declarations are exposed for technical reasons (or even unintentionally, as bugs).

Also note that the Limited API is not necessarily stable: compiling with `Py_LIMITED_API` with Python 3.8 means that the extension will run with Python 3.12, but it will not necessarily *compile* with Python 3.12. In particular, parts of the Limited API may be deprecated and removed, provided that the Stable ABI stays stable.



## 2.2 Platform Considerations

ABI stability depends not only on Python, but also on the compiler used, lower-level libraries and compiler options. For the purposes of the *Stable ABI*, these details define a “platform”. They usually depend on the OS type and processor architecture

It is the responsibility of each particular distributor of Python to ensure that all Python versions on a particular platform are built in a way that does not break the Stable ABI. This is the case with Windows and macOS releases from `python.org` and many third-party distributors.

## 2.3 Contents of Limited API

Currently, the *Limited API* includes the following items:

- `PyAIter_Check()`
- `PyArg_Parse()`
- `PyArg_ParseTuple()`
- `PyArg_ParseTupleAndKeywords()`
- `PyArg_UnpackTuple()`
- `PyArg_VaParse()`
- `PyArg_VaParseTupleAndKeywords()`
- `PyArg_ValidateKeywordArguments()`
- `PyBaseObject_Type`
- `PyBool_FromLong()`
- `PyBool_Type`
- `PyBuffer_FillContiguousStrides()`
- `PyBuffer_FillInfo()`
- `PyBuffer_FromContiguous()`
- `PyBuffer_GetPointer()`
- `PyBuffer_IsContiguous()`
- `PyBuffer_Release()`
- `PyBuffer_SizeFromFormat()`
- `PyBuffer_ToContiguous()`
- `PyByteArrayIter_Type`
- `PyByteArray_AsString()`
- `PyByteArray_Concat()`
- `PyByteArray_FromObject()`
- `PyByteArray_FromStringAndSize()`
- `PyByteArray_Resize()`
- `PyByteArray_Size()`
- `PyByteArray_Type`
- `PyBytesIter_Type`

- *PyBytes\_AsString()*
- *PyBytes\_AsStringAndSize()*
- *PyBytes\_Concat()*
- *PyBytes\_ConcatAndDel()*
- *PyBytes\_DecodeEscape()*
- *PyBytes\_FromFormat()*
- *PyBytes\_FromFormatV()*
- *PyBytes\_FromObject()*
- *PyBytes\_FromString()*
- *PyBytes\_FromStringAndSize()*
- *PyBytes\_Repr()*
- *PyBytes\_Size()*
- *PyBytes\_Type*
- *PyCFunction*
- *PyCFunctionWithKeywords*
- *PyCFunction\_Call()*
- *PyCFunction\_GetFlags()*
- *PyCFunction\_GetFunction()*
- *PyCFunction\_GetSelf()*
- *PyCFunction\_New()*
- *PyCFunction\_NewEx()*
- *PyCFunction\_Type*
- *PyCMethod\_New()*
- *PyCallIter\_New()*
- *PyCallIter\_Type*
- *PyCallable\_Check()*
- *PyCapsule\_Destructor*
- *PyCapsule\_GetContext()*
- *PyCapsule\_GetDestructor()*
- *PyCapsule\_GetName()*
- *PyCapsule\_GetPointer()*
- *PyCapsule\_Import()*
- *PyCapsule\_IsValid()*
- *PyCapsule\_New()*
- *PyCapsule\_SetContext()*
- *PyCapsule\_SetDestructor()*
- *PyCapsule\_SetName()*
- *PyCapsule\_SetPointer()*
- *PyCapsule\_Type*

- `PyClassMethodDescr_Type`
- `PyCodec_BackslashReplaceErrors()`
- `PyCodec_Decode()`
- `PyCodec_Decoder()`
- `PyCodec_Encode()`
- `PyCodec_Encoder()`
- `PyCodec_IgnoreErrors()`
- `PyCodec_IncrementalDecoder()`
- `PyCodec_IncrementalEncoder()`
- `PyCodec_KnownEncoding()`
- `PyCodec_LookupError()`
- `PyCodec_NameReplaceErrors()`
- `PyCodec_Register()`
- `PyCodec_RegisterError()`
- `PyCodec_ReplaceErrors()`
- `PyCodec_StreamReader()`
- `PyCodec_StreamWriter()`
- `PyCodec_StrictErrors()`
- `PyCodec_Unregister()`
- `PyCodec_XMLCharRefReplaceErrors()`
- `PyComplex_FromDoubles()`
- `PyComplex_ImagAsDouble()`
- `PyComplex_RealAsDouble()`
- `PyComplex_Type`
- `PyDescr_NewClassMethod()`
- `PyDescr_NewGetSet()`
- `PyDescr_NewMember()`
- `PyDescr_NewMethod()`
- `PyDictItems_Type`
- `PyDictIterItem_Type`
- `PyDictIterKey_Type`
- `PyDictIterValue_Type`
- `PyDictKeys_Type`
- `PyDictProxy_New()`
- `PyDictProxy_Type`
- `PyDictRevIterItem_Type`
- `PyDictRevIterKey_Type`
- `PyDictRevIterValue_Type`
- `PyDictValues_Type`

- `PyDict_Clear()`
- `PyDict_Contains()`
- `PyDict_Copy()`
- `PyDict_DelItem()`
- `PyDict_DelItemString()`
- `PyDict_GetItem()`
- `PyDict_GetItemString()`
- `PyDict_GetItemWithError()`
- `PyDict_Items()`
- `PyDict_Keys()`
- `PyDict_Merge()`
- `PyDict_MergeFromSeq2()`
- `PyDict_New()`
- `PyDict_Next()`
- `PyDict_SetItem()`
- `PyDict_SetItemString()`
- `PyDict_Size()`
- `PyDict_Type`
- `PyDict_Update()`
- `PyDict_Values()`
- `PyEllipsis_Type`
- `PyEnum_Type`
- `PyErr_BadArgument()`
- `PyErr_BadInternalCall()`
- `PyErr_CheckSignals()`
- `PyErr_Clear()`
- `PyErr_Display()`
- `PyErr_ExceptionMatches()`
- `PyErr_Fetch()`
- `PyErr_Format()`
- `PyErr_FormatV()`
- `PyErr_GetExcInfo()`
- `PyErr_GetHandledException()`
- `PyErr_GivenExceptionMatches()`
- `PyErr_NewException()`
- `PyErr_NewExceptionWithDoc()`
- `PyErr_NoMemory()`
- `PyErr_NormalizeException()`
- `PyErr_Occurred()`

- `PyErr_Print()`
- `PyErr_PrintEx()`
- `PyErr_ProgramText()`
- `PyErr_ResourceWarning()`
- `PyErr_Restore()`
- `PyErr_SetExcFromWindowsErr()`
- `PyErr_SetExcFromWindowsErrWithFilename()`
- `PyErr_SetExcFromWindowsErrWithFilenameObject()`
- `PyErr_SetExcFromWindowsErrWithFilenameObjects()`
- `PyErr_SetExcInfo()`
- `PyErr_SetFromErrno()`
- `PyErr_SetFromErrnoWithFilename()`
- `PyErr_SetFromErrnoWithFilenameObject()`
- `PyErr_SetFromErrnoWithFilenameObjects()`
- `PyErr_SetFromWindowsErr()`
- `PyErr_SetFromWindowsErrWithFilename()`
- `PyErr_SetHandledException()`
- `PyErr_SetImportError()`
- `PyErr_SetImportErrorSubclass()`
- `PyErr_SetInterrupt()`
- `PyErr_SetInterruptEx()`
- `PyErr_SetNone()`
- `PyErr_SetObject()`
- `PyErr_SetString()`
- `PyErr_SyntaxLocation()`
- `PyErr_SyntaxLocationEx()`
- `PyErr_WarnEx()`
- `PyErr_WarnExplicit()`
- `PyErr_WarnFormat()`
- `PyErr_WriteUnraisable()`
- `PyEval_AcquireLock()`
- `PyEval_AcquireThread()`
- `PyEval_CallFunction()`
- `PyEval_CallMethod()`
- `PyEval_CallObjectWithKeywords()`
- `PyEval_EvalCode()`
- `PyEval_EvalCodeEx()`
- `PyEval_EvalFrame()`
- `PyEval_EvalFrameEx()`

- `PyEval_GetBuiltins()`
- `PyEval_GetFrame()`
- `PyEval_GetFuncDesc()`
- `PyEval_GetFuncName()`
- `PyEval_GetGlobals()`
- `PyEval_GetLocals()`
- `PyEval_InitThreads()`
- `PyEval_ReleaseLock()`
- `PyEval_ReleaseThread()`
- `PyEval_RestoreThread()`
- `PyEval_SaveThread()`
- `PyEval_ThreadsInitialized()`
- `PyExc_ArithmeticError`
- `PyExc_AssertionError`
- `PyExc_AttributeError`
- `PyExc_BaseException`
- `PyExc_BaseExceptionGroup`
- `PyExc_BlockingIOError`
- `PyExc_BrokenPipeError`
- `PyExc_BufferError`
- `PyExc_BytesWarning`
- `PyExc_ChildProcessError`
- `PyExc_ConnectionAbortedError`
- `PyExc_ConnectionError`
- `PyExc_ConnectionRefusedError`
- `PyExc_ConnectionResetError`
- `PyExc_DeprecationWarning`
- `PyExc_EOFError`
- `PyExc_EncodingWarning`
- `PyExc_EnvironmentError`
- `PyExc_Exception`
- `PyExc_FileExistsError`
- `PyExc_FileNotFoundError`
- `PyExc_FloatingPointError`
- `PyExc_FutureWarning`
- `PyExc_GeneratorExit`
- `PyExc_IOError`
- `PyExc_ImportError`
- `PyExc_ImportWarning`

- PyExc\_IndentationError
- PyExc\_IndexError
- PyExc\_InterruptedError
- PyExc\_IsADirectoryError
- PyExc\_KeyError
- PyExc\_KeyboardInterrupt
- PyExc\_LookupError
- PyExc\_MemoryError
- PyExc\_ModuleNotFoundError
- PyExc\_NameError
- PyExc\_NotADirectoryError
- PyExc\_NotImplementedError
- PyExc\_OSError
- PyExc\_OverflowError
- PyExc\_PendingDeprecationWarning
- PyExc\_PermissionError
- PyExc\_ProcessLookupError
- PyExc\_RecursionError
- PyExc\_ReferenceError
- PyExc\_ResourceWarning
- PyExc\_RuntimeError
- PyExc\_RuntimeWarning
- PyExc\_StopAsyncIteration
- PyExc\_StopIteration
- PyExc\_SyntaxError
- PyExc\_SyntaxWarning
- PyExc\_SystemError
- PyExc\_SystemExit
- PyExc\_TabError
- PyExc\_TimeoutError
- PyExc\_TypeError
- PyExc\_UnboundLocalError
- PyExc\_UnicodeDecodeError
- PyExc\_UnicodeEncodeError
- PyExc\_UnicodeError
- PyExc\_UnicodeTranslateError
- PyExc\_UnicodeWarning
- PyExc\_UserWarning
- PyExc\_ValueError

- `PyExc_Warning`
- `PyExc_WindowsError`
- `PyExc_ZeroDivisionError`
- `PyExceptionClass_Name()`
- `PyException_GetCause()`
- `PyException_GetContext()`
- `PyException_GetTraceback()`
- `PyException_SetCause()`
- `PyException_SetContext()`
- `PyException_SetTraceback()`
- `PyFile_FromFd()`
- `PyFile_GetLine()`
- `PyFile_WriteObject()`
- `PyFile_WriteString()`
- `PyFilter_Type`
- `PyFloat_AsDouble()`
- `PyFloat_FromDouble()`
- `PyFloat_FromString()`
- `PyFloat_GetInfo()`
- `PyFloat_GetMax()`
- `PyFloat_GetMin()`
- `PyFloat_Type`
- `PyFrameObject`
- `PyFrame_GetCode()`
- `PyFrame_GetLineNumber()`
- `PyFrozenSet_New()`
- `PyFrozenSet_Type`
- `PyGC_Collect()`
- `PyGC_Disable()`
- `PyGC_Enable()`
- `PyGC_IsEnabled()`
- `PyGILState_Ensure()`
- `PyGILState_GetThisThreadState()`
- `PyGILState_Release()`
- `PyGILState_STATE`
- `PyGetSetDef`
- `PyGetSetDescr_Type`
- `PyImport_AddModule()`
- `PyImport_AddModuleObject()`



- `PyImport_AppendInittab()`
- `PyImport_ExecCodeModule()`
- `PyImport_ExecCodeModuleEx()`
- `PyImport_ExecCodeModuleObject()`
- `PyImport_ExecCodeModuleWithPathnames()`
- `PyImport_GetImporter()`
- `PyImport_GetMagicNumber()`
- `PyImport_GetMagicTag()`
- `PyImport_GetModule()`
- `PyImport_GetModuleDict()`
- `PyImport_Import()`
- `PyImport_ImportFrozenModule()`
- `PyImport_ImportFrozenModuleObject()`
- `PyImport_ImportModule()`
- `PyImport_ImportModuleLevel()`
- `PyImport_ImportModuleLevelObject()`
- `PyImport_ImportModuleNoBlock()`
- `PyImport_ReloadModule()`
- `PyIndex_Check()`
- `PyInterpreterState`
- `PyInterpreterState_Clear()`
- `PyInterpreterState_Delete()`
- `PyInterpreterState_Get()`
- `PyInterpreterState_GetDict()`
- `PyInterpreterState_GetID()`
- `PyInterpreterState_New()`
- `PyIter_Check()`
- `PyIter_Next()`
- `PyIter_Send()`
- `PyListIter_Type`
- `PyListRevIter_Type`
- `PyList_Append()`
- `PyList_AsTuple()`
- `PyList_GetItem()`
- `PyList_GetSlice()`
- `PyList_Insert()`
- `PyList_New()`
- `PyList_Reverse()`
- `PyList_SetItem()`

- *PyList\_SetSlice()*
- *PyList\_Size()*
- *PyList\_Sort()*
- *PyList\_Type*
- *PyLongObject*
- *PyLongRangeIter\_Type*
- *PyLong\_AsDouble()*
- *PyLong\_AsLong()*
- *PyLong\_AsLongAndOverflow()*
- *PyLong\_AsLongLong()*
- *PyLong\_AsLongLongAndOverflow()*
- *PyLong\_AsSize\_t()*
- *PyLong\_AsSsize\_t()*
- *PyLong\_AsUnsignedLong()*
- *PyLong\_AsUnsignedLongLong()*
- *PyLong\_AsUnsignedLongLongMask()*
- *PyLong\_AsUnsignedLongMask()*
- *PyLong\_AsVoidPtr()*
- *PyLong\_FromDouble()*
- *PyLong\_FromLong()*
- *PyLong\_FromLongLong()*
- *PyLong\_FromSize\_t()*
- *PyLong\_FromSsize\_t()*
- *PyLong\_FromString()*
- *PyLong\_FromUnsignedLong()*
- *PyLong\_FromUnsignedLongLong()*
- *PyLong\_FromVoidPtr()*
- *PyLong\_GetInfo()*
- *PyLong\_Type*
- *PyMap\_Type*
- *PyMapping\_Check()*
- *PyMapping\_GetItemString()*
- *PyMapping\_HasKey()*
- *PyMapping\_HasKeyString()*
- *PyMapping\_Items()*
- *PyMapping\_Keys()*
- *PyMapping\_Length()*
- *PyMapping\_SetItemString()*
- *PyMapping\_Size()*

- `PyMapping_Values()`
- `PyMem_Calloc()`
- `PyMem_Free()`
- `PyMem_Malloc()`
- `PyMem_Realloc()`
- `PyMemberDef`
- `PyMemberDescr_Type`
- `PyMemoryView_FromBuffer()`
- `PyMemoryView_FromMemory()`
- `PyMemoryView_FromObject()`
- `PyMemoryView_GetContiguous()`
- `PyMemoryView_Type`
- `PyMethodDef`
- `PyMethodDescr_Type`
- `PyModuleDef`
- `PyModuleDef_Base`
- `PyModuleDef_Init()`
- `PyModuleDef_Type`
- `PyModule_AddFunctions()`
- `PyModule_AddIntConstant()`
- `PyModule_AddObject()`
- `PyModule_AddObjectRef()`
- `PyModule_AddStringConstant()`
- `PyModule_AddType()`
- `PyModule_Create2()`
- `PyModule_ExecDef()`
- `PyModule_FromDefAndSpec2()`
- `PyModule_GetDef()`
- `PyModule_GetDict()`
- `PyModule_GetFilename()`
- `PyModule_GetFilenameObject()`
- `PyModule_GetName()`
- `PyModule_GetNameObject()`
- `PyModule_GetState()`
- `PyModule_New()`
- `PyModule_NewObject()`
- `PyModule_SetDocString()`
- `PyModule_Type`
- `PyNumber_Absolute()`

- `PyNumber_Add()`
- `PyNumber_And()`
- `PyNumber_AsSsize_t()`
- `PyNumber_Check()`
- `PyNumber_Divmod()`
- `PyNumber_Float()`
- `PyNumber_FloorDivide()`
- `PyNumber_InPlaceAdd()`
- `PyNumber_InPlaceAnd()`
- `PyNumber_InPlaceFloorDivide()`
- `PyNumber_InPlaceLshift()`
- `PyNumber_InPlaceMatrixMultiply()`
- `PyNumber_InPlaceMultiply()`
- `PyNumber_InPlaceOr()`
- `PyNumber_InPlacePower()`
- `PyNumber_InPlaceRemainder()`
- `PyNumber_InPlaceRshift()`
- `PyNumber_InPlaceSubtract()`
- `PyNumber_InPlaceTrueDivide()`
- `PyNumber_InPlaceXor()`
- `PyNumber_Index()`
- `PyNumber_Invert()`
- `PyNumber_Long()`
- `PyNumber_Lshift()`
- `PyNumber_MatrixMultiply()`
- `PyNumber_Multiply()`
- `PyNumber_Negative()`
- `PyNumber_Or()`
- `PyNumber_Positive()`
- `PyNumber_Power()`
- `PyNumber_Remainder()`
- `PyNumber_Rshift()`
- `PyNumber_Subtract()`
- `PyNumber_ToBase()`
- `PyNumber_TrueDivide()`
- `PyNumber_Xor()`
- `PyOS_AfterFork()`
- `PyOS_AfterFork_Child()`
- `PyOS_AfterFork_Parent()`

- `PyOS_BeforeFork()`
- `PyOS_CheckStack()`
- `PyOS_FSPath()`
- `PyOS_InputHook`
- `PyOS_InterruptOccurred()`
- `PyOS_double_to_string()`
- `PyOS_getsig()`
- `PyOS_mystricmp()`
- `PyOS_mystrnicmp()`
- `PyOS_setsig()`
- `PyOS_sighandler_t`
- `PyOS_snprintf()`
- `PyOS_string_to_double()`
- `PyOS_strtol()`
- `PyOS_strtoul()`
- `PyOS_vsnprintf()`
- `PyObject`
- `PyObject.ob_refcnt`
- `PyObject.ob_type`
- `PyObject_ASCII()`
- `PyObject_AsCharBuffer()`
- `PyObject_AsFileDescriptor()`
- `PyObject_AsReadBuffer()`
- `PyObject_AsWriteBuffer()`
- `PyObject_Bytes()`
- `PyObject_Call()`
- `PyObject_CallFunction()`
- `PyObject_CallFunctionObjArgs()`
- `PyObject_CallMethod()`
- `PyObject_CallMethodObjArgs()`
- `PyObject_CallNoArgs()`
- `PyObject_CallObject()`
- `PyObject_Calloc()`
- `PyObject_CheckBuffer()`
- `PyObject_CheckReadBuffer()`
- `PyObject_ClearWeakRefs()`
- `PyObject_CopyData()`
- `PyObject_DelItem()`
- `PyObject_DelItemString()`

- `PyObject_Dir()`
- `PyObject_Format()`
- `PyObject_Free()`
- `PyObject_GC_Del()`
- `PyObject_GC_IsFinalized()`
- `PyObject_GC_IsTracked()`
- `PyObject_GC_Track()`
- `PyObject_GC_UnTrack()`
- `PyObject_GenericGetAttr()`
- `PyObject_GenericGetDict()`
- `PyObject_GenericSetAttr()`
- `PyObject_GenericSetDict()`
- `PyObject_GetAIter()`
- `PyObject_GetAttr()`
- `PyObject_GetAttrString()`
- `PyObject_GetBuffer()`
- `PyObject_GetItem()`
- `PyObject_GetIter()`
- `PyObject_HasAttr()`
- `PyObject_HasAttrString()`
- `PyObject_Hash()`
- `PyObject_HashNotImplemented()`
- `PyObject_Init()`
- `PyObject_InitVar()`
- `PyObject_IsInstance()`
- `PyObject_IsSubclass()`
- `PyObject_IsTrue()`
- `PyObject_Length()`
- `PyObject_Malloc()`
- `PyObject_Not()`
- `PyObject_Realloc()`
- `PyObject_Repr()`
- `PyObject_RichCompare()`
- `PyObject_RichCompareBool()`
- `PyObject_SelfIter()`
- `PyObject_SetAttr()`
- `PyObject_SetAttrString()`
- `PyObject_SetItem()`
- `PyObject_Size()`

- *PyObject\_Str()*
- *PyObject\_Type()*
- *PyProperty\_Type*
- *PyRangeIter\_Type*
- *PyRange\_Type*
- *PyReversed\_Type*
- *PySeqIter\_New()*
- *PySeqIter\_Type*
- *PySequence\_Check()*
- *PySequence\_Concat()*
- *PySequence\_Contains()*
- *PySequence\_Count()*
- *PySequence\_DelItem()*
- *PySequence\_DelSlice()*
- *PySequence\_Fast()*
- *PySequence\_GetItem()*
- *PySequence\_GetSlice()*
- *PySequence\_In()*
- *PySequence\_InPlaceConcat()*
- *PySequence\_InPlaceRepeat()*
- *PySequence\_Index()*
- *PySequence\_Length()*
- *PySequence\_List()*
- *PySequence\_Repeat()*
- *PySequence\_SetItem()*
- *PySequence\_SetSlice()*
- *PySequence\_Size()*
- *PySequence\_Tuple()*
- *PySetIter\_Type*
- *PySet\_Add()*
- *PySet\_Clear()*
- *PySet\_Contains()*
- *PySet\_Discard()*
- *PySet\_New()*
- *PySet\_Pop()*
- *PySet\_Size()*
- *PySet\_Type*
- *PySlice\_AdjustIndices()*
- *PySlice\_GetIndices()*

- `PySlice_GetIndicesEx()`
- `PySlice_New()`
- `PySlice_Type`
- `PySlice_Unpack()`
- `PyState_AddModule()`
- `PyState_FindModule()`
- `PyState_RemoveModule()`
- `PyStructSequence_Desc`
- `PyStructSequence_Field`
- `PyStructSequence_GetItem()`
- `PyStructSequence_New()`
- `PyStructSequence_NewType()`
- `PyStructSequence_SetItem()`
- `PyStructSequence_UnnamedField`
- `PySuper_Type`
- `PySys_AddWarnOption()`
- `PySys_AddWarnOptionUnicode()`
- `PySys_AddXOption()`
- `PySys_FormatStderr()`
- `PySys_FormatStdout()`
- `PySys_GetObject()`
- `PySys_GetXOptions()`
- `PySys_HasWarnOptions()`
- `PySys_ResetWarnOptions()`
- `PySys_SetArgv()`
- `PySys_SetArgvEx()`
- `PySys_SetObject()`
- `PySys_SetPath()`
- `PySys_WriteStderr()`
- `PySys_WriteStdout()`
- `PyThreadState`
- `PyThreadState_Clear()`
- `PyThreadState_Delete()`
- `PyThreadState_Get()`
- `PyThreadState_GetDict()`
- `PyThreadState_GetFrame()`
- `PyThreadState_GetID()`
- `PyThreadState_GetInterpreter()`
- `PyThreadState_New()`



- *PyThreadState\_SetAsyncExc()*
- *PyThreadState\_Swap()*
- *PyThread\_GetInfo()*
- *PyThread\_ReInitTLS()*
- *PyThread\_acquire\_lock()*
- *PyThread\_acquire\_lock\_timed()*
- *PyThread\_allocate\_lock()*
- *PyThread\_create\_key()*
- *PyThread\_delete\_key()*
- *PyThread\_delete\_key\_value()*
- *PyThread\_exit\_thread()*
- *PyThread\_free\_lock()*
- *PyThread\_get\_key\_value()*
- *PyThread\_get\_stacksize()*
- *PyThread\_get\_thread\_ident()*
- *PyThread\_get\_thread\_native\_id()*
- *PyThread\_init\_thread()*
- *PyThread\_release\_lock()*
- *PyThread\_set\_key\_value()*
- *PyThread\_set\_stacksize()*
- *PyThread\_start\_new\_thread()*
- *PyThread\_tss\_alloc()*
- *PyThread\_tss\_create()*
- *PyThread\_tss\_delete()*
- *PyThread\_tss\_free()*
- *PyThread\_tss\_get()*
- *PyThread\_tss\_is\_created()*
- *PyThread\_tss\_set()*
- *PyTraceBack\_Here()*
- *PyTraceBack\_Print()*
- *PyTraceBack\_Type*
- *PyTupleIter\_Type*
- *PyTuple\_GetItem()*
- *PyTuple\_GetSlice()*
- *PyTuple\_New()*
- *PyTuple\_Pack()*
- *PyTuple\_SetItem()*
- *PyTuple\_Size()*
- *PyTuple\_Type*

- `PyTypeObject`
- `PyType_ClearCache()`
- `PyType_FromModuleAndSpec()`
- `PyType_FromSpec()`
- `PyType_FromSpecWithBases()`
- `PyType_GenericAlloc()`
- `PyType_GenericNew()`
- `PyType_GetFlags()`
- `PyType_GetModule()`
- `PyType_GetModuleState()`
- `PyType_GetName()`
- `PyType_GetQualName()`
- `PyType_GetSlot()`
- `PyType_IsSubtype()`
- `PyType_Modified()`
- `PyType_Ready()`
- `PyType_Slot`
- `PyType_Spec`
- `PyType_Type`
- `PyUnicodeDecodeError_Create()`
- `PyUnicodeDecodeError_GetEncoding()`
- `PyUnicodeDecodeError_GetEnd()`
- `PyUnicodeDecodeError_GetObject()`
- `PyUnicodeDecodeError_GetReason()`
- `PyUnicodeDecodeError_GetStart()`
- `PyUnicodeDecodeError_SetEnd()`
- `PyUnicodeDecodeError_SetReason()`
- `PyUnicodeDecodeError_SetStart()`
- `PyUnicodeEncodeError_GetEncoding()`
- `PyUnicodeEncodeError_GetEnd()`
- `PyUnicodeEncodeError_GetObject()`
- `PyUnicodeEncodeError_GetReason()`
- `PyUnicodeEncodeError_GetStart()`
- `PyUnicodeEncodeError_SetEnd()`
- `PyUnicodeEncodeError_SetReason()`
- `PyUnicodeEncodeError_SetStart()`
- `PyUnicodeIter_Type`
- `PyUnicodeTranslateError_GetEnd()`
- `PyUnicodeTranslateError_GetObject()`

- `PyUnicodeTranslateError_GetReason()`
- `PyUnicodeTranslateError_GetStart()`
- `PyUnicodeTranslateError_SetEnd()`
- `PyUnicodeTranslateError_SetReason()`
- `PyUnicodeTranslateError_SetStart()`
- `PyUnicode_Append()`
- `PyUnicode_AppendAndDel()`
- `PyUnicode_AsASCIIString()`
- `PyUnicode_AsCharmapString()`
- `PyUnicode_AsDecodedObject()`
- `PyUnicode_AsDecodedUnicode()`
- `PyUnicode_AsEncodedObject()`
- `PyUnicode_AsEncodedString()`
- `PyUnicode_AsEncodedUnicode()`
- `PyUnicode_AsLatin1String()`
- `PyUnicode_AsMBCSString()`
- `PyUnicode_AsRawUnicodeEscapeString()`
- `PyUnicode_AsUCS4()`
- `PyUnicode_AsUCS4Copy()`
- `PyUnicode_AsUTF16String()`
- `PyUnicode_AsUTF32String()`
- `PyUnicode_AsUTF8AndSize()`
- `PyUnicode_AsUTF8String()`
- `PyUnicode_AsUnicodeEscapeString()`
- `PyUnicode_AsWideChar()`
- `PyUnicode_AsWideCharString()`
- `PyUnicode_BuildEncodingMap()`
- `PyUnicode_Compare()`
- `PyUnicode_CompareWithASCIIString()`
- `PyUnicode_Concat()`
- `PyUnicode_Contains()`
- `PyUnicode_Count()`
- `PyUnicode_Decode()`
- `PyUnicode_DecodeASCII()`
- `PyUnicode_DecodeCharmap()`
- `PyUnicode_DecodeCodePageStateful()`
- `PyUnicode_DecodeFSDefault()`
- `PyUnicode_DecodeFSDefaultAndSize()`
- `PyUnicode_DecodeLatin1()`

- `PyUnicode_DecodeLocale()`
- `PyUnicode_DecodeLocaleAndSize()`
- `PyUnicode_DecodeMBCS()`
- `PyUnicode_DecodeMBCSStateful()`
- `PyUnicode_DecodeRawUnicodeEscape()`
- `PyUnicode_DecodeUTF16()`
- `PyUnicode_DecodeUTF16Stateful()`
- `PyUnicode_DecodeUTF32()`
- `PyUnicode_DecodeUTF32Stateful()`
- `PyUnicode_DecodeUTF7()`
- `PyUnicode_DecodeUTF7Stateful()`
- `PyUnicode_DecodeUTF8()`
- `PyUnicode_DecodeUTF8Stateful()`
- `PyUnicode_DecodeUnicodeEscape()`
- `PyUnicode_EncodeCodePage()`
- `PyUnicode_EncodeFSDefault()`
- `PyUnicode_EncodeLocale()`
- `PyUnicode_FSConverter()`
- `PyUnicode_FSDecoder()`
- `PyUnicode_Find()`
- `PyUnicode_FindChar()`
- `PyUnicode_Format()`
- `PyUnicode_FromEncodedObject()`
- `PyUnicode_FromFormat()`
- `PyUnicode_FromFormatV()`
- `PyUnicode_FromObject()`
- `PyUnicode_FromOrdinal()`
- `PyUnicode_FromString()`
- `PyUnicode_FromStringAndSize()`
- `PyUnicode_FromWideChar()`
- `PyUnicode_GetDefaultEncoding()`
- `PyUnicode_GetLength()`
- `PyUnicode_GetSize()`
- `PyUnicode_InternFromString()`
- `PyUnicode_InternImmortal()`
- `PyUnicode_InternInPlace()`
- `PyUnicode_IsIdentifier()`
- `PyUnicode_Join()`
- `PyUnicode_Partition()`

- `PyUnicode_RPartition()`
- `PyUnicode_RSplit()`
- `PyUnicode_ReadChar()`
- `PyUnicode_Replace()`
- `PyUnicode_Resize()`
- `PyUnicode_RichCompare()`
- `PyUnicode_Split()`
- `PyUnicode_Splitlines()`
- `PyUnicode_Substring()`
- `PyUnicode_Tailmatch()`
- `PyUnicode_Translate()`
- `PyUnicode_Type`
- `PyUnicode_WriteChar()`
- `PyVarObject`
- `PyVarObject.ob_base`
- `PyVarObject.ob_size`
- `PyWeakReference`
- `PyWeakref_GetObject()`
- `PyWeakref_NewProxy()`
- `PyWeakref_NewRef()`
- `PyWrapperDescr_Type`
- `PyWrapper_New()`
- `PyZip_Type`
- `Py_AddPendingCall()`
- `Py_AtExit()`
- `Py_BEGIN_ALLOW_THREADS`
- `Py_BLOCK_THREADS`
- `Py_BuildValue()`
- `Py_BytesMain()`
- `Py_CompileString()`
- `Py_DecRef()`
- `Py_DecodeLocale()`
- `Py_END_ALLOW_THREADS`
- `Py_EncodeLocale()`
- `Py_EndInterpreter()`
- `Py_EnterRecursiveCall()`
- `Py_Exit()`
- `Py_FatalError()`
- `Py_FileSystemDefaultEncodeErrors`

- `Py_FileSystemDefaultEncoding`
- `Py_Finalize()`
- `Py_FinalizeEx()`
- `Py_GenericAlias()`
- `Py_GenericAliasType`
- `Py_GetBuildInfo()`
- `Py_GetCompiler()`
- `Py_GetCopyright()`
- `Py_GetExecPrefix()`
- `Py_GetPath()`
- `Py_GetPlatform()`
- `Py_GetPrefix()`
- `Py_GetProgramFullPath()`
- `Py_GetProgramName()`
- `Py_GetPythonHome()`
- `Py_GetRecursionLimit()`
- `Py_GetVersion()`
- `Py_HasFileSystemDefaultEncoding`
- `Py_IncRef()`
- `Py_Initialize()`
- `Py_InitializeEx()`
- `Py_Is()`
- `Py_IsFalse()`
- `Py_IsInitialized()`
- `Py_IsNone()`
- `Py_IsTrue()`
- `Py_LeaveRecursiveCall()`
- `Py_Main()`
- `Py_MakePendingCalls()`
- `Py_NewInterpreter()`
- `Py_NewRef()`
- `Py_ReprEnter()`
- `Py_ReprLeave()`
- `Py_SetPath()`
- `Py_SetProgramName()`
- `Py_SetPythonHome()`
- `Py_SetRecursionLimit()`
- `Py_UCS4`
- `Py_UNBLOCK_THREADS`

- `Py_UTF8Mode`
- `Py_VaBuildValue()`
- `Py_Version`
- `Py_XNewRef()`
- `Py_buffer`
- `Py_intptr_t`
- `Py_ssize_t`
- `Py_uintptr_t`
- `allocfunc`
- `binaryfunc`
- `descrgetfunc`
- `descrsetfunc`
- `destructor`
- `getattrfunc`
- `getattrofunc`
- `getiterfunc`
- `getter`
- `hashfunc`
- `initproc`
- `inquiry`
- `iternextfunc`
- `lenfunc`
- `newfunc`
- `objobjargproc`
- `objobjproc`
- `reprfunc`
- `richcmpfunc`
- `setattrfunc`
- `setattrofunc`
- `setter`
- `ssizeargfunc`
- `ssizeobjargproc`
- `ssizessizeargfunc`
- `ssizessizeobjargproc`
- `symtable`
- `ternaryfunc`
- `traverseproc`
- `unaryfunc`
- `visitproc`





---

The Very High Level Layer

---

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are *Py\_eval\_input*, *Py\_file\_input*, and *Py\_single\_input*. These are described following the functions which accept them as parameters.

Note also that several of these functions take *FILE\** parameters. One particular issue which needs to be handled carefully is that the *FILE* structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that *FILE\** parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

int **Py\_Main** (int argc, wchar\_t \*\*argv)

*Μέρος του Σταθερό ABI.* The main program for the standard interpreter. This is made available for programs which embed Python. The *argc* and *argv* parameters should be prepared exactly as those which are passed to a C program's *main()* function (converted to *wchar\_t* according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled *SystemExit* is raised, this function will not return 1, but exit the process, as long as *Py\_InspectFlag* is not set.

int **Py\_BytesMain** (int argc, char \*\*argv)

*Μέρος του Σταθερό ABI από την έκδοση 3.8.* Similar to *Py\_Main()* but *argv* is an array of bytes strings. Νέο στην έκδοση 3.8.

int **PyRun\_AnyFile** (FILE \*fp, const char \*filename)

This is a simplified interface to *PyRun\_AnyFileExFlags()* below, leaving *closeit* set to 0 and *flags* set to NULL.

int **PyRun\_AnyFileFlags** (FILE \*fp, const char \*filename, *PyCompilerFlags* \*flags)

This is a simplified interface to *PyRun\_AnyFileExFlags()* below, leaving the *closeit* argument set to 0.

int **PyRun\_AnyFileEx** (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to *PyRun\_AnyFileExFlags()* below, leaving the *flags* argument set to NULL.

int **PyRun\_AnyFileExFlags** (FILE \*fp, const char \*filename, int closeit, *PyCompilerFlags* \*flags)

If *fp* refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of *PyRun\_InteractiveLoop()*, otherwise return the result of *PyRun\_SimpleFile()*. *filename* is decoded from the filesystem encoding (`sys.getfilesystemencoding()`). If *filename* is NULL, this function uses "???" as the filename. If *closeit* is true, the file is closed before *PyRun\_SimpleFileExFlags()* returns.

int **PyRun\_SimpleString** (const char \*command)

This is a simplified interface to *PyRun\_SimpleStringFlags()* below, leaving the *PyCompilerFlags\** argument set to NULL.

int **PyRun\_SimpleStringFlags** (const char \*command, *PyCompilerFlags* \*flags)

Executes the Python source code from *command* in the `__main__` module according to the *flags* argument. If `__main__` does not already exist, it is created. Returns 0 on success or -1 if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled `SystemExit` is raised, this function will not return -1, but exit the process, as long as `Py_InspectFlag` is not set.

int **PyRun\_SimpleFile** (FILE \*fp, const char \*filename)

This is a simplified interface to *PyRun\_SimpleFileExFlags()* below, leaving *closeit* set to 0 and *flags* set to NULL.

int **PyRun\_SimpleFileEx** (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to *PyRun\_SimpleFileExFlags()* below, leaving *flags* set to NULL.

int **PyRun\_SimpleFileExFlags** (FILE \*fp, const char \*filename, int closeit, *PyCompilerFlags* \*flags)

Similar to *PyRun\_SimpleStringFlags()*, but the Python source code is read from *fp* instead of an in-memory string. *filename* should be the name of the file, it is decoded from *filesystem encoding and error handler*. If *closeit* is true, the file is closed before *PyRun\_SimpleFileExFlags()* returns.

---

**Σημείωση:** On Windows, *fp* should be opened as binary mode (e.g. `fopen(filename, "rb")`). Otherwise, Python may not handle script file with LF line ending correctly.

---

int **PyRun\_InteractiveOne** (FILE \*fp, const char \*filename)

This is a simplified interface to *PyRun\_InteractiveOneFlags()* below, leaving *flags* set to NULL.

int **PyRun\_InteractiveOneFlags** (FILE \*fp, const char \*filename, *PyCompilerFlags* \*flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using `sys.ps1` and `sys.ps2`. *filename* is decoded from the *filesystem encoding and error handler*.

Returns 0 when the input was executed successfully, -1 if there was an exception, or an error code from the `errcode.h` include file distributed as part of Python if there was a parse error. (Note that `errcode.h` is not included by `Python.h`, so must be included specifically if needed.)

int **PyRun\_InteractiveLoop** (FILE \*fp, const char \*filename)

This is a simplified interface to *PyRun\_InteractiveLoopFlags()* below, leaving *flags* set to NULL.

int **PyRun\_InteractiveLoopFlags** (FILE \*fp, const char \*filename, *PyCompilerFlags* \*flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using `sys.ps1` and `sys.ps2`. *filename* is decoded from the *filesystem encoding and error handler*. Returns 0 at EOF or a negative number upon failure.

int (\***PyOS\_InputHook**)(void)

*Μέρος του Σταθερό ABI.* Can be set to point to a function with the prototype `int func(void)`. The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the `Modules/_tkinter.c` in the Python source code.

char **PyOS\_ReadlineFunctionPointer**(FILE\*, FILE\*, const char\*)

Can be set to point to a function with the prototype `char *func(FILE *stdin, FILE *stdout, char *prompt)`, overriding the default function used to read a single line of input at the interpreter's prompt. The function is expected to output the string *prompt* if it's not NULL, and then read a line of input from the provided standard input file, returning the resulting string. For example, The `readline` module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by `PyMem_RawMalloc()` or `PyMem_RawRealloc()`, or NULL if an error occurred.

Άλλαξε στην έκδοση 3.4: The result must be allocated by `PyMem_RawMalloc()` or `PyMem_RawRealloc()`, instead of being allocated by `PyMem_Malloc()` or `PyMem_Realloc()`.

**PyObject\*PyRun\_String**(const char \*str, int start, *PyObject* \*globals, *PyObject* \*locals)

*Επιστρεφόμενη τιμή*: New reference. This is a simplified interface to `PyRun_StringFlags()` below, leaving *flags* set to NULL.

**PyObject\*PyRun\_StringFlags**(const char \*str, int start, *PyObject* \*globals, *PyObject* \*locals, *PyCompilerFlags* \*flags)

*Επιστρεφόμενη τιμή*: New reference. Execute Python source code from *str* in the context specified by the objects *globals* and *locals* with the compiler flags specified by *flags*. *globals* must be a dictionary; *locals* can be any object that implements the mapping protocol. The parameter *start* specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or NULL if an exception was raised.

**PyObject\*PyRun\_File**(FILE \*fp, const char \*filename, int start, *PyObject* \*globals, *PyObject* \*locals)

*Επιστρεφόμενη τιμή*: New reference. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *closeit* set to 0 and *flags* set to NULL.

**PyObject\*PyRun\_FileEx**(FILE \*fp, const char \*filename, int start, *PyObject* \*globals, *PyObject* \*locals, int closeit)

*Επιστρεφόμενη τιμή*: New reference. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *flags* set to NULL.

**PyObject\*PyRun\_FileFlags**(FILE \*fp, const char \*filename, int start, *PyObject* \*globals, *PyObject* \*locals, *PyCompilerFlags* \*flags)

*Επιστρεφόμενη τιμή*: New reference. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *closeit* set to 0.

**PyObject\*PyRun\_FileExFlags**(FILE \*fp, const char \*filename, int start, *PyObject* \*globals, *PyObject* \*locals, int closeit, *PyCompilerFlags* \*flags)

*Επιστρεφόμενη τιμή*: New reference. Similar to `PyRun_StringFlags()`, but the Python source code is read from *fp* instead of an in-memory string. *filename* should be the name of the file, it is decoded from the *filesystem encoding and error handler*. If *closeit* is true, the file is closed before `PyRun_FileExFlags()` returns.

**PyObject\*Py\_CompileString**(const char \*str, const char \*filename, int start)

*Επιστρεφόμενη τιμή*: New reference. Μέρος του Σταθερό ABI. This is a simplified interface to `Py_CompileStringFlags()` below, leaving *flags* set to NULL.

**PyObject\*Py\_CompileStringFlags**(const char \*str, const char \*filename, int start, *PyCompilerFlags* \*flags)

*Επιστρεφόμενη τιμή*: New reference. This is a simplified interface to `Py_CompileStringExFlags()` below, with *optimize* set to -1.

**PyObject\*Py\_CompileStringObject**(const char \*str, *PyObject* \*filename, int start, *PyCompilerFlags* \*flags, int optimize)

*Επιστρεφόμενη τιμή*: New reference. Parse and compile the Python source code in *str*, returning the resulting code object. The start token is given by *start*; this can be used to constrain the code which can be compiled and should be `Py_eval_input`, `Py_file_input`, or `Py_single_input`. The filename specified by *filename* is used to construct the code object and may appear in `Traceback` or `SyntaxError` exception messages. This returns NULL if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of `-1` selects the optimization level of the interpreter as given by `-O` options. Explicit levels are `0` (no optimization; `__debug__` is true), `1` (asserts are removed, `__debug__` is false) or `2` (docstrings are removed too).

Νέο στην έκδοση 3.4.

***PyObject* \*Py\_CompileStringExFlags** (const char \*str, const char \*filename, int start, *PyCompilerFlags* \*flags, int optimize)

*Επιστρεφόμενη τιμή:* New reference. Like *Py\_CompileStringObject()*, but *filename* is a byte string decoded from the *filesystem encoding and error handler*.

Νέο στην έκδοση 3.2.

***PyObject* \*PyEval\_EvalCode** (*PyObject* \*co, *PyObject* \*globals, *PyObject* \*locals)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. This is a simplified interface to *PyEval\_EvalCodeEx()*, with just the code object, and global and local variables. The other arguments are set to NULL.

***PyObject* \*PyEval\_EvalCodeEx** (*PyObject* \*co, *PyObject* \*globals, *PyObject* \*locals, *PyObject* \*const \*args, int argcount, *PyObject* \*const \*kws, int kwcount, *PyObject* \*const \*defs, int defcount, *PyObject* \*kwdefs, *PyObject* \*closure)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for *keyword-only* arguments and a closure tuple of cells.

***PyObject* \*PyEval\_EvalFrame** (*PyFrameObject* \*f)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Evaluate an execution frame. This is a simplified interface to *PyEval\_EvalFrameEx()*, for backward compatibility.

***PyObject* \*PyEval\_EvalFrameEx** (*PyFrameObject* \*f, int throwflag)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame *f* is executed, interpreting bytecode and executing calls as needed. The additional *throwflag* parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the *throw()* methods of generator objects.

Άλλαξε στην έκδοση 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

int **PyEval\_MergeCompilerFlags** (*PyCompilerFlags* \*cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

int **Py\_eval\_input**

The start symbol from the Python grammar for isolated expressions; for use with *Py\_CompileString()*.

int **Py\_file\_input**

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with *Py\_CompileString()*. This is the symbol to use when compiling arbitrarily long Python source code.

int **Py\_single\_input**

The start symbol from the Python grammar for a single statement; for use with *Py\_CompileString()*. This is the symbol used for the interactive interpreter loop.

struct **PyCompilerFlags**

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as *int flags*, and in cases where code is being executed, it is passed as *PyCompilerFlags \*flags*. In this case, from `__future__` import can modify *flags*.

Whenever *PyCompilerFlags \*flags* is NULL, *cf\_flags* is treated as equal to 0, and any modification due to from `__future__` import is discarded.

int **cf\_flags**

Compiler flags.

int **cf\_feature\_version**

*cf\_feature\_version* is the minor Python version. It should be initialized to `PY_MINOR_VERSION`.

The field is ignored by default, it is used if and only if `PyCF_ONLY_AST` flag is set in *cf\_flags*.

Άλλαξε στην έκδοση 3.8: Added *cf\_feature\_version* field.

int **CO\_FUTURE\_DIVISION**

This bit can be set in *flags* to cause division operator `/` to be interpreted as «true division» according to [PEP 238](#).



---

Reference Counting

---

The macros in this section are used for managing reference counts of Python objects.

void **Py\_INCREF** (*PyObject* \*o)

Indicate taking a new *strong reference* to object *o*, indicating it is in use and should not be destroyed.

This function is usually used to convert a *borrowed reference* to a *strong reference* in-place. The *Py\_NewRef* () function can be used to create a new *strong reference*.

When done using the object, release it by calling *Py\_DECREF* () .

The object must not be NULL; if you aren't sure that it isn't NULL, use *Py\_XINCREF* () .

Do not expect this function to actually modify *o* in any way.

void **Py\_XINCREF** (*PyObject* \*o)

Similar to *Py\_INCREF* () , but the object *o* can be NULL, in which case this has no effect.

See also *Py\_XNewRef* () .

*PyObject* \***Py\_NewRef** (*PyObject* \*o)

Μέρος του Σταθερό ABI από την έκδοση 3.10. Create a new *strong reference* to an object: call *Py\_INCREF* () on *o* and return the object *o*.

When the *strong reference* is no longer needed, *Py\_DECREF* () should be called on it to release the reference.

The object *o* must not be NULL; use *Py\_XNewRef* () if *o* can be NULL.

For example:

```
Py_INCREF(obj);
self->attr = obj;
```

can be written as:

```
self->attr = Py_NewRef(obj);
```

See also *Py\_INCREF* () .

Νέο στην έκδοση 3.10.

*PyObject* \*Py\_XNewRef (*PyObject* \*o)

Μέρος του Σταθερό ABI από την έκδοση 3.10. Similar to *Py\_NewRef()*, but the object *o* can be NULL.

If the object *o* is NULL, the function just returns NULL.

Νέο στην έκδοση 3.10.

void Py\_DECREF (*PyObject* \*o)

Release a *strong reference* to object *o*, indicating the reference is no longer used.

Once the last *strong reference* is released (i.e. the object's reference count reaches 0), the object's type's deallocation function (which must not be NULL) is invoked.

This function is usually used to delete a *strong reference* before exiting its scope.

The object must not be NULL; if you aren't sure that it isn't NULL, use *Py\_XDECREF()*.

Do not expect this function to actually modify *o* in any way.

**Προειδοποίηση:** The deallocation function can cause arbitrary Python code to be invoked (e.g. when a class instance with a `__del__()` method is deallocated). While exceptions in such code are not propagated, the executed code has free access to all Python global variables. This means that any object that is reachable from a global variable should be in a consistent state before *Py\_DECREF()* is invoked. For example, code to delete an object from a list should copy a reference to the deleted object in a temporary variable, update the list data structure, and then call *Py\_DECREF()* for the temporary variable.

void Py\_XDECREF (*PyObject* \*o)

Similar to *Py\_DECREF()*, but the object *o* can be NULL, in which case this has no effect. The same warning from *Py\_DECREF()* applies here as well.

void Py\_CLEAR (*PyObject* \*o)

Release a *strong reference* for object *o*. The object may be NULL, in which case the macro has no effect; otherwise the effect is the same as for *Py\_DECREF()*, except that the argument is also set to NULL. The warning for *Py\_DECREF()* does not apply with respect to the object passed because the macro carefully uses a temporary variable and sets the argument to NULL before releasing the reference.

It is a good idea to use this macro whenever releasing a reference to an object that might be traversed during garbage collection.

void Py\_IncRef (*PyObject* \*o)

Μέρος του Σταθερό ABI. Indicate taking a new *strong reference* to object *o*. A function version of *Py\_XINCREF()*. It can be used for runtime dynamic embedding of Python.

void Py\_DecRef (*PyObject* \*o)

Μέρος του Σταθερό ABI. Release a *strong reference* to object *o*. A function version of *Py\_XDECREF()*. It can be used for runtime dynamic embedding of Python.

The following functions or macros are only for use within the interpreter core: *\_Py\_Dealloc()*, *\_Py\_ForgetReference()*, *\_Py\_NewReference()*, as well as the global variable *\_Py\_RefTotal*.



---

Exception Handling

---

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX `errno` variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually `NULL` if they are supposed to return a pointer, or `-1` if they return an integer (exception: the `PyArg_*` functions return `1` for success and `0` for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be `NULL` if non-set (although some combinations are forbidden, for example you can't have a non-`NULL` traceback if the exception type is `NULL`).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

---

**Σημείωση:** The error indicator is **not** the result of `sys.exc_info()`. The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

---

## 5.1 Printing and clearing

void **PyErr\_Clear**()

*Μέρος του Σταθερό ABI.* Clear the error indicator. If the error indicator is not set, there is no effect.

void **PyErr\_PrintEx**(int set\_sys\_last\_vars)

*Μέρος του Σταθερό ABI.* Print a standard traceback to `sys.stderr` and clear the error indicator. **Unless** the error is a `SystemExit`, in that case no traceback is printed and the Python process will exit with the error code specified by the `SystemExit` instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If `set_sys_last_vars` is nonzero, the variables `sys.last_type`, `sys.last_value` and `sys.last_traceback` will be set to the type, value and traceback of the printed exception, respectively.

void **PyErr\_Print** ()

*Μέρος του Σταθερό ABI.* Alias for `PyErr_PrintEx(1)`.

void **PyErr\_WriteUnraisable** (*PyObject* \*obj)

*Μέρος του Σταθερό ABI.* Call `sys.unraisablehook()` using the current exception and *obj* argument.

This utility function prints a warning message to `sys.stderr` when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an `__del__()` method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

An exception must be set when calling this function.

## 5.2 Raising exceptions

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a NULL pointer for use in a return statement.

void **PyErr\_SetString** (*PyObject* \*type, const char \*message)

*Μέρος του Σταθερό ABI.* This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. `PyExc_RuntimeError`. You need not create a new *strong reference* to it (e.g. with `Py_INCREF()`). The second argument is an error message; it is decoded from `'utf-8'`.

void **PyErr\_SetObject** (*PyObject* \*type, *PyObject* \*value)

*Μέρος του Σταθερό ABI.* This function is similar to `PyErr_SetString()` but lets you specify an arbitrary Python object for the «value» of the exception.

*PyObject* \***PyErr\_Format** (*PyObject* \*exception, const char \*format, ...)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. *Μέρος του Σταθερό ABI.* This function sets the error indicator and returns NULL. *exception* should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in `PyUnicode_FromFormat()`. *format* is an ASCII-encoded string.

*PyObject* \***PyErr\_FormatV** (*PyObject* \*exception, const char \*format, va\_list args)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. *Μέρος του Σταθερό ABI* από την έκδοση 3.5. Same as `PyErr_Format()`, but taking a *va\_list* argument rather than a variable number of arguments.

Νέο στην έκδοση 3.5.

void **PyErr\_SetNone** (*PyObject* \*type)

*Μέρος του Σταθερό ABI.* This is a shorthand for `PyErr_SetObject(type, Py_None)`.

int **PyErr\_BadArgument** ()

*Μέρος του Σταθερό ABI.* This is a shorthand for `PyErr_SetString(PyExc_TypeError, message)`, where *message* indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

*PyObject* \***PyErr\_NoMemory** ()

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. *Μέρος του Σταθερό ABI.* This is a shorthand for `PyErr_SetNone(PyExc_MemoryError)`; it returns NULL so an object allocation function can write `return PyErr_NoMemory()`; when it runs out of memory.

*PyObject* \*PyErr\_SetFromErrno (*PyObject* \*type)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable `errno`. It constructs a tuple object whose first item is the integer `errno` value and whose second item is the corresponding error message (gotten from `strerror()`), and then calls `PyErr_SetObject(type, object)`. On Unix, when the `errno` value is `EINTR`, indicating an interrupted system call, this calls `PyErr_CheckSignals()`, and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write `return PyErr_SetFromErrno(type)`; when the system call returns an error.

*PyObject* \*PyErr\_SetFromErrnoWithFilenameObject (*PyObject* \*type, *PyObject* \*filenameObject)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI. Similar to `PyErr_SetFromErrno()`, with the additional behavior that if `filenameObject` is not NULL, it is passed to the constructor of `type` as a third parameter. In the case of `OSError` exception, this is used to define the `filename` attribute of the exception instance.

*PyObject* \*PyErr\_SetFromErrnoWithFilenameObjects (*PyObject* \*type, *PyObject* \*filenameObject, *PyObject* \*filenameObject2)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI από την έκδοση 3.7. Similar to `PyErr_SetFromErrnoWithFilenameObject()`, but takes a second filename object, for raising errors when a function that takes two filenames fails.

Νέο στην έκδοση 3.4.

*PyObject* \*PyErr\_SetFromErrnoWithFilename (*PyObject* \*type, const char \*filename)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI. Similar to `PyErr_SetFromErrnoWithFilenameObject()`, but the filename is given as a C string. `filename` is decoded from the *filesystem encoding and error handler*.

*PyObject* \*PyErr\_SetFromWindowsErr (int ierr)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. This is a convenience function to raise `WindowsError`. If called with `ierr` of 0, the error code returned by a call to `GetLastError()` is used instead. It calls the Win32 function `FormatMessage()` to retrieve the Windows description of error code given by `ierr` or `GetLastError()`, then it constructs a tuple object whose first item is the `ierr` value and whose second item is the corresponding error message (gotten from `FormatMessage()`), and then calls `PyErr_SetObject(PyExc_WindowsError, object)`. This function always returns NULL.

Availability: Windows.

*PyObject* \*PyErr\_SetExcFromWindowsErr (*PyObject* \*type, int ierr)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Similar to `PyErr_SetFromWindowsErr()`, with an additional parameter specifying the exception type to be raised.

Availability: Windows.

*PyObject* \*PyErr\_SetFromWindowsErrWithFilename (int ierr, const char \*filename)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Similar to `PyErr_SetFromWindowsErr()`, with the additional behavior that if `filename` is not NULL, it is decoded from the filesystem encoding (`os.fsdecode()`) and passed to the constructor of `OSError` as a third parameter to be used to define the `filename` attribute of the exception instance.

Availability: Windows.

*PyObject* \*PyErr\_SetExcFromWindowsErrWithFilenameObject (*PyObject* \*type, int ierr, *PyObject* \*filename)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Similar to `PyErr_SetExcFromWindowsErr()`, with the additional behavior that if `filename` is not NULL, it is passed to the constructor of `OSError` as a third parameter to be used to define the `filename` attribute of the exception instance.

Availability: Windows.

*PyObject* \***PyErr\_SetExcFromWindowsErrWithFilenameObjects** (*PyObject* \*type, int ierr, *PyObject* \*filename, *PyObject* \*filename2)

*Επιστρεφόμενη τιμή: Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Similar to `PyErr_SetExcFromWindowsErrWithFilenameObject()`, but accepts a second filename object.*

Availability: Windows.

Νέο στην έκδοση 3.4.

*PyObject* \***PyErr\_SetExcFromWindowsErrWithFilename** (*PyObject* \*type, int ierr, const char \*filename)

*Επιστρεφόμενη τιμή: Πάντοτε NULL. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Similar to `PyErr_SetFromWindowsErrWithFilename()`, with an additional parameter specifying the exception type to be raised.*

Availability: Windows.

*PyObject* \***PyErr\_SetImportError** (*PyObject* \*msg, *PyObject* \*name, *PyObject* \*path)

*Επιστρεφόμενη τιμή: Πάντοτε NULL. Μέρος του Σταθερό ABI από την έκδοση 3.7. This is a convenience function to raise `ImportError`. `msg` will be set as the exception's message string. `name` and `path`, both of which can be `NULL`, will be set as the `ImportError`'s respective `name` and `path` attributes.*

Νέο στην έκδοση 3.3.

*PyObject* \***PyErr\_SetImportErrorSubclass** (*PyObject* \*exception, *PyObject* \*msg, *PyObject* \*name, *PyObject* \*path)

*Επιστρεφόμενη τιμή: Πάντοτε NULL. Μέρος του Σταθερό ABI από την έκδοση 3.6. Much like `PyErr_SetImportError()` but this function allows for specifying a subclass of `ImportError` to raise.*

Νέο στην έκδοση 3.6.

void **PyErr\_SyntaxLocationObject** (*PyObject* \*filename, int lineno, int col\_offset)

Set file, line, and offset information for the current exception. If the current exception is not a `SyntaxError`, then it sets additional attributes, which make the exception printing subsystem think the exception is a `SyntaxError`.

Νέο στην έκδοση 3.4.

void **PyErr\_SyntaxLocationEx** (const char \*filename, int lineno, int col\_offset)

*Μέρος του Σταθερό ABI από την έκδοση 3.7. Like `PyErr_SyntaxLocationObject()`, but `filename` is a byte string decoded from the *filesystem encoding and error handler*.*

Νέο στην έκδοση 3.2.

void **PyErr\_SyntaxLocation** (const char \*filename, int lineno)

*Μέρος του Σταθερό ABI. Like `PyErr_SyntaxLocationEx()`, but the `col_offset` parameter is omitted.*

void **PyErr\_BadInternalCall** ()

*Μέρος του Σταθερό ABI. This is a shorthand for `PyErr_SetString(PyExc_SystemError, message)`, where `message` indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.*

## 5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python `warnings` module. They normally print a warning message to `sys.stderr`; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example, `Py_DECREF()` owned references and return an error value).

int **PyErr\_WarnEx** (*PyObject* \*category, const char \*message, *Py\_ssize\_t* stack\_level)

*Μέρος του Σταθερό ABI.* Issue a warning message. The *category* argument is a warning category (see below) or NULL; the *message* argument is a UTF-8 encoded string. *stack\_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack\_level* of 1 is the function calling `PyErr_WarnEx()`, 2 is the function above that, and so forth.

Warning categories must be subclasses of `PyExc_Warning`; `PyExc_Warning` is a subclass of `PyExc_Exception`; the default warning category is `PyExc_RuntimeWarning`. The standard Python warning categories are available as global variables whose names are enumerated at [Standard Warning Categories](#).

For information about warning control, see the documentation for the `warnings` module and the `-W` option in the command line documentation. There is no C API for warning control.

int **PyErr\_WarnExplicitObject** (*PyObject* \*category, *PyObject* \*message, *PyObject* \*filename, int lineno, *PyObject* \*module, *PyObject* \*registry)

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function `warnings.warn_explicit()`; see there for more information. The *module* and *registry* arguments may be set to NULL to get the default effect described there.

Νέο στην έκδοση 3.4.

int **PyErr\_WarnExplicit** (*PyObject* \*category, const char \*message, const char \*filename, int lineno, const char \*module, *PyObject* \*registry)

*Μέρος του Σταθερό ABI.* Similar to `PyErr_WarnExplicitObject()` except that *message* and *module* are UTF-8 encoded strings, and *filename* is decoded from the *filesystem encoding and error handler*.

int **PyErr\_WarnFormat** (*PyObject* \*category, *Py\_ssize\_t* stack\_level, const char \*format, ...)

*Μέρος του Σταθερό ABI.* Function similar to `PyErr_WarnEx()`, but use `PyUnicode_FromFormat()` to format the warning message. *format* is an ASCII-encoded string.

Νέο στην έκδοση 3.2.

int **PyErr\_ResourceWarning** (*PyObject* \*source, *Py\_ssize\_t* stack\_level, const char \*format, ...)

*Μέρος του Σταθερό ABI από την έκδοση 3.6.* Function similar to `PyErr_WarnFormat()`, but *category* is `ResourceWarning` and it passes *source* to `warnings.WarningMessage`.

Νέο στην έκδοση 3.6.

## 5.4 Querying the error indicator

*PyObject* \***PyErr\_Occurred** ()

*Επιστρεφόμενη τιμή: Borrowed reference.* *Μέρος του Σταθερό ABI.* Test whether the error indicator is set. If set, return the exception *type* (the first argument to the last call to one of the `PyErr_Set*` functions or to `PyErr_Restore()`). If not set, return NULL. You do not own a reference to the return value, so you do not need to `Py_DECREF()` it.

The caller must hold the GIL.

**Σημείωση:** Do not compare the return value to a specific exception; use `PyErr_ExceptionMatches()` instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

int **PyErr\_ExceptionMatches** (*PyObject* \*exc)

*Μέρος του Σταθερό ABI.* Equivalent to `PyErr_GivenExceptionMatches(PyErr_Occurred(), exc)`. This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

int **PyErr\_GivenExceptionMatches** (*PyObject* \*given, *PyObject* \*exc)

*Μέρος του Σταθερό ABI.* Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

void **PyErr\_Fetch** (*PyObject* \*\*ptype, *PyObject* \*\*pvalue, *PyObject* \*\*ptraceback)

*Μέρος του Σταθερό ABI.* Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to NULL. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be NULL even when the type object is not.

**Σημείωση:** This function is normally only used by code that needs to catch exceptions or by code that needs to save and restore the error indicator temporarily, e.g.:

```
{
    PyObject *type, *value, *traceback;
    PyErr_Fetch(&type, &value, &traceback);

    /* ... code that might produce other errors ... */

    PyErr_Restore(type, value, traceback);
}
```

void **PyErr\_Restore** (*PyObject* \*type, *PyObject* \*value, *PyObject* \*traceback)

*Μέρος του Σταθερό ABI.* Set the error indicator from the three objects. If the error indicator is already set, it is cleared first. If the objects are NULL, the error indicator is cleared. Do not pass a NULL type and non-NULL value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

**Σημείωση:** This function is normally only used by code that needs to save and restore the error indicator temporarily. Use `PyErr_Fetch()` to save the current error indicator.

void **PyErr\_NormalizeException** (*PyObject* \*\*exc, *PyObject* \*\*val, *PyObject* \*\*tb)

*Μέρος του Σταθερό ABI.* Under certain circumstances, the values returned by `PyErr_Fetch()` below can be «unnormalized», meaning that *\*exc* is a class object but *\*val* is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

**Σημείωση:** This function *does not* implicitly set the `__traceback__` attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
    PyException_SetTraceback(val, tb);
}
```



*PyObject* \*PyErr\_GetHandledException (void)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Retrieve the active exception instance, as would be returned by `sys.exception()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns a new reference to the exception or NULL. Does not modify the interpreter's exception state.

---

**Σημείωση:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_SetHandledException()` to restore or clear the exception state.

---

Νέο στην έκδοση 3.11.

void PyErr\_SetHandledException (*PyObject* \*exc)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Set the active exception, as known from `sys.exception()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. To clear the exception state, pass NULL.

---

**Σημείωση:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_GetHandledException()` to get the exception state.

---

Νέο στην έκδοση 3.11.

void PyErr\_GetExcInfo (*PyObject* \*\*ptype, *PyObject* \*\*pvalue, *PyObject* \*\*ptraceback)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Retrieve the old-style representation of the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be NULL. Does not modify the exception info state. This function is kept for backwards compatibility. Prefer using `PyErr_GetHandledException()`.

---

**Σημείωση:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_SetExcInfo()` to restore or clear the exception state.

---

Νέο στην έκδοση 3.3.

void PyErr\_SetExcInfo (*PyObject* \*type, *PyObject* \*value, *PyObject* \*traceback)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Set the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass NULL for all three arguments. This function is kept for backwards compatibility. Prefer using `PyErr_SetHandledException()`.

---

**Σημείωση:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_GetExcInfo()` to read the exception state.

---

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.11: The `type` and `traceback` arguments are no longer used and can be NULL. The interpreter now derives them from the exception instance (the `value` argument). The function still steals references of all three arguments.

## 5.5 Signal Handling

int **PyErr\_CheckSignals** ()

*Μέρος του Σταθερό ABI.* This function interacts with Python's signal handling.

If the function is called from the main thread and under the main Python interpreter, it checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the `signal` module is supported, this can invoke a signal handler written in Python.

The function attempts to handle all pending signals, and then returns 0. However, if a Python signal handler raises an exception, the error indicator is set and the function returns -1 immediately (such that other pending signals may not have been handled yet: they will be on the next `PyErr_CheckSignals()` invocation).

If the function is called from a non-main thread, or under a non-main Python interpreter, it does nothing and returns 0.

This function can be called by long-running C code that wants to be interruptible by user requests (such as by pressing Ctrl-C).

---

**Σημείωση:** The default Python signal handler for SIGINT raises the `KeyboardInterrupt` exception.

---

void **PyErr\_SetInterrupt** ()

*Μέρος του Σταθερό ABI.* Simulate the effect of a SIGINT signal arriving. This is equivalent to `PyErr_SetInterruptEx(SIGINT)`.

---

**Σημείωση:** This function is async-signal-safe. It can be called without the *GIL* and from a C signal handler.

---

int **PyErr\_SetInterruptEx** (int signum)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Simulate the effect of a signal arriving. The next time `PyErr_CheckSignals()` is called, the Python signal handler for the given signal number will be called.

This function can be called by C code that sets up its own signal handling and wants Python signal handlers to be invoked as expected when an interruption is requested (for example when the user presses Ctrl-C to interrupt an operation).

If the given signal isn't handled by Python (it was set to `signal.SIG_DFL` or `signal.SIG_IGN`), it will be ignored.

If *signum* is outside of the allowed range of signal numbers, -1 is returned. Otherwise, 0 is returned. The error indicator is never changed by this function.

---

**Σημείωση:** This function is async-signal-safe. It can be called without the *GIL* and from a C signal handler.

---

Νέο στην έκδοση 3.10.

int **PySignal\_SetWakeupFd** (int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. *fd* must be non-blocking. It returns the previous such file descriptor.

The value -1 disables the feature; this is the initial state. This is equivalent to `signal.set_wakeup_fd()` in Python, but without any error checking. *fd* should be a valid file descriptor. The function should only be called from the main thread.

Άλλαξε στην έκδοση 3.5: On Windows, the function now also supports socket handles.



## 5.6 Exception Classes

*PyObject* \*PyErr\_NewException (const char \*name, *PyObject* \*base, *PyObject* \*dict)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. This utility function creates and returns a new exception class. The *name* argument must be the name of the new exception, a C string of the form `module.classname`. The *base* and *dict* arguments are normally NULL. This creates a class object derived from `Exception` (accessible in C as `PyExc_Exception`).

The `__module__` attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

*PyObject* \*PyErr\_NewExceptionWithDoc (const char \*name, const char \*doc, *PyObject* \*base, *PyObject* \*dict)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Same as `PyErr_NewException()`, except that the new exception class can easily be given a docstring: If *doc* is non-NULL, it will be used as the docstring for the exception class.

Νέο στην έκδοση 3.2.

## 5.7 Exception Objects

*PyObject* \*PyException\_GetTraceback (*PyObject* \*ex)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the traceback associated with the exception as a new reference, as accessible from Python through the `__traceback__` attribute. If there is no traceback associated, this returns NULL.

int PyException\_SetTraceback (*PyObject* \*ex, *PyObject* \*tb)

Μέρος του Σταθερό ABI. Set the traceback associated with the exception to *tb*. Use `Py_None` to clear it.

*PyObject* \*PyException\_GetContext (*PyObject* \*ex)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the context (another exception instance during whose handling *ex* was raised) associated with the exception as a new reference, as accessible from Python through the `__context__` attribute. If there is no context associated, this returns NULL.

void PyException\_SetContext (*PyObject* \*ex, *PyObject* \*ctx)

Μέρος του Σταθερό ABI. Set the context associated with the exception to *ctx*. Use NULL to clear it. There is no type check to make sure that *ctx* is an exception instance. This steals a reference to *ctx*.

*PyObject* \*PyException\_GetCause (*PyObject* \*ex)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the cause (either an exception instance, or None, set by `raise ... from ...`) associated with the exception as a new reference, as accessible from Python through the `__cause__` attribute.

void PyException\_SetCause (*PyObject* \*ex, *PyObject* \*cause)

Μέρος του Σταθερό ABI. Set the cause associated with the exception to *cause*. Use NULL to clear it. There is no type check to make sure that *cause* is either an exception instance or None. This steals a reference to *cause*.

The `__suppress_context__` attribute is implicitly set to True by this function.

## 5.8 Unicode Exception Objects

The following functions are used to create and modify Unicode exceptions from C.

*PyObject* \*PyUnicodeDecodeError\_Create (const char \*encoding, const char \*object, *Py\_ssize\_t* length, *Py\_ssize\_t* start, *Py\_ssize\_t* end, const char \*reason)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a UnicodeDecodeError object with the attributes *encoding*, *object*, *length*, *start*, *end* and *reason*. *encoding* and *reason* are UTF-8 encoded strings.

*PyObject* \*PyUnicodeDecodeError\_GetEncoding (*PyObject* \*exc)

*PyObject* \*PyUnicodeEncodeError\_GetEncoding (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the *encoding* attribute of the given exception object.

*PyObject* \*PyUnicodeDecodeError\_GetObject (*PyObject* \*exc)

*PyObject* \*PyUnicodeEncodeError\_GetObject (*PyObject* \*exc)

*PyObject* \*PyUnicodeTranslateError\_GetObject (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the *object* attribute of the given exception object.

int PyUnicodeDecodeError\_GetStart (*PyObject* \*exc, *Py\_ssize\_t* \*start)

int PyUnicodeEncodeError\_GetStart (*PyObject* \*exc, *Py\_ssize\_t* \*start)

int PyUnicodeTranslateError\_GetStart (*PyObject* \*exc, *Py\_ssize\_t* \*start)

Μέρος του Σταθερό ABI. Get the *start* attribute of the given exception object and place it into \*start. *start* must not be NULL. Return 0 on success, -1 on failure.

int PyUnicodeDecodeError\_SetStart (*PyObject* \*exc, *Py\_ssize\_t* start)

int PyUnicodeEncodeError\_SetStart (*PyObject* \*exc, *Py\_ssize\_t* start)

int PyUnicodeTranslateError\_SetStart (*PyObject* \*exc, *Py\_ssize\_t* start)

Μέρος του Σταθερό ABI. Set the *start* attribute of the given exception object to *start*. Return 0 on success, -1 on failure.

int PyUnicodeDecodeError\_GetEnd (*PyObject* \*exc, *Py\_ssize\_t* \*end)

int PyUnicodeEncodeError\_GetEnd (*PyObject* \*exc, *Py\_ssize\_t* \*end)

int PyUnicodeTranslateError\_GetEnd (*PyObject* \*exc, *Py\_ssize\_t* \*end)

Μέρος του Σταθερό ABI. Get the *end* attribute of the given exception object and place it into \*end. *end* must not be NULL. Return 0 on success, -1 on failure.

int PyUnicodeDecodeError\_SetEnd (*PyObject* \*exc, *Py\_ssize\_t* end)

int PyUnicodeEncodeError\_SetEnd (*PyObject* \*exc, *Py\_ssize\_t* end)

int PyUnicodeTranslateError\_SetEnd (*PyObject* \*exc, *Py\_ssize\_t* end)

Μέρος του Σταθερό ABI. Set the *end* attribute of the given exception object to *end*. Return 0 on success, -1 on failure.

*PyObject* \*PyUnicodeDecodeError\_GetReason (*PyObject* \*exc)

*PyObject* \*PyUnicodeEncodeError\_GetReason (*PyObject* \*exc)

*PyObject* \*PyUnicodeTranslateError\_GetReason (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the *reason* attribute of the given exception object.

int PyUnicodeDecodeError\_SetReason (*PyObject* \*exc, const char \*reason)

int PyUnicodeEncodeError\_SetReason (*PyObject* \*exc, const char \*reason)

int PyUnicodeTranslateError\_SetReason (*PyObject* \*exc, const char \*reason)

Μέρος του Σταθερό ABI. Set the *reason* attribute of the given exception object to *reason*. Return 0 on success, -1 on failure.

## 5.9 Recursion Control

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically). They are also not needed for *tp\_call* implementations because the *call protocol* takes care of recursion handling.

int **Py\_EnterRecursiveCall** (const char \*where)

*Μέρος του Σταθερό ABI από την έκδοση 3.9.* Marks a point where a recursive C-level call is about to be performed.

If `USE_STACKCHECK` is defined, this function checks if the OS stack overflowed using `PyOS_CheckStack()`. If this is the case, it sets a `MemoryError` and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a `RecursionError` is set and a nonzero value is returned. Otherwise, zero is returned.

*where* should be a UTF-8 encoded string such as " in instance check" to be concatenated to the `RecursionError` message caused by the recursion depth limit.

Άλλαξε στην έκδοση 3.9: This function is now also available in the *limited API*.

void **Py\_LeaveRecursiveCall** (void)

*Μέρος του Σταθερό ABI από την έκδοση 3.9.* Ends a `Py_EnterRecursiveCall()`. Must be called once for each *successful* invocation of `Py_EnterRecursiveCall()`.

Άλλαξε στην έκδοση 3.9: This function is now also available in the *limited API*.

Properly implementing *tp\_repr* for container types requires special recursion handling. In addition to protecting the stack, *tp\_repr* also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to `reprlib.recursive_repr()`.

int **Py\_ReprEnter** (*PyObject* \*object)

*Μέρος του Σταθερό ABI.* Called at the beginning of the *tp\_repr* implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the *tp\_repr* implementation should return a string object indicating a cycle. As examples, `dict` objects return `{...}` and `list` objects return `[...]`.

The function will return a negative integer if the recursion limit is reached. In that case the *tp\_repr* implementation should typically return `NULL`.

Otherwise, the function returns zero and the *tp\_repr* implementation can continue normally.

void **Py\_ReprLeave** (*PyObject* \*object)

*Μέρος του Σταθερό ABI.* Ends a `Py_ReprEnter()`. Must be called once for each invocation of `Py_ReprEnter()` that returns zero.

## 5.10 Standard Exceptions

All standard Python exceptions are available as global variables whose names are `PyExc_` followed by the Python exception name. These have the type *PyObject\**; they are all class objects. For completeness, here are all the variables:

C Name	Python Name	Notes
<code>PyExc_BaseException</code>	<code>BaseException</code>	1
<code>PyExc_Exception</code>	<code>Exception</code>	Σελίδα 60, 1
<code>PyExc_ArithmeticError</code>	<code>ArithmeticError</code>	Σελίδα 60, 1
<code>PyExc_AssertionError</code>	<code>AssertionError</code>	

συνέχεια στην επόμενη σελίδα

Πίνακας 1 – συνεχίζεται από την προηγούμενη σελίδα

C Name	Python Name	Notes
PyExc_AttributeError	AttributeError	
PyExc_BlockingIOError	BlockingIOError	
PyExc_BrokenPipeError	BrokenPipeError	
PyExc_BufferError	BufferError	
PyExc_ChildProcessError	ChildProcessError	
PyExc_ConnectionAbortedE	ConnectionAbortedError	
PyExc_ConnectionError	ConnectionError	
PyExc_ConnectionRefusedE	ConnectionRefusedError	
PyExc_ConnectionResetErr	ConnectionResetError	
PyExc_EOFError	EOFError	
PyExc_FileExistsError	FileExistsError	
PyExc_FileNotFoundError	FileNotFoundError	
PyExc_FloatingPointError	FloatingPointError	
PyExc_GeneratorExit	GeneratorExit	
PyExc_ImportError	ImportError	
PyExc_IndentationError	IndentationError	
PyExc_IndexError	IndexError	
PyExc_InterruptedError	InterruptedError	
PyExc_IsADirectoryError	IsADirectoryError	
PyExc_KeyError	KeyError	
PyExc_KeyboardInterrupt	KeyboardInterrupt	
PyExc_LookupError	LookupError	Σελίδα 60, 1
PyExc_MemoryError	MemoryError	
PyExc_ModuleNotFoundError	ModuleNotFoundError	
PyExc_NameError	NameError	
PyExc_NotADirectoryError	NotADirectoryError	
PyExc_NotImplementedError	NotImplementedError	
PyExc_OSError	OSError	<sup>1</sup>
PyExc_OverflowError	OverflowError	
PyExc_PermissionError	PermissionError	
PyExc_ProcessLookupError	ProcessLookupError	
PyExc_RecursionError	RecursionError	
PyExc_ReferenceError	ReferenceError	
PyExc_RuntimeError	RuntimeError	
PyExc_StopAsyncIteration	StopAsyncIteration	
PyExc_StopIteration	StopIteration	
PyExc_SyntaxError	SyntaxError	
PyExc_SystemError	SystemError	
PyExc_SystemExit	SystemExit	
PyExc_TabError	TabError	
PyExc_TimeoutError	TimeoutError	
PyExc_TypeError	TypeError	
PyExc_UnboundLocalError	UnboundLocalError	
PyExc_UnicodeDecodeError	UnicodeDecodeError	
PyExc_UnicodeEncodeError	UnicodeEncodeError	
PyExc_UnicodeError	UnicodeError	
PyExc_UnicodeTranslateEr	UnicodeTranslateError	
PyExc_ValueError	ValueError	
PyExc_ZeroDivisionError	ZeroDivisionError	

Νέο στην έκδοση 3.3: PyExc\_BlockingIOError, PyExc\_BrokenPipeError, PyExc\_ChildProcessError, PyExc\_ConnectionError, PyExc\_ConnectionAbortedError, PyExc\_ConnectionRefusedError, PyExc\_ConnectionResetError, PyExc\_FileExistsError, PyExc\_FileNotFoundError, PyExc\_InterruptedError,

<sup>1</sup> This is a base class for other standard exceptions.

`PyExc_IsADirectoryError`, `PyExc_NotADirectoryError`, `PyExc_PermissionError`, `PyExc_ProcessLookupError` and `PyExc_TimeoutError` were introduced following [PEP 3151](#).

Νέο στην έκδοση 3.5: `PyExc_StopAsyncIteration` and `PyExc_RecursionError`.

Νέο στην έκδοση 3.6: `PyExc_ModuleNotFoundError`.

These are compatibility aliases to `PyExc_OSError`:

C Name	Notes
<code>PyExc_EnvironmentError</code>	
<code>PyExc_IOError</code>	
<code>PyExc_WindowsError</code>	<sup>2</sup>

Άλλαξε στην έκδοση 3.3: These aliases used to be separate exception types.

Notes:

## 5.11 Standard Warning Categories

All standard Python warning categories are available as global variables whose names are `PyExc_` followed by the Python exception name. These have the type *PyObject\**; they are all class objects. For completeness, here are all the variables:

C Name	Python Name	Notes
<code>PyExc_Warning</code>	<code>Warning</code>	<sup>3</sup>
<code>PyExc_BytesWarning</code>	<code>BytesWarning</code>	
<code>PyExc_DeprecationWarning</code>	<code>DeprecationWarning</code>	
<code>PyExc_FutureWarning</code>	<code>FutureWarning</code>	
<code>PyExc_ImportWarning</code>	<code>ImportWarning</code>	
<code>PyExc_PendingDeprecationWarning</code>	<code>PendingDeprecationWarning</code>	
<code>PyExc_ResourceWarning</code>	<code>ResourceWarning</code>	
<code>PyExc_RuntimeWarning</code>	<code>RuntimeWarning</code>	
<code>PyExc_SyntaxWarning</code>	<code>SyntaxWarning</code>	
<code>PyExc_UnicodeWarning</code>	<code>UnicodeWarning</code>	
<code>PyExc_UserWarning</code>	<code>UserWarning</code>	

Νέο στην έκδοση 3.2: `PyExc_ResourceWarning`.

Notes:

<sup>2</sup> Only defined on Windows; protect code that uses this by testing that the preprocessor macro `MS_WINDOWS` is defined.

<sup>3</sup> This is a base class for other standard warning categories.



The functions in this chapter perform various utility tasks, ranging from helping C code be more portable across platforms, using Python modules from C, and parsing function arguments and constructing Python values from C values.

## 6.1 Operating System Utilities

*PyObject* \*PyOS\_FSPath (*PyObject* \*path)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.6. Return the file system representation for *path*. If the object is a `str` or `bytes` object, then a new *strong reference* is returned. If the object implements the `os.PathLike` interface, then `__fspath__()` is returned as long as it is a `str` or `bytes` object. Otherwise `TypeError` is raised and `NULL` is returned.

Νέο στην έκδοση 3.6.

int Py\_FdIsInteractive (FILE \*fp, const char \*filename)

Return true (nonzero) if the standard I/O file *fp* with name *filename* is deemed interactive. This is the case for files for which `isatty(fileno(fp))` is true. If the global flag `Py_InteractiveFlag` is true, this function also returns true if the *filename* pointer is `NULL` or if the name is equal to one of the strings `'<stdin>'` or `'???'`.

void PyOS\_BeforeFork ()

Μέρος του Σταθερό ABI on platforms with `fork()` από την έκδοση 3.7. Function to prepare some internal state before a process fork. This should be called before calling `fork()` or any similar function that clones the current process. Only available on systems where `fork()` is defined.

**Προειδοποίηση:** The C `fork()` call should only be made from the *«main» thread* (of the *«main» interpreter*). The same is true for `PyOS_BeforeFork()`.

Νέο στην έκδοση 3.7.

void PyOS\_AfterFork\_Parent ()

Μέρος του Σταθερό ABI on platforms with `fork()` από την έκδοση 3.7. Function to update some internal state after a process fork. This should be called from the parent process after calling `fork()` or any similar

function that clones the current process, regardless of whether process cloning was successful. Only available on systems where `fork()` is defined.

**Προειδοποίηση:** The C `fork()` call should only be made from the «*main*» thread (of the «*main*» interpreter). The same is true for `PyOS_AfterFork_Parent()`.

Νέο στην έκδοση 3.7.

void **PyOS\_AfterFork\_Child()**

*Μέρος του Σταθερό ABI on platforms with fork()* από την έκδοση 3.7. Function to update internal interpreter state after a process fork. This must be called from the child process after calling `fork()`, or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where `fork()` is defined.

**Προειδοποίηση:** The C `fork()` call should only be made from the «*main*» thread (of the «*main*» interpreter). The same is true for `PyOS_AfterFork_Child()`.

Νέο στην έκδοση 3.7.

**Δείτε επίσης:**

`os.register_at_fork()` allows registering custom Python functions to be called by `PyOS_BeforeFork()`, `PyOS_AfterFork_Parent()` and `PyOS_AfterFork_Child()`.

void **PyOS\_AfterFork()**

*Μέρος του Σταθερό ABI on platforms with fork()*. Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

Αποσύρθηκε στην έκδοση 3.7: This function is superseded by `PyOS_AfterFork_Child()`.

int **PyOS\_CheckStack()**

*Μέρος του Σταθερό ABI on platforms with USE\_STACKCHECK* από την έκδοση 3.7. Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when `USE_STACKCHECK` is defined (currently on certain versions of Windows using the Microsoft Visual C++ compiler). `USE_STACKCHECK` will be defined automatically; you should never change the definition in your own code.

typedef void (\***PyOS\_sighandler\_t**)(int)

*Μέρος του Σταθερό ABI.*

*PyOS\_sighandler\_t* **PyOS\_getsig**(int *i*)

*Μέρος του Σταθερό ABI.* Return the current signal handler for signal *i*. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly!

*PyOS\_sighandler\_t* **PyOS\_setsig**(int *i*, *PyOS\_sighandler\_t* *h*)

*Μέρος του Σταθερό ABI.* Set the signal handler for signal *i* to be *h*; return the old signal handler. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly!

wchar\_t \***Py\_DecodeLocale**(const char \**arg*, size\_t \**size*)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.*

**Προειδοποίηση:** This function should not be called directly: use the `PyConfig` API with the `PyConfig_SetBytesString()` function which ensures that *Python is preinitialized*.

This function must not be called before *Python is preinitialized* and so that the `LC_CTYPE` locale is properly configured: see the `Py_PreInitialize()` function.



Decode a byte string from the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, undecodable bytes are decoded as characters in range U+DC80..U+DCFF; and if a byte sequence can be decoded as a surrogate character, the bytes are escaped using the surrogateescape error handler instead of decoding them.

Return a pointer to a newly allocated wide character string, use `PyMem_RawFree()` to free the memory. If `size` is not NULL, write the number of wide characters excluding the null character into `*size`

Return NULL on decoding error or memory allocation error. If `size` is not NULL, `*size` is set to `(size_t)-1` on memory error or set to `(size_t)-2` on decoding error.

The *filesystem encoding and error handler* are selected by `PyConfig_Read()`: see *filesystem\_encoding* and *filesystem\_errors* members of `PyConfig`.

Decoding errors should never happen, unless there is a bug in the C library.

Use the `Py_EncodeLocale()` function to encode the character string back to a byte string.

#### Δείτε επίσης:

The `PyUnicode_DecodeFSDefaultAndSize()` and `PyUnicode_DecodeLocaleAndSize()` functions.

Νέο στην έκδοση 3.5.

Αλλάξε στην έκδοση 3.7: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Αλλάξε στην έκδοση 3.8: The function now uses the UTF-8 encoding on Windows if `Py_LegacyWindowsFSEncodingFlag` is zero;

char **\*Py\_EncodeLocale** (const wchar\_t \*text, size\_t \*error\_pos)

Μέρος του Σταθερού ABI από την έκδοση 3.7. Encode a wide character string to the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Return a pointer to a newly allocated byte string, use `PyMem_Free()` to free the memory. Return NULL on encoding error or memory allocation error.

If `error_pos` is not NULL, `*error_pos` is set to `(size_t)-1` on success, or set to the index of the invalid character on encoding error.

The *filesystem encoding and error handler* are selected by `PyConfig_Read()`: see *filesystem\_encoding* and *filesystem\_errors* members of `PyConfig`.

Use the `Py_DecodeLocale()` function to decode the bytes string back to a wide character string.

**Προειδοποίηση:** This function must not be called before *Python is preinitialized* and so that the LC\_CTYPE locale is properly configured: see the `Py_PreInitialize()` function.

#### Δείτε επίσης:

The `PyUnicode_EncodeFSDefault()` and `PyUnicode_EncodeLocale()` functions.

Νέο στην έκδοση 3.5.

Αλλάξε στην έκδοση 3.7: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Αλλάξε στην έκδοση 3.8: The function now uses the UTF-8 encoding on Windows if `Py_LegacyWindowsFSEncodingFlag` is zero.

## 6.2 System Functions

These are utility functions that make functionality from the `sys` module accessible to C code. They all work with the current interpreter thread's `sys` module's dict, which is contained in the internal thread state structure.

*PyObject* \***PySys\_GetObject** (const char \*name)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return the object *name* from the `sys` module or `NULL` if it does not exist, without setting an exception.

int **PySys\_SetObject** (const char \*name, *PyObject* \*v)

*Μέρος του Σταθερό ABI.* Set *name* in the `sys` module to *v* unless *v* is `NULL`, in which case *name* is deleted from the `sys` module. Returns 0 on success, -1 on error.

void **PySys\_ResetWarnOptions** ()

*Μέρος του Σταθερό ABI.* Reset `sys.warnoptions` to an empty list. This function may be called prior to `Py_Initialize()`.

void **PySys\_AddWarnOption** (const wchar\_t \*s)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.warnoptions` should be used instead, see *Python Initialization Configuration*.

Append *s* to `sys.warnoptions`. This function must be called prior to `Py_Initialize()` in order to affect the warnings filter list.

Αποσύρθηκε στην έκδοση 3.11.

void **PySys\_AddWarnOptionUnicode** (*PyObject* \*unicode)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.warnoptions` should be used instead, see *Python Initialization Configuration*.

Append *unicode* to `sys.warnoptions`.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of `warnings` in `Py_Initialize()` to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

Αποσύρθηκε στην έκδοση 3.11.

void **PySys\_SetPath** (const wchar\_t \*path)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.module_search_paths` and `PyConfig.module_search_paths_set` should be used instead, see *Python Initialization Configuration*.

Set `sys.path` to a list object of paths found in *path* which should be a list of paths separated with the platform's search path delimiter (`:` on Unix, `;` on Windows).

Αποσύρθηκε στην έκδοση 3.11.

void **PySys\_WriteStdout** (const char \*format, ...)

*Μέρος του Σταθερό ABI.* Write the output string described by *format* to `sys.stdout`. No exceptions are raised, even if truncation occurs (see below).

*format* should limit the total size of the formatted output string to 1000 bytes or less – after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted «%s» formats should occur; these should be limited using «%.<N>s» where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for «%f», which can print hundreds of digits for very large numbers.

If a problem occurs, or `sys.stdout` is unset, the formatted message is written to the real (C level) *stdout*.

void **PySys\_WriteStderr** (const char \*format, ...)

*Μέρος του Σταθερό ABI.* As `PySys_WriteStdout()`, but write to `sys.stderr` or *stderr* instead.

void **PySys\_FormatStdout** (const char \*format, ...)

*Μέρος του Σταθερό ABI.* Function similar to `PySys_WriteStdout()` but format the message using `PyUnicode_FromFormatV()` and don't truncate the message to an arbitrary length.

Νέο στην έκδοση 3.2.

void **PySys\_FormatStderr** (const char \*format, ...)

*Μέρος του Σταθερό ABI.* As `PySys_FormatStdout()`, but write to `sys.stderr` or `stderr` instead.

Νέο στην έκδοση 3.2.

void **PySys\_AddXOption** (const wchar\_t \*s)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* This API is kept for backward compatibility: setting `PyConfig.xoptions` should be used instead, see *Python Initialization Configuration*.

Parse `s` as a set of `-X` options and add them to the current options mapping as returned by `PySys_GetXOptions()`. This function may be called prior to `Py_Initialize()`.

Νέο στην έκδοση 3.2.

Αποσύρθηκε στην έκδοση 3.11.

*PyObject* \***PySys\_GetXOptions** ()

*Επιστρεφόμενη τιμή: Borrowed reference.* *Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return the current dictionary of `-X` options, similarly to `sys._xoptions`. On error, NULL is returned and an exception is set.

Νέο στην έκδοση 3.2.

int **PySys\_Audit** (const char \*event, const char \*format, ...)

Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure.

If any hooks have been added, `format` and other arguments will be used to construct a tuple to pass. Apart from `N`, the same format characters as used in `Py_BuildValue()` are available. If the built value is not a tuple, it will be added into a single-element tuple. (The `N` format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

Note that `#` format characters should always be treated as `Py_ssize_t`, regardless of whether `PY_SSIZE_T_CLEAN` was defined.

`sys.audit()` performs the same function from Python code.

Νέο στην έκδοση 3.8.

Άλλαξε στην έκδοση 3.8.2: Require `Py_ssize_t` for `#` format characters. Previously, an unavoidable deprecation warning was raised.

int **PySys\_AddAuditHook** (*PyAuditHookFunction* hook, void \*userData)

Append the callable `hook` to the list of active auditing hooks. Return zero on success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

The `userData` pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

This function is safe to call before `Py_Initialize()`. When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from `Exception` (other errors will not be silenced).

The hook function is always called with the GIL held by the Python interpreter that raised the event.

See **PEP 578** for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

If the interpreter is initialized, this function raises an auditing event `sys.addaudithook` with no arguments. If any existing hooks raise an exception derived from `Exception`, the new hook will not be

added and the exception is cleared. As a result, callers cannot assume that their hook has been added unless they control all existing hooks.

typedef int (**\*Py\_AuditHookFunction**)(const char \*event, *PyObject* \*args, void \*userData)

The type of the hook function. *event* is the C string event argument passed to *PySys\_Audit()*. *args* is guaranteed to be a *PyTupleObject*. *userData* is the argument passed to *PySys\_AddAuditHook()*.

Νέο στην έκδοση 3.8.

## 6.3 Process Control

void **Py\_FatalError** (const char \*message)

*Μέρος του Σταθερό ABI.* Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function *abort()* is called which will attempt to produce a *core* file.

The *Py\_FatalError()* function is replaced with a macro which logs automatically the name of the current function, unless the *Py\_LIMITED\_API* macro is defined.

Άλλαξε στην έκδοση 3.9: Log the function name automatically.

void **Py\_Exit** (int status)

*Μέρος του Σταθερό ABI.* Exit the current process. This calls *Py\_FinalizeEx()* and then calls the standard C library function *exit(status)*. If *Py\_FinalizeEx()* indicates an error, the exit status is set to 120.

Άλλαξε στην έκδοση 3.6: Errors from finalization no longer ignored.

int **Py\_AtExit** (void (\*func)())

*Μέρος του Σταθερό ABI.* Register a cleanup function to be called by *Py\_FinalizeEx()*. The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful, *Py\_AtExit()* returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

## 6.4 Importing Modules

*PyObject* \***PyImport\_ImportModule** (const char \*name)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* This is a wrapper around *PyImport\_Import()* which takes a *const char\** as an argument instead of a *PyObject\**.

*PyObject* \***PyImport\_ImportModuleNoBlock** (const char \*name)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* This function is a deprecated alias of *PyImport\_ImportModule()*.

Άλλαξε στην έκδοση 3.3: This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

*PyObject* \***PyImport\_ImportModuleEx** (const char \*name, *PyObject* \*globals, *PyObject* \*locals, *PyObject* \*fromlist)

*Επιστρεφόμενη τιμή:* New reference. Import a module. This is best described by referring to the built-in Python function *\_\_import\_\_()*.

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for *\_\_import\_\_()*, the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with `PyImport_ImportModule()`.

**`PyObject*PyImport_ImportModuleLevelObject`** (`PyObject*` name, `PyObject*` globals, `PyObject*` locals, `PyObject*` fromlist, int level)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Import a module. This is best described by referring to the built-in Python function `__import__()`, as the standard `__import__()` function calls this function directly.

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for `__import__()`, the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Νέο στην έκδοση 3.3.

**`PyObject*PyImport_ImportModuleLevel`** (const char\* name, `PyObject*` globals, `PyObject*` locals, `PyObject*` fromlist, int level)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Similar to `PyImport_ImportModuleLevelObject()`, but the name is a UTF-8 encoded string instead of a Unicode object.

Άλλαξε στην έκδοση 3.3: Negative values for *level* are no longer accepted.

**`PyObject*PyImport_Import`** (`PyObject*` name)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. This is a higher-level interface that calls the current «import hook function» (with an explicit *level* of 0, meaning absolute import). It invokes the `__import__()` function from the `__builtins__` of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

This function always uses absolute imports.

**`PyObject*PyImport_ReloadModule`** (`PyObject*` m)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Reload a module. Return a new reference to the reloaded module, or NULL with an exception set on failure (the module still exists in this case).

**`PyObject*PyImport_AddModuleObject`** (`PyObject*` name)

*Επιστρεφόμενη τιμή:* Borrowed reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Return the module object corresponding to a module name. The *name* argument may be of the form `package.module`. First check the modules dictionary if there's one there, and if not, create a new one and insert it in the modules dictionary. Return NULL with an exception set on failure.

---

**Σημείωση:** This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use `PyImport_ImportModule()` or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

---

Νέο στην έκδοση 3.3.

**`PyObject*PyImport_AddModule`** (const char\* name)

*Επιστρεφόμενη τιμή:* Borrowed reference. Μέρος του Σταθερό ABI. Similar to `PyImport_AddModuleObject()`, but the name is a UTF-8 encoded string instead of a Unicode object.

**`PyObject*PyImport_ExecCodeModule`** (const char\* name, `PyObject*` co)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Given a module name (possibly of the form `package.module`) and a code object read from a Python bytecode file or obtained from the built-in function `compile()`, load the module. Return a new reference to the module object, or NULL with an exception set if an error occurred. *name* is removed from `sys.modules` in error cases, even if *name* was already in `sys.modules` on entry to `PyImport_ExecCodeModule()`. Leaving incompletely initialized modules in `sys.modules` is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's `__spec__` and `__loader__` will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's `__loader__` (if set) and to an instance of `SourceFileLoader` otherwise.

The module's `__file__` attribute will be set to the code object's `co_filename`. If applicable, `__cached__` will also be set.

This function will reload the module if it was already imported. See `PyImport_ReloadModule()` for the intended way to reload a module.

If `name` points to a dotted name of the form `package.module`, any package structures not already created will still not be created.

See also `PyImport_ExecCodeModuleEx()` and `PyImport_ExecCodeModuleWithPathnames()`.

**PyObject\*PyImport\_ExecCodeModuleEx** (const char \*name, PyObject \*co, const char \*pathname)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Like `PyImport_ExecCodeModule()`, but the `__file__` attribute of the module object is set to `pathname` if it is non-NULL.

See also `PyImport_ExecCodeModuleWithPathnames()`.

**PyObject\*PyImport\_ExecCodeModuleObject** (PyObject \*name, PyObject \*co, PyObject \*pathname, PyObject \*cpathname)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Like `PyImport_ExecCodeModuleEx()`, but the `__cached__` attribute of the module object is set to `cpathname` if it is non-NULL. Of the three functions, this is the preferred one to use.

Νέο στην έκδοση 3.3.

**PyObject\*PyImport\_ExecCodeModuleWithPathnames** (const char \*name, PyObject \*co, const char \*pathname, const char \*cpathname)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Like `PyImport_ExecCodeModuleObject()`, but `name`, `pathname` and `cpathname` are UTF-8 encoded strings. Attempts are also made to figure out what the value for `pathname` should be from `cpathname` if the former is set to NULL.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.3: Uses `imp.source_from_cache()` in calculating the source path if only the bytecode path is provided.

**longPyImport\_GetMagicNumber** ()

*Μέρος του Σταθερό ABI.* Return the magic number for Python bytecode files (a.k.a. `.pyc` file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns `-1` on error.

Άλλαξε στην έκδοση 3.3: Return value of `-1` upon failure.

**const char\*PyImport\_GetMagicTag** ()

*Μέρος του Σταθερό ABI.* Return the magic tag string for **PEP 3147** format Python bytecode file names. Keep in mind that the value at `sys.implementation.cache_tag` is authoritative and should be used instead of this function.

Νέο στην έκδοση 3.2.

**PyObject\*PyImport\_GetModuleDict** ()

*Επιστρεφόμενη τιμή:* Borrowed reference. Μέρος του Σταθερό ABI. Return the dictionary used for the module administration (a.k.a. `sys.modules`). Note that this is a per-interpreter variable.

**PyObject\*PyImport\_GetModule** (PyObject \*name)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.8. Return the already imported module with the given name. If the module has not been imported yet then returns NULL but does not set an error. Returns NULL and sets an error if the lookup failed.

Νέο στην έκδοση 3.7.



*PyObject* \*PyImport\_GetImporter (*PyObject* \*path)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI. Return a finder object for a `sys.path/pkg.__path__` item *path*, possibly by fetching it from the `sys.path_importer_cache` dict. If it wasn't yet cached, traverse `sys.path_hooks` until a hook is found that can handle the path item. Return `None` if no hook could; this tells our caller that the *path based finder* could not find a finder for this path item. Cache the result in `sys.path_importer_cache`. Return a new reference to the finder object.

int PyImport\_ImportFrozenModuleObject (*PyObject* \*name)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Load a frozen module named *name*. Return 1 for success, 0 if the module is not found, and -1 with an exception set if the initialization failed. To access the imported module on a successful load, use `PyImport_ImportModule()`. (Note the misnomer — this function would reload the module if it was already imported.)

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.4: The `__file__` attribute is no longer set on the module.

int PyImport\_ImportFrozenModule (const char \*name)

Μέρος του Σταθερό ABI. Similar to `PyImport_ImportFrozenModuleObject()`, but the name is a UTF-8 encoded string instead of a Unicode object.

struct `_frozen`

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see `Tools/freeze/` in the Python source distribution). Its definition, found in `Include/import.h`, is:

```
struct _frozen {
    const char *name;
    const unsigned char *code;
    int size;
    bool is_package;
};
```

Άλλαξε στην έκδοση 3.11: The new `is_package` field indicates whether the module is a package or not. This replaces setting the `size` field to a negative value.

const struct `_frozen` \*PyImport\_FrozenModules

This pointer is initialized to point to an array of `_frozen` records, terminated by one whose members are all `NULL` or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

int PyImport\_AppendInittab (const char \*name, *PyObject* \*(\*initfunc)(void))

Μέρος του Σταθερό ABI. Add a single module to the existing table of built-in modules. This is a convenience wrapper around `PyImport_ExtendInittab()`, returning -1 if the table could not be extended. The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import. This should be called before `Py_Initialize()`.

struct `_inittab`

Structure describing a single entry in the list of built-in modules. Programs which embed Python may use an array of these structures in conjunction with `PyImport_ExtendInittab()` to provide additional built-in modules. The structure consists of two members:

const char \*name

The module name, as an ASCII encoded string.

*PyObject* \*(\*initfunc)(void)

Initialization function for a module built into the interpreter.

int PyImport\_ExtendInittab (struct `_inittab` \*newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains `NULL` for the *name* field; failure to provide the sentinel value can result in a memory fault. Returns 0 on success or -1 if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This must be called before `Py_Initialize()`.

If Python is initialized multiple times, `PyImport_AppendInittab()` or `PyImport_ExtendInittab()` must be called before each Python initialization.

## 6.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the `marshal` module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports two versions of the data format: version 0 is the historical version, version 1 shares interned strings in the file, and upon unmarshalling. Version 2 uses a binary format for floating point numbers. `Py_MARSHAL_VERSION` indicates the current file format (currently 2).

void **PyMarshal\_WriteLongToFile** (long value, FILE \*file, int version)

Marshal a long integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native long type. *version* indicates the file format.

This function can fail, in which case it sets the error indicator. Use `PyErr_Occurred()` to check for that.

void **PyMarshal\_WriteObjectToFile** (PyObject \*value, FILE \*file, int version)

Marshal a Python object, *value*, to *file*. *version* indicates the file format.

This function can fail, in which case it sets the error indicator. Use `PyErr_Occurred()` to check for that.

PyObject \***PyMarshal\_WriteObjectToString** (PyObject \*value, int version)

*Επιστρεφόμενη τιμή: New reference.* Return a bytes object containing the marshalled representation of *value*. *version* indicates the file format.

The following functions allow marshalled values to be read back in.

long **PyMarshal\_ReadLongFromFile** (FILE \*file)

Return a C long from the data stream in a FILE\* opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of long.

On error, sets the appropriate exception (EOFError) and returns -1.

int **PyMarshal\_ReadShortFromFile** (FILE \*file)

Return a C short from the data stream in a FILE\* opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of short.

On error, sets the appropriate exception (EOFError) and returns -1.

PyObject \***PyMarshal\_ReadObjectFromFile** (FILE \*file)

*Επιστρεφόμενη τιμή: New reference.* Return a Python object from the data stream in a FILE\* opened for reading.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject \***PyMarshal\_ReadLastObjectFromFile** (FILE \*file)

*Επιστρεφόμενη τιμή: New reference.* Return a Python object from the data stream in a FILE\* opened for reading. Unlike `PyMarshal_ReadObjectFromFile()`, this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject \***PyMarshal\_ReadObjectFromString** (const char \*data, Py\_ssize\_t len)

*Επιστρεφόμενη τιμή: New reference.* Return a Python object from the data stream in a byte buffer containing *len* bytes pointed to by *data*.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.



## 6.6 Parsing arguments and building values

These functions are useful when creating your own extensions functions and methods. Additional information and examples are available in [extending-index](#).

The first three of these functions described, `PyArg_ParseTuple()`, `PyArg_ParseTupleAndKeywords()`, and `PyArg_Parse()`, all use *format strings* which are used to tell the function about the expected arguments. The format strings use the same syntax for each of these functions.

### 6.6.1 Parsing arguments

A format string consists of zero or more «format units.» A format unit describes one Python object; it is usually a single character or a parenthesized sequence of format units. With a few exceptions, a format unit that is not a parenthesized sequence normally corresponds to a single address argument to these functions. In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that matches the format unit; and the entry in [square] brackets is the type of the C variable(s) whose address should be passed.

#### Strings and buffers

These formats allow accessing an object as a contiguous chunk of memory. You don't have to provide raw storage for the returned unicode or bytes area.

Unless otherwise stated, buffers are not NUL-terminated.

There are three ways strings and buffers can be converted to C:

- Formats such as `y*` and `s*` fill a `Py_buffer` structure. This locks the underlying buffer so that the caller can subsequently use the buffer even inside a `Py_BEGIN_ALLOW_THREADS` block without the risk of mutable data being resized or destroyed. As a result, **you have to call** `PyBuffer_Release()` after you have finished processing the data (or in any early abort case).
- The `es`, `es#`, `et` and `et#` formats allocate the result buffer. **You have to call** `PyMem_Free()` after you have finished processing the data (or in any early abort case).
- Other formats take a `str` or a read-only *bytes-like object*, such as `bytes`, and provide a `const char *` pointer to its buffer. In this case the buffer is «borrowed»: it is managed by the corresponding Python object, and shares the lifetime of this object. You won't have to release any memory yourself.

To ensure that the underlying buffer may be safely borrowed, the object's `PyBufferProcs.bf_releasebuffer` field must be `NULL`. This disallows common mutable objects such as `bytearray`, but also some read-only objects such as `memoryview` of `bytes`.

Besides this `bf_releasebuffer` requirement, there is no check to verify whether the input object is immutable (e.g. whether it would honor a request for a writable buffer, or whether another thread can mutate the data).

---

**Σημείωση:** For all # variants of formats (`s#`, `y#`, etc.), the macro `PY_SSIZE_T_CLEAN` must be defined before including `Python.h`. On Python 3.9 and older, the type of the length argument is `Py_ssize_t` if the `PY_SSIZE_T_CLEAN` macro is defined, or `int` otherwise.

---

#### **s (str) [const char \*]**

Convert a Unicode object to a C pointer to a character string. A pointer to an existing string is stored in the character pointer variable whose address you pass. The C string is NUL-terminated. The Python string must not contain embedded null code points; if it does, a `ValueError` exception is raised. Unicode objects are converted to C strings using `'utf-8'` encoding. If this conversion fails, a `UnicodeError` is raised.

---

**Σημείωση:** This format does not accept *bytes-like objects*. If you want to accept filesystem paths and convert them to C character strings, it is preferable to use the `O&` format with `PyUnicode_FSConverter()` as

*converter.*

---

Άλλαξε στην έκδοση 3.5: Previously, `TypeError` was raised when embedded null code points were encountered in the Python string.

**s\* (str or bytes-like object) [Py\_buffer]**

This format accepts Unicode objects as well as bytes-like objects. It fills a `Py_buffer` structure provided by the caller. In this case the resulting C string may contain embedded NUL bytes. Unicode objects are converted to C strings using `'utf-8'` encoding.

**s# (str, read-only bytes-like object) [const char \*, Py\_ssize\_t]**

Like `s*`, except that it provides a *borrowed buffer*. The result is stored into two C variables, the first one a pointer to a C string, the second one its length. The string may contain embedded null bytes. Unicode objects are converted to C strings using `'utf-8'` encoding.

**z (str or None) [const char \*]**

Like `s`, but the Python object may also be `None`, in which case the C pointer is set to `NULL`.

**z\* (str, bytes-like object or None) [Py\_buffer]**

Like `s*`, but the Python object may also be `None`, in which case the `buf` member of the `Py_buffer` structure is set to `NULL`.

**z# (str, read-only bytes-like object or None) [const char \*, Py\_ssize\_t]**

Like `s#`, but the Python object may also be `None`, in which case the C pointer is set to `NULL`.

**y (read-only bytes-like object) [const char \*]**

This format converts a bytes-like object to a C pointer to a *borrowed* character string; it does not accept Unicode objects. The bytes buffer must not contain embedded null bytes; if it does, a `ValueError` exception is raised.

Άλλαξε στην έκδοση 3.5: Previously, `TypeError` was raised when embedded null bytes were encountered in the bytes buffer.

**y\* (bytes-like object) [Py\_buffer]**

This variant on `s*` doesn't accept Unicode objects, only bytes-like objects. **This is the recommended way to accept binary data.**

**y# (read-only bytes-like object) [const char \*, Py\_ssize\_t]**

This variant on `s#` doesn't accept Unicode objects, only bytes-like objects.

**S (bytes) [PyObject\*]**

Requires that the Python object is a `bytes` object, without attempting any conversion. Raises `TypeError` if the object is not a bytes object. The C variable may also be declared as `PyObject*`.

**Y (bytearray) [PyByteArrayObject\*]**

Requires that the Python object is a `bytearray` object, without attempting any conversion. Raises `TypeError` if the object is not a `bytearray` object. The C variable may also be declared as `PyObject*`.

**u (str) [const Py\_UNICODE\*]**

Convert a Python Unicode object to a C pointer to a NUL-terminated buffer of Unicode characters. You must pass the address of a `Py_UNICODE` pointer variable, which will be filled with the pointer to an existing Unicode buffer. Please note that the width of a `Py_UNICODE` character depends on compilation options (it is either 16 or 32 bits). The Python string must not contain embedded null code points; if it does, a `ValueError` exception is raised.

Άλλαξε στην έκδοση 3.5: Previously, `TypeError` was raised when embedded null code points were encountered in the Python string.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsWideCharString()`.

**u# (str) [const Py\_UNICODE\*, Py\_ssize\_t]**

This variant on `u` stores into two C variables, the first one a pointer to a Unicode data buffer, the second one its length. This variant allows null code points.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsWideCharString()`.

**z (str or None) [const Py\_UNICODE \*]**

Like `u`, but the Python object may also be `None`, in which case the `Py_UNICODE` pointer is set to `NULL`.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsWideCharString()`.

**z# (str or None) [const Py\_UNICODE \*, Py\_ssize\_t]**

Like `u#`, but the Python object may also be `None`, in which case the `Py_UNICODE` pointer is set to `NULL`.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsWideCharString()`.

**U (str) [PyObject \*]**

Requires that the Python object is a Unicode object, without attempting any conversion. Raises `TypeError` if the object is not a Unicode object. The C variable may also be declared as `PyObject*`.

**w\* (read-write bytes-like object) [Py\_buffer]**

This format accepts any object which implements the read-write buffer interface. It fills a `Py_buffer` structure provided by the caller. The buffer may contain embedded null bytes. The caller have to call `PyBuffer_Release()` when it is done with the buffer.

**es (str) [const char \*encoding, char \*\*buffer]**

This variant on `s` is used for encoding Unicode into a character buffer. It only works for encoded data without embedded NUL bytes.

This format requires two arguments. The first is only used as input, and must be a `const char*` which points to the name of an encoding as a NUL-terminated string, or `NULL`, in which case `'utf-8'` encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a `char**`; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument.

`PyArg_ParseTuple()` will allocate a buffer of the needed size, copy the encoded data into this buffer and adjust `*buffer` to reference the newly allocated storage. The caller is responsible for calling `PyMem_Free()` to free the allocated buffer after use.

**et (str, bytes or bytearray) [const char \*encoding, char \*\*buffer]**

Same as `es` except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

**es# (str) [const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length]**

This variant on `s#` is used for encoding Unicode into a character buffer. Unlike the `es` format, this variant allows input data which contains NUL characters.

It requires three arguments. The first is only used as input, and must be a `const char*` which points to the name of an encoding as a NUL-terminated string, or `NULL`, in which case `'utf-8'` encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a `char**`; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument. The third argument must be a pointer to an integer; the referenced integer will be set to the number of bytes in the output buffer.

There are two modes of operation:

If `*buffer` points a `NULL` pointer, the function will allocate a buffer of the needed size, copy the encoded data into this buffer and set `*buffer` to reference the newly allocated storage. The caller is responsible for calling `PyMem_Free()` to free the allocated buffer after usage.

If `*buffer` points to a non-`NULL` pointer (an already allocated buffer), `PyArg_ParseTuple()` will use this location as the buffer and interpret the initial value of `*buffer_length` as the buffer size. It will then copy the encoded data into the buffer and NUL-terminate it. If the buffer is not large enough, a `ValueError` will be set.

In both cases, `*buffer_length` is set to the length of the encoded data without the trailing NUL byte.

**et# (str, bytes or bytearray) [const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length]**

Same as `es#` except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

## Numbers

### **b(int) [unsigned char]**

Convert a nonnegative Python integer to an unsigned tiny int, stored in a C `unsigned char`.

### **B(int) [unsigned char]**

Convert a Python integer to a tiny int without overflow checking, stored in a C `unsigned char`.

### **h(int) [short int]**

Convert a Python integer to a C `short int`.

### **H(int) [unsigned short int]**

Convert a Python integer to a C `unsigned short int`, without overflow checking.

### **i(int) [int]**

Convert a Python integer to a plain C `int`.

### **I(int) [unsigned int]**

Convert a Python integer to a C `unsigned int`, without overflow checking.

### **l(int) [long int]**

Convert a Python integer to a C `long int`.

### **k(int) [unsigned long]**

Convert a Python integer to a C `unsigned long` without overflow checking.

### **L(int) [long long]**

Convert a Python integer to a C `long long`.

### **K(int) [unsigned long long]**

Convert a Python integer to a C `unsigned long long` without overflow checking.

### **n(int) [Py\_ssize\_t]**

Convert a Python integer to a C `Py_ssize_t`.

### **c(bytes or bytearray of length 1) [char]**

Convert a Python byte, represented as a `bytes` or `bytearray` object of length 1, to a C `char`.

Αλλάξε στην έκδοση 3.3: Allow `bytearray` objects.

### **C(str of length 1) [int]**

Convert a Python character, represented as a `str` object of length 1, to a C `int`.

### **f(float) [float]**

Convert a Python floating point number to a C `float`.

### **d(float) [double]**

Convert a Python floating point number to a C `double`.

### **D(complex) [Py\_complex]**

Convert a Python complex number to a C `Py_complex` structure.

## Other objects

### **O(object) [PyObject\*]**

Store a Python object (without any conversion) in a C object pointer. The C program thus receives the actual object that was passed. A new *strong reference* to the object is not created (i.e. its reference count is not increased). The pointer stored is not `NULL`.

### **O!(object) [PyObject\*, PyObject\*]**

Store a Python object in a C object pointer. This is similar to `O`, but takes two C arguments: the first is the address of a Python type object, the second is the address of the C variable (of type `PyObject*`) into which the object pointer is stored. If the Python object does not have the required type, `TypeError` is raised.

**O& (object) [converter, anything]**

Convert a Python object to a C variable through a *converter* function. This takes two arguments: the first is a function, the second is the address of a C variable (of arbitrary type), converted to `void*`. The *converter* function in turn is called as follows:

```
status = converter(object, address);
```

where *object* is the Python object to be converted and *address* is the `void*` argument that was passed to the `PyArg_Parse*` function. The returned *status* should be 1 for a successful conversion and 0 if the conversion has failed. When the conversion fails, the *converter* function should raise an exception and leave the content of *address* unmodified.

If the *converter* returns `Py_CLEANUP_SUPPORTED`, it may get called a second time if the argument parsing eventually fails, giving the converter a chance to release any memory that it had already allocated. In this second call, the *object* parameter will be `NULL`; *address* will have the same value as in the original call.

Άλλαξε στην έκδοση 3.1: `Py_CLEANUP_SUPPORTED` was added.

**p (bool) [int]**

Tests the value passed in for truth (a boolean predicate) and converts the result to its equivalent C true/false integer value. Sets the int to 1 if the expression was true and 0 if it was false. This accepts any valid Python value. See *truth* for more information about how Python tests values for truth.

Νέο στην έκδοση 3.3.

**(items) (tuple) [matching-items]**

The object must be a Python sequence whose length is the number of format units in *items*. The C arguments must correspond to the individual format units in *items*. Format units for sequences may be nested.

It is possible to pass «long» integers (integers whose value exceeds the platform's `LONG_MAX`) however no proper range checking is done — the most significant bits are silently truncated when the receiving field is too small to receive the value (actually, the semantics are inherited from downcasts in C — your mileage may vary).

A few other characters have a meaning in a format string. These may not occur inside nested parentheses. They are:

|

Indicates that the remaining arguments in the Python argument list are optional. The C variables corresponding to optional arguments should be initialized to their default value — when an optional argument is not specified, `PyArg_ParseTuple()` does not touch the contents of the corresponding C variable(s).

\$

`PyArg_ParseTupleAndKeywords()` only: Indicates that the remaining arguments in the Python argument list are keyword-only. Currently, all keyword-only arguments must also be optional arguments, so | must always be specified before \$ in the format string.

Νέο στην έκδοση 3.3.

:

The list of format units ends here; the string after the colon is used as the function name in error messages (the «associated value» of the exception that `PyArg_ParseTuple()` raises).

;

The list of format units ends here; the string after the semicolon is used as the error message *instead* of the default error message. : and ; mutually exclude each other.

Note that any Python object references which are provided to the caller are *borrowed* references; do not release them (i.e. do not decrement their reference count)!

Additional arguments passed to these functions must be addresses of variables whose type is determined by the format string; these are used to store values from the input tuple. There are a few cases, as described in the list of format units above, where these parameters are used as input values; they should match what is specified for the corresponding format unit in that case.

For the conversion to succeed, the *arg* object must match the format and the format must be exhausted. On success, the `PyArg_Parse*` functions return true, otherwise they return false and raise an appropriate exception. When the

`PyArg_Parse*` functions fail due to conversion failure in one of the format units, the variables at the addresses corresponding to that and the following format units are left untouched.

## API Functions

int **PyArg\_ParseTuple** (*PyObject* \*args, const char \*format, ...)

*Μέρος του Σταθερό ABI.* Parse the parameters of a function that takes only positional parameters into local variables. Returns true on success; on failure, it returns false and raises the appropriate exception.

int **PyArg\_VaParse** (*PyObject* \*args, const char \*format, va\_list vargs)

*Μέρος του Σταθερό ABI.* Identical to `PyArg_ParseTuple()`, except that it accepts a `va_list` rather than a variable number of arguments.

int **PyArg\_ParseTupleAndKeywords** (*PyObject* \*args, *PyObject* \*kw, const char \*format, char \*keywords[], ...)

*Μέρος του Σταθερό ABI.* Parse the parameters of a function that takes both positional and keyword parameters into local variables. The `keywords` argument is a NULL-terminated array of keyword parameter names. Empty names denote *positional-only parameters*. Returns true on success; on failure, it returns false and raises the appropriate exception.

Άλλαξε στην έκδοση 3.6: Added support for *positional-only parameters*.

int **PyArg\_VaParseTupleAndKeywords** (*PyObject* \*args, *PyObject* \*kw, const char \*format, char \*keywords[], va\_list vargs)

*Μέρος του Σταθερό ABI.* Identical to `PyArg_ParseTupleAndKeywords()`, except that it accepts a `va_list` rather than a variable number of arguments.

int **PyArg\_ValidateKeywordArguments** (*PyObject*\*)

*Μέρος του Σταθερό ABI.* Ensure that the keys in the keywords argument dictionary are strings. This is only needed if `PyArg_ParseTupleAndKeywords()` is not used, since the latter already does this check.

Νέο στην έκδοση 3.2.

int **PyArg\_Parse** (*PyObject* \*args, const char \*format, ...)

*Μέρος του Σταθερό ABI.* Function used to deconstruct the argument lists of «old-style» functions — these are functions which use the `METH_OLDARGS` parameter parsing method, which has been removed in Python 3. This is not recommended for use in parameter parsing in new code, and most code in the standard interpreter has been modified to no longer use this for that purpose. It does remain a convenient way to decompose other tuples, however, and may continue to be used for that purpose.

int **PyArg\_UnpackTuple** (*PyObject* \*args, const char \*name, *Py\_ssize\_t* min, *Py\_ssize\_t* max, ...)

*Μέρος του Σταθερό ABI.* A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as `METH_VARARGS` in function or method tables. The tuple containing the actual parameters should be passed as `args`; it must actually be a tuple. The length of the tuple must be at least `min` and no more than `max`; `min` and `max` may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a *PyObject\** variable; these will be filled in with the values from `args`; they will contain *borrowed references*. The variables which correspond to optional parameters not given by `args` will not be filled in; these should be initialized by the caller. This function returns true on success and false if `args` is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

This is an example of the use of this function, taken from the sources for the `_weakref` helper module for weak references:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;
```

(συνέχεια στην επόμενη σελίδα)



(συνεχίζεται από την προηγούμενη σελίδα)

```

if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
    result = PyWeakref_NewRef(object, callback);
}
return result;
}

```

The call to `PyArg_UnpackTuple()` in this example is entirely equivalent to this call to `PyArg_ParseTuple()`:

```
PyArg_ParseTuple(args, "O|O:ref", &object, &callback)
```

## 6.6.2 Building values

*PyObject* \***Py\_BuildValue** (const char \*format, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του **Σταθερό ABI**. Create a new value based on a format string similar to those accepted by the `PyArg_Parse*` family of functions and a sequence of values. Returns the value or NULL in the case of an error; an exception will be raised if NULL is returned.

`Py_BuildValue()` does not always build a tuple. It builds a tuple only if its format string contains two or more format units. If the format string is empty, it returns None; if it contains exactly one format unit, it returns whatever object is described by that format unit. To force it to return a tuple of size 0 or one, parenthesize the format string.

When memory buffers are passed as parameters to supply data to build objects, as for the `s` and `s#` formats, the required data is copied. Buffers provided by the caller are never referenced by the objects created by `Py_BuildValue()`. In other words, if your code invokes `malloc()` and passes the allocated memory to `Py_BuildValue()`, your code is responsible for calling `free()` for that memory once `Py_BuildValue()` returns.

In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that the format unit will return; and the entry in [square] brackets is the type of the C value(s) to be passed.

The characters space, tab, colon and comma are ignored in format strings (but not within format units such as `s#`). This can be used to make long format strings a tad more readable.

**s (str or None) [const char \*]**

Convert a null-terminated C string to a Python `str` object using 'utf-8' encoding. If the C string pointer is NULL, None is used.

**s# (str or None) [const char \*, Py\_ssize\_t]**

Convert a C string and its length to a Python `str` object using 'utf-8' encoding. If the C string pointer is NULL, the length is ignored and None is returned.

**y (bytes) [const char \*]**

This converts a C string to a Python `bytes` object. If the C string pointer is NULL, None is returned.

**y# (bytes) [const char \*, Py\_ssize\_t]**

This converts a C string and its lengths to a Python object. If the C string pointer is NULL, None is returned.

**z (str or None) [const char \*]**

Same as `s`.

**z# (str or None) [const char \*, Py\_ssize\_t]**

Same as `s#`.

**u (str) [const wchar\_t \*]**

Convert a null-terminated `wchar_t` buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is NULL, None is returned.

**u# (str) [const wchar\_t \*, Py\_ssize\_t]**

Convert a Unicode (UTF-16 or UCS-4) data buffer and its length to a Python Unicode object. If the Unicode buffer pointer is NULL, the length is ignored and None is returned.

**U (str or None) [const char \*]**

Same as s.

**U# (str or None) [const char \*, Py\_ssize\_t]**

Same as s#.

**i (int) [int]**

Convert a plain C int to a Python integer object.

**b (int) [char]**

Convert a plain C char to a Python integer object.

**h (int) [short int]**

Convert a plain C short int to a Python integer object.

**l (int) [long int]**

Convert a C long int to a Python integer object.

**B (int) [unsigned char]**

Convert a C unsigned char to a Python integer object.

**H (int) [unsigned short int]**

Convert a C unsigned short int to a Python integer object.

**I (int) [unsigned int]**

Convert a C unsigned int to a Python integer object.

**k (int) [unsigned long]**

Convert a C unsigned long to a Python integer object.

**L (int) [long long]**

Convert a C long long to a Python integer object.

**K (int) [unsigned long long]**

Convert a C unsigned long long to a Python integer object.

**n (int) [Py\_ssize\_t]**

Convert a C Py\_ssize\_t to a Python integer.

**c (bytes of length 1) [char]**

Convert a C int representing a byte to a Python bytes object of length 1.

**C (str of length 1) [int]**

Convert a C int representing a character to Python str object of length 1.

**d (float) [double]**

Convert a C double to a Python floating point number.

**f (float) [float]**

Convert a C float to a Python floating point number.

**D (complex) [Py\_complex \*]**

Convert a C Py\_complex structure to a Python complex number.

**O (object) [PyObject \*]**

Pass a Python object untouched but create a new *strong reference* to it (i.e. its reference count is incremented by one). If the object passed in is a NULL pointer, it is assumed that this was caused because the call producing the argument found an error and set an exception. Therefore, `Py_BuildValue()` will return NULL but won't raise an exception. If no exception has been raised yet, `SystemError` is set.

**S (object) [PyObject \*]**

Same as O.



**N (object) [PyObject \*]**

Same as O, except it doesn't create a new *strong reference*. Useful when the object is created by a call to an object constructor in the argument list.

**O& (object) [converter, anything]**

Convert *anything* to a Python object through a *converter* function. The function is called with *anything* (which should be compatible with `void*`) as its argument and should return a «new» Python object, or NULL if an error occurred.

**(items) (tuple) [matching-items]**

Convert a sequence of C values to a Python tuple with the same number of items.

**[items] (list) [matching-items]**

Convert a sequence of C values to a Python list with the same number of items.

**{items} (dict) [matching-items]**

Convert a sequence of C values to a Python dictionary. Each pair of consecutive C values adds one item to the dictionary, serving as key and value, respectively.

If there is an error in the format string, the `SystemError` exception is set and NULL returned.

*PyObject* \***Py\_VaBuildValue** (const char \*format, va\_list args)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Identical to `Py_BuildValue()`, except that it accepts a `va_list` rather than a variable number of arguments.

## 6.7 String conversion and formatting

Functions for number conversion and formatted string output.

int **PyOS\_snprintf** (char \*str, size\_t size, const char \*format, ...)

*Μέρος του Σταθερό ABI.* Output not more than *size* bytes to *str* according to the format string *format* and the extra arguments. See the Unix man page `snprintf(3)`.

int **PyOS\_vsnprintf** (char \*str, size\_t size, const char \*format, va\_list va)

*Μέρος του Σταθερό ABI.* Output not more than *size* bytes to *str* according to the format string *format* and the variable argument list *va*. Unix man page `vsnprintf(3)`.

`PyOS_snprintf()` and `PyOS_vsnprintf()` wrap the Standard C library functions `snprintf()` and `vsnprintf()`. Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

The wrappers ensure that `str[size-1]` is always `'\0'` upon return. They never write more than *size* bytes (including the trailing `'\0'`) into *str*. Both functions require that `str != NULL`, `size > 0`, `format != NULL` and `size < INT_MAX`. Note that this means there is no equivalent to the C99 `n = snprintf(NULL, 0, ...)` which would determine the necessary buffer size.

The return value (*rv*) for these functions should be interpreted as follows:

- When `0 <= rv < size`, the output conversion was successful and *rv* characters were written to *str* (excluding the trailing `'\0'` byte at `str[rv]`).
- When `rv >= size`, the output conversion was truncated and a buffer with `rv + 1` bytes would have been needed to succeed. `str[size-1]` is `'\0'` in this case.
- When `rv < 0`, «something bad happened.» `str[size-1]` is `'\0'` in this case too, but the rest of *str* is undefined. The exact cause of the error depends on the underlying platform.

The following functions provide locale-independent string to number conversions.

unsigned long **PyOS\_strtoul** (const char \*str, char \*\*ptr, int base)

*Μέρος του Σταθερό ABI.* Convert the initial part of the string in *str* to an unsigned long value according to the given *base*, which must be between 2 and 36 inclusive, or be the special value 0.

Leading white space and case of characters are ignored. If `base` is zero it looks for a leading `0b`, `0o` or `0x` to tell which base. If these are absent it defaults to 10. Base must be 0 or between 2 and 36 (inclusive). If `ptr` is non-NULL it will contain a pointer to the end of the scan.

If the converted value falls out of range of corresponding return type, range error occurs (`errno` is set to `ERANGE`) and `ULONG_MAX` is returned. If no conversion can be performed, 0 is returned.

See also the Unix man page `strtoul(3)`.

Νέο στην έκδοση 3.2.

`long PyOS_strtol (const char *str, char **ptr, int base)`

*Μέρος του Σταθερό ABI.* Convert the initial part of the string in `str` to an `long` value according to the given `base`, which must be between 2 and 36 inclusive, or be the special value 0.

Same as `PyOS_strtoul()`, but return a `long` value instead and `LONG_MAX` on overflows.

See also the Unix man page `strtol(3)`.

Νέο στην έκδοση 3.2.

`double PyOS_string_to_double (const char *s, char **endptr, PyObject *overflow_exception)`

*Μέρος του Σταθερό ABI.* Convert a string `s` to a `double`, raising a Python exception on failure. The set of accepted strings corresponds to the set of strings accepted by Python's `float()` constructor, except that `s` must not have leading or trailing whitespace. The conversion is independent of the current locale.

If `endptr` is NULL, convert the whole string. Raise `ValueError` and return `-1.0` if the string is not a valid representation of a floating-point number.

If `endptr` is not NULL, convert as much of the string as possible and set `*endptr` to point to the first unconverted character. If no initial segment of the string is the valid representation of a floating-point number, set `*endptr` to point to the beginning of the string, raise `ValueError`, and return `-1.0`.

If `s` represents a value that is too large to store in a float (for example, `"1e500"` is such a string on many platforms) then if `overflow_exception` is NULL return `Py_HUGE_VAL` (with an appropriate sign) and don't set any exception. Otherwise, `overflow_exception` must point to a Python exception object; raise that exception and return `-1.0`. In both cases, set `*endptr` to point to the first character after the converted value.

If any other error occurs during the conversion (for example an out-of-memory error), set the appropriate Python exception and return `-1.0`.

Νέο στην έκδοση 3.1.

`char *PyOS_double_to_string (double val, char format_code, int precision, int flags, int *ptype)`

*Μέρος του Σταθερό ABI.* Convert a `double val` to a string using supplied `format_code`, `precision`, and `flags`.

`format_code` must be one of `'e'`, `'E'`, `'f'`, `'F'`, `'g'`, `'G'` or `'r'`. For `'r'`, the supplied `precision` must be 0 and is ignored. The `'r'` format code specifies the standard `repr()` format.

`flags` can be zero or more of the values `Py_DTSTF_SIGN`, `Py_DTSTF_ADD_DOT_0`, or `Py_DTSTF_ALT`, or-ed together:

- `Py_DTSTF_SIGN` means to always precede the returned string with a sign character, even if `val` is non-negative.
- `Py_DTSTF_ADD_DOT_0` means to ensure that the returned string will not look like an integer.
- `Py_DTSTF_ALT` means to apply «alternate» formatting rules. See the documentation for the `PyOS_snprintf()` `'#'` specifier for details.

If `ptype` is non-NULL, then the value it points to will be set to one of `Py_DTST_FINITE`, `Py_DTST_INFINITE`, or `Py_DTST_NAN`, signifying that `val` is a finite number, an infinite number, or not a number, respectively.

The return value is a pointer to `buffer` with the converted string or NULL if the conversion failed. The caller is responsible for freeing the returned string by calling `PyMem_Free()`.

Νέο στην έκδοση 3.1.

int **PyOS\_stricmp** (const char \*s1, const char \*s2)

Case insensitive comparison of strings. The function works almost identically to `strcmp()` except that it ignores the case.

int **PyOS\_strncmp** (const char \*s1, const char \*s2, *Py\_ssize\_t* size)

Case insensitive comparison of strings. The function works almost identically to `strncmp()` except that it ignores the case.

## 6.8 PyHash API

See also the *PyTypeObject*.*tp\_hash* member.

type **Py\_hash\_t**

Hash value type: signed integer.

Νέο στην έκδοση 3.2.

type **Py\_uhash\_t**

Hash value type: unsigned integer.

Νέο στην έκδοση 3.2.

type **PyHash\_FuncDef**

Hash function definition used by *PyHash\_GetFuncDef()*.

const char \***name**

Hash function name (UTF-8 encoded string).

const int **hash\_bits**

Internal size of the hash value in bits.

const int **seed\_bits**

Size of seed input in bits.

Νέο στην έκδοση 3.4.

*PyHash\_FuncDef* \***PyHash\_GetFuncDef** (void)

Get the hash function definition.

**Δείτε επίσης:**

**PEP 456** «Secure and interchangeable hash algorithm».

Νέο στην έκδοση 3.4.

## 6.9 Reflection

*PyObject* \***PyEval\_GetBuiltins** (void)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return a dictionary of the builtins in the current execution frame, or the interpreter of the thread state if no frame is currently executing.

*PyObject* \***PyEval\_GetLocals** (void)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return a dictionary of the local variables in the current execution frame, or NULL if no frame is currently executing.

*PyObject* \***PyEval\_GetGlobals** (void)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return a dictionary of the global variables in the current execution frame, or NULL if no frame is currently executing.

*PyFrameObject* \*PyEval\_GetFrame (void)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return the current thread state's frame, which is NULL if no frame is currently executing.

See also *PyThreadState\_GetFrame()*.

const char \*PyEval\_GetFuncName (*PyObject* \*func)

*Μέρος του Σταθερό ABI.* Return the name of *func* if it is a function, class or instance object, else the name of *func*'s type.

const char \*PyEval\_GetFuncDesc (*PyObject* \*func)

*Μέρος του Σταθερό ABI.* Return a description string, depending on the type of *func*. Return values include «()» for functions and methods, « constructor», « instance», and « object». Concatenated with the result of *PyEval\_GetFuncName()*, the result will be a description of *func*.

## 6.10 Codec registry and support functions

int PyCodec\_Register (*PyObject* \*search\_function)

*Μέρος του Σταθερό ABI.* Register a new codec search function.

As side effect, this tries to load the `encodings` package, if not yet done, to make sure that it is always first in the list of search functions.

int PyCodec\_Unregister (*PyObject* \*search\_function)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Unregister a codec search function and clear the registry's cache. If the search function is not registered, do nothing. Return 0 on success. Raise an exception and return -1 on error.

Νέο στην έκδοση 3.10.

int PyCodec\_KnownEncoding (const char \*encoding)

*Μέρος του Σταθερό ABI.* Return 1 or 0 depending on whether there is a registered codec for the given *encoding*. This function always succeeds.

*PyObject* \*PyCodec\_Encode (*PyObject* \*object, const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Generic codec based encoding API.

*object* is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a `LookupError` if no encoder can be found.

*PyObject* \*PyCodec\_Decode (*PyObject* \*object, const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Generic codec based decoding API.

*object* is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a `LookupError` if no encoder can be found.

### 6.10.1 Codec lookup API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a `KeyError` is set and NULL returned.

*PyObject* \*PyCodec\_Encoder (const char \*encoding)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Get an encoder function for the given *encoding*.

*PyObject* \*PyCodec\_Decoder (const char \*encoding)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Get a decoder function for the given *encoding*.

*PyObject* \*PyCodec\_IncrementalEncoder (const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Get an IncrementalEncoder object for the given *encoding*.

*PyObject* \*PyCodec\_IncrementalDecoder (const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Get an IncrementalDecoder object for the given *encoding*.

*PyObject* \*PyCodec\_StreamReader (const char \*encoding, *PyObject* \*stream, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Get a StreamReader factory function for the given *encoding*.

*PyObject* \*PyCodec\_StreamWriter (const char \*encoding, *PyObject* \*stream, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Get a StreamWriter factory function for the given *encoding*.

## 6.10.2 Registry API for Unicode encoding error handlers

int PyCodec\_RegisterError (const char \*name, *PyObject* \*error)

*Μέρος του Σταθερό ABI.* Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of UnicodeEncodeError, UnicodeDecodeError or UnicodeTranslateError that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Unicode Exception Objects* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

Return 0 on success, -1 on error.

*PyObject* \*PyCodec\_LookupError (const char \*name)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Lookup the error handling callback function registered under *name*. As a special case NULL can be passed, in which case the error handling callback for «strict» will be returned.

*PyObject* \*PyCodec\_StrictErrors (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* Πάντοτε NULL. Μέρος του Σταθερό ABI. Raise *exc* as an exception.

*PyObject* \*PyCodec\_IgnoreErrors (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Ignore the unicode error, skipping the faulty input.

*PyObject* \*PyCodec\_ReplaceErrors (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Replace the unicode encode error with ? or U+FFFD.

*PyObject* \*PyCodec\_XMLCharRefReplaceErrors (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Replace the unicode encode error with XML character references.

*PyObject* \*PyCodec\_BackslashReplaceErrors (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Replace the unicode encode error with backslash escapes (\x, \u and \U).

*PyObject* \***PyCodec\_NameReplaceErrors** (*PyObject* \*exc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Replace the unicode encode error with \N{ . . . } escapes.

Νέο στην έκδοση 3.5.

---

Abstract Objects Layer

---

The functions in this chapter interact with Python objects regardless of their type, or with wide classes of object types (e.g. all numerical types, or all sequence types). When used on object types for which they do not apply, they will raise a Python exception.

It is not possible to use these functions on objects that are not properly initialized, such as a list object that has been created by `PyList_New()`, but whose items have not been set to some non-NULL value yet.

## 7.1 Object Protocol

### *PyObject* \*Py\_NotImplemented

The `NotImplemented` singleton, used to signal that an operation is not implemented for the given type combination.

### Py\_RETURN\_NOTIMPLEMENTED

Properly handle returning *Py\_NotImplemented* from within a C function (that is, create a new *strong reference* to `NotImplemented` and return it).

### Py\_PRINT\_RAW

Flag to be used with multiple functions that print the object (like *PyObject\_Print()* and *PyFile\_WriteObject()*). If passed, these function would use the `str()` of the object instead of the `repr()`.

### int PyObject\_Print (PyObject \*o, FILE \*fp, int flags)

Print an object *o*, on file *fp*. Returns -1 on error. The flags argument is used to enable certain printing options. The only option currently supported is *Py\_PRINT\_RAW*; if given, the `str()` of the object is written instead of the `repr()`.

### int PyObject\_HasAttr (PyObject \*o, PyObject \*attr\_name)

Μέρος του Σταθερό ABI. Returns 1 if *o* has the attribute *attr\_name*, and 0 otherwise. This is equivalent to the Python expression `hasattr(o, attr_name)`. This function always succeeds.

---

**Σημείωση:** Exceptions that occur when this calls `__getattr__()` and `__getattribute__()` methods are silently ignored. For proper error handling, use *PyObject\_GetAttr()* instead.

---



`int PyObject_HasAttrString(PyObject *o, const char *attr_name)`

*Μέρος του Σταθερό ABI.* This is the same as `PyObject_HasAttr()`, but `attr_name` is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

---

**Σημείωση:** Exceptions that occur when this calls `__getattr__()` and `__getattribute__()` methods or while creating the temporary `str` object are silently ignored. For proper error handling, use `PyObject_GetAttrString()` instead.

---

`PyObject *PyObject_GetAttr(PyObject *o, PyObject *attr_name)`

*Επιστρεφόμενη τιμή:* *New reference.* *Μέρος του Σταθερό ABI.* Retrieve an attribute named `attr_name` from object `o`. Returns the attribute value on success, or `NULL` on failure. This is the equivalent of the Python expression `o.attr_name`.

`PyObject *PyObject_GetAttrString(PyObject *o, const char *attr_name)`

*Επιστρεφόμενη τιμή:* *New reference.* *Μέρος του Σταθερό ABI.* This is the same as `PyObject_GetAttr()`, but `attr_name` is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

`PyObject *PyObject_GenericGetAttr(PyObject *o, PyObject *name)`

*Επιστρεφόμενη τιμή:* *New reference.* *Μέρος του Σταθερό ABI.* Generic attribute getter function that is meant to be put into a type object's `tp_getattro` slot. It looks for a descriptor in the dictionary of classes in the object's MRO as well as an attribute in the object's `__dict__` (if present). As outlined in descriptors, data descriptors take preference over instance attributes, while non-data descriptors don't. Otherwise, an `AttributeError` is raised.

`int PyObject_SetAttr(PyObject *o, PyObject *attr_name, PyObject *v)`

*Μέρος του Σταθερό ABI.* Set the value of the attribute named `attr_name`, for object `o`, to the value `v`. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o.attr_name = v`.

If `v` is `NULL`, the attribute is deleted. This behaviour is deprecated in favour of using `PyObject_DelAttr()`, but there are currently no plans to remove it.

`int PyObject_SetAttrString(PyObject *o, const char *attr_name, PyObject *v)`

*Μέρος του Σταθερό ABI.* This is the same as `PyObject_SetAttr()`, but `attr_name` is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

If `v` is `NULL`, the attribute is deleted, but this feature is deprecated in favour of using `PyObject_DelAttrString()`.

`int PyObject_GenericSetAttr(PyObject *o, PyObject *name, PyObject *value)`

*Μέρος του Σταθερό ABI.* Generic attribute setter and deleter function that is meant to be put into a type object's `tp_setattro` slot. It looks for a data descriptor in the dictionary of classes in the object's MRO, and if found it takes preference over setting or deleting the attribute in the instance dictionary. Otherwise, the attribute is set or deleted in the object's `__dict__` (if present). On success, `0` is returned, otherwise an `AttributeError` is raised and `-1` is returned.

`int PyObject_DelAttr(PyObject *o, PyObject *attr_name)`

Delete attribute named `attr_name`, for object `o`. Returns `-1` on failure. This is the equivalent of the Python statement `del o.attr_name`.

`int PyObject_DelAttrString(PyObject *o, const char *attr_name)`

This is the same as `PyObject_DelAttr()`, but `attr_name` is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

`PyObject *PyObject_GenericGetDict(PyObject *o, void *context)`

*Επιστρεφόμενη τιμή:* *New reference.* *Μέρος του Σταθερό ABI από την έκδοση 3.10.* A generic implementation for the getter of a `__dict__` descriptor. It creates the dictionary if necessary.



This function may also be called to get the `__dict__` of the object *o*. Pass `NULL` for *context* when calling it. Since this function may need to allocate memory for the dictionary, it may be more efficient to call `PyObject_GetAttr()` when accessing an attribute on the object.

On failure, returns `NULL` with an exception set.

Νέο στην έκδοση 3.3.

**int PyObject\_GenericSetDict** (*PyObject* \*o, *PyObject* \*value, void \*context)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* A generic implementation for the setter of a `__dict__` descriptor. This implementation does not allow the dictionary to be deleted.

Νέο στην έκδοση 3.3.

*PyObject* \*\***PyObject\_GetDictPtr** (*PyObject* \*obj)

Return a pointer to `__dict__` of the object *obj*. If there is no `__dict__`, return `NULL` without setting an exception.

This function may need to allocate memory for the dictionary, so it may be more efficient to call `PyObject_GetAttr()` when accessing an attribute on the object.

*PyObject* \***PyObject\_RichCompare** (*PyObject* \*o1, *PyObject* \*o2, int opid)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Compare the values of *o1* and *o2* using the operation specified by *opid*, which must be one of `Py_LT`, `Py_LE`, `Py_EQ`, `Py_NE`, `Py_GT`, or `Py_GE`, corresponding to `<`, `<=`, `==`, `!=`, `>`, or `>=` respectively. This is the equivalent of the Python expression `o1 op o2`, where `op` is the operator corresponding to *opid*. Returns the value of the comparison on success, or `NULL` on failure.

**int PyObject\_RichCompareBool** (*PyObject* \*o1, *PyObject* \*o2, int opid)

*Μέρος του Σταθερό ABI.* Compare the values of *o1* and *o2* using the operation specified by *opid*, like `PyObject_RichCompare()`, but returns `-1` on error, `0` if the result is false, `1` otherwise.

---

**Σημείωση:** If *o1* and *o2* are the same object, `PyObject_RichCompareBool()` will always return `1` for `Py_EQ` and `0` for `Py_NE`.

---

*PyObject* \***PyObject\_Format** (*PyObject* \*obj, *PyObject* \*format\_spec)

*Μέρος του Σταθερό ABI.* Format *obj* using *format\_spec*. This is equivalent to the Python expression `format(obj, format_spec)`.

*format\_spec* may be `NULL`. In this case the call is equivalent to `format(obj)`. Returns the formatted string on success, `NULL` on failure.

*PyObject* \***PyObject\_Repr** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `repr(o)`. Called by the `repr()` built-in function.

Άλλαξε στην έκδοση 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

*PyObject* \***PyObject\_ASCII** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* As `PyObject_Repr()`, compute a string representation of object *o*, but escape the non-ASCII characters in the string returned by `PyObject_Repr()` with `\x`, `\u` or `\U` escapes. This generates a string similar to that returned by `PyObject_Repr()` in Python 2. Called by the `ascii()` built-in function.

*PyObject* \***PyObject\_Str** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `str(o)`. Called by the `str()` built-in function and, therefore, by the `print()` function.

Άλλαξε στην έκδοση 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

*PyObject* \*PyObject\_Bytes (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Compute a bytes representation of object *o*. NULL is returned on failure and a bytes object on success. This is equivalent to the Python expression `bytes(o)`, when *o* is not an integer. Unlike `bytes(o)`, a `TypeError` is raised when *o* is an integer instead of a zero-initialized bytes object.

int PyObject\_IsSubclass (*PyObject* \*derived, *PyObject* \*cls)

*Μέρος του Σταθερό ABI.* Return 1 if the class *derived* is identical to or derived from the class *cls*, otherwise return 0. In case of an error, return -1.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a `__subclasscheck__()` method, it will be called to determine the subclass status as described in [PEP 3119](#). Otherwise, *derived* is a subclass of *cls* if it is a direct or indirect subclass, i.e. contained in `cls.__mro__`.

Normally only class objects, i.e. instances of `type` or a derived class, are considered classes. However, objects can override this by having a `__bases__` attribute (which must be a tuple of base classes).

int PyObject\_IsInstance (*PyObject* \*inst, *PyObject* \*cls)

*Μέρος του Σταθερό ABI.* Return 1 if *inst* is an instance of the class *cls* or a subclass of *cls*, or 0 if not. On error, returns -1 and sets an exception.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a `__instancecheck__()` method, it will be called to determine the subclass status as described in [PEP 3119](#). Otherwise, *inst* is an instance of *cls* if its class is a subclass of *cls*.

An instance *inst* can override what is considered its class by having a `__class__` attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a `__bases__` attribute (which must be a tuple of base classes).

*Py\_hash\_t* PyObject\_Hash (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Compute and return the hash value of an object *o*. On failure, return -1. This is the equivalent of the Python expression `hash(o)`.

Άλλαξε στην έκδοση 3.2: The return type is now `Py_hash_t`. This is a signed integer the same size as `Py_ssize_t`.

*Py\_hash\_t* PyObject\_HashNotImplemented (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Set a `TypeError` indicating that `type(o)` is not *hashable* and return -1. This function receives special treatment when stored in a `tp_hash` slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

int PyObject\_IsTrue (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Returns 1 if the object *o* is considered to be true, and 0 otherwise. This is equivalent to the Python expression `not not o`. On failure, return -1.

int PyObject\_Not (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Returns 0 if the object *o* is considered to be true, and 1 otherwise. This is equivalent to the Python expression `not o`. On failure, return -1.

*PyObject* \*PyObject\_Type (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* When *o* is non-NULL, returns a type object corresponding to the object type of object *o*. On failure, raises `SystemError` and returns NULL. This is equivalent to the Python expression `type(o)`. This function creates a new *strong reference* to the return value. There's really no reason to use this function instead of the `Py_TYPE()` function, which returns a pointer of type `PyTypeObject*`, except when a new *strong reference* is needed.

**int PyObject\_TypeCheck** (*PyObject* \*o, *PyTypeObject* \*type)

Return non-zero if the object *o* is of type *type* or a subtype of *type*, and 0 otherwise. Both parameters must be non-NULL.

*Py\_ssize\_t* **PyObject\_Size** (*PyObject* \*o)

*Py\_ssize\_t* **PyObject\_Length** (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Return the length of object *o*. If the object *o* provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression `len(o)`.

*Py\_ssize\_t* **PyObject\_LengthHint** (*PyObject* \*o, *Py\_ssize\_t* defaultvalue)

Return an estimated length for the object *o*. First try to return its actual length, then an estimate using `__length_hint__()`, and finally return the default value. On error return -1. This is the equivalent to the Python expression `operator.length_hint(o, defaultvalue)`.

Νέο στην έκδοση 3.4.

*PyObject* \***PyObject\_GetItem** (*PyObject* \*o, *PyObject* \*key)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return element of *o* corresponding to the object *key* or NULL on failure. This is the equivalent of the Python expression `o[key]`.

**int PyObject\_SetItem** (*PyObject* \*o, *PyObject* \*key, *PyObject* \*v)

*Μέρος του Σταθερό ABI.* Map the object *key* to the value *v*. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement `o[key] = v`. This function *does not* steal a reference to *v*.

**int PyObject\_DelItem** (*PyObject* \*o, *PyObject* \*key)

*Μέρος του Σταθερό ABI.* Remove the mapping for the object *key* from the object *o*. Return -1 on failure. This is equivalent to the Python statement `del o[key]`.

*PyObject* \***PyObject\_Dir** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* This is equivalent to the Python expression `dir(o)`, returning a (possibly empty) list of strings appropriate for the object argument, or NULL if there was an error. If the argument is NULL, this is like the Python `dir()`, returning the names of the current locals; in this case, if no execution frame is active then NULL is returned but `PyErr_Occurred()` will return false.

*PyObject* \***PyObject\_GetIter** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* This is equivalent to the Python expression `iter(o)`. It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises `TypeError` and returns NULL if the object cannot be iterated.

*PyObject* \***PyObject\_GetAIter** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI από την έκδοση 3.10.* This is the equivalent to the Python expression `aiter(o)`. Takes an `AsyncIterable` object and returns an `AsyncIterator` for it. This is typically a new iterator but if the argument is an `AsyncIterator`, this returns itself. Raises `TypeError` and returns NULL if the object cannot be iterated.

Νέο στην έκδοση 3.10.

## 7.2 Call Protocol

CPython supports two different calling protocols: *tp\_call* and *vectorcall*.

## 7.2.1 The `tp_call` Protocol

Instances of classes that set `tp_call` are callable. The signature of the slot is:

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

A call is made using a tuple for the positional arguments and a dict for the keyword arguments, similarly to `callable(*args, **kwargs)` in Python code. *args* must be non-NULL (use an empty tuple if there are no arguments) but *kwargs* may be *NULL* if there are no keyword arguments.

This convention is not only used by `tp_call`: `tp_new` and `tp_init` also pass arguments this way.

To call an object, use `PyObject_Call()` or another *call API*.

## 7.2.2 The Vectorcall Protocol

Νέο στην έκδοση 3.9.

The vectorcall protocol was introduced in **PEP 590** as an additional protocol for making calls more efficient.

As rule of thumb, CPython will prefer the vectorcall for internal calls if the callable supports it. However, this is not a hard rule. Additionally, some third-party extensions use `tp_call` directly (rather than using `PyObject_Call()`). Therefore, a class supporting vectorcall must also implement `tp_call`. Moreover, the callable must behave the same regardless of which protocol is used. The recommended way to achieve this is by setting `tp_call` to `PyVectorcall_Call()`. This bears repeating:

**Προειδοποίηση:** A class supporting vectorcall **must** also implement `tp_call` with the same semantics.

A class should not implement vectorcall if that would be slower than `tp_call`. For example, if the callee needs to convert the arguments to an args tuple and kwargs dict anyway, then there is no point in implementing vectorcall.

Classes can implement the vectorcall protocol by enabling the `Py_TPFLAGS_HAVE_VECTORCALL` flag and setting `tp_vectorcall_offset` to the offset inside the object structure where a *vectorcallfunc* appears. This is a pointer to a function with the following signature:

```
typedef PyObject *(*vectorcallfunc)(PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwnames)
```

- *callable* is the object being called.
- *args* is a C array consisting of the positional arguments followed by the values of the keyword arguments. This can be *NULL* if there are no arguments.
- *nargsf* is the number of positional arguments plus possibly the `PY_VECTORCALL_ARGUMENTS_OFFSET` flag. To get the actual number of positional arguments from *nargsf*, use `PyVectorcall_NARGS()`.
- *kwnames* is a tuple containing the names of the keyword arguments; in other words, the keys of the kwargs dict. These names must be strings (instances of `str` or a subclass) and they must be unique. If there are no keyword arguments, then *kwnames* can instead be *NULL*.

### **PY\_VECTORCALL\_ARGUMENTS\_OFFSET**

If this flag is set in a vectorcall *nargsf* argument, the callee is allowed to temporarily change `args[-1]`. In other words, *args* points to argument 1 (not 0) in the allocated vector. The callee must restore the value of `args[-1]` before returning.

For `PyObject_VectorcallMethod()`, this flag means instead that `args[0]` may be changed.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use `PY_VECTORCALL_ARGUMENTS_OFFSET`. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) very efficiently.

Νέο στην έκδοση 3.8.

To call an object that implements vectorcall, use a *call API* function as with any other callable. `PyObject_Vectorcall()` will usually be most efficient.

**Σημείωση:** In CPython 3.8, the vectorcall API and related functions were available provisionally under names with a leading underscore: `_PyObject_Vectorcall`, `_Py_TPFLAGS_HAVE_VECTORCALL`, `_PyObject_VectorcallMethod`, `_PyVectorcall_Function`, `_PyObject_CallOneArg`, `_PyObject_CallMethodNoArgs`, `_PyObject_CallMethodOneArg`. Additionally, `PyObject_VectorcallDict` was available as `_PyObject_FastCallDict`. The old names are still defined as aliases of the new, non-underscored names.

## Recursion Control

When using `tp_call`, callees do not need to worry about *recursion*: CPython uses `Py_EnterRecursiveCall()` and `Py_LeaveRecursiveCall()` for calls made using `tp_call`.

For efficiency, this is not the case for calls done using vectorcall: the callee should use `Py_EnterRecursiveCall` and `Py_LeaveRecursiveCall` if needed.

## Vectorcall Support API

`Py_ssize_t` **PyVectorcall\_NARGS** (`size_t` nargsf)

Given a vectorcall *nargsf* argument, return the actual number of arguments. Currently equivalent to:

```
(Py_ssize_t)(nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET)
```

However, the function `PyVectorcall_NARGS` should be used to allow for future extensions.

Νέο στην έκδοση 3.8.

*vectorcallfunc* **PyVectorcall\_Function** (`PyObject *`op)

If *op* does not support the vectorcall protocol (either because the type does not or because the specific instance does not), return `NULL`. Otherwise, return the vectorcall function pointer stored in *op*. This function never raises an exception.

This is mostly useful to check whether or not *op* supports vectorcall, which can be done by checking `PyVectorcall_Function(op) != NULL`.

Νέο στην έκδοση 3.9.

`PyObject *`**PyVectorcall\_Call** (`PyObject *`callable, `PyObject *`tuple, `PyObject *`dict)

Call *callable*'s *vectorcallfunc* with positional and keyword arguments given in a tuple and dict, respectively.

This is a specialized function, intended to be put in the `tp_call` slot or be used in an implementation of `tp_call`. It does not check the `Py_TPFLAGS_HAVE_VECTORCALL` flag and it does not fall back to `tp_call`.

Νέο στην έκδοση 3.8.

## 7.2.3 Object Calling API

Various functions are available for calling a Python object. Each converts its arguments to a convention supported by the called object – either *tp\_call* or *vectorcall*. In order to do as little conversion as possible, pick one that best fits the format of data you have available.

The following table summarizes the available functions; please see individual documentation for details.

Function	callable	args	kwargs
<code>PyObject_Call()</code>	<code>PyObject *</code>	<code>tuple</code>	<code>dict/NULL</code>
<code>PyObject_CallNoArgs()</code>	<code>PyObject *</code>	<code>—</code>	<code>—</code>
<code>PyObject_CallOneArg()</code>	<code>PyObject *</code>	<code>1 object</code>	<code>—</code>
<code>PyObject_CallObject()</code>	<code>PyObject *</code>	<code>tuple/NULL</code>	<code>—</code>
<code>PyObject_CallFunction()</code>	<code>PyObject *</code>	<code>format</code>	<code>—</code>
<code>PyObject_CallMethod()</code>	<code>obj + char*</code>	<code>format</code>	<code>—</code>
<code>PyObject_CallFunctionObjArgs()</code>	<code>PyObject *</code>	<code>variadic</code>	<code>—</code>
<code>PyObject_CallMethodObjArgs()</code>	<code>obj + name</code>	<code>variadic</code>	<code>—</code>
<code>PyObject_CallMethodNoArgs()</code>	<code>obj + name</code>	<code>—</code>	<code>—</code>
<code>PyObject_CallMethodOneArg()</code>	<code>obj + name</code>	<code>1 object</code>	<code>—</code>
<code>PyObject_Vectorcall()</code>	<code>PyObject *</code>	<code>vectorcall</code>	<code>vectorcall</code>
<code>PyObject_VectorcallDict()</code>	<code>PyObject *</code>	<code>vectorcall</code>	<code>dict/NULL</code>
<code>PyObject_VectorcallMethod()</code>	<code>arg + name</code>	<code>vectorcall</code>	<code>vectorcall</code>

*PyObject \****PyObject\_Call** (*PyObject \**callable, *PyObject \**args, *PyObject \**kwargs)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call a callable Python object *callable*, with arguments given by the tuple *args*, and named arguments given by the dictionary *kwargs*.

*args* must not be *NULL*; use an empty tuple if no arguments are needed. If no named arguments are needed, *kwargs* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args, **kwargs)`.

*PyObject \****PyObject\_CallNoArgs** (*PyObject \**callable)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.10. Call a callable Python object *callable* without any arguments. It is the most efficient way to call a callable Python object without any argument.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

*PyObject \****PyObject\_CallOneArg** (*PyObject \**callable, *PyObject \**arg)

*Επιστρεφόμενη τιμή:* New reference. Call a callable Python object *callable* with exactly 1 positional argument *arg* and no keyword arguments.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

*PyObject \****PyObject\_CallObject** (*PyObject \**callable, *PyObject \**args)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call a callable Python object *callable*, with arguments given by the tuple *args*. If no arguments are needed, then *args* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args)`.

*PyObject \****PyObject\_CallFunction** (*PyObject \**callable, *const char \**format, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call a callable Python object *callable*, with a variable number of C arguments. The C arguments are described using a *Py\_BuildValue()* style format string. The format can be *NULL*, indicating that no arguments are provided.



Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args)`.

Note that if you only pass *PyObject\** args, *PyObject\_CallFunctionObjArgs()* is a faster alternative.

Άλλαξε στην έκδοση 3.4: The type of *format* was changed from `char *`.

*PyObject* \***PyObject\_CallMethod** (*PyObject* \*obj, const char \*name, const char \*format, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call the method named *name* of object *obj* with a variable number of C arguments. The C arguments are described by a *Py\_BuildValue()* format string that should produce a tuple.

The format can be *NULL*, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `obj.name(arg1, arg2, ...)`.

Note that if you only pass *PyObject\** args, *PyObject\_CallMethodObjArgs()* is a faster alternative.

Άλλαξε στην έκδοση 3.4: The types of *name* and *format* were changed from `char *`.

*PyObject* \***PyObject\_CallFunctionObjArgs** (*PyObject* \*callable, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call a callable Python object *callable*, with a variable number of *PyObject\** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(arg1, arg2, ...)`.

*PyObject* \***PyObject\_CallMethodObjArgs** (*PyObject* \*obj, *PyObject* \*name, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Call a method of the Python object *obj*, where the name of the method is given as a Python string object in *name*. It is called with a variable number of *PyObject\** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

*PyObject* \***PyObject\_CallMethodNoArgs** (*PyObject* \*obj, *PyObject* \*name)

Call a method of the Python object *obj* without arguments, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

*PyObject* \***PyObject\_CallMethodOneArg** (*PyObject* \*obj, *PyObject* \*name, *PyObject* \*arg)

Call a method of the Python object *obj* with a single positional argument *arg*, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

*PyObject* \***PyObject\_Vectorcall** (*PyObject* \*callable, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwnames)

Call a callable Python object *callable*. The arguments are the same as for *vectorcallfunc*. If *callable* supports *vectorcall*, this directly calls the *vectorcall* function stored in *callable*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

*PyObject* \***PyObject\_VectorcallDict** (*PyObject* \*callable, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwdict)

Call *callable* with positional arguments passed exactly as in the *vectorcall* protocol, but with keyword arguments passed as a dictionary *kwdict*. The *args* array contains only the positional arguments.

Regardless of which protocol is used internally, a conversion of arguments needs to be done. Therefore, this function should only be used if the caller already has a dictionary ready to use for the keyword arguments, but not a tuple for the positional arguments.

Νέο στην έκδοση 3.9.

*PyObject* \***PyObject\_VectorcallMethod** (*PyObject* \*name, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwnames)

Call a method using the *vectorcall* calling convention. The name of the method is given as a Python string *name*. The object whose method is called is *args[0]*, and the *args* array starting at *args[1]* represents the arguments of the call. There must be at least one positional argument. *nargsf* is the number of positional arguments including *args[0]*, plus *PY\_VECTORCALL\_ARGUMENTS\_OFFSET* if the value of *args[0]* may temporarily be changed. Keyword arguments can be passed just like in *PyObject\_Vectorcall()*.

If the object has the *Py\_TPFLAGS\_METHOD\_DESCRIPTOR* feature, this will call the unbound method object with the full *args* vector as arguments.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Νέο στην έκδοση 3.9.

## 7.2.4 Call Support API

int **PyCallable\_Check** (*PyObject* \*o)

*Μέρος του Σταθερό ABI*. Determine if the object *o* is callable. Return 1 if the object is callable and 0 otherwise. This function always succeeds.

## 7.3 Number Protocol

int **PyNumber\_Check** (*PyObject* \*o)

*Μέρος του Σταθερό ABI*. Returns 1 if the object *o* provides numeric protocols, and false otherwise. This function always succeeds.

Άλλαξε στην έκδοση 3.8: Returns 1 if *o* is an index integer.

*PyObject* \***PyNumber\_Add** (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI*. Returns the result of adding *o1* and *o2*, or *NULL* on failure. This is the equivalent of the Python expression *o1* + *o2*.

*PyObject* \***PyNumber\_Subtract** (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI*. Returns the result of subtracting *o2* from *o1*, or *NULL* on failure. This is the equivalent of the Python expression *o1* - *o2*.

*PyObject* \***PyNumber\_Multiply** (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI*. Returns the result of multiplying *o1* and *o2*, or *NULL* on failure. This is the equivalent of the Python expression *o1* \* *o2*.

*PyObject* \***PyNumber\_MatrixMultiply** (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7*. Returns the result of matrix multiplication on *o1* and *o2*, or *NULL* on failure. This is the equivalent of the Python expression *o1* @ *o2*.

Νέο στην έκδοση 3.5.



*PyObject* \*PyNumber\_FloorDivide (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the floor of *o1* divided by *o2*, or NULL on failure. This is the equivalent of the Python expression `o1 // o2`.

*PyObject* \*PyNumber\_TrueDivide (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or NULL on failure. The return value is «approximate» because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. This is the equivalent of the Python expression `o1 / o2`.

*PyObject* \*PyNumber\_Remainder (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the remainder of dividing *o1* by *o2*, or NULL on failure. This is the equivalent of the Python expression `o1 % o2`.

*PyObject* \*PyNumber\_Divmod (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. See the built-in function `divmod()`. Returns NULL on failure. This is the equivalent of the Python expression `divmod(o1, o2)`.

*PyObject* \*PyNumber\_Power (*PyObject* \*o1, *PyObject* \*o2, *PyObject* \*o3)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. See the built-in function `pow()`. Returns NULL on failure. This is the equivalent of the Python expression `pow(o1, o2, o3)`, where *o3* is optional. If *o3* is to be ignored, pass `Py_None` in its place (passing NULL for *o3* would cause an illegal memory access).

*PyObject* \*PyNumber\_Negative (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the negation of *o* on success, or NULL on failure. This is the equivalent of the Python expression `-o`.

*PyObject* \*PyNumber\_Positive (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns *o* on success, or NULL on failure. This is the equivalent of the Python expression `+o`.

*PyObject* \*PyNumber\_Absolute (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the absolute value of *o*, or NULL on failure. This is the equivalent of the Python expression `abs(o)`.

*PyObject* \*PyNumber\_Invert (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the bitwise negation of *o* on success, or NULL on failure. This is the equivalent of the Python expression `~o`.

*PyObject* \*PyNumber\_Lshift (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of left shifting *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 << o2`.

*PyObject* \*PyNumber\_Rshift (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of right shifting *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 >> o2`.

*PyObject* \*PyNumber\_And (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise and» of *o1* and *o2* on success and NULL on failure. This is the equivalent of the Python expression `o1 & o2`.

*PyObject* \*PyNumber\_Xor (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise exclusive or» of *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 ^ o2`.

*PyObject* \*PyNumber\_Or (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise or» of *o1* and *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 | o2`.

*PyObject* \*PyNumber\_InPlaceAdd (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of adding *o1* and *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 += o2`.

*PyObject* \*PyNumber\_InPlaceSubtract (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of subtracting *o2* from *o1*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 -= o2`.

*PyObject* \*PyNumber\_InPlaceMultiply (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of multiplying *o1* and *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 *= o2`.

*PyObject* \*PyNumber\_InPlaceMatrixMultiply (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Returns the result of matrix multiplication on *o1* and *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 @= o2`.

Νέο στην έκδοση 3.5.

*PyObject* \*PyNumber\_InPlaceFloorDivide (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the mathematical floor of dividing *o1* by *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 //= o2`.

*PyObject* \*PyNumber\_InPlaceTrueDivide (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or NULL on failure. The return value is «approximate» because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 /= o2`.

*PyObject* \*PyNumber\_InPlaceRemainder (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the remainder of dividing *o1* by *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 %= o2`.

*PyObject* \*PyNumber\_InPlacePower (*PyObject* \*o1, *PyObject* \*o2, *PyObject* \*o3)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. See the built-in function `pow()`. Returns NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 **= o2` when *o3* is `Py_None`, or an in-place variant of `pow(o1, o2, o3)` otherwise. If *o3* is to be ignored, pass `Py_None` in its place (passing NULL for *o3* would cause an illegal memory access).

*PyObject* \*PyNumber\_InPlaceLshift (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of left shifting *o1* by *o2* on success, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 <= o2`.

*PyObject* \*PyNumber\_InPlaceRshift (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the result of right shifting *o1* by *o2* on success, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 >= o2`.

*PyObject* \*PyNumber\_InPlaceAnd (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise and» of *o1* and *o2* on success and NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 &= o2`.

*PyObject* \*PyNumber\_InPlaceXor (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise exclusive or» of *o1* by *o2* on success, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 ^= o2`.

*PyObject* \*PyNumber\_InPlaceOr (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the «bitwise or» of *o1* and *o2* on success, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 |= o2`.

*PyObject* \*PyNumber\_Long (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the *o* converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression `int(o)`.

*PyObject* \*PyNumber\_Float (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the *o* converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression `float(o)`.

*PyObject* \*PyNumber\_Index (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the *o* converted to a Python int on success or NULL with a `TypeError` exception raised on failure.

Άλλαξε στην έκδοση 3.10: The result always has exact type `int`. Previously, the result could have been an instance of a subclass of `int`.

*PyObject* \*PyNumber\_ToBase (*PyObject* \*n, int base)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Returns the integer *n* converted to base *base* as a string. The *base* argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of `'0b'`, `'0o'`, or `'0x'`, respectively. If *n* is not a Python int, it is converted with `PyNumber_Index()` first.

*Py\_ssize\_t* PyNumber\_AsSsize\_t (*PyObject* \*o, *PyObject* \*exc)

Μέρος του Σταθερό ABI. Returns *o* converted to a *Py\_ssize\_t* value if *o* can be interpreted as an integer. If the call fails, an exception is raised and `-1` is returned.

If *o* can be converted to a Python int but the attempt to convert to a *Py\_ssize\_t* value would raise an `OverflowError`, then the *exc* argument is the type of exception that will be raised (usually `IndexError` or `OverflowError`). If *exc* is NULL, then the exception is cleared and the value is clipped to `PY_SSIZE_T_MIN` for a negative integer or `PY_SSIZE_T_MAX` for a positive integer.

int PyIndex\_Check (*PyObject* \*o)

Μέρος του Σταθερό ABI από την έκδοση 3.8. Returns 1 if *o* is an index integer (has the `nb_index` slot of the `tp_as_number` structure filled in), and 0 otherwise. This function always succeeds.

## 7.4 Sequence Protocol

int PySequence\_Check (*PyObject* \*o)

Μέρος του Σταθερό ABI. Return 1 if the object provides the sequence protocol, and 0 otherwise. Note that it returns 1 for Python classes with a `__getitem__()` method, unless they are `dict` subclasses, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

*Py\_ssize\_t* PySequence\_Size (*PyObject* \*o)

*Py\_ssize\_t* PySequence\_Length (*PyObject* \*o)

Μέρος του Σταθερό ABI. Returns the number of objects in sequence *o* on success, and `-1` on failure. This is equivalent to the Python expression `len(o)`.

*PyObject* \*PySequence\_Concat (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the concatenation of *o1* and *o2* on success, and NULL on failure. This is the equivalent of the Python expression `o1 + o2`.

*PyObject* \*PySequence\_Repeat (*PyObject* \*o, *Py\_ssize\_t* count)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the result of repeating sequence object *o* count times, or NULL on failure. This is the equivalent of the Python expression `o * count`.

*PyObject* \*PySequence\_InPlaceConcat (*PyObject* \*o1, *PyObject* \*o2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the concatenation of *o1* and *o2* on success, and NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python expression `o1 += o2`.

*PyObject* \*PySequence\_InPlaceRepeat (*PyObject* \*o, *Py\_ssize\_t* count)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the result of repeating sequence object *o* count times, or NULL on failure. The operation is done *in-place* when *o* supports it. This is the equivalent of the Python expression `o *= count`.

*PyObject* \*PySequence\_GetItem (*PyObject* \*o, *Py\_ssize\_t* i)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the *i*th element of *o*, or NULL on failure. This is the equivalent of the Python expression `o[i]`.

*PyObject* \*PySequence\_GetSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the slice of sequence object *o* between *i1* and *i2*, or NULL on failure. This is the equivalent of the Python expression `o[i1:i2]`.

int PySequence\_SetItem (*PyObject* \*o, *Py\_ssize\_t* i, *PyObject* \*v)

Μέρος του Σταθερό ABI. Assign object *v* to the *i*th element of *o*. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement `o[i] = v`. This function *does not* steal a reference to *v*.

If *v* is NULL, the element is deleted, but this feature is deprecated in favour of using `PySequence_DelItem()`.

int PySequence\_DelItem (*PyObject* \*o, *Py\_ssize\_t* i)

Μέρος του Σταθερό ABI. Delete the *i*th element of object *o*. Returns -1 on failure. This is the equivalent of the Python statement `del o[i]`.

int PySequence\_SetSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2, *PyObject* \*v)

Μέρος του Σταθερό ABI. Assign the sequence object *v* to the slice in sequence object *o* from *i1* to *i2*. This is the equivalent of the Python statement `o[i1:i2] = v`.

int PySequence\_DelSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2)

Μέρος του Σταθερό ABI. Delete the slice in sequence object *o* from *i1* to *i2*. Returns -1 on failure. This is the equivalent of the Python statement `del o[i1:i2]`.

*Py\_ssize\_t* PySequence\_Count (*PyObject* \*o, *PyObject* \*value)

Μέρος του Σταθερό ABI. Return the number of occurrences of *value* in *o*, that is, return the number of keys for which `o[key] == value`. On failure, return -1. This is equivalent to the Python expression `o.count(value)`.

int PySequence\_Contains (*PyObject* \*o, *PyObject* \*value)

Μέρος του Σταθερό ABI. Determine if *o* contains *value*. If an item in *o* is equal to *value*, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression `value in o`.

*Py\_ssize\_t* PySequence\_Index (*PyObject* \*o, *PyObject* \*value)

Μέρος του Σταθερό ABI. Return the first index *i* for which `o[i] == value`. On error, return -1. This is equivalent to the Python expression `o.index(value)`.

*PyObject* \*PySequence\_List (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a list object with the same contents as the sequence or iterable *o*, or NULL on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression `list(o)`.

*PyObject* \*PySequence\_Tuple (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a tuple object with the same contents as the sequence or iterable *o*, or NULL on failure. If *o* is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression `tuple(o)`.

*PyObject* \*PySequence\_Fast (*PyObject* \*o, const char \*m)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the sequence or iterable *o* as an object usable by the other `PySequence_Fast*` family of functions. If the object is not a sequence or iterable, raises `TypeError` with *m* as the message text. Returns NULL on failure.

The `PySequence_Fast*` functions are thus named because they assume *o* is a *PyTupleObject* or a *PyListObject* and access the data fields of *o* directly.

As a CPython implementation detail, if *o* is already a sequence or list, it will be returned.

*Py\_ssize\_t* PySequence\_Fast\_GET\_SIZE (*PyObject* \*o)

Returns the length of *o*, assuming that *o* was returned by `PySequence_Fast()` and that *o* is not NULL. The size can also be retrieved by calling `PySequence_Size()` on *o*, but `PySequence_Fast_GET_SIZE()` is faster because it can assume *o* is a list or tuple.

*PyObject* \*PySequence\_Fast\_GET\_ITEM (*PyObject* \*o, *Py\_ssize\_t* i)

*Επιστρεφόμενη τιμή:* Borrowed reference. Return the *i*th element of *o*, assuming that *o* was returned by `PySequence_Fast()`, *o* is not NULL, and that *i* is within bounds.

*PyObject* \*\*PySequence\_Fast\_ITEMS (*PyObject* \*o)

Return the underlying array of *PyObject* pointers. Assumes that *o* was returned by `PySequence_Fast()` and *o* is not NULL.

Note, if a list gets resized, the reallocation may relocate the items array. So, only use the underlying array pointer in contexts where the sequence cannot change.

*PyObject* \*PySequence\_ITEM (*PyObject* \*o, *Py\_ssize\_t* i)

*Επιστρεφόμενη τιμή:* New reference. Return the *i*th element of *o* or NULL on failure. Faster form of `PySequence_GetItem()` but without checking that `PySequence_Check()` on *o* is true and without adjustment for negative indices.

## 7.5 Mapping Protocol

See also `PyObject_GetItem()`, `PyObject_SetItem()` and `PyObject_DelItem()`.

int PyMapping\_Check (*PyObject* \*o)

Μέρος του Σταθερό ABI. Return 1 if the object provides the mapping protocol or supports slicing, and 0 otherwise. Note that it returns 1 for Python classes with a `__getitem__()` method, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

*Py\_ssize\_t* PyMapping\_Size (*PyObject* \*o)

*Py\_ssize\_t* PyMapping\_Length (*PyObject* \*o)

Μέρος του Σταθερό ABI. Returns the number of keys in object *o* on success, and -1 on failure. This is equivalent to the Python expression `len(o)`.

*PyObject* \*PyMapping\_GetItemString (*PyObject* \*o, const char \*key)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. This is the same as `PyObject_GetItem()`, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject\**.

int PyMapping\_SetItemString (*PyObject* \*o, const char \*key, *PyObject* \*v)

Μέρος του Σταθερό ABI. This is the same as `PyObject_SetItem()`, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject\**.



int **PyMapping\_DelItem** (*PyObject* \*o, *PyObject* \*key)

This is an alias of *PyObject\_DelItem()*.

int **PyMapping\_DelItemString** (*PyObject* \*o, const char \*key)

This is the same as *PyObject\_DelItem()*, but *key* is specified as a const char\* UTF-8 encoded bytes string, rather than a *PyObject\**.

int **PyMapping\_HasKey** (*PyObject* \*o, *PyObject* \*key)

*Μέρος του Σταθερό ABI.* Return 1 if the mapping object has the key *key* and 0 otherwise. This is equivalent to the Python expression `key in o`. This function always succeeds.

---

**Σημείωση:** Exceptions which occur when this calls `__getitem__()` method are silently ignored. For proper error handling, use *PyObject\_GetItem()* instead.

---

int **PyMapping\_HasKeyString** (*PyObject* \*o, const char \*key)

*Μέρος του Σταθερό ABI.* This is the same as *PyMapping\_HasKey()*, but *key* is specified as a const char\* UTF-8 encoded bytes string, rather than a *PyObject\**.

---

**Σημείωση:** Exceptions that occur when this calls `__getitem__()` method or while creating the temporary `str` object are silently ignored. For proper error handling, use *PyMapping\_GetItemString()* instead.

---

*PyObject* \***PyMapping\_Keys** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* On success, return a list of the keys in object *o*. On failure, return NULL.

Άλλαξε στην έκδοση 3.7: Previously, the function returned a list or a tuple.

*PyObject* \***PyMapping\_Values** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* On success, return a list of the values in object *o*. On failure, return NULL.

Άλλαξε στην έκδοση 3.7: Previously, the function returned a list or a tuple.

*PyObject* \***PyMapping\_Items** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* On success, return a list of the items in object *o*, where each item is a tuple containing a key-value pair. On failure, return NULL.

Άλλαξε στην έκδοση 3.7: Previously, the function returned a list or a tuple.

## 7.6 Iterator Protocol

There are two functions specifically for working with iterators.

int **PyIter\_Check** (*PyObject* \*o)

*Μέρος του Σταθερό ABI από την έκδοση 3.8.* Return non-zero if the object *o* can be safely passed to *PyIter\_Next()*, and 0 otherwise. This function always succeeds.

int **PyAsyncIter\_Check** (*PyObject* \*o)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Return non-zero if the object *o* provides the `AsyncIterator` protocol, and 0 otherwise. This function always succeeds.

Νέο στην έκδοση 3.10.

*PyObject* \***PyIter\_Next** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return the next value from the iterator *o*. The object must be an iterator according to *PyIter\_Check()* (it is up to the caller to check this). If there are no remaining values, returns NULL with no exception set. If an error occurs while retrieving the item, returns NULL and passes along the exception.

To write a loop which iterates over an iterator, the C code should look something like this:

```
PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while ((item = PyIter_Next(iterator))) {
    /* do something with item */
    ...
    /* release reference when done */
    Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
}
else {
    /* continue doing useful work */
}
```

#### type **PySendResult**

The enum value used to represent different results of `PyIter_Send()`.

Νέο στην έκδοση 3.10.

*PySendResult* **PyIter\_Send** (*PyObject* \*iter, *PyObject* \*arg, *PyObject* \*\*presult)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Sends the *arg* value into the iterator *iter*. Returns:

- `PYGEN_RETURN` if iterator returns. Return value is returned via *presult*.
- `PYGEN_NEXT` if iterator yields. Yielded value is returned via *presult*.
- `PYGEN_ERROR` if iterator has raised an exception. *presult* is set to `NULL`.

Νέο στην έκδοση 3.10.

## 7.7 Buffer Protocol

Certain objects available in Python wrap access to an underlying memory array or *buffer*. Such objects include the built-in `bytes` and `bytearray`, and some extension types like `array.array`. Third-party libraries may define their own types for special purposes, such as image processing or numeric analysis.

While each of these types have their own semantics, they share the common characteristic of being backed by a possibly large memory buffer. It is then desirable, in some situations, to access that buffer directly and without intermediate copying.

Python provides such a facility at the C level in the form of the *buffer protocol*. This protocol has two sides:

- on the producer side, a type can export a «buffer interface» which allows objects of that type to expose information about their underlying buffer. This interface is described in the section *Buffer Object Structures*;
- on the consumer side, several means are available to obtain a pointer to the raw underlying data of an object (for example a method parameter).

Simple objects such as `bytes` and `bytearray` expose their underlying buffer in byte-oriented form. Other forms are possible; for example, the elements exposed by an `array.array` can be multi-byte values.

An example consumer of the buffer interface is the `write()` method of file objects: any object that can export a series of bytes through the buffer interface can be written to a file. While `write()` only needs read-only access

to the internal contents of the object passed to it, other methods such as `readinto()` need write access to the contents of their argument. The buffer interface allows objects to selectively allow or reject exporting of read-write and read-only buffers.

There are two ways for a consumer of the buffer interface to acquire a buffer over a target object:

- call `PyObject_GetBuffer()` with the right parameters;
- call `PyArg_ParseTuple()` (or one of its siblings) with one of the `y*`, `w*` or `s*` *format codes*.

In both cases, `PyBuffer_Release()` must be called when the buffer isn't needed anymore. Failure to do so could lead to various issues such as resource leaks.

## 7.7.1 Buffer structure

Buffer structures (or simply «buffers») are useful as a way to expose the binary data from another object to the Python programmer. They can also be used as a zero-copy slicing mechanism. Using their ability to reference a block of memory, it is possible to expose any data to the Python programmer quite easily. The memory could be a large, constant array in a C extension, it could be a raw block of memory for manipulation before passing to an operating system library, or it could be used to pass around structured data in its native, in-memory format.

Contrary to most data types exposed by the Python interpreter, buffers are not `PyObject` pointers but rather simple C structures. This allows them to be created and copied very simply. When a generic wrapper around a buffer is needed, a `memoryview` object can be created.

For short instructions how to write an exporting object, see *Buffer Object Structures*. For obtaining a buffer, see `PyObject_GetBuffer()`.

type **Py\_buffer**

*Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών) από την έκδοση 3.11.*

void **\*buf**

A pointer to the start of the logical structure described by the buffer fields. This can be any location within the underlying physical memory block of the exporter. For example, with negative *strides* the value may point to the end of the memory block.

For *contiguous* arrays, the value points to the beginning of the memory block.

`PyObject *`**obj**

A new reference to the exporting object. The reference is owned by the consumer and automatically released (i.e. reference count decremented) and set to NULL by `PyBuffer_Release()`. The field is the equivalent of the return value of any standard C-API function.

As a special case, for *temporary* buffers that are wrapped by `PyMemoryView_FromBuffer()` or `PyBuffer_FillInfo()` this field is NULL. In general, exporting objects MUST NOT use this scheme.

`Py_ssize_t` **len**

`product(shape) * itemsize`. For contiguous arrays, this is the length of the underlying memory block. For non-contiguous arrays, it is the length that the logical structure would have if it were copied to a contiguous representation.

Accessing `((char *)buf)[0]` up to `((char *)buf)[len-1]` is only valid if the buffer has been obtained by a request that guarantees contiguity. In most cases such a request will be `PyBUF_SIMPLE` or `PyBUF_WRITABLE`.

int **readonly**

An indicator of whether the buffer is read-only. This field is controlled by the `PyBUF_WRITABLE` flag.

`Py_ssize_t` **itemsize**

Item size in bytes of a single element. Same as the value of `struct.calcsize()` called on non-NULL *format* values.



Important exception: If a consumer requests a buffer without the `PyBUF_FORMAT` flag, `format` will be set to NULL, but `itemsize` still has the value for the original format.

If `shape` is present, the equality product(`shape`) \* `itemsize` == `len` still holds and the consumer can use `itemsize` to navigate the buffer.

If `shape` is NULL as a result of a `PyBUF_SIMPLE` or a `PyBUF_WRITABLE` request, the consumer must disregard `itemsize` and assume `itemsize` == 1.

const char \***format**

A NUL terminated string in struct module style syntax describing the contents of a single item. If this is NULL, "B" (unsigned bytes) is assumed.

This field is controlled by the `PyBUF_FORMAT` flag.

int **ndim**

The number of dimensions the memory represents as an n-dimensional array. If it is 0, `buf` points to a single item representing a scalar. In this case, `shape`, `strides` and `suboffsets` MUST be NULL. The maximum number of dimensions is given by `PyBUF_MAX_NDIM`.

`Py_ssize_t` \***shape**

An array of `Py_ssize_t` of length `ndim` indicating the shape of the memory as an n-dimensional array. Note that `shape[0] * ... * shape[ndim-1] * itemsize` MUST be equal to `len`.

Shape values are restricted to `shape[n] >= 0`. The case `shape[n] == 0` requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

`Py_ssize_t` \***strides**

An array of `Py_ssize_t` of length `ndim` giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case `strides[n] <= 0`. See *complex arrays* for further information.

The strides array is read-only for the consumer.

`Py_ssize_t` \***suboffsets**

An array of `Py_ssize_t` of length `ndim`. If `suboffsets[n] >= 0`, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after de-referencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be NULL (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

void \***internal**

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

Constants:

**PyBUF\_MAX\_NDIM**

The maximum number of dimensions the memory represents. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to `PyBUF_MAX_NDIM` dimensions. Currently set to 64.

## 7.7.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via `PyObject_GetBuffer()`. Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the *flags* argument to specify the exact buffer type it can handle.

All *Py\_buffer* fields are unambiguously defined by the request type.

### request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values: *obj*, *buf*, *len*, *itemsize*, *ndim*.

### readonly, format

#### **PyBUF\_WRITABLE**

Controls the *readonly* field. If set, the exporter **MUST** provide a writable buffer or else report failure. Otherwise, the exporter **MAY** provide either a read-only or writable buffer, but the choice **MUST** be consistent for all consumers.

#### **PyBUF\_FORMAT**

Controls the *format* field. If set, this field **MUST** be filled in correctly. Otherwise, this field **MUST** be `NULL`.

*PyBUF\_WRITABLE* can be |'d to any of the flags in the next section. Since *PyBUF\_SIMPLE* is defined as 0, *PyBUF\_WRITABLE* can be used as a stand-alone flag to request a simple writable buffer.

*PyBUF\_FORMAT* can be |'d to any of the flags except *PyBUF\_SIMPLE*. The latter already implies format B (unsigned bytes).

### shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

Request	shape	strides	suboffsets
<b>PyBUF_INDIRECT</b>	yes	yes	if needed
<b>PyBUF_STRIDES</b>	yes	yes	<code>NULL</code>
<b>PyBUF_ND</b>	yes	<code>NULL</code>	<code>NULL</code>
<b>PyBUF_SIMPLE</b>	<code>NULL</code>	<code>NULL</code>	<code>NULL</code>

## contiguity requests

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

Request	shape	strides	suboffsets	contig
<b>PyBUF_C_CONTIGUOUS</b>	yes	yes	NULL	C
<b>PyBUF_F_CONTIGUOUS</b>	yes	yes	NULL	F
<b>PyBUF_ANY_CONTIGUOUS</b>	yes	yes	NULL	C or F
<i>PyBUF_ND</i>	yes	NULL	NULL	C

## compound requests

All possible requests are fully defined by some combination of the flags in the previous section. For convenience, the buffer protocol provides frequently used combinations as single flags.

In the following table *U* stands for undefined contiguity. The consumer would have to call *PyBuffer\_IsContiguous()* to determine contiguity.

Request	shape	strides	suboffsets	contig	readonly	format
<b>PyBUF_FULL</b>	yes	yes	if needed	U	0	yes
<b>PyBUF_FULL_RO</b>	yes	yes	if needed	U	1 or 0	yes
<b>PyBUF_RECORDS</b>	yes	yes	NULL	U	0	yes
<b>PyBUF_RECORDS_RO</b>	yes	yes	NULL	U	1 or 0	yes
<b>PyBUF_STRIDED</b>	yes	yes	NULL	U	0	NULL
<b>PyBUF_STRIDED_RO</b>	yes	yes	NULL	U	1 or 0	NULL
<b>PyBUF_CONTIG</b>	yes	NULL	NULL	C	0	NULL
<b>PyBUF_CONTIG_RO</b>	yes	NULL	NULL	C	1 or 0	NULL

## 7.7.3 Complex arrays

### NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by *itemsizes*, *ndim*, *shape* and *strides*.

If *ndim* == 0, the memory location pointed to by *buf* is interpreted as a scalar of size *itemsizes*. In that case, both *shape* and *strides* are NULL.

If *strides* is NULL, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, *buf* can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsizes, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
    the bounds of the allocated memory:
        char *mem: start of the physical memory block
        memlen: length of the physical memory block
        offset: (char *)buf - mem
    """
    if offset % itemsizes:
        return False
    if offset < 0 or offset+itemsizes > memlen:
        return False
    if any(v % itemsizes for v in strides):
        return False

    if ndim <= 0:
        return ndim == 0 and not shape and not strides
    if 0 in shape:
        return True

    imin = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] <= 0)
    imax = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] > 0)

    return 0 <= offset+imin and offset+imax+itemsizes <= memlen
```

### PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array `char v[2][2][3]` can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: `char (*v[2])[2][3]`. In suboffsets representation, those two pointers can be embedded at the start of *buf*, pointing to two `char x[2][3]` arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-NULL strides and suboffsets:

```
void *get_item_pointer(int ndim, void *buf, Py_ssize_t *strides,
                      Py_ssize_t *suboffsets, Py_ssize_t *indices) {
    char *pointer = (char*)buf;
    int i;
    for (i = 0; i < ndim; i++) {
        pointer += strides[i] * indices[i];
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

    if (suboffsets[i] >= 0 ) {
        pointer = *((char**)pointer) + suboffsets[i];
    }
}
return (void*)pointer;
}

```

## 7.7.4 Buffer-related functions

int **PyObject\_CheckBuffer** (*PyObject* \*obj)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Return 1 if *obj* supports the buffer interface otherwise 0. When 1 is returned, it doesn't guarantee that *PyObject\_GetBuffer()* will succeed. This function always succeeds.

int **PyObject\_GetBuffer** (*PyObject* \*exporter, *Py\_buffer* \*view, int flags)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Send a request to *exporter* to fill in *view* as specified by *flags*. If the exporter cannot provide a buffer of the exact type, it MUST raise *BufferError*, set *view->obj* to *NULL* and return -1.

On success, fill in *view*, set *view->obj* to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, *view->obj* MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to *PyObject\_GetBuffer()* must be paired with calls to *PyBuffer\_Release()*, similar to *malloc()* and *free()*. Thus, after the consumer is done with the buffer, *PyBuffer\_Release()* must be called exactly once.

void **PyBuffer\_Release** (*Py\_buffer* \*view)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Release the buffer *view* and release the *strong reference* (i.e. decrement the reference count) to the view's supporting object, *view->obj*. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via *PyObject\_GetBuffer()*.

*Py\_ssize\_t* **PyBuffer\_SizeFromFormat** (const char \*format)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Return the implied *itemsz* from *format*. On error, raise an exception and return -1.

Νέο στην έκδοση 3.9.

int **PyBuffer\_IsContiguous** (const *Py\_buffer* \*view, char order)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Return 1 if the memory defined by the *view* is C-style (*order* is 'C') or Fortran-style (*order* is 'F') *contiguous* or either one (*order* is 'A'). Return 0 otherwise. This function always succeeds.

void **\*PyBuffer\_GetPointer** (const *Py\_buffer* \*view, const *Py\_ssize\_t* \*indices)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Get the memory area pointed to by the *indices* inside the given *view*. *indices* must point to an array of *view->ndim* indices.

int **PyBuffer\_FromContiguous** (const *Py\_buffer* \*view, const void \*buf, *Py\_ssize\_t* len, char fort)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Copy contiguous *len* bytes from *buf* to *view*. *fort* can be 'C' or 'F' (for C-style or Fortran-style ordering). 0 is returned on success, -1 on error.

int **PyBuffer\_ToContiguous** (void \*buf, const *Py\_buffer* \*src, *Py\_ssize\_t* len, char order)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Copy *len* bytes from *src* to its contiguous representation in *buf*. *order* can be 'C' or 'F' or 'A' (for C-style or Fortran-style ordering or either one). 0 is returned on success, -1 on error.

This function fails if *len* != *src->len*.

int **PyObject\_CopyData** (*PyObject* \*dest, *PyObject* \*src)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Copy data from *src* to *dest* buffer. Can convert between C-style and or Fortran-style buffers.

0 is returned on success, -1 on error.

void **PyBuffer\_FillContiguousStrides** (int ndims, *Py\_ssize\_t* \*shape, *Py\_ssize\_t* \*strides, int itemsize, char order)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Fill the *strides* array with byte-strides of a *contiguous* (C-style if *order* is 'C' or Fortran-style if *order* is 'F') array of the given shape with the given number of bytes per element.

int **PyBuffer\_FillInfo** (*Py\_buffer* \*view, *PyObject* \*exporter, void \*buf, *Py\_ssize\_t* len, int readonly, int flags)

Μέρος του Σταθερό ABI από την έκδοση 3.11. Handle buffer requests for an exporter that wants to expose *buf* of size *len* with writability set according to *readonly*. *buf* is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and `PyBUF_WRITABLE` is set in *flags*.

On success, set *view*->*obj* to a new reference to *exporter* and return 0. Otherwise, raise `BufferError`, set *view*->*obj* to NULL and return -1;

If this function is used as part of a *getbufferproc*, *exporter* MUST be set to the exporting object and *flags* must be passed unmodified. Otherwise, *exporter* MUST be NULL.

## 7.8 Old Buffer Protocol

Αποσύρθηκε στην έκδοση 3.0.

These functions were part of the «old buffer protocol» API in Python 2. In Python 3, this protocol doesn't exist anymore but the functions are still exposed to ease porting 2.x code. They act as a compatibility wrapper around the *new buffer protocol*, but they don't give you control over the lifetime of the resources acquired when a buffer is exported.

Therefore, it is recommended that you call `PyObject_GetBuffer()` (or the *y\** or *w\** *format codes* with the `PyArg_ParseTuple()` family of functions) to get a buffer view over an object, and `PyBuffer_Release()` when the buffer view can be released.

int **PyObject\_AsCharBuffer** (*PyObject* \*obj, const char \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

Μέρος του Σταθερό ABI. Returns a pointer to a read-only memory location usable as character-based input. The *obj* argument must support the single-segment character buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a `TypeError` on error.

int **PyObject\_AsReadBuffer** (*PyObject* \*obj, const void \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

Μέρος του Σταθερό ABI. Returns a pointer to a read-only memory location containing arbitrary data. The *obj* argument must support the single-segment readable buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a `TypeError` on error.

int **PyObject\_CheckReadBuffer** (*PyObject* \*o)

Μέρος του Σταθερό ABI. Returns 1 if *o* supports the single-segment readable buffer interface. Otherwise returns 0. This function always succeeds.

Note that this function tries to get and release a buffer, and exceptions which occur while calling corresponding functions will get suppressed. To get error reporting use `PyObject_GetBuffer()` instead.

int **PyObject\_AsWriteBuffer** (*PyObject* \*obj, void \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

Μέρος του Σταθερό ABI. Returns a pointer to a writable memory location. The *obj* argument must support the single-segment, character buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a `TypeError` on error.

---

Concrete Objects Layer

---

The functions in this chapter are specific to certain Python object types. Passing them an object of the wrong type is not a good idea; if you receive an object from a Python program and you are not sure that it has the right type, you must perform a type check first; for example, to check that an object is a dictionary, use `PyDict_Check()`. The chapter is structured like the «family tree» of Python object types.

**Προειδοποίηση:** While the functions described in this chapter carefully check the type of the objects which are passed in, many of them do not check for `NULL` being passed instead of a valid object. Allowing `NULL` to be passed in can cause memory access violations and immediate termination of the interpreter.

## 8.1 Fundamental Objects

This section describes Python type objects and the singleton object `None`.

### 8.1.1 Type Objects

type **PyTypeObject**

*Μέρος του Περιορισμένου API (ως μια αδιαφανής κατασκευή).* The C structure of the objects used to describe built-in types.

*PyTypeObject* **PyType\_Type**

*Μέρος του Σταθερό ABI.* This is the type object for type objects; it is the same object as `type` in the Python layer.

int **PyType\_Check** (*PyObject* \*o)

Return non-zero if the object *o* is a type object, including instances of types derived from the standard type object. Return 0 in all other cases. This function always succeeds.

int **PyType\_CheckExact** (*PyObject* \*o)

Return non-zero if the object *o* is a type object, but not a subtype of the standard type object. Return 0 in all other cases. This function always succeeds.

unsigned int **PyType\_ClearCache** ()

*Μέρος του Σταθερό ABI.* Clear the internal lookup cache. Return the current version tag.

unsigned long **PyType\_GetFlags** (PyTypeObject \*type)

*Μέρος του Σταθερό ABI.* Return the `tp_flags` member of `type`. This function is primarily meant for use with `Py_LIMITED_API`; the individual flag bits are guaranteed to be stable across Python releases, but access to `tp_flags` itself is not part of the *limited API*.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.4: The return type is now `unsigned long` rather than `long`.

void **PyType\_Modified** (PyTypeObject \*type)

*Μέρος του Σταθερό ABI.* Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

int **PyType\_HasFeature** (PyTypeObject \*o, int feature)

Return non-zero if the type object `o` sets the feature `feature`. Type features are denoted by single bit flags.

int **PyType\_IS\_GC** (PyTypeObject \*o)

Return true if the type object includes support for the cycle detector; this tests the type flag `Py_TPFLAGS_HAVE_GC`.

int **PyType\_IsSubtype** (PyTypeObject \*a, PyTypeObject \*b)

*Μέρος του Σταθερό ABI.* Return true if `a` is a subtype of `b`.

This function only checks for actual subtypes, which means that `__subclasscheck__()` is not called on `b`. Call `PyObject_IsSubclass()` to do the same check that `issubclass()` would do.

PyObject \***PyType\_GenericAlloc** (PyTypeObject \*type, Py\_ssize\_t nitems)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Generic handler for the `tp_alloc` slot of a type object. Use Python's default memory allocation mechanism to allocate a new instance and initialize all its contents to NULL.

PyObject \***PyType\_GenericNew** (PyTypeObject \*type, PyObject \*args, PyObject \*kwargs)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Generic handler for the `tp_new` slot of a type object. Create a new instance using the type's `tp_alloc` slot.

int **PyType\_Ready** (PyTypeObject \*type)

*Μέρος του Σταθερό ABI.* Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return 0 on success, or return -1 and sets an exception on error.

---

**Σημείωση:** If some of the base classes implements the GC protocol and the provided type does not include the `Py_TPFLAGS_HAVE_GC` in its flags, then the GC protocol will be automatically implemented from its parents. On the contrary, if the type being created does include `Py_TPFLAGS_HAVE_GC` in its flags then it **must** implement the GC protocol itself by at least implementing the `tp_traverse` handle.

---

PyObject \***PyType\_GetName** (PyTypeObject \*type)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI από την έκδοση 3.11.* Return the type's name. Equivalent to getting the type's `__name__` attribute.

Νέο στην έκδοση 3.11.

PyObject \***PyType\_GetQualName** (PyTypeObject \*type)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI από την έκδοση 3.11.* Return the type's qualified name. Equivalent to getting the type's `__qualname__` attribute.

Νέο στην έκδοση 3.11.



void **\*PyType\_GetSlot** (*PyTypeObject* \*type, int slot)

*Μέρος του Σταθερό ABI από την έκδοση 3.4.* Return the function pointer stored in the given slot. If the result is NULL, this indicates that either the slot is NULL, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See `PyType_Slot.slot` for possible values of the *slot* argument.

Νέο στην έκδοση 3.4.

Άλλαξε στην έκδοση 3.10: `PyType_GetSlot()` can now accept all types. Previously, it was limited to *heap types*.

*PyObject* **\*PyType\_GetModule** (*PyTypeObject* \*type)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Return the module object associated with the given type when the type was created using `PyType_FromModuleAndSpec()`.

If no module is associated with the given type, sets `TypeError` and returns NULL.

This function is usually used to get the module in which a method is defined. Note that in such a method, `PyType_GetModule(Py_TYPE(self))` may not return the intended result. `Py_TYPE(self)` may be a *subclass* of the intended class, and subclasses are not necessarily defined in the same module as their superclass. See `PyCMethod` to get the class that defines the method. See `PyType_GetModuleByDef()` for cases when `PyCMethod` cannot be used.

Νέο στην έκδοση 3.9.

void **\*PyType\_GetModuleState** (*PyTypeObject* \*type)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Return the state of the module object associated with the given type. This is a shortcut for calling `PyModule_GetState()` on the result of `PyType_GetModule()`.

If no module is associated with the given type, sets `TypeError` and returns NULL.

If the *type* has an associated module but its state is NULL, returns NULL without setting an exception.

Νέο στην έκδοση 3.9.

*PyObject* **\*PyType\_GetModuleByDef** (*PyTypeObject* \*type, struct *PyModuleDef* \*def)

Find the first superclass whose module was created from the given `PyModuleDef def`, and return that module.

If no module is found, raises a `TypeError` and returns NULL.

This function is intended to be used together with `PyModule_GetState()` to get module state from slot methods (such as `tp_init` or `nb_add`) and other places where a method's defining class cannot be passed using the `PyCMethod` calling convention.

Νέο στην έκδοση 3.11.

## Creating Heap-Allocated Types

The following functions and structs are used to create *heap types*.

*PyObject* **\*PyType\_FromModuleAndSpec** (*PyObject* \*module, *PyType\_Spec* \*spec, *PyObject* \*bases)

*Επιστρεφόμενη τιμή:* *New reference.* *Μέρος του Σταθερό ABI από την έκδοση 3.10.* Creates and returns a *heap type* from the *spec* (`Py_TPFLAGS_HEAPTYPE`).

The *bases* argument can be used to specify base classes; it can either be only one class or a tuple of classes. If *bases* is NULL, the `Py_tp_bases` slot is used instead. If that also is NULL, the `Py_tp_base` slot is used instead. If that also is NULL, the new type derives from `object`.

The *module* argument can be used to record the module in which the new class is defined. It must be a module object or NULL. If not NULL, the module is associated with the new type and can later be retrieved with `PyType_GetModule()`. The associated module is not inherited by subclasses; it must be specified for each class individually.

This function calls `PyType_Ready()` on the new type.

Νέο στην έκδοση 3.9.

Αλλάξε στην έκδοση 3.10: The function now accepts a single class as the *bases* argument and NULL as the *tp\_doc* slot.

*PyObject* \***PyType\_FromSpecWithBases** (*PyType\_Spec* \*spec, *PyObject* \*bases)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.3. Equivalent to `PyType_FromModuleAndSpec(NULL, spec, bases)`.

Νέο στην έκδοση 3.3.

*PyObject* \***PyType\_FromSpec** (*PyType\_Spec* \*spec)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Equivalent to `PyType_FromSpecWithBases(spec, NULL)`.

type **PyType\_Spec**

Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών). Structure defining a type's behavior.

const char \*PyType\_Spec.name

Name of the type, used to set *PyTypeObject.tp\_name*.

int PyType\_Spec.basicsize

int PyType\_Spec.itemsize

Size of the instance in bytes, used to set *PyTypeObject.tp\_basicsize* and *PyTypeObject.tp\_itemsize*.

int PyType\_Spec.flags

Type flags, used to set *PyTypeObject.tp\_flags*.

If the `Py_TPFLAGS_HEAPTYPE` flag is not set, *PyType\_FromSpecWithBases()* sets it automatically.

*PyType\_Slot* \*PyType\_Spec.slots

Array of *PyType\_Slot* structures. Terminated by the special slot value {0, NULL}.

type **PyType\_Slot**

Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών). Structure defining optional functionality of a type, containing a slot ID and a value pointer.

int PyType\_Slot.slot

A slot ID.

Slot IDs are named like the field names of the structures *PyTypeObject*, *PyNumberMethods*, *PySequenceMethods*, *PyMappingMethods* and *PyAsyncMethods* with an added `Py_` prefix. For example, use:

- `Py_tp_dealloc` to set *PyTypeObject.tp\_dealloc*
- `Py_nb_add` to set *PyNumberMethods.nb\_add*
- `Py_sq_length` to set *PySequenceMethods.sq\_length*

The following fields cannot be set at all using *PyType\_Spec* and *PyType\_Slot*:

- *tp\_dict*
- *tp\_mro*
- *tp\_cache*
- *tp\_subclasses*
- *tp\_weaklist*
- *tp\_vectorcall*
- *tp\_weaklistoffset* (see *PyMemberDef*)

- `tp_dictoffset` (see *PyMemberDef*)
- `tp_vectorcall_offset` (see *PyMemberDef*)

Setting `Py_tp_bases` or `Py_tp_base` may be problematic on some platforms. To avoid issues, use the *bases* argument of *PyType\_FromSpecWithBases()* instead.

Αλλάξε στην έκδοση 3.9: Slots in *PyBufferProcs* may be set in the unlimited API.

Αλλάξε στην έκδοση 3.11: *bf\_getbuffer* and *bf\_releasebuffer* are now available under the *limited API*.

void \*PyType\_Slot.**pfunc**

The desired value of the slot. In most cases, this is a pointer to a function.

Slots other than `Py_tp_doc` may not be NULL.

## 8.1.2 The None Object

Note that the *PyTypeObject* for `None` is not directly exposed in the Python/C API. Since `None` is a singleton, testing for object identity (using `==` in C) is sufficient. There is no `PyNone_Check()` function for the same reason.

*PyObject* \*Py\_None

The Python `None` object, denoting lack of value. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

Py\_RETURN\_NONE

Properly handle returning *Py\_None* from within a C function (that is, increment the reference count of `None` and return it.)

## 8.2 Numeric Objects

### 8.2.1 Integer Objects

All integers are implemented as «long» integer objects of arbitrary size.

On error, most `PyLong_As*` APIs return `(return type) - 1` which cannot be distinguished from a number. Use *PyErr\_Occurred()* to disambiguate.

type PyLongObject

Μέρος του Περιορισμένο API (ως μια αδιαφανής κατασκευή). This subtype of *PyObject* represents a Python integer object.

*PyTypeObject* PyLong\_Type

Μέρος του Σταθερό ABI. This instance of *PyTypeObject* represents the Python integer type. This is the same object as `int` in the Python layer.

int PyLong\_Check (PyObject \*p)

Return true if its argument is a *PyLongObject* or a subtype of *PyLongObject*. This function always succeeds.

int PyLong\_CheckExact (PyObject \*p)

Return true if its argument is a *PyLongObject*, but not a subtype of *PyLongObject*. This function always succeeds.

*PyObject* \*PyLong\_FromLong (long v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from v, or NULL on failure.

The current implementation keeps an array of integer objects for all integers between  $-5$  and  $256$ . When you create an int in that range you actually just get back a reference to the existing object.

*PyObject* \*PyLong\_FromUnsignedLong (unsigned long v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from a C unsigned long, or NULL on failure.

*PyObject* \*PyLong\_FromSsize\_t (Py\_ssize\_t v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from a C *Py\_ssize\_t*, or NULL on failure.

*PyObject* \*PyLong\_FromSize\_t (size\_t v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from a C *size\_t*, or NULL on failure.

*PyObject* \*PyLong\_FromLongLong (long long v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from a C long long, or NULL on failure.

*PyObject* \*PyLong\_FromUnsignedLongLong (unsigned long long v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from a C unsigned long long, or NULL on failure.

*PyObject* \*PyLong\_FromDouble (double v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* object from the integer part of v, or NULL on failure.

*PyObject* \*PyLong\_FromString (const char \*str, char \*\*pend, int base)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new *PyLongObject* based on the string value in *str*, which is interpreted according to the radix in *base*. If *pend* is non-NULL, *\*pend* will point to the first character in *str* which follows the representation of the number. If *base* is 0, *str* is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a *ValueError*. If *base* is not 0, it must be between 2 and 36, inclusive. Leading spaces and single underscores after a base specifier and between digits are ignored. If there are no digits, *ValueError* will be raised.

**Δείτε επίσης:**

Python methods *int.to\_bytes()* and *int.from\_bytes()* to convert a *PyLongObject* to/from an array of bytes in base 256. You can call those from C using *PyObject\_CallMethod()*.

*PyObject* \*PyLong\_FromUnicodeObject (*PyObject* \*u, int base)

*Επιστρεφόμενη τιμή:* New reference. Convert a sequence of Unicode digits in the string *u* to a Python integer value.

Νέο στην έκδοση 3.3.

*PyObject* \*PyLong\_FromVoidPtr (void \*p)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Python integer from the pointer *p*. The pointer value can be retrieved from the resulting value using *PyLong\_AsVoidPtr()*.

long PyLong\_AsLong (*PyObject* \*obj)

Μέρος του Σταθερό ABI. Return a C long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its *\_\_index\_\_()* method (if present) to convert it to a *PyLongObject*.

Raise *OverflowError* if the value of *obj* is out of range for a long.

Returns  $-1$  on error. Use *PyErr\_Occurred()* to disambiguate.

Αλλάξε στην έκδοση 3.8: Use *\_\_index\_\_()* if available.

Αλλάξε στην έκδοση 3.10: This function will no longer use *\_\_int\_\_()*.

`long PyLong_AsLongAndOverflow(PyObject *obj, int *overflow)`

*Μέρος του Σταθερό ABI.* Return a C long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than `LONG_MAX` or less than `LONG_MIN`, set *\*overflow* to 1 or -1, respectively, and return -1; otherwise, set *\*overflow* to 0. If any other exception occurs set *\*overflow* to 0 and return -1 as usual.

Returns -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Άλλαξε στην έκδοση 3.8: Use `__index__()` if available.

Άλλαξε στην έκδοση 3.10: This function will no longer use `__int__()`.

`long long PyLong_AsLongLong(PyObject *obj)`

*Μέρος του Σταθερό ABI.* Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Raise *OverflowError* if the value of *obj* is out of range for a long long.

Returns -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Άλλαξε στην έκδοση 3.8: Use `__index__()` if available.

Άλλαξε στην έκδοση 3.10: This function will no longer use `__int__()`.

`long long PyLong_AsLongLongAndOverflow(PyObject *obj, int *overflow)`

*Μέρος του Σταθερό ABI.* Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than `LLONG_MAX` or less than `LLONG_MIN`, set *\*overflow* to 1 or -1, respectively, and return -1; otherwise, set *\*overflow* to 0. If any other exception occurs set *\*overflow* to 0 and return -1 as usual.

Returns -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.8: Use `__index__()` if available.

Άλλαξε στην έκδοση 3.10: This function will no longer use `__int__()`.

`Py_ssize_t PyLong_AsSsize_t(PyObject *pylong)`

*Μέρος του Σταθερό ABI.* Return a C *Py\_ssize\_t* representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for a *Py\_ssize\_t*.

Returns -1 on error. Use *PyErr\_Occurred()* to disambiguate.

`unsigned long PyLong_AsUnsignedLong(PyObject *pylong)`

*Μέρος του Σταθερό ABI.* Return a C unsigned long representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for a unsigned long.

Returns (unsigned long)-1 on error. Use *PyErr\_Occurred()* to disambiguate.

`size_t PyLong_AsSize_t(PyObject *pylong)`

*Μέρος του Σταθερό ABI.* Return a C *size\_t* representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for a *size\_t*.

Returns (size\_t)-1 on error. Use *PyErr\_Occurred()* to disambiguate.

unsigned long long **PyLong\_AsUnsignedLongLong** (*PyObject* \*pylong)

*Μέρος του Σταθερό ABI.* Return a C unsigned long long representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for an unsigned long long.

Returns (unsigned long long) -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Άλλαξε στην έκδοση 3.1: A negative *pylong* now raises *OverflowError*, not *TypeError*.

unsigned long **PyLong\_AsUnsignedLongMask** (*PyObject* \*obj)

*Μέρος του Σταθερό ABI.* Return a C unsigned long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its *\_\_index\_\_()* method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long, return the reduction of that value modulo *ULONG\_MAX + 1*.

Returns (unsigned long) -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Άλλαξε στην έκδοση 3.8: Use *\_\_index\_\_()* if available.

Άλλαξε στην έκδοση 3.10: This function will no longer use *\_\_int\_\_()*.

unsigned long long **PyLong\_AsUnsignedLongLongMask** (*PyObject* \*obj)

*Μέρος του Σταθερό ABI.* Return a C unsigned long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its *\_\_index\_\_()* method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long long, return the reduction of that value modulo *ULLONG\_MAX + 1*.

Returns (unsigned long long) -1 on error. Use *PyErr\_Occurred()* to disambiguate.

Άλλαξε στην έκδοση 3.8: Use *\_\_index\_\_()* if available.

Άλλαξε στην έκδοση 3.10: This function will no longer use *\_\_int\_\_()*.

double **PyLong\_AsDouble** (*PyObject* \*pylong)

*Μέρος του Σταθερό ABI.* Return a C double representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for a double.

Returns -1.0 on error. Use *PyErr\_Occurred()* to disambiguate.

void **\*PyLong\_AsVoidPtr** (*PyObject* \*pylong)

*Μέρος του Σταθερό ABI.* Convert a Python integer *pylong* to a C void pointer. If *pylong* cannot be converted, an *OverflowError* will be raised. This is only assured to produce a usable void pointer for values created with *PyLong\_FromVoidPtr()*.

Returns NULL on error. Use *PyErr\_Occurred()* to disambiguate.

## 8.2.2 Boolean Objects

Booleans in Python are implemented as a subclass of integers. There are only two booleans, *Py\_False* and *Py\_True*. As such, the normal creation and deletion functions don't apply to booleans. The following macros are available, however.

*PyTypeObject* **PyBool\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python boolean type; it is the same object as *bool* in the Python layer.

int **PyBool\_Check** (*PyObject* \*o)

Return true if *o* is of type *PyBool\_Type*. This function always succeeds.



***PyObject* \*Py\_False**

The Python `False` object. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

***PyObject* \*Py\_True**

The Python `True` object. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

**Py\_RETURN\_FALSE**

Return `Py_False` from a function, properly incrementing its reference count.

**Py\_RETURN\_TRUE**

Return `Py_True` from a function, properly incrementing its reference count.

***PyObject* \*PyBool\_FromLong** (long v)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a new reference to `Py_True` or `Py_False` depending on the truth value of v.

## 8.2.3 Floating Point Objects

**type `PyFloatObject`**

This subtype of *PyObject* represents a Python floating point object.

***PyTypeObject* `PyFloat_Type`**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python floating point type. This is the same object as `float` in the Python layer.

**int `PyFloat_Check`** (*PyObject* \*p)

Return true if its argument is a *PyFloatObject* or a subtype of *PyFloatObject*. This function always succeeds.

**int `PyFloat_CheckExact`** (*PyObject* \*p)

Return true if its argument is a *PyFloatObject*, but not a subtype of *PyFloatObject*. This function always succeeds.

***PyObject* \*PyFloat\_FromString** (*PyObject* \*str)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Create a *PyFloatObject* object based on the string value in *str*, or NULL on failure.

***PyObject* \*PyFloat\_FromDouble** (double v)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Create a *PyFloatObject* object from v, or NULL on failure.

**double `PyFloat_AsDouble`** (*PyObject* \*pyfloat)

*Μέρος του Σταθερό ABI.* Return a C double representation of the contents of *pyfloat*. If *pyfloat* is not a Python floating point object but has a `__float__()` method, this method will first be called to convert *pyfloat* into a float. If `__float__()` is not defined then it falls back to `__index__()`. This method returns `-1.0` upon failure, so one should call *PyErr\_Occurred()* to check for errors.

Άλλαξε στην έκδοση 3.8: Use `__index__()` if available.

**double `PyFloat_AS_DOUBLE`** (*PyObject* \*pyfloat)

Return a C double representation of the contents of *pyfloat*, but without error checking.

***PyObject* \*PyFloat\_GetInfo** (void)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a structseq instance which contains information about the precision, minimum and maximum values of a float. It's a thin wrapper around the header file `float.h`.

double **PyFloat\_GetMax** ()

*Μέρος του Σταθερό ABI.* Return the maximum representable finite float *DBL\_MAX* as C double.

double **PyFloat\_GetMin** ()

*Μέρος του Σταθερό ABI.* Return the minimum normalized positive float *DBL\_MIN* as C double.

### Pack and Unpack functions

The pack and unpack functions provide an efficient platform-independent way to store floating-point values as byte strings. The Pack routines produce a bytes string from a C double, and the Unpack routines produce a C double from such a bytes string. The suffix (2, 4 or 8) specifies the number of bytes in the bytes string.

On platforms that appear to use IEEE 754 formats these functions work by copying bits. On other platforms, the 2-byte format is identical to the IEEE 754 binary16 half-precision format, the 4-byte format (32-bit) is identical to the IEEE 754 binary32 single precision format, and the 8-byte format to the IEEE 754 binary64 double precision format, although the packing of INFs and NaNs (if such things exist on the platform) isn't handled correctly, and attempting to unpack a bytes string containing an IEEE INF or NaN will raise an exception.

On non-IEEE platforms with more precision, or larger dynamic range, than IEEE 754 supports, not all values can be packed; on non-IEEE platforms with less precision, or smaller dynamic range, not all values can be unpacked. What happens in such cases is partly accidental (alas).

Νέο στην έκδοση 3.11.

### Pack functions

The pack routines write 2, 4 or 8 bytes, starting at *p*. *le* is an int argument, non-zero if you want the bytes string in little-endian format (exponent last, at *p*+1, *p*+3, or *p*+6 *p*+7), zero if you want big-endian format (exponent first, at *p*). The PY\_BIG\_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: 0 if all is OK, -1 if error (and an exception is set, most likely `OverflowError`).

There are two problems on non-IEEE platforms:

- What this does is undefined if *x* is a NaN or infinity.
- `-0.0` and `+0.0` produce the same bytes string.

int **PyFloat\_Pack2** (double *x*, unsigned char \**p*, int *le*)

Pack a C double as the IEEE 754 binary16 half-precision format.

int **PyFloat\_Pack4** (double *x*, unsigned char \**p*, int *le*)

Pack a C double as the IEEE 754 binary32 single precision format.

int **PyFloat\_Pack8** (double *x*, unsigned char \**p*, int *le*)

Pack a C double as the IEEE 754 binary64 double precision format.

### Unpack functions

The unpack routines read 2, 4 or 8 bytes, starting at *p*. *le* is an int argument, non-zero if the bytes string is in little-endian format (exponent last, at *p*+1, *p*+3 or *p*+6 and *p*+7), zero if big-endian (exponent first, at *p*). The PY\_BIG\_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: The unpacked double. On error, this is `-1.0` and `PyErr_Occurred()` is true (and an exception is set, most likely `OverflowError`).

Note that on a non-IEEE platform this will refuse to unpack a bytes string that represents a NaN or infinity.



double **PyFloat\_Unpack2** (const unsigned char \*p, int le)

Unpack the IEEE 754 binary16 half-precision format as a C double.

double **PyFloat\_Unpack4** (const unsigned char \*p, int le)

Unpack the IEEE 754 binary32 single precision format as a C double.

double **PyFloat\_Unpack8** (const unsigned char \*p, int le)

Unpack the IEEE 754 binary64 double precision format as a C double.

## 8.2.4 Complex Number Objects

Python's complex number objects are implemented as two distinct types when viewed from the C API: one is the Python object exposed to Python programs, and the other is a C structure which represents the actual complex number value. The API provides functions for working with both.

### Complex Numbers as C Structures

Note that the functions which accept these structures as parameters and return them as results do so *by value* rather than dereferencing them through pointers. This is consistent throughout the API.

type **Py\_complex**

The C structure which corresponds to the value portion of a Python complex number object. Most of the functions for dealing with complex number objects use structures of this type as input or output values, as appropriate. It is defined as:

```
typedef struct {
    double real;
    double imag;
} Py_complex;
```

*Py\_complex* **\_Py\_c\_sum** (*Py\_complex* left, *Py\_complex* right)

Return the sum of two complex numbers, using the C *Py\_complex* representation.

*Py\_complex* **\_Py\_c\_diff** (*Py\_complex* left, *Py\_complex* right)

Return the difference between two complex numbers, using the C *Py\_complex* representation.

*Py\_complex* **\_Py\_c\_neg** (*Py\_complex* num)

Return the negation of the complex number *num*, using the C *Py\_complex* representation.

*Py\_complex* **\_Py\_c\_prod** (*Py\_complex* left, *Py\_complex* right)

Return the product of two complex numbers, using the C *Py\_complex* representation.

*Py\_complex* **\_Py\_c\_quot** (*Py\_complex* dividend, *Py\_complex* divisor)

Return the quotient of two complex numbers, using the C *Py\_complex* representation.

If *divisor* is null, this method returns zero and sets `errno` to `EDOM`.

*Py\_complex* **\_Py\_c\_pow** (*Py\_complex* num, *Py\_complex* exp)

Return the exponentiation of *num* by *exp*, using the C *Py\_complex* representation.

If *num* is null and *exp* is not a positive real number, this method returns zero and sets `errno` to `EDOM`.

## Complex Numbers as Python Objects

type **PyComplexObject**

This subtype of *PyObject* represents a Python complex number object.

*PyTypeObject* **PyComplex\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python complex number type. It is the same object as `complex` in the Python layer.

int **PyComplex\_Check** (*PyObject* \*p)

Return true if its argument is a *PyComplexObject* or a subtype of *PyComplexObject*. This function always succeeds.

int **PyComplex\_CheckExact** (*PyObject* \*p)

Return true if its argument is a *PyComplexObject*, but not a subtype of *PyComplexObject*. This function always succeeds.

*PyObject* \***PyComplex\_FromCComplex** (*Py\_complex* v)

*Επιστρεφόμενη τιμή: New reference.* Create a new Python complex number object from a C *Py\_complex* value.

*PyObject* \***PyComplex\_FromDoubles** (double real, double imag)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Return a new *PyComplexObject* object from *real* and *imag*.

double **PyComplex\_RealAsDouble** (*PyObject* \*op)

*Μέρος του Σταθερό ABI.* Return the real part of *op* as a C double.

double **PyComplex\_ImagAsDouble** (*PyObject* \*op)

*Μέρος του Σταθερό ABI.* Return the imaginary part of *op* as a C double.

*Py\_complex* **PyComplex\_AsCComplex** (*PyObject* \*op)

Return the *Py\_complex* value of the complex number *op*.

If *op* is not a Python complex number object but has a `__complex__()` method, this method will first be called to convert *op* to a Python complex number object. If `__complex__()` is not defined then it falls back to `__float__()`. If `__float__()` is not defined then it falls back to `__index__()`. Upon failure, this method returns `-1.0` as a real value.

Άλλαξε στην έκδοση 3.8: Use `__index__()` if available.

## 8.3 Sequence Objects

Generic operations on sequence objects were discussed in the previous chapter; this section deals with the specific kinds of sequence objects that are intrinsic to the Python language.

### 8.3.1 Bytes Objects

These functions raise `TypeError` when expecting a bytes parameter and called with a non-bytes parameter.

type **PyBytesObject**

This subtype of *PyObject* represents a Python bytes object.

*PyTypeObject* **PyBytes\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python bytes type; it is the same object as `bytes` in the Python layer.

**int PyBytes\_Check** (*PyObject* \*o)

Return true if the object *o* is a bytes object or an instance of a subtype of the bytes type. This function always succeeds.

**int PyBytes\_CheckExact** (*PyObject* \*o)

Return true if the object *o* is a bytes object, but not an instance of a subtype of the bytes type. This function always succeeds.

*PyObject* \***PyBytes\_FromString** (const char \*v)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new bytes object with a copy of the string *v* as value on success, and NULL on failure. The parameter *v* must not be NULL; it will not be checked.

*PyObject* \***PyBytes\_FromStringAndSize** (const char \*v, *Py\_ssize\_t* len)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new bytes object with a copy of the string *v* as value and length *len* on success, and NULL on failure. If *v* is NULL, the contents of the bytes object are uninitialized.

*PyObject* \***PyBytes\_FromFormat** (const char \*format, ...)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Take a C `printf()`-style *format* string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the *format* string. The following format characters are allowed:

Format Characters	Type	Comment
%%	<i>n/a</i>	The literal % character.
%c	int	A single byte, represented as a C int.
%d	int	Equivalent to <code>printf("%d").</code> <sup>1</sup>
%u	unsigned int	Equivalent to <code>printf("%u").</code> <sup>1</sup>
%ld	long	Equivalent to <code>printf("%ld").</code> <sup>1</sup>
%lu	unsigned long	Equivalent to <code>printf("%lu").</code> <sup>1</sup>
%zd	<i>Py_ssize_t</i>	Equivalent to <code>printf("%zd").</code> <sup>1</sup>
%zu	<i>size_t</i>	Equivalent to <code>printf("%zu").</code> <sup>1</sup>
%i	int	Equivalent to <code>printf("%i").</code> <sup>1</sup>
%x	int	Equivalent to <code>printf("%x").</code> <sup>1</sup>
%s	const char*	A null-terminated C character array.
%p	const void*	The hex representation of a C pointer. Mostly equivalent to <code>printf("%p")</code> except that it is guaranteed to start with the literal 0x regardless of what the platform's <code>printf</code> yields.

An unrecognized format character causes all the rest of the format string to be copied as-is to the result object, and any extra arguments discarded.

*PyObject* \***PyBytes\_FromFormatV** (const char \*format, va\_list vargs)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Identical to *PyBytes\_FromFormat()* except that it takes exactly two arguments.

*PyObject* \***PyBytes\_FromObject** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the bytes representation of object *o* that implements the buffer protocol.

*Py\_ssize\_t* **PyBytes\_Size** (*PyObject* \*o)

Μέρος του Σταθερό ABI. Return the length of the bytes in bytes object *o*.

*Py\_ssize\_t* **PyBytes\_GET\_SIZE** (*PyObject* \*o)

Similar to *PyBytes\_Size()*, but without error checking.

<sup>1</sup> For integer specifiers (d, u, ld, lu, zd, zu, i, x): the 0-conversion flag has effect even when a precision is given.

char **\*PyBytes\_AsString** (*PyObject* \*o)

*Μέρος του Σταθερό ABI.* Return a pointer to the contents of *o*. The pointer refers to the internal buffer of *o*, which consists of `len(o) + 1` bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using `PyBytes_FromStringAndSize(NULL, size)`. It must not be deallocated. If *o* is not a bytes object at all, `PyBytes_AsString()` returns NULL and raises `TypeError`.

char **\*PyBytes\_AS\_STRING** (*PyObject* \*string)

Similar to `PyBytes_AsString()`, but without error checking.

int **PyBytes\_AsStringAndSize** (*PyObject* \*obj, char \*\*buffer, *Py\_ssize\_t* \*length)

*Μέρος του Σταθερό ABI.* Return the null-terminated contents of the object *obj* through the output variables *buffer* and *length*. Returns 0 on success.

If *length* is NULL, the bytes object may not contain embedded null bytes; if it does, the function returns -1 and a `ValueError` is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using `PyBytes_FromStringAndSize(NULL, size)`. It must not be deallocated. If *obj* is not a bytes object at all, `PyBytes_AsStringAndSize()` returns -1 and raises `TypeError`.

Άλλαξε στην έκδοση 3.5: Previously, `TypeError` was raised when embedded null bytes were encountered in the bytes object.

void **PyBytes\_Concat** (*PyObject* \*\*bytes, *PyObject* \*newpart)

*Μέρος του Σταθερό ABI.* Create a new bytes object in *\*bytes* containing the contents of *newpart* appended to *bytes*; the caller will own the new reference. The reference to the old value of *bytes* will be stolen. If the new object cannot be created, the old reference to *bytes* will still be discarded and the value of *\*bytes* will be set to NULL; the appropriate exception will be set.

void **PyBytes\_ConcatAndDel** (*PyObject* \*\*bytes, *PyObject* \*newpart)

*Μέρος του Σταθερό ABI.* Create a new bytes object in *\*bytes* containing the contents of *newpart* appended to *bytes*. This version releases the *strong reference* to *newpart* (i.e. decrements its reference count).

int **\_PyBytes\_Resize** (*PyObject* \*\*bytes, *Py\_ssize\_t* newsize)

A way to resize a bytes object even though it is «immutable». Only use this to build up a brand new bytes object; don't use this if the bytes may already be known in other parts of the code. It is an error to call this function if the refcount on the input bytes object is not one. Pass the address of an existing bytes object as an lvalue (it may be written into), and the new size desired. On success, *\*bytes* holds the resized bytes object and 0 is returned; the address in *\*bytes* may differ from its input value. If the reallocation fails, the original bytes object at *\*bytes* is deallocated, *\*bytes* is set to NULL, `MemoryError` is set, and -1 is returned.

## 8.3.2 Byte Array Objects

type **PyByteArrayObject**

This subtype of *PyObject* represents a Python bytearray object.

*PyTypeObject* **PyByteArray\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python bytearray type; it is the same object as `bytearray` in the Python layer.

## Type check macros

int **PyByteArray\_Check** (*PyObject* \*o)

Return true if the object *o* is a bytearray object or an instance of a subtype of the bytearray type. This function always succeeds.

int **PyByteArray\_CheckExact** (*PyObject* \*o)

Return true if the object *o* is a bytearray object, but not an instance of a subtype of the bytearray type. This function always succeeds.

## Direct API functions

*PyObject* \***PyByteArray\_FromObject** (*PyObject* \*o)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a new bytearray object from any object, *o*, that implements the *buffer protocol*.

*PyObject* \***PyByteArray\_FromStringAndSize** (const char \*string, *Py\_ssize\_t* len)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Create a new bytearray object from *string* and its length, *len*. On failure, NULL is returned.

*PyObject* \***PyByteArray\_Concat** (*PyObject* \*a, *PyObject* \*b)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Concat bytearrays *a* and *b* and return a new bytearray with the result.

*Py\_ssize\_t* **PyByteArray\_Size** (*PyObject* \*bytearray)

*Μέρος του Σταθερό ABI.* Return the size of *bytearray* after checking for a NULL pointer.

char \***PyByteArray\_AsString** (*PyObject* \*bytearray)

*Μέρος του Σταθερό ABI.* Return the contents of *bytearray* as a char array after checking for a NULL pointer. The returned array always has an extra null byte appended.

int **PyByteArray\_Resize** (*PyObject* \*bytearray, *Py\_ssize\_t* len)

*Μέρος του Σταθερό ABI.* Resize the internal buffer of *bytearray* to *len*.

## Macros

These macros trade safety for speed and they don't check pointers.

char \***PyByteArray\_AS\_STRING** (*PyObject* \*bytearray)

Similar to *PyByteArray\_AsString()*, but without error checking.

*Py\_ssize\_t* **PyByteArray\_GET\_SIZE** (*PyObject* \*bytearray)

Similar to *PyByteArray\_Size()*, but without error checking.

## 8.3.3 Unicode Objects and Codecs

### Unicode Objects

Since the implementation of **PEP 393** in Python 3.3, Unicode objects internally use a variety of representations, in order to allow handling the complete range of Unicode characters while staying memory efficient. There are special cases for strings where all code points are below 128, 256, or 65536; otherwise, code points must be below 1114112 (which is the full Unicode range).

*Py\_UNICODE\** and UTF-8 representations are created on demand and cached in the Unicode object. The *Py\_UNICODE\** representation is deprecated and inefficient.

Due to the transition between the old APIs and the new APIs, Unicode objects can internally be in two states depending on how they were created:

- «canonical» Unicode objects are all objects created by a non-deprecated Unicode API. They use the most efficient representation allowed by the implementation.
- «legacy» Unicode objects have been created through one of the deprecated APIs (typically `PyUnicode_FromUnicode()`) and only bear the `Py_UNICODE*` representation; you will have to call `PyUnicode_READY()` on them before calling any other API.

---

**Σημείωση:** The «legacy» Unicode object will be removed in Python 3.12 with deprecated APIs. All Unicode objects will be «canonical» since then. See [PEP 623](#) for more information.

---

### Unicode Type

These are the basic Unicode object types used for the Unicode implementation in Python:

type `Py_UCS4`

type `Py_UCS2`

type `Py_UCS1`

*Μέρος του Σταθερό ABI.* These types are typedefs for unsigned integer types wide enough to contain characters of 32 bits, 16 bits and 8 bits, respectively. When dealing with single Unicode characters, use `Py_UCS4`.

Νέο στην έκδοση 3.3.

type `Py_UNICODE`

This is a typedef of `wchar_t`, which is a 16-bit type or 32-bit type depending on the platform.

Άλλαξε στην έκδοση 3.3: In previous versions, this was a 16-bit type or a 32-bit type depending on whether you selected a «narrow» or «wide» Unicode version of Python at build time.

type `PyASCIIObject`

type `PyCompactUnicodeObject`

type `PyUnicodeObject`

These subtypes of `PyObject` represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return `PyObject` pointers.

Νέο στην έκδοση 3.3.

*PyTypeObject* `PyUnicode_Type`

*Μέρος του Σταθερό ABI.* This instance of `PyTypeObject` represents the Python Unicode type. It is exposed to Python code as `str`.

The following APIs are C macros and static inlined functions for fast checks and access to internal read-only data of Unicode objects:

int `PyUnicode_Check` (`PyObject` \*obj)

Return true if the object *obj* is a Unicode object or an instance of a Unicode subtype. This function always succeeds.

int `PyUnicode_CheckExact` (`PyObject` \*obj)

Return true if the object *obj* is a Unicode object, but not an instance of a subtype. This function always succeeds.

int `PyUnicode_READY` (`PyObject` \*unicode)

Ensure the string object *o* is in the «canonical» representation. This is required before using any of the access macros described below.

Returns 0 on success and -1 with an exception set on failure, which in particular happens if memory allocation fails.

Νέο στην έκδοση 3.3.

Καταργήθηκε στην έκδοση 3.10, θα αφαιρεθεί στην έκδοση 3.12: This API will be removed with `PyUnicode_FromUnicode()`.

`Py_ssize_t PyUnicode_GET_LENGTH(PyObject *unicode)`

Return the length of the Unicode string, in code points. *unicode* has to be a Unicode object in the «canonical» representation (not checked).

Νέο στην έκδοση 3.3.

`Py_UCS1 *PyUnicode_1BYTE_DATA(PyObject *unicode)`

`Py_UCS2 *PyUnicode_2BYTE_DATA(PyObject *unicode)`

`Py_UCS4 *PyUnicode_4BYTE_DATA(PyObject *unicode)`

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use `PyUnicode_KIND()` to select the right macro. Make sure `PyUnicode_READY()` has been called before accessing this.

Νέο στην έκδοση 3.3.

`PyUnicode_WCHAR_KIND`

`PyUnicode_1BYTE_KIND`

`PyUnicode_2BYTE_KIND`

`PyUnicode_4BYTE_KIND`

Return values of the `PyUnicode_KIND()` macro.

Νέο στην έκδοση 3.3.

Καταργήθηκε στην έκδοση 3.10, θα αφαιρεθεί στην έκδοση 3.12: `PyUnicode_WCHAR_KIND` is deprecated.

`int PyUnicode_KIND(PyObject *unicode)`

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. *unicode* has to be a Unicode object in the «canonical» representation (not checked).

Νέο στην έκδοση 3.3.

`void *PyUnicode_DATA(PyObject *unicode)`

Return a void pointer to the raw Unicode buffer. *unicode* has to be a Unicode object in the «canonical» representation (not checked).

Νέο στην έκδοση 3.3.

`void PyUnicode_WRITE(int kind, void *data, Py_ssize_t index, Py_UCS4 value)`

Write into a canonical representation *data* (as obtained with `PyUnicode_DATA()`). This function performs no sanity checks, and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

Νέο στην έκδοση 3.3.

`Py_UCS4 PyUnicode_READ(int kind, void *data, Py_ssize_t index)`

Read a code point from a canonical representation *data* (as obtained with `PyUnicode_DATA()`). No checks or ready calls are performed.

Νέο στην έκδοση 3.3.

`Py_UCS4 PyUnicode_READ_CHAR(PyObject *unicode, Py_ssize_t index)`

Read a character from a Unicode object *unicode*, which must be in the «canonical» representation. This is less efficient than `PyUnicode_READ()` if you do multiple consecutive reads.

Νέο στην έκδοση 3.3.



*Py\_UCS4* **PyUnicode\_MAX\_CHAR\_VALUE** (*PyObject* \*unicode)

Return the maximum code point that is suitable for creating another string based on *unicode*, which must be in the «canonical» representation. This is always an approximation but more efficient than iterating over the string.

Νέο στην έκδοση 3.3.

*Py\_ssize\_t* **PyUnicode\_GET\_SIZE** (*PyObject* \*unicode)

Return the size of the deprecated *Py\_UNICODE* representation, in code units (this includes surrogate pairs as 2 units). *unicode* has to be a Unicode object (not checked).

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

*Py\_ssize\_t* **PyUnicode\_GET\_DATA\_SIZE** (*PyObject* \*unicode)

Return the size of the deprecated *Py\_UNICODE* representation in bytes. *unicode* has to be a Unicode object (not checked).

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

*Py\_UNICODE* \***PyUnicode\_AS\_UNICODE** (*PyObject* \*unicode)

const char \***PyUnicode\_AS\_DATA** (*PyObject* \*unicode)

Return a pointer to a *Py\_UNICODE* representation of the object. The returned buffer is always terminated with an extra null code point. It may also contain embedded null code points, which would cause the string to be truncated when used in most C functions. The *AS\_DATA* form casts the pointer to `const char*`. The *unicode* argument has to be a Unicode object (not checked).

Άλλαξε στην έκδοση 3.3: This function is now inefficient – because in many cases the *Py\_UNICODE* representation does not exist and needs to be created – and can fail (return NULL with an exception set). Try to port the code to use the new *PyUnicode\_nBYTE\_DATA()* macros or use *PyUnicode\_WRITE()* or *PyUnicode\_READ()*.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using the *PyUnicode\_nBYTE\_DATA()* family of macros.

int **PyUnicode\_IsIdentifier** (*PyObject* \*unicode)

Μέρος του Σταθερό ABI. Return 1 if the string is a valid identifier according to the language definition, section identifiers. Return 0 otherwise.

Άλλαξε στην έκδοση 3.9: The function does not call *Py\_FatalError()* anymore if the string is not ready.

## Unicode Character Properties

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

int **Py\_UNICODE\_ISSPACE** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a whitespace character.

int **Py\_UNICODE\_ISLOWER** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a lowercase character.

int **Py\_UNICODE\_ISUPPER** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is an uppercase character.

int **Py\_UNICODE\_ISTITLE** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a titlecase character.

int **Py\_UNICODE\_ISLINEBREAK** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a linebreak character.



int **Py\_UNICODE\_ISDECIMAL** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a decimal character.

int **Py\_UNICODE\_ISDIGIT** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a digit character.

int **Py\_UNICODE\_ISNUMERIC** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a numeric character.

int **Py\_UNICODE\_ISALPHA** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is an alphabetic character.

int **Py\_UNICODE\_ISALNUM** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is an alphanumeric character.

int **Py\_UNICODE\_ISPRINTABLE** (*Py\_UCS4* ch)

Return 1 or 0 depending on whether *ch* is a printable character. Nonprintable characters are those characters defined in the Unicode character database as «Other» or «Separator», excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when `repr()` is invoked on a string. It has no bearing on the handling of strings written to `sys.stdout` or `sys.stderr`.)

These APIs can be used for fast direct character conversions:

*Py\_UCS4* **Py\_UNICODE\_TOLOWER** (*Py\_UCS4* ch)

Return the character *ch* converted to lower case.

Αποσύρθηκε στην έκδοση 3.3: This function uses simple case mappings.

*Py\_UCS4* **Py\_UNICODE\_TOUPPER** (*Py\_UCS4* ch)

Return the character *ch* converted to upper case.

Αποσύρθηκε στην έκδοση 3.3: This function uses simple case mappings.

*Py\_UCS4* **Py\_UNICODE\_TOTITLE** (*Py\_UCS4* ch)

Return the character *ch* converted to title case.

Αποσύρθηκε στην έκδοση 3.3: This function uses simple case mappings.

int **Py\_UNICODE\_TODECIMAL** (*Py\_UCS4* ch)

Return the character *ch* converted to a decimal positive integer. Return `-1` if this is not possible. This macro does not raise exceptions.

int **Py\_UNICODE\_TODIGIT** (*Py\_UCS4* ch)

Return the character *ch* converted to a single digit integer. Return `-1` if this is not possible. This macro does not raise exceptions.

double **Py\_UNICODE\_TONUMERIC** (*Py\_UCS4* ch)

Return the character *ch* converted to a double. Return `-1.0` if this is not possible. This macro does not raise exceptions.

These APIs can be used to work with surrogates:

**Py\_UNICODE\_IS\_SURROGATE** (ch)

Check if *ch* is a surrogate (`0xD800 <= ch <= 0xDFFF`).

**Py\_UNICODE\_IS\_HIGH\_SURROGATE** (ch)

Check if *ch* is a high surrogate (`0xD800 <= ch <= 0xDBFF`).

**Py\_UNICODE\_IS\_LOW\_SURROGATE** (ch)

Check if *ch* is a low surrogate (`0xDC00 <= ch <= 0xDFFF`).

**Py\_UNICODE\_JOIN\_SURROGATES** (high, low)

Join two surrogate characters and return a single *Py\_UCS4* value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair.

## Creating and accessing Unicode strings

To create Unicode objects and access their basic sequence properties, use these APIs:

*PyObject* \***PyUnicode\_New** (*Py\_ssize\_t* size, *Py\_UCS4* maxchar)

*Επιστρεφόμενη τιμή:* *New reference.* Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable.

Νέο στην έκδοση 3.3.

*PyObject* \***PyUnicode\_FromKindAndData** (int kind, const void \*buffer, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* *New reference.* Create a new Unicode object with the given *kind* (possible values are *PyUnicode\_1BYTE\_KIND* etc., as returned by *PyUnicode\_KIND()*). The *buffer* must point to an array of *size* units of 1, 2 or 4 bytes per character, as given by the kind.

If necessary, the input *buffer* is copied and transformed into the canonical representation. For example, if the *buffer* is a UCS4 string (*PyUnicode\_4BYTE\_KIND*) and it consists only of codepoints in the UCS1 range, it will be transformed into UCS1 (*PyUnicode\_1BYTE\_KIND*).

Νέο στην έκδοση 3.3.

*PyObject* \***PyUnicode\_FromStringAndSize** (const char \*str, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* *New reference.* Μέρος του Σταθερό ABI. Create a Unicode object from the char buffer *str*. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. If the buffer is not NULL, the return value might be a shared object, i.e. modification of the data is not allowed.

If *str* is NULL, this function behaves like *PyUnicode\_FromUnicode()* with the buffer set to NULL. This usage is deprecated in favor of *PyUnicode\_New()*, and will be removed in Python 3.12.

*PyObject* \***PyUnicode\_FromString** (const char \*str)

*Επιστρεφόμενη τιμή:* *New reference.* Μέρος του Σταθερό ABI. Create a Unicode object from a UTF-8 encoded null-terminated char buffer *str*.

*PyObject* \***PyUnicode\_FromFormat** (const char \*format, ...)

*Επιστρεφόμενη τιμή:* *New reference.* Μέρος του Σταθερό ABI. Take a C `printf()`-style *format* string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the *format* ASCII-encoded string. The following format characters are allowed:

Format Characters	Type	Comment
<code>%%</code>	<i>n/a</i>	The literal <code>%</code> character.
<code>%c</code>	<code>int</code>	A single character, represented as a C int.
<code>%d</code>	<code>int</code>	Equivalent to <code>printf("%d").</code> <sup>1</sup>
<code>%u</code>	<code>unsigned int</code>	Equivalent to <code>printf("%u").</code> <sup>1</sup> <small>Σελίδα 131, 1</small>
<code>%ld</code>	<code>long</code>	Equivalent to <code>printf("%ld").</code> <sup>1</sup>
<code>%li</code>	<code>long</code>	Equivalent to <code>printf("%li").</code> <sup>1</sup>
<code>%lu</code>	<code>unsigned long</code>	Equivalent to <code>printf("%lu").</code> <sup>1</sup>
<code>%lld</code>	<code>long long</code>	Equivalent to <code>printf("%lld").</code> <sup>1</sup>
<code>%lli</code>	<code>long long</code>	Equivalent to <code>printf("%lli").</code> <sup>1</sup>
<code>%llu</code>	<code>unsigned long long</code>	Equivalent to <code>printf("%llu").</code> <sup>1</sup>
<code>%zd</code>	<code>Py_ssize_t</code>	Equivalent to <code>printf("%zd").</code> <sup>1</sup>
<code>%zi</code>	<code>Py_ssize_t</code>	Equivalent to <code>printf("%zi").</code> <sup>1</sup>
<code>%zu</code>	<code>size_t</code>	Equivalent to <code>printf("%zu").</code> <sup>1</sup>
<code>%i</code>	<code>int</code>	Equivalent to <code>printf("%i").</code> <sup>1</sup>
<code>%x</code>	<code>int</code>	Equivalent to <code>printf("%x").</code> <sup>1</sup>
<code>%s</code>	<code>const char*</code>	A null-terminated C character array.
<code>%p</code>	<code>const void*</code>	The hex representation of a C pointer. Mostly equivalent to <code>printf("%p")</code> except that it is guaranteed to start with the literal <code>0x</code> regardless of what the platform's <code>printf</code> yields.
<code>%A</code>	<code>PyObject*</code>	The result of calling <code>ascii()</code> .
<code>%U</code>	<code>PyObject*</code>	A Unicode object.
<code>%V</code>	<code>PyObject*, const char*</code>	A Unicode object (which may be <code>NULL</code> ) and a null-terminated C character array as a second parameter (which will be used, if the first parameter is <code>NULL</code> ).
<code>%S</code>	<code>PyObject*</code>	The result of calling <code>PyObject_Str()</code> .
<code>%R</code>	<code>PyObject*</code>	The result of calling <code>PyObject_Repr()</code> .

An unrecognized format character causes all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

**Σημείωση:** The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes for `"%s"` and `"%V"` (if the `PyObject*` argument is `NULL`), and a number of characters for `"%A"`, `"%U"`, `"%S"`, `"%R"` and `"%V"` (if the `PyObject*` argument is not `NULL`).

Άλλαξε στην έκδοση 3.2: Support for `"%lld"` and `"%llu"` added.

Άλλαξε στην έκδοση 3.3: Support for `"%li"`, `"%lli"` and `"%zi"` added.

Άλλαξε στην έκδοση 3.4: Support width and precision formatter for `"%s"`, `"%A"`, `"%U"`, `"%V"`, `"%S"`, `"%R"` added.

**PyObject\*PyUnicode\_FromFormatV** (const char \*format, va\_list args)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Identical to `PyUnicode_FromFormat()` except that it takes exactly two arguments.

**PyObject\*PyUnicode\_FromObject** (PyObject \*obj)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If *obj* is already a true Unicode object (not a subtype), return a new *strong reference* to the object.

Objects other than Unicode or its subtypes will cause a `TypeError`.

<sup>1</sup> For integer specifiers (d, u, ld, li, lu, lld, lli, llu, zd, zi, zu, i, x): the 0-conversion flag has effect even when a precision is given.

*PyObject* \*PyUnicode\_FromEncodedObject (*PyObject* \*obj, const char \*encoding, const char \*errors)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI. Decode an encoded object *obj* to a Unicode object.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be NULL to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a `TypeError` to be set.

The API returns NULL if there was an error. The caller is responsible for decref'ing the returned objects.

*Py\_ssize\_t* PyUnicode\_GetLength (*PyObject* \*unicode)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Return the length of the Unicode object, in code points.

Νέο στην έκδοση 3.3.

*Py\_ssize\_t* PyUnicode\_CopyCharacters (*PyObject* \*to, *Py\_ssize\_t* to\_start, *PyObject* \*from, *Py\_ssize\_t* from\_start, *Py\_ssize\_t* how\_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to `memcpy()` if possible. Returns `-1` and sets an exception on error, otherwise returns the number of copied characters.

Νέο στην έκδοση 3.3.

*Py\_ssize\_t* PyUnicode\_Fill (*PyObject* \*unicode, *Py\_ssize\_t* start, *Py\_ssize\_t* length, *Py\_UCS4* fill\_char)

Fill a string with a character: write *fill\_char* into `unicode[start:start+length]`.

Fail if *fill\_char* is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return `-1` and raise an exception on error.

Νέο στην έκδοση 3.3.

int PyUnicode\_WriteChar (*PyObject* \*unicode, *Py\_ssize\_t* index, *Py\_UCS4* character)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Write a character to a string. The string must have been created through `PyUnicode_New()`. Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that its reference count is one).

Νέο στην έκδοση 3.3.

*Py\_UCS4* PyUnicode\_ReadChar (*PyObject* \*unicode, *Py\_ssize\_t* index)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Read a character from a string. This function checks that *unicode* is a Unicode object and the index is not out of bounds, in contrast to `PyUnicode_READ_CHAR()`, which performs no error checking.

Νέο στην έκδοση 3.3.

*PyObject* \*PyUnicode\_Substring (*PyObject* \*unicode, *Py\_ssize\_t* start, *Py\_ssize\_t* end)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI από την έκδοση 3.7. Return a substring of *unicode*, from character index *start* (included) to character index *end* (excluded). Negative indices are not supported.

Νέο στην έκδοση 3.3.

*Py\_UCS4* \*PyUnicode\_AsUCS4 (*PyObject* \*unicode, *Py\_UCS4* \*buffer, *Py\_ssize\_t* buflen, int copy\_null)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Copy the string *unicode* into a UCS4 buffer, including a null character, if *copy\_null* is set. Returns NULL and sets an exception on error (in particular, a `SystemError` if *buflen* is smaller than the length of *unicode*). *buffer* is returned on success.

Νέο στην έκδοση 3.3.

*Py\_UCS4* \*PyUnicode\_AsUCS4Copy (*PyObject* \*unicode)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Copy the string *unicode* into a new UCS4 buffer that is allocated using *PyMem\_Malloc()*. If this fails, NULL is returned with a *MemoryError* set. The returned buffer always has an extra null code point appended.

Νέο στην έκδοση 3.3.

## Deprecated Py\_UNICODE APIs

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12.

These API functions are deprecated with the implementation of **PEP 393**. Extension modules can continue using them, as they will not be removed in Python 3.x, but need to be aware that their use can now cause performance and memory hits.

*PyObject* \*PyUnicode\_FromUnicode (const *Py\_UNICODE* \*u, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* *New reference.* Create a Unicode object from the *Py\_UNICODE* buffer *u* of the given size. *u* may be NULL which causes the contents to be undefined. It is the user's responsibility to fill in the needed data. The buffer is copied into the new object.

If the buffer is not NULL, the return value might be a shared object. Therefore, modification of the resulting Unicode object is only allowed when *u* is NULL.

If the buffer is NULL, *PyUnicode\_READY()* must be called once the string content has been filled before using any of the access macros such as *PyUnicode\_KIND()*.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_FromKindAndData()*, *PyUnicode\_FromWideChar()*, or *PyUnicode\_New()*.

*Py\_UNICODE* \*PyUnicode\_AsUnicode (*PyObject* \*unicode)

Return a read-only pointer to the Unicode object's internal *Py\_UNICODE* buffer, or NULL on error. This will create the *Py\_UNICODE\** representation of the object if it is not yet available. The buffer is always terminated with an extra null code point. Note that the resulting *Py\_UNICODE* string may also contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_AsUCS4()*, *PyUnicode\_AsWideChar()*, *PyUnicode\_ReadChar()* or similar new APIs.

*Py\_UNICODE* \*PyUnicode\_AsUnicodeAndSize (*PyObject* \*unicode, *Py\_ssize\_t* \*size)

Like *PyUnicode\_AsUnicode()*, but also saves the *Py\_UNICODE()* array length (excluding the extra null terminator) in *size*. Note that the resulting *Py\_UNICODE\** string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Νέο στην έκδοση 3.3.

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_AsUCS4()*, *PyUnicode\_AsWideChar()*, *PyUnicode\_ReadChar()* or similar new APIs.

*Py\_ssize\_t* PyUnicode\_GetSize (*PyObject* \*unicode)

*Μέρος του Σταθερό ABI.* Return the size of the deprecated *Py\_UNICODE* representation, in code units (this includes surrogate pairs as 2 units).

Καταργήθηκε στην έκδοση 3.3, θα αφαιρεθεί στην έκδοση 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

## Locale Encoding

The current locale encoding can be used to decode text from the operating system.

**PyObject\*PyUnicode\_DecodeLocaleAndSize** (const char \*str, Py\_ssize\_t length, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The decoder uses "strict" error handler if *errors* is NULL. *str* must end with a null character but cannot contain embedded null characters.

Use `PyUnicode_DecodeFSDefaultAndSize()` to decode a string from `Py_FileSystemDefaultEncoding` (the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

**Δείτε επίσης:**

The `Py_DecodeLocale()` function.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, `Py_DecodeLocale()` was used for the surrogateescape, and the current locale encoding was used for strict.

**PyObject\*PyUnicode\_DecodeLocale** (const char \*str, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Similar to `PyUnicode_DecodeLocaleAndSize()`, but compute the string length using `strlen()`.

Νέο στην έκδοση 3.3.

**PyObject\*PyUnicode\_EncodeLocale** (PyObject \*unicode, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The encoder uses "strict" error handler if *errors* is NULL. Return a bytes object. *unicode* cannot contain embedded null characters.

Use `PyUnicode_EncodeFSDefault()` to encode a string to `Py_FileSystemDefaultEncoding` (the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

**Δείτε επίσης:**

The `Py_EncodeLocale()` function.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, `Py_EncodeLocale()` was used for the surrogateescape, and the current locale encoding was used for strict.

## File System Encoding

To encode and decode file names and other environment strings, `Py_FileSystemDefaultEncoding` should be used as the encoding, and `Py_FileSystemDefaultEncodeErrors` should be used as the error handler (PEP 383 and PEP 529). To encode file names to bytes during argument parsing, the "O&" converter should be used, passing `PyUnicode_FSConverter()` as the conversion function:

**int PyUnicode\_FSConverter** (PyObject \*obj, void \*result)

*Μέρος του Σταθερό ABI.* ParseTuple converter: encode str objects – obtained directly or through the `os.PathLike` interface – to bytes using `PyUnicode_EncodeFSDefault()`; bytes objects are output as-is. *result* must be a `PyBytesObject*` which must be released when it is no longer used.

Νέο στην έκδοση 3.1.



Άλλαξε στην έκδοση 3.6: Accepts a *path-like object*.

To decode file names to `str` during argument parsing, the `"O&"` converter should be used, passing `PyUnicode_FSDecoder()` as the conversion function:

int **PyUnicode\_FSDecoder** (*PyObject* \*obj, void \*result)

*Μέρος του Σταθερό ABI.* ParseTuple converter: decode bytes objects – obtained either directly or indirectly through the `os.PathLike` interface – to `str` using `PyUnicode_DecodeFSDefaultAndSize()`; `str` objects are output as-is. *result* must be a *PyUnicodeObject*\* which must be released when it is no longer used.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.6: Accepts a *path-like object*.

*PyObject* \***PyUnicode\_DecodeFSDefaultAndSize** (const char \*str, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Decode a string from the *filesystem encoding and error handler*.

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

`Py_FileSystemDefaultEncoding` is initialized at startup from the locale encoding and cannot be modified later. If you need to decode a string from the current locale encoding, use `PyUnicode_DecodeLocaleAndSize()`.

**Δείτε επίσης:**

The `Py_DecodeLocale()` function.

Άλλαξε στην έκδοση 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

*PyObject* \***PyUnicode\_DecodeFSDefault** (const char \*str)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Decode a null-terminated string from the *filesystem encoding and error handler*.

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

Use `PyUnicode_DecodeFSDefaultAndSize()` if you know the string length.

Άλλαξε στην έκδοση 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

*PyObject* \***PyUnicode\_EncodeFSDefault** (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Encode a Unicode object to `Py_FileSystemDefaultEncoding` with the `Py_FileSystemDefaultEncodeErrors` error handler, and return bytes. Note that the resulting bytes object may contain null bytes.

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

`Py_FileSystemDefaultEncoding` is initialized at startup from the locale encoding and cannot be modified later. If you need to encode a string to the current locale encoding, use `PyUnicode_EncodeLocale()`.

**Δείτε επίσης:**

The `Py_EncodeLocale()` function.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

## wchar\_t Support

wchar\_t support for platforms which support it:

*PyObject* \***PyUnicode\_FromWideChar** (const wchar\_t \*wstr, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Create a Unicode object from the wchar\_t buffer wstr of the given size. Passing -1 as the size indicates that the function must itself compute the length, using wcslen(). Return NULL on failure.

*Py\_ssize\_t* **PyUnicode\_AsWideChar** (*PyObject* \*unicode, wchar\_t \*wstr, *Py\_ssize\_t* size)

*Μέρος του Σταθερό ABI.* Copy the Unicode object contents into the wchar\_t buffer wstr. At most size wchar\_t characters are copied (excluding a possibly trailing null termination character). Return the number of wchar\_t characters copied or -1 in case of an error.

When wstr is NULL, instead return the size that would be required to store all of unicode including a terminating null.

Note that the resulting wchar\_t\* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the wchar\_t\* string is null-terminated in case this is required by the application. Also, note that the wchar\_t\* string might contain null characters, which would cause the string to be truncated when used with most C functions.

wchar\_t \***PyUnicode\_AsWideCharString** (*PyObject* \*unicode, *Py\_ssize\_t* \*size)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Convert the Unicode object to a wide character string. The output string always ends with a null character. If size is not NULL, write the number of wide characters (excluding the trailing null termination character) into \*size. Note that the resulting wchar\_t string might contain null characters, which would cause the string to be truncated when used with most C functions. If size is NULL and the wchar\_t\* string contains null characters a ValueError is raised.

Returns a buffer allocated by PyMem\_New (use PyMem\_Free() to free it) on success. On error, returns NULL and \*size is undefined. Raises a MemoryError if memory allocation is failed.

Νέο στην έκδοση 3.2.

Άλλαξε στην έκδοση 3.7: Raises a ValueError if size is NULL and the wchar\_t\* string contains null characters.

## Built-in Codecs

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in str() string object constructor.

Setting encoding to NULL causes the default encoding to be used which is UTF-8. The file system calls should use PyUnicode\_FSConverter() for encoding file names. This uses the variable Py\_FileSystemDefaultEncoding internally. This variable should be treated as read-only: on some systems, it will be a pointer to a static string, on others, it will change at run-time (such as when the application invokes setlocale).

Error handling is set by errors which may also be set to NULL meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is «strict» (ValueError is raised).

The codecs all use a similar interface. Only deviations from the following generic ones are documented for simplicity.



## Generic Codecs

These are the generic codec APIs:

*PyObject* \***PyUnicode\_Decode** (const char \*str, *Py\_ssize\_t* size, const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Create a Unicode object by decoding *size* bytes of the encoded string *str*. *encoding* and *errors* have the same meaning as the parameters of the same name in the `str()` built-in function. The codec to be used is looked up using the Python codec registry. Return `NULL` if an exception was raised by the codec.

*PyObject* \***PyUnicode\_AsEncodedString** (*PyObject* \*unicode, const char \*encoding, const char \*errors)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Encode a Unicode object and return the result as Python bytes object. *encoding* and *errors* have the same meaning as the parameters of the same name in the Unicode `encode()` method. The codec to be used is looked up using the Python codec registry. Return `NULL` if an exception was raised by the codec.

## UTF-8 Codecs

These are the UTF-8 codec APIs:

*PyObject* \***PyUnicode\_DecodeUTF8** (const char \*str, *Py\_ssize\_t* size, const char \*errors)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *str*. Return `NULL` if an exception was raised by the codec.

*PyObject* \***PyUnicode\_DecodeUTF8Stateful** (const char \*str, *Py\_ssize\_t* size, const char \*errors, *Py\_ssize\_t* \*consumed)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* If *consumed* is `NULL`, behave like `PyUnicode_DecodeUTF8()`. If *consumed* is not `NULL`, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \***PyUnicode\_AsUTF8String** (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is «strict». Return `NULL` if an exception was raised by the codec.

const char \***PyUnicode\_AsUTF8AndSize** (*PyObject* \*unicode, *Py\_ssize\_t* \*size)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in *size*. The *size* argument can be `NULL`; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in *size*), regardless of whether there are any other null code points.

In the case of an error, `NULL` is returned with an exception set and no *size* is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer. The buffer is deallocated and pointers to it become invalid when the Unicode object is garbage collected.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.7: The return type is now `const char *` rather of `char *`.

Άλλαξε στην έκδοση 3.10: This function is a part of the *limited API*.

const char \***PyUnicode\_AsUTF8** (*PyObject* \*unicode)

As `PyUnicode_AsUTF8AndSize()`, but does not store the size.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.7: The return type is now `const char *` rather of `char *`.

## UTF-32 Codecs

These are the UTF-32 codec APIs:

*PyObject* \***PyUnicode\_DecodeUTF32** (const char \*str, *Py\_ssize\_t* size, const char \*errors, int \*byteorder)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to «strict».

If *byteorder* is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0:  native order
*byteorder == 1:  big endian
```

If *\*byteorder* is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *\*byteorder* is -1 or 1, any byte order mark is copied to the output.

After completion, *\*byteorder* is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_DecodeUTF32Stateful** (const char \*str, *Py\_ssize\_t* size, const char \*errors, int \*byteorder, *Py\_ssize\_t* \*consumed)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. If *consumed* is NULL, behave like *PyUnicode\_DecodeUTF32()*. If *consumed* is not NULL, *PyUnicode\_DecodeUTF32Stateful()* will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \***PyUnicode\_AsUTF32String** (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is «strict». Return NULL if an exception was raised by the codec.

## UTF-16 Codecs

These are the UTF-16 codec APIs:

*PyObject* \***PyUnicode\_DecodeUTF16** (const char \*str, *Py\_ssize\_t* size, const char \*errors, int \*byteorder)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Decode *size* bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to «strict».

If *byteorder* is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0:  native order
*byteorder == 1:  big endian
```

If *\*byteorder* is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *\*byteorder* is -1 or 1, any byte order mark is copied to the output (where it will result in either a \ufeff or a \ufffe character).

After completion, *\*byteorder* is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_DecodeUTF16Stateful (const char \*str, Py\_ssize\_t size, const char \*errors, int \*byteorder, Py\_ssize\_t \*consumed)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. If *consumed* is NULL, behave like *PyUnicode\_DecodeUTF16()*. If *consumed* is not NULL, *PyUnicode\_DecodeUTF16Stateful()* will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \*PyUnicode\_AsUTF16String (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is «strict». Return NULL if an exception was raised by the codec.

## UTF-7 Codecs

These are the UTF-7 codec APIs:

*PyObject* \*PyUnicode\_DecodeUTF7 (const char \*str, Py\_ssize\_t size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_DecodeUTF7Stateful (const char \*str, Py\_ssize\_t size, const char \*errors, Py\_ssize\_t \*consumed)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. If *consumed* is NULL, behave like *PyUnicode\_DecodeUTF7()*. If *consumed* is not NULL, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

## Unicode-Escape Codecs

These are the «Unicode Escape» codec APIs:

*PyObject* \*PyUnicode\_DecodeUnicodeEscape (const char \*str, Py\_ssize\_t size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_AsUnicodeEscapeString (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

## Raw-Unicode-Escape Codecs

These are the «Raw Unicode Escape» codec APIs:

*PyObject* \*PyUnicode\_DecodeRawUnicodeEscape (const char \*str, Py\_ssize\_t size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_AsRawUnicodeEscapeString (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

## Latin-1 Codecs

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

*PyObject* \*PyUnicode\_DecodeLatin1 (const char \*str, *Py\_ssize\_t* size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_AsLatin1String (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

## ASCII Codecs

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

*PyObject* \*PyUnicode\_DecodeASCII (const char \*str, *Py\_ssize\_t* size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the ASCII encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_AsASCIIString (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

## Character Map Codecs

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the `encodings` package). The codec uses mappings to encode and decode characters. The mapping objects provided must support the `__getitem__()` mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

*PyObject* \*PyUnicode\_DecodeCharmap (const char \*str, *Py\_ssize\_t* length, *PyObject* \*mapping, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a Unicode object by decoding *size* bytes of the encoded string *str* using the given *mapping* object. Return NULL if an exception was raised by the codec.

If *mapping* is NULL, Latin-1 decoding will be applied. Else *mapping* must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes – ones which cause a `LookupError`, as well as ones which get mapped to None, `0xFFFE` or `'\ufffe'`, are treated as undefined mappings and cause an error.

*PyObject* \*PyUnicode\_AsCharmapString (*PyObject* \*unicode, *PyObject* \*mapping)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Encode a Unicode object using the given *mapping* object and return the result as a bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a `LookupError`) as well as mapped to None are treated as «undefined mapping» and cause an error.

The following codec API is special in that maps Unicode to Unicode.

*PyObject* \*PyUnicode\_Translate (*PyObject* \*unicode, *PyObject* \*table, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Translate a string by applying a character mapping table to it and return the resulting Unicode object. Return NULL if an exception was raised by the codec.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the `__getitem__()` interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a `LookupError`) are left untouched and are copied as-is.

*errors* has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

## MBCS codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

*PyObject* \*PyUnicode\_DecodeMBCS (const char \*str, *Py\_ssize\_t* size, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Create a Unicode object by decoding *size* bytes of the MBCS encoded string *str*. Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_DecodeMBCSStateful (const char \*str, *Py\_ssize\_t* size, const char \*errors, *Py\_ssize\_t* \*consumed)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. If *consumed* is NULL, behave like `PyUnicode_DecodeMBCS()`. If *consumed* is not NULL, `PyUnicode_DecodeMBCSStateful()` will not decode trailing lead byte and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \*PyUnicode\_AsMBCSString (*PyObject* \*unicode)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is «strict». Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_EncodeCodePage (int code\_page, *PyObject* \*unicode, const char \*errors)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI on Windows από την έκδοση 3.7. Encode the Unicode object using the specified code page and return a Python bytes object. Return NULL if an exception was raised by the codec. Use `CP_ACP` code page to get the MBCS encoder.

Νέο στην έκδοση 3.3.

## Methods & Slots

### Methods and Slot Functions

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or -1 if an exception occurs.

*PyObject* \*PyUnicode\_Concat (*PyObject* \*left, *PyObject* \*right)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Concat two strings giving a new Unicode string.

*PyObject* \*PyUnicode\_Split (*PyObject* \*unicode, *PyObject* \*sep, *Py\_ssize\_t* maxsplit)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Split a string giving a list of Unicode strings. If *sep* is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most *maxsplit* splits will be done. If negative, no limit is set. Separators are not included in the resulting list.



*PyObject* \***PyUnicode\_Splitlines** (*PyObject* \*unicode, int keepends)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του [Σταθερό ABI](#). Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If *keepends* is 0, the Line break characters are not included in the resulting strings.

*PyObject* \***PyUnicode\_Join** (*PyObject* \*separator, *PyObject* \*seq)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του [Σταθερό ABI](#). Join a sequence of strings using the given *separator* and return the resulting Unicode string.

*Py\_ssize\_t* **PyUnicode\_Tailmatch** (*PyObject* \*unicode, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Μέρος του [Σταθερό ABI](#). Return 1 if *substr* matches *unicode*[start:end] at the given tail end (*direction* == -1 means to do a prefix match, *direction* == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.

*Py\_ssize\_t* **PyUnicode\_Find** (*PyObject* \*unicode, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Μέρος του [Σταθερό ABI](#). Return the first position of *substr* in *unicode*[start:end] using the given *direction* (*direction* == 1 means to do a forward search, *direction* == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

*Py\_ssize\_t* **PyUnicode\_FindChar** (*PyObject* \*unicode, *Py\_UCS4* ch, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Μέρος του [Σταθερό ABI](#) από την έκδοση 3.7. Return the first position of the character *ch* in *unicode*[start:end] using the given *direction* (*direction* == 1 means to do a forward search, *direction* == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.7: *start* and *end* are now adjusted to behave like *unicode*[start:end].

*Py\_ssize\_t* **PyUnicode\_Count** (*PyObject* \*unicode, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end)

Μέρος του [Σταθερό ABI](#). Return the number of non-overlapping occurrences of *substr* in *unicode*[start:end]. Return -1 if an error occurred.

*PyObject* \***PyUnicode\_Replace** (*PyObject* \*unicode, *PyObject* \*substr, *PyObject* \*replstr, *Py\_ssize\_t* maxcount)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του [Σταθερό ABI](#). Replace at most *maxcount* occurrences of *substr* in *unicode* with *replstr* and return the resulting Unicode object. *maxcount* == -1 means replace all occurrences.

int **PyUnicode\_Compare** (*PyObject* \*left, *PyObject* \*right)

Μέρος του [Σταθερό ABI](#). Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively.

This function returns -1 upon failure, so one should call *PyErr\_Occurred()* to check for errors.

int **PyUnicode\_CompareWithASCIIString** (*PyObject* \*unicode, const char \*string)

Μέρος του [Σταθερό ABI](#). Compare a Unicode object, *unicode*, with *string* and return -1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

*PyObject* \***PyUnicode\_RichCompare** (*PyObject* \*left, *PyObject* \*right, int op)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του [Σταθερό ABI](#). Rich compare two Unicode strings and return one of the following:

- NULL in case an exception was raised
- *Py\_True* or *Py\_False* for successful comparisons
- *Py\_NotImplemented* in case the type combination is unknown

Possible values for *op* are *Py\_GT*, *Py\_GE*, *Py\_EQ*, *Py\_NE*, *Py\_LT*, and *Py\_LE*.

*PyObject* \***PyUnicode\_Format** (*PyObject* \*format, *PyObject* \*args)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του Σταθερό ABI. Return a new string object from *format* and *args*; this is analogous to `format % args`.

int **PyUnicode\_Contains** (*PyObject* \*unicode, *PyObject* \*substr)

*Μέρος του Σταθερό ABI*. Check whether *substr* is contained in *unicode* and return true or false accordingly. *substr* has to coerce to a one element Unicode string. -1 is returned if there was an error.

void **PyUnicode\_InternInPlace** (*PyObject* \*\*p\_unicode)

*Μέρος του Σταθερό ABI*. Intern the argument \**p\_unicode* in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as \**p\_unicode*, it sets \**p\_unicode* to it (releasing the reference to the old string object and creating a new *strong reference* to the interned string object), otherwise it leaves \**p\_unicode* alone and interns it (creating a new *strong reference*). (Clarification: even though there is a lot of talk about references, think of this function as reference-neutral; you own the object after the call if and only if you owned it before the call.)

*PyObject* \***PyUnicode\_InternFromString** (const char \*str)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του Σταθερό ABI. A combination of *PyUnicode\_FromString()* and *PyUnicode\_InternInPlace()*, returning either a new Unicode string object that has been interned, or a new («owned») reference to an earlier interned string object with the same value.

## 8.3.4 Tuple Objects

type **PyTupleObject**

This subtype of *PyObject* represents a Python tuple object.

*PyTypeObject* **PyTuple\_Type**

*Μέρος του Σταθερό ABI*. This instance of *PyTypeObject* represents the Python tuple type; it is the same object as `tuple` in the Python layer.

int **PyTuple\_Check** (*PyObject* \*p)

Return true if *p* is a tuple object or an instance of a subtype of the tuple type. This function always succeeds.

int **PyTuple\_CheckExact** (*PyObject* \*p)

Return true if *p* is a tuple object, but not an instance of a subtype of the tuple type. This function always succeeds.

*PyObject* \***PyTuple\_New** (*Py\_ssize\_t* len)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του Σταθερό ABI. Return a new tuple object of size *len*, or NULL on failure.

*PyObject* \***PyTuple\_Pack** (*Py\_ssize\_t* n, ...)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του Σταθερό ABI. Return a new tuple object of size *n*, or NULL on failure. The tuple values are initialized to the subsequent *n* C arguments pointing to Python objects. `PyTuple_Pack(2, a, b)` is equivalent to `Py_BuildValue("(OO)", a, b)`.

*Py\_ssize\_t* **PyTuple\_Size** (*PyObject* \*p)

*Μέρος του Σταθερό ABI*. Take a pointer to a tuple object, and return the size of that tuple.

*Py\_ssize\_t* **PyTuple\_GET\_SIZE** (*PyObject* \*p)

Return the size of the tuple *p*, which must be non-NULL and point to a tuple; no error checking is performed.

*PyObject* \***PyTuple\_GetItem** (*PyObject* \*p, *Py\_ssize\_t* pos)

*Επιστρεφόμενη τιμή:* *Borrowed reference*. Μέρος του Σταθερό ABI. Return the object at position *pos* in the tuple pointed to by *p*. If *pos* is negative or out of bounds, return NULL and set an `IndexError` exception.

*PyObject* \***PyTuple\_GET\_ITEM** (*PyObject* \*p, *Py\_ssize\_t* pos)

*Επιστρεφόμενη τιμή:* Borrowed reference. Like *PyTuple\_GetItem()*, but does no checking of its arguments.

*PyObject* \***PyTuple\_GetSlice** (*PyObject* \*p, *Py\_ssize\_t* low, *Py\_ssize\_t* high)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return the slice of the tuple pointed to by *p* between *low* and *high*, or NULL on failure. This is the equivalent of the Python expression *p*[*low*:*high*]. Indexing from the end of the list is not supported.

int **PyTuple\_SetItem** (*PyObject* \*p, *Py\_ssize\_t* pos, *PyObject* \*o)

Μέρος του Σταθερό ABI. Insert a reference to object *o* at position *pos* of the tuple pointed to by *p*. Return 0 on success. If *pos* is out of bounds, return -1 and set an *IndexError* exception.

---

**Σημείωση:** This function «steals» a reference to *o* and discards a reference to an item already in the tuple at the affected position.

---

void **PyTuple\_SET\_ITEM** (*PyObject* \*p, *Py\_ssize\_t* pos, *PyObject* \*o)

Like *PyTuple\_SetItem()*, but does no error checking, and should *only* be used to fill in brand new tuples.

---

**Σημείωση:** This function «steals» a reference to *o*, and, unlike *PyTuple\_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in the tuple at position *pos* will be leaked.

---

int **PyTuple\_Resize** (*PyObject* \*\*p, *Py\_ssize\_t* newsize)

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns 0 on success. Client code should never assume that the resulting value of *\*p* will be the same as before calling this function. If the object referenced by *\*p* is replaced, the original *\*p* is destroyed. On failure, returns -1 and sets *\*p* to NULL, and raises *MemoryError* or *SystemError*.

### 8.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of *namedtuple()* objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

*PyObject* \***PyStructSequence\_NewType** (*PyStructSequence\_Desc* \*desc)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a new struct sequence type from the data in *desc*, described below. Instances of the resulting type can be created with *PyStructSequence\_New()*.

void **PyStructSequence\_InitType** (*PyTypeObject* \*type, *PyStructSequence\_Desc* \*desc)

Initializes a struct sequence type *type* from *desc* in place.

int **PyStructSequence\_InitType2** (*PyTypeObject* \*type, *PyStructSequence\_Desc* \*desc)

The same as *PyStructSequence\_InitType*, but returns 0 on success and -1 on failure.

Νέο στην έκδοση 3.4.

type **PyStructSequence\_Desc**

Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών). Contains the meta information of a struct sequence type to create.

const char \***name**

Name of the struct sequence type.



const char \***doc**

Pointer to docstring for the type or NULL to omit.

*PyStructSequence\_Field* \***fields**

Pointer to NULL-terminated array with field names of the new type.

int **n\_in\_sequence**

Number of fields visible to the Python side (if used as tuple).

type **PyStructSequence\_Field**

*Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών).* Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as *PyObject\**. The index in the *fields* array of the *PyStructSequence\_Desc* determines which field of the struct sequence is described.

const char \***name**

Name for the field or NULL to end the list of named fields, set to *PyStructSequence\_UnnamedField* to leave unnamed.

const char \***doc**

Field docstring or NULL to omit.

const char \*const **PyStructSequence\_UnnamedField**

*Μέρος του Σταθερό ABI από την έκδοση 3.11.* Special value for a field name to leave it unnamed.

Άλλαξε στην έκδοση 3.9: The type was changed from char \*.

*PyObject* \***PyStructSequence\_New** (*PyTypeObject* \*type)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Creates an instance of *type*, which must have been created with *PyStructSequence\_NewType()*.

*PyObject* \***PyStructSequence\_GetItem** (*PyObject* \*p, *Py\_ssize\_t* pos)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return the object at position *pos* in the struct sequence pointed to by *p*. No bounds checking is performed.

*PyObject* \***PyStructSequence\_GET\_ITEM** (*PyObject* \*p, *Py\_ssize\_t* pos)

*Επιστρεφόμενη τιμή: Borrowed reference.* Macro equivalent of *PyStructSequence\_GetItem()*.

void **PyStructSequence\_SetItem** (*PyObject* \*p, *Py\_ssize\_t* pos, *PyObject* \*o)

*Μέρος του Σταθερό ABI.* Sets the field at index *pos* of the struct sequence *p* to value *o*. Like *PyTuple\_SET\_ITEM()*, this should only be used to fill in brand new instances.

---

**Σημείωση:** This function «steals» a reference to *o*.

---

void **PyStructSequence\_SET\_ITEM** (*PyObject* \*p, *Py\_ssize\_t* \*pos, *PyObject* \*o)

Similar to *PyStructSequence\_SetItem()*, but implemented as a static inlined function.

---

**Σημείωση:** This function «steals» a reference to *o*.

---

### 8.3.6 List Objects

type **PyListObject**

This subtype of *PyObject* represents a Python list object.

*PyTypeObject* **PyList\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python list type. This is the same object as `list` in the Python layer.

int **PyList\_Check** (*PyObject* \*p)

Return true if *p* is a list object or an instance of a subtype of the list type. This function always succeeds.

int **PyList\_CheckExact** (*PyObject* \*p)

Return true if *p* is a list object, but not an instance of a subtype of the list type. This function always succeeds.

*PyObject* \***PyList\_New** (*Py\_ssize\_t* len)

*Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI.* Return a new list of length *len* on success, or NULL on failure.

---

**Σημείωση:** If *len* is greater than zero, the returned list object's items are set to NULL. Thus you cannot use abstract API functions such as *PySequence\_SetItem()* or expose the object to Python code before setting all items to a real object with *PyList\_SetItem()*.

---

*Py\_ssize\_t* **PyList\_Size** (*PyObject* \*list)

*Μέρος του Σταθερό ABI.* Return the length of the list object in *list*; this is equivalent to `len(list)` on a list object.

*Py\_ssize\_t* **PyList\_GET\_SIZE** (*PyObject* \*list)

Similar to *PyList\_Size()*, but without error checking.

*PyObject* \***PyList\_GetItem** (*PyObject* \*list, *Py\_ssize\_t* index)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return the object at position *index* in the list pointed to by *list*. The position must be non-negative; indexing from the end of the list is not supported. If *index* is out of bounds ( $<0$  or  $\geq \text{len}(\text{list})$ ), return NULL and set an `IndexError` exception.

*PyObject* \***PyList\_GET\_ITEM** (*PyObject* \*list, *Py\_ssize\_t* i)

*Επιστρεφόμενη τιμή: Borrowed reference.* Similar to *PyList\_GetItem()*, but without error checking.

int **PyList\_SetItem** (*PyObject* \*list, *Py\_ssize\_t* index, *PyObject* \*item)

*Μέρος του Σταθερό ABI.* Set the item at index *index* in list to *item*. Return 0 on success. If *index* is out of bounds, return -1 and set an `IndexError` exception.

---

**Σημείωση:** This function «steals» a reference to *item* and discards a reference to an item already in the list at the affected position.

---

void **PyList\_SET\_ITEM** (*PyObject* \*list, *Py\_ssize\_t* i, *PyObject* \*o)

Macro form of *PyList\_SetItem()* without error checking. This is normally only used to fill in new lists where there is no previous content.

---

**Σημείωση:** This macro «steals» a reference to *item*, and, unlike *PyList\_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in *list* at position *i* will be leaked.

---

int **PyList\_Insert** (*PyObject* \*list, *Py\_ssize\_t* index, *PyObject* \*item)

*Μέρος του Σταθερό ABI.* Insert the item *item* into list *list* in front of index *index*. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to `list.insert(index, item)`.

int **PyList\_Append** (*PyObject* \*list, *PyObject* \*item)

*Μέρος του Σταθερό ABI.* Append the object *item* at the end of list *list*. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to `list.append(item)`.

*PyObject* \***PyList\_GetSlice** (*PyObject* \*list, *Py\_ssize\_t* low, *Py\_ssize\_t* high)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a list of the objects in *list* containing the objects *between* *low* and *high*. Return NULL and set an exception if unsuccessful. Analogous to `list[low:high]`. Indexing from the end of the list is not supported.

int **PyList\_SetSlice** (*PyObject* \*list, *Py\_ssize\_t* low, *Py\_ssize\_t* high, *PyObject* \*itemlist)

*Μέρος του Σταθερό ABI.* Set the slice of *list* between *low* and *high* to the contents of *itemlist*. Analogous to `list[low:high] = itemlist`. The *itemlist* may be NULL, indicating the assignment of an empty list (slice deletion). Return 0 on success, -1 on failure. Indexing from the end of the list is not supported.

int **PyList\_Sort** (*PyObject* \*list)

*Μέρος του Σταθερό ABI.* Sort the items of *list* in place. Return 0 on success, -1 on failure. This is equivalent to `list.sort()`.

int **PyList\_Reverse** (*PyObject* \*list)

*Μέρος του Σταθερό ABI.* Reverse the items of *list* in place. Return 0 on success, -1 on failure. This is the equivalent of `list.reverse()`.

*PyObject* \***PyList\_AsTuple** (*PyObject* \*list)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a new tuple object containing the contents of *list*; equivalent to `tuple(list)`.

## 8.4 Container Objects

### 8.4.1 Dictionary Objects

type **PyDictObject**

This subtype of *PyObject* represents a Python dictionary object.

*PyTypeObject* **PyDict\_Type**

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python dictionary type. This is the same object as `dict` in the Python layer.

int **PyDict\_Check** (*PyObject* \*p)

Return true if *p* is a dict object or an instance of a subtype of the dict type. This function always succeeds.

int **PyDict\_CheckExact** (*PyObject* \*p)

Return true if *p* is a dict object, but not an instance of a subtype of the dict type. This function always succeeds.

*PyObject* \***PyDict\_New** ()

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a new empty dictionary, or NULL on failure.

*PyObject* \***PyDictProxy\_New** (*PyObject* \*mapping)

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Return a `types.MappingProxyType` object for a mapping which enforces read-only behavior. This is normally used to create a view to prevent modification of the dictionary for non-dynamic class types.

void **PyDict\_Clear** (*PyObject* \*p)

*Μέρος του Σταθερό ABI.* Empty an existing dictionary of all key-value pairs.

int **PyDict\_Contains** (*PyObject* \*p, *PyObject* \*key)

*Μέρος του Σταθερό ABI.* Determine if dictionary *p* contains *key*. If an item in *p* matches *key*, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression `key in p`.

*PyObject* \*PyDict\_Copy (*PyObject* \*p)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Return a new dictionary that contains the same key-value pairs as *p*.

int PyDict\_SetItem (*PyObject* \*p, *PyObject* \*key, *PyObject* \*val)

*Μέρος του Σταθερό ABI.* Insert *val* into the dictionary *p* with a key of *key*. *key* must be *hashable*; if it isn't, *TypeError* will be raised. Return 0 on success or -1 on failure. This function *does not* steal a reference to *val*.

int PyDict\_SetItemString (*PyObject* \*p, const char \*key, *PyObject* \*val)

*Μέρος του Σταθερό ABI.* This is the same as *PyDict\_SetItem()*, but *key* is specified as a const char\* UTF-8 encoded bytes string, rather than a *PyObject*\*.

int PyDict\_DelItem (*PyObject* \*p, *PyObject* \*key)

*Μέρος του Σταθερό ABI.* Remove the entry in dictionary *p* with key *key*. *key* must be *hashable*; if it isn't, *TypeError* is raised. If *key* is not in the dictionary, *KeyError* is raised. Return 0 on success or -1 on failure.

int PyDict\_DelItemString (*PyObject* \*p, const char \*key)

*Μέρος του Σταθερό ABI.* This is the same as *PyDict\_DelItem()*, but *key* is specified as a const char\* UTF-8 encoded bytes string, rather than a *PyObject*\*.

*PyObject* \*PyDict\_GetItem (*PyObject* \*p, *PyObject* \*key)

*Επιστρεφόμενη τιμή:* *Borrowed reference. Μέρος του Σταθερό ABI.* Return the object from dictionary *p* which has a key *key*. Return NULL if the key *key* is not present, but *without* setting an exception.

---

**Σημείωση:** Exceptions that occur while this calls *\_\_hash\_\_()* and *\_\_eq\_\_()* methods are silently ignored. Prefer the *PyDict\_GetItemWithError()* function instead.

---

Αλλάξε στην έκδοση 3.10: Calling this API without *GIL* held had been allowed for historical reason. It is no longer allowed.

*PyObject* \*PyDict\_GetItemWithError (*PyObject* \*p, *PyObject* \*key)

*Επιστρεφόμενη τιμή:* *Borrowed reference. Μέρος του Σταθερό ABI.* Variant of *PyDict\_GetItem()* that does not suppress exceptions. Return NULL **with** an exception set if an exception occurred. Return NULL **without** an exception set if the key wasn't present.

*PyObject* \*PyDict\_GetItemString (*PyObject* \*p, const char \*key)

*Επιστρεφόμενη τιμή:* *Borrowed reference. Μέρος του Σταθερό ABI.* This is the same as *PyDict\_GetItem()*, but *key* is specified as a const char\* UTF-8 encoded bytes string, rather than a *PyObject*\*.

---

**Σημείωση:** Exceptions that occur while this calls *\_\_hash\_\_()* and *\_\_eq\_\_()* methods or while creating the temporary str object are silently ignored. Prefer using the *PyDict\_GetItemWithError()* function with your own *PyUnicode\_FromString()* key instead.

---

*PyObject* \*PyDict\_SetDefault (*PyObject* \*p, *PyObject* \*key, *PyObject* \*defaultobj)

*Επιστρεφόμενη τιμή:* *Borrowed reference.* This is the same as the Python-level *dict.setdefault()*. If present, it returns the value corresponding to *key* from the dictionary *p*. If the key is not in the dict, it is inserted with value *defaultobj* and *defaultobj* is returned. This function evaluates the hash function of *key* only once, instead of evaluating it independently for the lookup and the insertion.

Νέο στην έκδοση 3.4.

*PyObject* \*PyDict\_Items (*PyObject* \*p)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Return a *PyListObject* containing all the items from the dictionary.

*PyObject* \*PyDict\_Keys (*PyObject* \*p)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI. Return a *PyListObject* containing all the keys from the dictionary.

*PyObject* \*PyDict\_Values (*PyObject* \*p)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI. Return a *PyListObject* containing all the values from the dictionary *p*.

*Py\_ssize\_t* PyDict\_Size (*PyObject* \*p)

Μέρος του Σταθερό ABI. Return the number of items in the dictionary. This is equivalent to `len(p)` on a dictionary.

int PyDict\_Next (*PyObject* \*p, *Py\_ssize\_t* \*ppos, *PyObject* \*\*pkey, *PyObject* \*\*pvalue)

Μέρος του Σταθερό ABI. Iterate over all key-value pairs in the dictionary *p*. The *Py\_ssize\_t* referred to by *ppos* must be initialized to 0 prior to the first call to this function to start the iteration; the function returns true for each pair in the dictionary, and false once all pairs have been reported. The parameters *pkey* and *pvalue* should either point to *PyObject*\* variables that will be filled in with each key and value, respectively, or may be NULL. Any references returned through them are borrowed. *ppos* should not be altered during iteration. Its value represents offsets within the internal dictionary structure, and since the structure is sparse, the offsets are not consecutive.

For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

The dictionary *p* should not be mutated during iteration. It is safe to modify the values of the keys as you iterate over the dictionary, but only so long as the set of keys does not change. For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}
```

int PyDict\_Merge (*PyObject* \*a, *PyObject* \*b, int override)

Μέρος του Σταθερό ABI. Iterate over mapping object *b* adding key-value pairs to dictionary *a*. *b* may be a dictionary, or any object supporting *PyMapping\_Keys()* and *PyObject\_GetItem()*. If *override* is true, existing pairs in *a* will be replaced if a matching key is found in *b*, otherwise pairs will only be added if there is not a matching key in *a*. Return 0 on success or -1 if an exception was raised.

int PyDict\_Update (*PyObject* \*a, *PyObject* \*b)

Μέρος του Σταθερό ABI. This is the same as `PyDict_Merge(a, b, 1)` in C, and is similar to `a.update(b)` in Python except that *PyDict\_Update()* doesn't fall back to the iterating over a sequence

of key value pairs if the second argument has no «keys» attribute. Return 0 on success or -1 if an exception was raised.

int **PyDict\_MergeFromSeq2** (*PyObject* \*a, *PyObject* \*seq2, int override)

*Μέρος του Σταθερό ABI.* Update or merge into dictionary *a*, from the key-value pairs in *seq2*. *seq2* must be an iterable object producing iterable objects of length 2, viewed as key-value pairs. In case of duplicate keys, the last wins if *override* is true, else the first wins. Return 0 on success or -1 if an exception was raised. Equivalent Python (except for the return value):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
            a[key] = value
```

## 8.4.2 Set Objects

This section details the public API for set and frozenset objects. Any functionality not listed below is best accessed using either the abstract object protocol (including *PyObject\_CallMethod()*, *PyObject\_RichCompareBool()*, *PyObject\_Hash()*, *PyObject\_Repr()*, *PyObject\_IsTrue()*, *PyObject\_Print()*, and *PyObject\_GetIter()*) or the abstract number protocol (including *PyNumber\_And()*, *PyNumber\_Subtract()*, *PyNumber\_Or()*, *PyNumber\_Xor()*, *PyNumber\_InPlaceAnd()*, *PyNumber\_InPlaceSubtract()*, *PyNumber\_InPlaceOr()*, and *PyNumber\_InPlaceXor()*).

type **PySetObject**

This subtype of *PyObject* is used to hold the internal data for both set and frozenset objects. It is like a *PyDictObject* in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and all are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

*PyTypeObject* **PySet\_Type**

*Μέρος του Σταθερό ABI.* This is an instance of *PyTypeObject* representing the Python set type.

*PyTypeObject* **PyFrozenSet\_Type**

*Μέρος του Σταθερό ABI.* This is an instance of *PyTypeObject* representing the Python frozenset type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

int **PySet\_Check** (*PyObject* \*p)

Return true if *p* is a set object or an instance of a subtype. This function always succeeds.

int **PyFrozenSet\_Check** (*PyObject* \*p)

Return true if *p* is a frozenset object or an instance of a subtype. This function always succeeds.

int **PyAnySet\_Check** (*PyObject* \*p)

Return true if *p* is a set object, a frozenset object, or an instance of a subtype. This function always succeeds.

int **PySet\_CheckExact** (*PyObject* \*p)

Return true if *p* is a set object but not an instance of a subtype. This function always succeeds.

Νέο στην έκδοση 3.10.

int **PyAnySet\_CheckExact** (*PyObject* \*p)

Return true if *p* is a set object or a frozenset object but not an instance of a subtype. This function always succeeds.



**int PyFrozenSet\_CheckExact** (*PyObject* \*p)

Return true if *p* is a `frozenset` object but not an instance of a subtype. This function always succeeds.

*PyObject* \***PySet\_New** (*PyObject* \*iterable)

*Επιστρεφόμενη τιμή*: New reference. *Μέρος του Σταθερό ABI*. Return a new `set` containing objects returned by the *iterable*. The *iterable* may be `NULL` to create a new empty `set`. Return the new `set` on success or `NULL` on failure. Raise `TypeError` if *iterable* is not actually iterable. The constructor is also useful for copying a `set` (`c=set(s)`).

*PyObject* \***PyFrozenSet\_New** (*PyObject* \*iterable)

*Επιστρεφόμενη τιμή*: New reference. *Μέρος του Σταθερό ABI*. Return a new `frozenset` containing objects returned by the *iterable*. The *iterable* may be `NULL` to create a new empty `frozenset`. Return the new `set` on success or `NULL` on failure. Raise `TypeError` if *iterable* is not actually iterable.

The following functions and macros are available for instances of `set` or `frozenset` or instances of their subtypes.

*Py\_ssize\_t* **PySet\_Size** (*PyObject* \*anyset)

*Μέρος του Σταθερό ABI*. Return the length of a `set` or `frozenset` object. Equivalent to `len(anyset)`. Raises a `SystemError` if *anyset* is not a `set`, `frozenset`, or an instance of a subtype.

*Py\_ssize\_t* **PySet\_GET\_SIZE** (*PyObject* \*anyset)

Macro form of `PySet_Size()` without error checking.

**int PySet\_Contains** (*PyObject* \*anyset, *PyObject* \*key)

*Μέρος του Σταθερό ABI*. Return 1 if found, 0 if not found, and -1 if an error is encountered. Unlike the Python `__contains__()` method, this function does not automatically convert unhashable sets into temporary `frozensets`. Raise a `TypeError` if the *key* is unhashable. Raise `SystemError` if *anyset* is not a `set`, `frozenset`, or an instance of a subtype.

**int PySet\_Add** (*PyObject* \*set, *PyObject* \*key)

*Μέρος του Σταθερό ABI*. Add *key* to a `set` instance. Also works with `frozenset` instances (like `PyTuple_SetItem()` it can be used to fill in the values of brand new `frozensets` before they are exposed to other code). Return 0 on success or -1 on failure. Raise a `TypeError` if the *key* is unhashable. Raise a `MemoryError` if there is no room to grow. Raise a `SystemError` if *set* is not an instance of `set` or its subtype.

The following functions are available for instances of `set` or its subtypes but not for instances of `frozenset` or its subtypes.

**int PySet\_Discard** (*PyObject* \*set, *PyObject* \*key)

*Μέρος του Σταθερό ABI*. Return 1 if found and removed, 0 if not found (no action taken), and -1 if an error is encountered. Does not raise `KeyError` for missing keys. Raise a `TypeError` if the *key* is unhashable. Unlike the Python `discard()` method, this function does not automatically convert unhashable sets into temporary `frozensets`. Raise `SystemError` if *set* is not an instance of `set` or its subtype.

*PyObject* \***PySet\_Pop** (*PyObject* \*set)

*Επιστρεφόμενη τιμή*: New reference. *Μέρος του Σταθερό ABI*. Return a new reference to an arbitrary object in the *set*, and removes the object from the *set*. Return `NULL` on failure. Raise `KeyError` if the *set* is empty. Raise a `SystemError` if *set* is not an instance of `set` or its subtype.

**int PySet\_Clear** (*PyObject* \*set)

*Μέρος του Σταθερό ABI*. Empty an existing `set` of all elements. Return 0 on success. Return -1 and raise `SystemError` if *set* is not an instance of `set` or its subtype.

## 8.5 Function Objects

### 8.5.1 Function Objects

There are a few functions specific to Python functions.

type **PyFunctionObject**

The C structure used for functions.

*PyTypeObject* **PyFunction\_Type**

This is an instance of *PyTypeObject* and represents the Python function type. It is exposed to Python programmers as `types.FunctionType`.

int **PyFunction\_Check** (*PyObject* \*o)

Return true if *o* is a function object (has type *PyFunction\_Type*). The parameter must not be NULL. This function always succeeds.

*PyObject* \***PyFunction\_New** (*PyObject* \*code, *PyObject* \*globals)

*Επιστρεφόμενη τιμή: New reference.* Return a new function object associated with the code object *code*. *globals* must be a dictionary with the global variables accessible to the function.

The function's docstring and name are retrieved from the code object. `__module__` is retrieved from *globals*. The argument defaults, annotations and closure are set to NULL. `__qualname__` is set to the same value as the code object's `co_qualname` field.

*PyObject* \***PyFunction\_NewWithQualName** (*PyObject* \*code, *PyObject* \*globals, *PyObject* \*qualname)

*Επιστρεφόμενη τιμή: New reference.* As *PyFunction\_New()*, but also allows setting the function object's `__qualname__` attribute. *qualname* should be a unicode object or NULL; if NULL, the `__qualname__` attribute is set to the same value as the code object's `co_qualname` field.

Νέο στην έκδοση 3.3.

*PyObject* \***PyFunction\_GetCode** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the code object associated with the function object *op*.

*PyObject* \***PyFunction\_GetGlobals** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the globals dictionary associated with the function object *op*.

*PyObject* \***PyFunction\_GetModule** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return a *borrowed reference* to the `__module__` attribute of the function object *op*. It can be NULL.

This is normally a `string` containing the module name, but can be set to any other object by Python code.

*PyObject* \***PyFunction\_GetDefaults** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the argument default values of the function object *op*. This can be a tuple of arguments or NULL.

int **PyFunction\_SetDefaults** (*PyObject* \*op, *PyObject* \*defaults)

Set the argument default values for the function object *op*. *defaults* must be `Py_None` or a tuple.

Raises `SystemError` and returns `-1` on failure.

*PyObject* \***PyFunction\_GetClosure** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the closure associated with the function object *op*. This can be NULL or a tuple of cell objects.

int **PyFunction\_SetClosure** (*PyObject* \*op, *PyObject* \*closure)

Set the closure associated with the function object *op*. *closure* must be `Py_None` or a tuple of cell objects.

Raises `SystemError` and returns `-1` on failure.



*PyObject* \***PyFunction\_GetAnnotations** (*PyObject* \*op)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the annotations of the function object *op*. This can be a mutable dictionary or NULL.

int **PyFunction\_SetAnnotations** (*PyObject* \*op, *PyObject* \*annotations)

Set the annotations for the function object *op*. *annotations* must be a dictionary or `Py_None`.

Raises `SystemError` and returns `-1` on failure.

## 8.5.2 Instance Method Objects

An instance method is a wrapper for a *PyCFunction* and the new way to bind a *PyCFunction* to a class object. It replaces the former call `PyMethod_New(func, NULL, class)`.

*PyTypeObject* **PyInstanceMethod\_Type**

This instance of *PyTypeObject* represents the Python instance method type. It is not exposed to Python programs.

int **PyInstanceMethod\_Check** (*PyObject* \*o)

Return true if *o* is an instance method object (has type *PyInstanceMethod\_Type*). The parameter must not be NULL. This function always succeeds.

*PyObject* \***PyInstanceMethod\_New** (*PyObject* \*func)

*Επιστρεφόμενη τιμή: New reference.* Return a new instance method object, with *func* being any callable object. *func* is the function that will be called when the instance method is called.

*PyObject* \***PyInstanceMethod\_Function** (*PyObject* \*im)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the function object associated with the instance method *im*.

*PyObject* \***PyInstanceMethod\_GET\_FUNCTION** (*PyObject* \*im)

*Επιστρεφόμενη τιμή: Borrowed reference.* Macro version of *PyInstanceMethod\_Function()* which avoids error checking.

## 8.5.3 Method Objects

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

*PyTypeObject* **PyMethod\_Type**

This instance of *PyTypeObject* represents the Python method type. This is exposed to Python programs as `types.MethodType`.

int **PyMethod\_Check** (*PyObject* \*o)

Return true if *o* is a method object (has type *PyMethod\_Type*). The parameter must not be NULL. This function always succeeds.

*PyObject* \***PyMethod\_New** (*PyObject* \*func, *PyObject* \*self)

*Επιστρεφόμενη τιμή: New reference.* Return a new method object, with *func* being any callable object and *self* the instance the method should be bound. *func* is the function that will be called when the method is called. *self* must not be NULL.

*PyObject* \***PyMethod\_Function** (*PyObject* \*meth)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the function object associated with the method *meth*.

*PyObject* \***PyMethod\_GET\_FUNCTION** (*PyObject* \*meth)

*Επιστρεφόμενη τιμή: Borrowed reference.* Macro version of *PyMethod\_Function()* which avoids error checking.

*PyObject* \***PyMethod\_Self** (*PyObject* \*meth)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the instance associated with the method *meth*.

*PyObject* \***PyMethod\_GET\_SELF** (*PyObject* \*meth)

*Επιστρεφόμενη τιμή: Borrowed reference.* Macro version of *PyMethod\_Self()* which avoids error checking.

## 8.5.4 Cell Objects

«Cell» objects are used to implement variables referenced by multiple scopes. For each such variable, a cell object is created to store the value; the local variables of each stack frame that references the value contains a reference to the cells from outer scopes which also use that variable. When the value is accessed, the value contained in the cell is used instead of the cell object itself. This de-referencing of the cell object requires support from the generated byte-code; these are not automatically de-referenced when accessed. Cell objects are not likely to be useful elsewhere.

type **PyCellObject**

The C structure used for cell objects.

*PyTypeObject* **PyCell\_Type**

The type object corresponding to cell objects.

int **PyCell\_Check** (*PyObject* \*ob)

Return true if *ob* is a cell object; *ob* must not be NULL. This function always succeeds.

*PyObject* \***PyCell\_New** (*PyObject* \*ob)

*Επιστρεφόμενη τιμή: New reference.* Create and return a new cell object containing the value *ob*. The parameter may be NULL.

*PyObject* \***PyCell\_Get** (*PyObject* \*cell)

*Επιστρεφόμενη τιμή: New reference.* Return the contents of the cell *cell*.

*PyObject* \***PyCell\_GET** (*PyObject* \*cell)

*Επιστρεφόμενη τιμή: Borrowed reference.* Return the contents of the cell *cell*, but without checking that *cell* is non-NULL and a cell object.

int **PyCell\_Set** (*PyObject* \*cell, *PyObject* \*value)

Set the contents of the cell object *cell* to *value*. This releases the reference to any current content of the cell. *value* may be NULL. *cell* must be non-NULL; if it is not a cell object, -1 will be returned. On success, 0 will be returned.

void **PyCell\_SET** (*PyObject* \*cell, *PyObject* \*value)

Sets the value of the cell object *cell* to *value*. No reference counts are adjusted, and no checks are made for safety; *cell* must be non-NULL and must be a cell object.

## 8.5.5 Code Objects

Code objects are a low-level detail of the CPython implementation. Each one represents a chunk of executable code that hasn't yet been bound into a function.

type **PyCodeObject**

The C structure of the objects used to describe code objects. The fields of this type are subject to change at any time.

*PyTypeObject* **PyCode\_Type**

This is an instance of *PyTypeObject* representing the Python code object.

int **PyCode\_Check** (*PyObject* \*co)

Return true if *co* is a code object. This function always succeeds.

`int PyCode_GetNumFree (PyCodeObject *co)`

Return the number of free variables in *co*.

*PyCodeObject* \***PyCode\_New** (int argcount, int kwnonlyargcount, int nlocals, int stacksize, int flags, *PyObject* \*code, *PyObject* \*consts, *PyObject* \*names, *PyObject* \*varnames, *PyObject* \*freevars, *PyObject* \*cellvars, *PyObject* \*filename, *PyObject* \*name, *PyObject* \*qualname, int firstlineno, *PyObject* \*linetable, *PyObject* \*exceptiontable)

*Επιστρεφόμενη τιμή:* *New reference*. Return a new code object. If you need a dummy code object to create a frame, use *PyCode\_NewEmpty()* instead. Calling *PyCode\_New()* directly will bind you to a precise Python version since the definition of the bytecode changes often. The many arguments of this function are inter-dependent in complex ways, meaning that subtle changes to values are likely to result in incorrect execution or VM crashes. Use this function only with extreme care.

Άλλαξε στην έκδοση 3.11: Added *qualname* and *exceptiontable* parameters.

*PyCodeObject* \***PyCode\_NewWithPosOnlyArgs** (int argcount, int posonlyargcount, int kwnonlyargcount, int nlocals, int stacksize, int flags, *PyObject* \*code, *PyObject* \*consts, *PyObject* \*names, *PyObject* \*varnames, *PyObject* \*freevars, *PyObject* \*cellvars, *PyObject* \*filename, *PyObject* \*name, *PyObject* \*qualname, int firstlineno, *PyObject* \*linetable, *PyObject* \*exceptiontable)

*Επιστρεφόμενη τιμή:* *New reference*. Similar to *PyCode\_New()*, but with an extra «posonlyargcount» for positional-only arguments. The same caveats that apply to *PyCode\_New* also apply to this function.

Νέο στην έκδοση 3.8.

Άλλαξε στην έκδοση 3.11: Added *qualname* and *exceptiontable* parameters.

*PyCodeObject* \***PyCode\_NewEmpty** (const char \*filename, const char \*funcname, int firstlineno)

*Επιστρεφόμενη τιμή:* *New reference*. Return a new empty code object with the specified filename, function name, and first line number. The resulting code object will raise an *Exception* if executed.

`int PyCode_Addr2Line (PyCodeObject *co, int byte_offset)`

Return the line number of the instruction that occurs on or before *byte\_offset* and ends after it. If you just need the line number of a frame, use *PyFrame\_GetLineNumber()* instead.

For efficiently iterating over the line numbers in a code object, use [the API described in PEP 626](#).

`int PyCode_Addr2Location (PyObject *co, int byte_offset, int *start_line, int *start_column, int *end_line, int *end_column)`

Sets the passed *int* pointers to the source code line and column numbers for the instruction at *byte\_offset*. Sets the value to 0 when information is not available for any particular element.

Returns 1 if the function succeeds and 0 otherwise.

Νέο στην έκδοση 3.11.

*PyObject* \***PyCode\_GetCode** (*PyCodeObject* \*co)

Equivalent to the Python code `getattr(co, 'co_code')`. Returns a strong reference to a *PyBytesObject* representing the bytecode in a code object. On error, NULL is returned and an exception is raised.

This *PyBytesObject* may be created on-demand by the interpreter and does not necessarily represent the bytecode actually executed by CPython. The primary use case for this function is debuggers and profilers.

Νέο στην έκδοση 3.11.

*PyObject* \***PyCode\_GetVarNames** (*PyCodeObject* \*co)

Equivalent to the Python code `getattr(co, 'co_varnames')`. Returns a new reference to a *PyTupleObject* containing the names of the local variables. On error, NULL is returned and an exception is raised.

Νέο στην έκδοση 3.11.

*PyObject* \*PyCode\_GetCellvars (*PyCodeObject* \*co)

Equivalent to the Python code `getattr(co, 'co_cellvars')`. Returns a new reference to a *PyTupleObject* containing the names of the local variables that are referenced by nested functions. On error, NULL is returned and an exception is raised.

Νέο στην έκδοση 3.11.

*PyObject* \*PyCode\_GetFreevars (*PyCodeObject* \*co)

Equivalent to the Python code `getattr(co, 'co_freevars')`. Returns a new reference to a *PyTupleObject* containing the names of the free variables. On error, NULL is returned and an exception is raised.

Νέο στην έκδοση 3.11.

## 8.6 Other Objects

### 8.6.1 File Objects

These APIs are a minimal emulation of the Python 2 C API for built-in file objects, which used to rely on the buffered I/O (`FILE*`) support from the C standard library. In Python 3, files and streams use the new `io` module, which defines several layers over the low-level unbuffered I/O of the operating system. The functions described below are convenience C wrappers over these new APIs, and meant mostly for internal error reporting in the interpreter; third-party code is advised to access the `io` APIs instead.

*PyObject* \*PyFile\_FromFd (int fd, const char \*name, const char \*mode, int buffering, const char \*encoding, const char \*errors, const char \*newline, int closefd)

*Επιστρεφόμενη τιμή:* *New reference.* Μέρος του **Σταθερό ABI**. Create a Python file object from the file descriptor of an already opened file *fd*. The arguments *name*, *encoding*, *errors* and *newline* can be NULL to use the defaults; *buffering* can be *-1* to use the default. *name* is ignored and kept for backward compatibility. Return NULL on failure. For a more comprehensive description of the arguments, please refer to the `io.open()` function documentation.

**Προειδοποίηση:** Since Python streams have their own buffering layer, mixing them with OS-level file descriptors can produce various issues (such as unexpected ordering of data).

Άλλαξε στην έκδοση 3.2: Ignore *name* attribute.

int PyObject\_AsFileDescriptor (*PyObject* \*p)

Μέρος του **Σταθερό ABI**. Return the file descriptor associated with *p* as an `int`. If the object is an integer, its value is returned. If not, the object's `fileno()` method is called if it exists; the method must return an integer, which is returned as the file descriptor value. Sets an exception and returns `-1` on failure.

*PyObject* \*PyFile\_GetLine (*PyObject* \*p, int n)

*Επιστρεφόμενη τιμή:* *New reference.* Μέρος του **Σταθερό ABI**. Equivalent to `p.readline([n])`, this function reads one line from the object *p*. *p* may be a file object or any object with a `readline()` method. If *n* is 0, exactly one line is read, regardless of the length of the line. If *n* is greater than 0, no more than *n* bytes will be read from the file; a partial line can be returned. In both cases, an empty string is returned if the end of the file is reached immediately. If *n* is less than 0, however, one line is read regardless of length, but `EOFError` is raised if the end of the file is reached immediately.

int PyFile\_SetOpenCodeHook (*Py\_OpenCodeHookFunction* handler)

Overrides the normal behavior of `io.open_code()` to pass its parameter through the provided handler.

The *handler* is a function of type:

```
typedef PyObject *(*Py_OpenCodeHookFunction)(PyObject*, void*)
```

Equivalent of `PyObject *(*)(PyObject *path, void *userData)`, where *path* is guaranteed to be *PyUnicodeObject*.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

As this hook is intentionally used during import, avoid importing new modules during its execution unless they are known to be frozen or available in `sys.modules`.

Once a hook has been set, it cannot be removed or replaced, and later calls to `PyFile_SetOpenCodeHook()` will fail. On failure, the function returns -1 and sets an exception if the interpreter has been initialized.

This function is safe to call before `Py_Initialize()`.

Raises an auditing event `setopencodehook` with no arguments.

Νέο στην έκδοση 3.8.

```
int PyFile_WriteObject (PyObject *obj, PyObject *p, int flags)
```

*Μέρος του Σταθερό ABI.* Write object *obj* to file object *p*. The only supported flag for *flags* is `Py_PRINT_RAW`; if given, the `str()` of the object is written instead of the `repr()`. Return 0 on success or -1 on failure; the appropriate exception will be set.

```
int PyFile_WriteString (const char *s, PyObject *p)
```

*Μέρος του Σταθερό ABI.* Write string *s* to file object *p*. Return 0 on success or -1 on failure; the appropriate exception will be set.

## 8.6.2 Module Objects

```
PyTypeObject PyModule_Type
```

*Μέρος του Σταθερό ABI.* This instance of *PyTypeObject* represents the Python module type. This is exposed to Python programs as `types.ModuleType`.

```
int PyModule_Check (PyObject *p)
```

Return true if *p* is a module object, or a subtype of a module object. This function always succeeds.

```
int PyModule_CheckExact (PyObject *p)
```

Return true if *p* is a module object, but not a subtype of *PyModule\_Type*. This function always succeeds.

```
PyObject *PyModule_NewObject (PyObject *name)
```

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return a new module object with the `__name__` attribute set to *name*. The module's `__name__`, `__doc__`, `__package__`, and `__loader__` attributes are filled in (all but `__name__` are set to None); the caller is responsible for providing a `__file__` attribute.

Νέο στην έκδοση 3.3.

Άλλαξε στην έκδοση 3.4: `__package__` and `__loader__` are set to None.

```
PyObject *PyModule_New (const char *name)
```

*Επιστρεφόμενη τιμή:* New reference. *Μέρος του Σταθερό ABI.* Similar to `PyModule_NewObject()`, but the name is a UTF-8 encoded string instead of a Unicode object.

```
PyObject *PyModule_GetDict (PyObject *module)
```

*Επιστρεφόμενη τιμή:* Borrowed reference. *Μέρος του Σταθερό ABI.* Return the dictionary object that implements *module*'s namespace; this object is the same as the `__dict__` attribute of the module object. If *module* is not a module object (or a subtype of a module object), `SystemError` is raised and NULL is returned.

It is recommended extensions use other `PyModule_*` and `PyObject_*` functions rather than directly manipulate a module's `__dict__`.

*PyObject* \*PyModule\_GetNameObject (*PyObject* \*module)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI από την έκδοση 3.7. Return *module*'s `__name__` value. If the module does not provide one, or if it is not a string, `SystemError` is raised and `NULL` is returned.

Νέο στην έκδοση 3.3.

const char \*PyModule\_GetName (*PyObject* \*module)

Μέρος του Σταθερό ABI. Similar to `PyModule_GetNameObject()` but return the name encoded to 'utf-8'.

void \*PyModule\_GetState (*PyObject* \*module)

Μέρος του Σταθερό ABI. Return the «state» of the module, that is, a pointer to the block of memory allocated at module creation time, or `NULL`. See `PyModuleDef.m_size`.

*PyModuleDef* \*PyModule\_GetDef (*PyObject* \*module)

Μέρος του Σταθερό ABI. Return a pointer to the `PyModuleDef` struct from which the module was created, or `NULL` if the module wasn't created from a definition.

*PyObject* \*PyModule\_GetFilenameObject (*PyObject* \*module)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI. Return the name of the file from which *module* was loaded using *module*'s `__file__` attribute. If this is not defined, or if it is not a unicode string, raise `SystemError` and return `NULL`; otherwise return a reference to a Unicode object.

Νέο στην έκδοση 3.2.

const char \*PyModule\_GetFilename (*PyObject* \*module)

Μέρος του Σταθερό ABI. Similar to `PyModule_GetFilenameObject()` but return the filename encoded to "utf-8".

Αποσύρθηκε στην έκδοση 3.2: `PyModule_GetFilename()` raises `UnicodeEncodeError` on unencodable filenames, use `PyModule_GetFilenameObject()` instead.

## Initializing C modules

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using `PyImport_AppendInittab()`). See building or extending-with-embedding for details.

The initialization function can either pass a module definition instance to `PyModule_Create()`, and return the resulting module object, or request «multi-phase initialization» by returning the definition struct itself.

type `PyModuleDef`

Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών). The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

`PyModuleDef_Base m_base`

Always initialize this member to `PyModuleDef_HEAD_INIT`.

const char \*`m_name`

Name for the new module.

const char \*`m_doc`

Docstring for the module; usually a docstring variable created with `PyDoc_STRVAR` is used.

*Py\_ssize\_t* `m_size`

Module state may be kept in a per-module memory area that can be retrieved with `PyModule_GetState()`, rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on `m_size` on module creation, and freed when the module object is deallocated, after the `m_free` function has been called, if present.



Setting `m_size` to `-1` means that the module does not support sub-interpreters, because it has global state.

Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state. Non-negative `m_size` is required for multi-phase initialization.

See [PEP 3121](#) for more details.

#### *PyMethodDef* \***m\_methods**

A pointer to a table of module-level functions, described by *PyMethodDef* values. Can be `NULL` if no functions are present.

#### *PyModuleDef\_Slot* \***m\_slots**

An array of slot definitions for multi-phase initialization, terminated by a `{0, NULL}` entry. When using single-phase initialization, *m\_slots* must be `NULL`.

Άλλαξε στην έκδοση 3.5: Prior to version 3.5, this member was always set to `NULL`, and was defined as:

*inquiry* **m\_reload**

#### *traverseproc* **m\_traverse**

A traversal function to call during GC traversal of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is `NULL`.

Άλλαξε στην έκδοση 3.9: No longer called before the module state is allocated.

#### *inquiry* **m\_clear**

A clear function to call during GC clearing of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is `NULL`.

Like *PyTypeObject.tp\_clear*, this function is not *always* called before a module is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and *m\_free* is called directly.

Άλλαξε στην έκδοση 3.9: No longer called before the module state is allocated.

#### *freefunc* **m\_free**

A function to call during deallocation of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is `NULL`.

Άλλαξε στην έκδοση 3.9: No longer called before the module state is allocated.

## Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as «single-phase initialization», and uses one of the following two module creation functions:

*PyObject* \***PyModule\_Create** (*PyModuleDef* \*def)

*Επιστρεφόμενη τιμή:* *New reference*. Create a new module object, given the definition in *def*. This behaves like *PyModule\_Create2()* with *module\_api\_version* set to *PYTHON\_API\_VERSION*.

*PyObject* \***PyModule\_Create2** (*PyModuleDef* \*def, int module\_api\_version)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του **Σταθερό ABI**. Create a new module object, given the definition in *def*, assuming the API version *module\_api\_version*. If that version does not match the version of the running interpreter, a *RuntimeWarning* is emitted.

---

**Σημείωση:** Most uses of this function should be using *PyModule\_Create()* instead; only use this if you are sure you need it.

---

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like *PyModule\_AddObjectRef()*.

## Multi-phase initialization

An alternate way to specify extensions is to request «multi-phase initialization». Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and the *execution phase*, when it is populated. The distinction is similar to the *\_\_new\_\_()* and *\_\_init\_\_()* methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the *sys.modules* entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection – as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using *PyModule\_GetState()*), or its contents (such as the module's *\_\_dict\_\_* or individual classes created with *PyType\_FromSpec()*).

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (*PyInit\_modulename*) returns a *PyModuleDef* instance with non-empty *m\_slots*. Before it is returned, the *PyModuleDef* instance must be initialized with the following function:

*PyObject* \***PyModuleDef\_Init** (*PyModuleDef* \*def)

*Επιστρεφόμενη τιμή:* *Borrowed reference*. Μέρος του **Σταθερό ABI** από την έκδοση 3.5. Ensures a module definition is a properly initialized Python object that correctly reports its type and reference count.

Returns *def* cast to *PyObject\**, or *NULL* if an error occurred.

Νέο στην έκδοση 3.5.

The *m\_slots* member of the module definition must point to an array of *PyModuleDef\_Slot* structures:

type **PyModuleDef\_Slot**

int **slot**

A slot ID, chosen from the available values explained below.

void \***value**

Value of the slot, whose meaning depends on the slot ID.

Νέο στην έκδοση 3.5.



The `m_slots` array must be terminated by a slot with id 0.

The available slot types are:

#### **Py\_mod\_create**

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature:

*PyObject* \***create\_module** (*PyObject* \*spec, *PyModuleDef* \*def)

The function receives a `ModuleSpec` instance, as defined in [PEP 451](#), and the module definition. It should return a new module object, or set an error and return `NULL`.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple `Py_mod_create` slots may not be specified in one module definition.

If `Py_mod_create` is not specified, the import machinery will create a normal module object using `PyModule_New()`. The name is taken from *spec*, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of `PyModule_Type`. Any type can be used, as long as it supports setting and getting import-related attributes. However, only `PyModule_Type` instances may be returned if the `PyModuleDef` has non-NULL `m_traverse`, `m_clear`, `m_free`; non-zero `m_size`; or slots other than `Py_mod_create`.

#### **Py\_mod\_exec**

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

int **exec\_module** (*PyObject* \*module)

If multiple `Py_mod_exec` slots are specified, they are processed in the order they appear in the `m_slots` array.

See [PEP 489](#) for more details on multi-phase initialization.

### **Low-level module creation functions**

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both `PyModule_FromDefAndSpec` and `PyModule_ExecDef` must be called to fully initialize a module.

*PyObject* \***PyModule\_FromDefAndSpec** (*PyModuleDef* \*def, *PyObject* \*spec)

*Επιστρεφόμενη τιμή:* *New reference*. Create a new module object, given the definition in *def* and the `ModuleSpec` *spec*. This behaves like `PyModule_FromDefAndSpec2()` with `module_api_version` set to `PYTHON_API_VERSION`.

Νέο στην έκδοση 3.5.

*PyObject* \***PyModule\_FromDefAndSpec2** (*PyModuleDef* \*def, *PyObject* \*spec, int module\_api\_version)

*Επιστρεφόμενη τιμή:* *New reference*. Μέρος του **Σταθερό ABI** από την έκδοση 3.7. Create a new module object, given the definition in *def* and the `ModuleSpec` *spec*, assuming the API version `module_api_version`. If that version does not match the version of the running interpreter, a `RuntimeWarning` is emitted.

---

**Σημείωση:** Most uses of this function should be using `PyModule_FromDefAndSpec()` instead; only use this if you are sure you need it.

---

Νέο στην έκδοση 3.5.

int **PyModule\_ExecDef** (*PyObject* \*module, *PyModuleDef* \*def)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Process any execution slots (*Py\_mod\_exec*) given in *def*.

Νέο στην έκδοση 3.5.

int **PyModule\_SetDocString** (*PyObject* \*module, const char \*docstring)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Set the docstring for *module* to *docstring*. This function is called automatically when creating a module from *PyModuleDef*, using either *PyModule\_Create* or *PyModule\_FromDefAndSpec*.

Νέο στην έκδοση 3.5.

int **PyModule\_AddFunctions** (*PyObject* \*module, *PyMethodDef* \*functions)

Μέρος του Σταθερό ABI από την έκδοση 3.7. Add the functions from the NULL terminated *functions* array to *module*. Refer to the *PyMethodDef* documentation for details on individual entries (due to the lack of a shared module namespace, module level «functions» implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes). This function is called automatically when creating a module from *PyModuleDef*, using either *PyModule\_Create* or *PyModule\_FromDefAndSpec*.

Νέο στην έκδοση 3.5.

## Support functions

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

int **PyModule\_AddObjectRef** (*PyObject* \*module, const char \*name, *PyObject* \*value)

Μέρος του Σταθερό ABI από την έκδοση 3.10. Add an object to *module* as *name*. This is a convenience function which can be used from the module's initialization function.

On success, return 0. On error, raise an exception and return -1.

Return NULL if *value* is NULL. It must be called with an exception raised in this case.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_DECREF(obj);
    return res;
}
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_XDECREF(obj);
    return res;
}
```

Note that *Py\_XDECREF()* should be used instead of *Py\_DECREF()* in this case, since *obj* can be NULL.

Νέο στην έκδοση 3.10.

`int PyModule_AddObject (PyObject *module, const char *name, PyObject *value)`

*Μέρος του Σταθερό ABI.* Similar to `PyModule_AddObjectRef()`, but steals a reference to *value* on success (if it returns 0).

The new `PyModule_AddObjectRef()` function is recommended, since it is easy to introduce reference leaks by misusing the `PyModule_AddObject()` function.

**Σημείωση:** Unlike other functions that steal references, `PyModule_AddObject()` only releases the reference to *value* **on success**.

This means that its return value must be checked, and calling code must `Py_DECREF()` *value* manually on error.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_DECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_XDECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}
```

Note that `Py_XDECREF()` should be used instead of `Py_DECREF()` in this case, since *obj* can be NULL.

`int PyModule_AddIntConstant (PyObject *module, const char *name, long value)`

*Μέρος του Σταθερό ABI.* Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

`int PyModule_AddStringConstant (PyObject *module, const char *name, const char *value)`

*Μέρος του Σταθερό ABI.* Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be NULL-terminated. Return -1 on error, 0 on success.

`PyModule_AddIntMacro (module, macro)`

Add an int constant to *module*. The name and the value are taken from *macro*. For example `PyModule_AddIntMacro(module, AF_INET)` adds the int constant `AF_INET` with the value of `AF_INET` to *module*. Return -1 on error, 0 on success.

**PyModule\_AddStringMacro** (module, macro)

Add a string constant to *module*.

int **PyModule\_AddType** (*PyObject* \*module, *PyTypeObject* \*type)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Add a type object to *module*. The type object is finalized by calling internally *PyType\_Ready()*. The name of the type object is taken from the last component of *tp\_name* after dot. Return -1 on error, 0 on success.

Νέο στην έκδοση 3.9.

## Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

*PyObject* \***PyState\_FindModule** (*PyModuleDef* \*def)

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Returns the module object that was created from *def* for the current interpreter. This method requires that the module object has been attached to the interpreter state with *PyState\_AddModule()* beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

int **PyState\_AddModule** (*PyObject* \*module, *PyModuleDef* \*def)

*Μέρος του Σταθερό ABI από την έκδοση 3.3.* Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via *PyState\_FindModule()*.

Only effective on modules created using single-phase initialization.

Python calls *PyState\_AddModule* automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls *PyState\_FindModule*. The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

The caller must hold the GIL.

Return 0 on success or -1 on failure.

Νέο στην έκδοση 3.3.

int **PyState\_RemoveModule** (*PyModuleDef* \*def)

*Μέρος του Σταθερό ABI από την έκδοση 3.3.* Removes the module object created from *def* from the interpreter state. Return 0 on success or -1 on failure.

The caller must hold the GIL.

Νέο στην έκδοση 3.3.

## 8.6.3 Iterator Objects

Python provides two general-purpose iterator objects. The first, a sequence iterator, works with an arbitrary sequence supporting the *\_\_getitem\_\_()* method. The second works with a callable object and a sentinel value, calling the callable for each item in the sequence, and ending the iteration when the sentinel value is returned.

*PyTypeObject* **PySeqIter\_Type**

*Μέρος του Σταθερό ABI.* Type object for iterator objects returned by *PySeqIter\_New()* and the one-argument form of the *iter()* built-in function for built-in sequence types.

int **PySeqIter\_Check** (*PyObject* \*op)

Return true if the type of *op* is *PySeqIter\_Type*. This function always succeeds.

*PyObject* \*PySeqIter\_New (*PyObject* \*seq)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return an iterator that works with a general sequence object, *seq*. The iteration ends when the sequence raises `IndexError` for the subscripting operation.

*PyTypeObject* PyCallIter\_Type

Μέρος του Σταθερό ABI. Type object for iterator objects returned by *PyCallIter\_New()* and the two-argument form of the `iter()` built-in function.

int PyCallIter\_Check (*PyObject* \*op)

Return true if the type of *op* is *PyCallIter\_Type*. This function always succeeds.

*PyObject* \*PyCallIter\_New (*PyObject* \*callable, *PyObject* \*sentinel)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new iterator. The first parameter, *callable*, can be any Python callable object that can be called with no parameters; each call to it should return the next item in the iteration. When *callable* returns a value equal to *sentinel*, the iteration will be terminated.

## 8.6.4 Descriptor Objects

«Descriptors» are objects that describe some attribute of an object. They are found in the dictionary of type objects.

*PyTypeObject* PyProperty\_Type

Μέρος του Σταθερό ABI. The type object for the built-in descriptor types.

*PyObject* \*PyDescr\_NewGetSet (*PyTypeObject* \*type, struct *PyGetSetDef* \*getset)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI.

*PyObject* \*PyDescr\_NewMember (*PyTypeObject* \*type, struct *PyMemberDef* \*meth)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI.

*PyObject* \*PyDescr\_NewMethod (*PyTypeObject* \*type, struct *PyMethodDef* \*meth)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI.

*PyObject* \*PyDescr\_NewWrapper (*PyTypeObject* \*type, struct wrapperbase \*wrapper, void \*wrapped)

*Επιστρεφόμενη τιμή:* New reference.

*PyObject* \*PyDescr\_NewClassMethod (*PyTypeObject* \*type, *PyMethodDef* \*method)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI.

int PyDescr\_IsData (*PyObject* \*descr)

Return non-zero if the descriptor objects *descr* describes a data attribute, or 0 if it describes a method. *descr* must be a descriptor object; there is no error checking.

*PyObject* \*PyWrapper\_New (*PyObject*\*, *PyObject*\*)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI.

## 8.6.5 Slice Objects

*PyTypeObject* PySlice\_Type

Μέρος του Σταθερό ABI. The type object for slice objects. This is the same as `slice` in the Python layer.

int PySlice\_Check (*PyObject* \*ob)

Return true if *ob* is a slice object; *ob* must not be NULL. This function always succeeds.

*PyObject* \*PySlice\_New (*PyObject* \*start, *PyObject* \*stop, *PyObject* \*step)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Return a new slice object with the given values. The *start*, *stop*, and *step* parameters are used as the values of the slice object attributes of the same names. Any of the values may be NULL, in which case the `None` will be used for the corresponding attribute. Return NULL if the new object could not be allocated.

int **PySlice\_GetIndices** (*PyObject* \*slice, *Py\_ssize\_t* length, *Py\_ssize\_t* \*start, *Py\_ssize\_t* \*stop, *Py\_ssize\_t* \*step)

*Μέρος του Σταθερό ABI.* Retrieve the start, stop and step indices from the slice object *slice*, assuming a sequence of length *length*. Treats indices greater than *length* as errors.

Returns 0 on success and -1 on error with no exception set (unless one of the indices was not None and failed to be converted to an integer, in which case -1 is returned with an exception set).

You probably do not want to use this function.

Άλλαξε στην έκδοση 3.2: The parameter type for the *slice* parameter was *PySliceObject\** before.

int **PySlice\_GetIndicesEx** (*PyObject* \*slice, *Py\_ssize\_t* length, *Py\_ssize\_t* \*start, *Py\_ssize\_t* \*stop, *Py\_ssize\_t* \*step, *Py\_ssize\_t* \*slicelength)

*Μέρος του Σταθερό ABI.* Usable replacement for *PySlice\_GetIndices()*. Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Returns 0 on success and -1 on error with exception set.

**Σημείωση:** This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of *PySlice\_Unpack()* and *PySlice\_AdjustIndices()* where

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength) < 0) {
    // return error
}
```

is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);
```

Άλλαξε στην έκδοση 3.2: The parameter type for the *slice* parameter was *PySliceObject\** before.

Άλλαξε στην έκδοση 3.6.1: If *Py\_LIMITED\_API* is not set or set to the value between 0x03050400 and 0x03060000 (not including) or 0x03060100 or higher *PySlice\_GetIndicesEx()* is implemented as a macro using *PySlice\_Unpack()* and *PySlice\_AdjustIndices()*. Arguments *start*, *stop* and *step* are evaluated more than once.

Αποσύρθηκε στην έκδοση 3.6.1: If *Py\_LIMITED\_API* is set to the value less than 0x03050400 or between 0x03060000 and 0x03060100 (not including) *PySlice\_GetIndicesEx()* is a deprecated function.

int **PySlice\_Unpack** (*PyObject* \*slice, *Py\_ssize\_t* \*start, *Py\_ssize\_t* \*stop, *Py\_ssize\_t* \*step)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than *PY\_SSIZE\_T\_MAX* to *PY\_SSIZE\_T\_MAX*, silently boost the start and stop values less than *PY\_SSIZE\_T\_MIN* to *PY\_SSIZE\_T\_MIN*, and silently boost the step values less than *-PY\_SSIZE\_T\_MAX* to *-PY\_SSIZE\_T\_MAX*.

Return -1 on error, 0 on success.

Νέο στην έκδοση 3.6.1.

*Py\_ssize\_t* **PySlice\_AdjustIndices** (*Py\_ssize\_t* length, *Py\_ssize\_t* \*start, *Py\_ssize\_t* \*stop, *Py\_ssize\_t* step)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

Νέο στην έκδοση 3.6.1.



## Ellipsis Object

*PyObject* \*Py\_Ellipsis

The Python `Ellipsis` object. This object has no methods. It needs to be treated just like any other object with respect to reference counts. Like *Py\_None* it is a singleton object.

## 8.6.6 MemoryView objects

A `memoryview` object exposes the C level *buffer interface* as a Python object which can then be passed around like any other object.

*PyObject* \*PyMemoryView\_FromObject (*PyObject* \*obj)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a `memoryview` object from an object that provides the buffer interface. If *obj* supports writable buffer exports, the `memoryview` object will be read/write, otherwise it may be either read-only or read/write at the discretion of the exporter.

**PyBUF\_READ**

Flag to request a readonly buffer.

**PyBUF\_WRITE**

Flag to request a writable buffer.

*PyObject* \*PyMemoryView\_FromMemory (char \*mem, *Py\_ssize\_t* size, int flags)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.7. Create a `memoryview` object using *mem* as the underlying buffer. *flags* can be one of *PyBUF\_READ* or *PyBUF\_WRITE*.

Νέο στην έκδοση 3.3.

*PyObject* \*PyMemoryView\_FromBuffer (const *Py\_buffer* \*view)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI από την έκδοση 3.11. Create a `memoryview` object wrapping the given buffer structure *view*. For simple byte buffers, *PyMemoryView\_FromMemory()* is the preferred function.

*PyObject* \*PyMemoryView\_GetContiguous (*PyObject* \*obj, int buffertype, char order)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του Σταθερό ABI. Create a `memoryview` object to a *contiguous* chunk of memory (in either “C” or “Fortran *order*”) from an object that defines the buffer interface. If memory is contiguous, the `memoryview` object points to the original memory. Otherwise, a copy is made and the `memoryview` points to a new bytes object.

*buffertype* can be one of *PyBUF\_READ* or *PyBUF\_WRITE*.

int PyMemoryView\_Check (*PyObject* \*obj)

Return true if the object *obj* is a `memoryview` object. It is not currently allowed to create subclasses of `memoryview`. This function always succeeds.

*Py\_buffer* \*PyMemoryView\_GET\_BUFFER (*PyObject* \*mview)

Return a pointer to the `memoryview`’s private copy of the exporter’s buffer. *mview* **must** be a `memoryview` instance; this macro doesn’t check its type, you must do it yourself or you will risk crashes.

*PyObject* \*PyMemoryView\_GET\_BASE (*PyObject* \*mview)

Return either a pointer to the exporting object that the `memoryview` is based on or NULL if the `memoryview` has been created by one of the functions *PyMemoryView\_FromMemory()* or *PyMemoryView\_FromBuffer()*. *mview* **must** be a `memoryview` instance.



## 8.6.7 Weak Reference Objects

Python supports *weak references* as first-class objects. There are two specific object types which directly implement weak references. The first is a simple reference object, and the second acts as a proxy for the original object as much as it can.

int **PyWeakref\_Check** (*PyObject* \*ob)

Return true if *ob* is either a reference or proxy object. This function always succeeds.

int **PyWeakref\_CheckRef** (*PyObject* \*ob)

Return true if *ob* is a reference object. This function always succeeds.

int **PyWeakref\_CheckProxy** (*PyObject* \*ob)

Return true if *ob* is a proxy object. This function always succeeds.

*PyObject* \***PyWeakref\_NewRef** (*PyObject* \*ob, *PyObject* \*callback)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Return a weak reference object for the object *ob*. This will always return a new reference, but is not guaranteed to create a new object; an existing reference object may be returned. The second parameter, *callback*, can be a callable object that receives notification when *ob* is garbage collected; it should accept a single parameter, which will be the weak reference object itself. *callback* may also be *None* or *NULL*. If *ob* is not a weakly referencable object, or if *callback* is not callable, *None*, or *NULL*, this will return *NULL* and raise *TypeError*.

*PyObject* \***PyWeakref\_NewProxy** (*PyObject* \*ob, *PyObject* \*callback)

*Επιστρεφόμενη τιμή:* *New reference. Μέρος του Σταθερό ABI.* Return a weak reference proxy object for the object *ob*. This will always return a new reference, but is not guaranteed to create a new object; an existing proxy object may be returned. The second parameter, *callback*, can be a callable object that receives notification when *ob* is garbage collected; it should accept a single parameter, which will be the weak reference object itself. *callback* may also be *None* or *NULL*. If *ob* is not a weakly referencable object, or if *callback* is not callable, *None*, or *NULL*, this will return *NULL* and raise *TypeError*.

*PyObject* \***PyWeakref\_GetObject** (*PyObject* \*ref)

*Επιστρεφόμενη τιμή:* *Borrowed reference. Μέρος του Σταθερό ABI.* Return the referenced object from a weak reference, *ref*. If the referent is no longer live, returns *Py\_None*.

---

**Σημείωση:** This function returns a *borrowed reference* to the referenced object. This means that you should always call *Py\_INCREF()* on the object except when it cannot be destroyed before the last usage of the borrowed reference.

---

*PyObject* \***PyWeakref\_GET\_OBJECT** (*PyObject* \*ref)

*Επιστρεφόμενη τιμή:* *Borrowed reference.* Similar to *PyWeakref\_GetObject()*, but does no error checking.

void **PyObject\_ClearWeakRefs** (*PyObject* \*object)

*Μέρος του Σταθερό ABI.* This function is called by the *tp\_dealloc* handler to clear weak references.

This iterates through the weak references for *object* and calls callbacks for those references which have one. It returns when all callbacks have been attempted.

## 8.6.8 Capsules

Refer to using-capsules for more information on using these objects.

Νέο στην έκδοση 3.1.

type **PyCapsule**

This subtype of *PyObject* represents an opaque value, useful for C extension modules who need to pass an opaque value (as a `void*` pointer) through Python code to other C code. It is often used to make a C function pointer defined in one module available to other modules, so the regular import mechanism can be used to access C APIs defined in dynamically loaded modules.

type **PyCapsule\_Destructor**

Μέρος του Σταθερό ABI. The type of a destructor callback for a capsule. Defined as:

```
typedef void (*PyCapsule_Destructor)(PyObject *);
```

See *PyCapsule\_New()* for the semantics of *PyCapsule\_Destructor* callbacks.

int **PyCapsule\_CheckExact** (*PyObject* \*p)

Return true if its argument is a *PyCapsule*. This function always succeeds.

*PyObject* \***PyCapsule\_New** (void \*pointer, const char \*name, *PyCapsule\_Destructor* destructor)

Επιστρεφόμενη τιμή: New reference. Μέρος του Σταθερό ABI. Create a *PyCapsule* encapsulating the pointer. The pointer argument may not be NULL.

On failure, set an exception and return NULL.

The name string may either be NULL or a pointer to a valid C string. If non-NULL, this string must outlive the capsule. (Though it is permitted to free it inside the destructor.)

If the destructor argument is not NULL, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the name should be specified as `modulename.attribute`. This will enable other modules to import the capsule using *PyCapsule\_Import()*.

void \***PyCapsule\_GetPointer** (*PyObject* \*capsule, const char \*name)

Μέρος του Σταθερό ABI. Retrieve the pointer stored in the capsule. On failure, set an exception and return NULL.

The name parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is NULL, the name passed in must also be NULL. Python uses the C function `strcmp()` to compare capsule names.

*PyCapsule\_Destructor* **PyCapsule\_GetDestructor** (*PyObject* \*capsule)

Μέρος του Σταθερό ABI. Return the current destructor stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL destructor. This makes a NULL return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

void \***PyCapsule\_GetContext** (*PyObject* \*capsule)

Μέρος του Σταθερό ABI. Return the current context stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL context. This makes a NULL return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

const char \***PyCapsule\_GetName** (*PyObject* \*capsule)

Μέρος του Σταθερό ABI. Return the current name stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL name. This makes a NULL return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

void **PyCapsule\_Import** (const char \*name, int no\_block)

*Μέρος του Σταθερό ABI.* Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in `module.attribute`. The *name* stored in the capsule must match this string exactly.

Return the capsule's internal *pointer* on success. On failure, set an exception and return NULL.

Άλλαξε στην έκδοση 3.3: *no\_block* has no effect anymore.

int **PyCapsule\_IsValid** (*PyObject* \*capsule, const char \*name)

*Μέρος του Σταθερό ABI.* Determines whether or not *capsule* is a valid capsule. A valid capsule is non-NULL, passes *PyCapsule\_CheckExact()*, has a non-NULL pointer stored in it, and its internal name matches the *name* parameter. (See *PyCapsule\_GetPointer()* for information on how capsule names are compared.)

In other words, if *PyCapsule\_IsValid()* returns a true value, calls to any of the accessors (any function starting with *PyCapsule\_Get*) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return 0 otherwise. This function will not fail.

int **PyCapsule\_SetContext** (*PyObject* \*capsule, void \*context)

*Μέρος του Σταθερό ABI.* Set the context pointer inside *capsule* to *context*.

Return 0 on success. Return nonzero and set an exception on failure.

int **PyCapsule\_SetDestructor** (*PyObject* \*capsule, *PyCapsule\_Destructor* destructor)

*Μέρος του Σταθερό ABI.* Set the destructor inside *capsule* to *destructor*.

Return 0 on success. Return nonzero and set an exception on failure.

int **PyCapsule\_SetName** (*PyObject* \*capsule, const char \*name)

*Μέρος του Σταθερό ABI.* Set the name inside *capsule* to *name*. If non-NULL, the name must outlive the capsule. If the previous *name* stored in the capsule was not NULL, no attempt is made to free it.

Return 0 on success. Return nonzero and set an exception on failure.

int **PyCapsule\_SetPointer** (*PyObject* \*capsule, void \*pointer)

*Μέρος του Σταθερό ABI.* Set the void pointer inside *capsule* to *pointer*. The pointer may not be NULL.

Return 0 on success. Return nonzero and set an exception on failure.

## 8.6.9 Frame Objects

type **PyFrameObject**

*Μέρος του Περιορισμένο API (ως μια αδιαφανής κατασκευή).* The C structure of the objects used to describe frame objects.

There are no public members in this structure.

Άλλαξε στην έκδοση 3.11: The members of this structure were removed from the public C API. Refer to the What's New entry for details.

The *PyEval\_GetFrame()* and *PyThreadState\_GetFrame()* functions can be used to get a frame object.

See also *Reflection*.

*PyTypeObject* **PyFrame\_Type**

The type of frame objects. It is the same object as `types.FrameType` in the Python layer.

Άλλαξε στην έκδοση 3.11: Previously, this type was only available after including `<frameobject.h>`.

`int PyFrame_Check (PyObject *obj)`

Return non-zero if *obj* is a frame object.

Άλλαξε στην έκδοση 3.11: Previously, this function was only available after including `<frameobject.h>`.

`PyFrameObject *PyFrame_GetBack (PyFrameObject *frame)`

Get the *frame* next outer frame.

Return a *strong reference*, or NULL if *frame* has no outer frame.

Νέο στην έκδοση 3.9.

`PyObject *PyFrame_GetBuiltins (PyFrameObject *frame)`

Get the *frame*'s `f_builtins` attribute.

Return a *strong reference*. The result cannot be NULL.

Νέο στην έκδοση 3.11.

`PyCodeObject *PyFrame_GetCode (PyFrameObject *frame)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Get the *frame* code.

Return a *strong reference*.

The result (frame code) cannot be NULL.

Νέο στην έκδοση 3.9.

`PyObject *PyFrame_GetGenerator (PyFrameObject *frame)`

Get the generator, coroutine, or async generator that owns this frame, or NULL if this frame is not owned by a generator. Does not raise an exception, even if the return value is NULL.

Return a *strong reference*, or NULL.

Νέο στην έκδοση 3.11.

`PyObject *PyFrame_GetGlobals (PyFrameObject *frame)`

Get the *frame*'s `f_globals` attribute.

Return a *strong reference*. The result cannot be NULL.

Νέο στην έκδοση 3.11.

`int PyFrame_GetLasti (PyFrameObject *frame)`

Get the *frame*'s `f_lasti` attribute.

Returns -1 if *frame.f\_lasti* is None.

Νέο στην έκδοση 3.11.

`PyObject *PyFrame_GetLocals (PyFrameObject *frame)`

Get the *frame*'s `f_locals` attribute (dict).

Return a *strong reference*.

Νέο στην έκδοση 3.11.

`int PyFrame_GetLineNumber (PyFrameObject *frame)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Return the line number that *frame* is currently executing.

### 8.6.10 Generator Objects

Generator objects are what Python uses to implement generator iterators. They are normally created by iterating over a function that yields values, rather than explicitly calling `PyGen_New()` or `PyGen_NewWithQualName()`.

type **PyGenObject**

The C structure used for generator objects.

*PyTypeObject* **PyGen\_Type**

The type object corresponding to generator objects.

int **PyGen\_Check** (*PyObject* \*ob)

Return true if *ob* is a generator object; *ob* must not be NULL. This function always succeeds.

int **PyGen\_CheckExact** (*PyObject* \*ob)

Return true if *ob*'s type is *PyGen\_Type*; *ob* must not be NULL. This function always succeeds.

*PyObject* \***PyGen\_New** (*PyFrameObject* \*frame)

*Επιστρεφόμενη τιμή: New reference.* Create and return a new generator object based on the *frame* object. A reference to *frame* is stolen by this function. The argument must not be NULL.

*PyObject* \***PyGen\_NewWithQualName** (*PyFrameObject* \*frame, *PyObject* \*name, *PyObject* \*qualname)

*Επιστρεφόμενη τιμή: New reference.* Create and return a new generator object based on the *frame* object, with `__name__` and `__qualname__` set to *name* and *qualname*. A reference to *frame* is stolen by this function. The *frame* argument must not be NULL.

### 8.6.11 Coroutine Objects

Νέο στην έκδοση 3.5.

Coroutine objects are what functions declared with an `async` keyword return.

type **PyCoroObject**

The C structure used for coroutine objects.

*PyTypeObject* **PyCoro\_Type**

The type object corresponding to coroutine objects.

int **PyCoro\_CheckExact** (*PyObject* \*ob)

Return true if *ob*'s type is *PyCoro\_Type*; *ob* must not be NULL. This function always succeeds.

*PyObject* \***PyCoro\_New** (*PyFrameObject* \*frame, *PyObject* \*name, *PyObject* \*qualname)

*Επιστρεφόμενη τιμή: New reference.* Create and return a new coroutine object based on the *frame* object, with `__name__` and `__qualname__` set to *name* and *qualname*. A reference to *frame* is stolen by this function. The *frame* argument must not be NULL.

### 8.6.12 Context Variables Objects

Νέο στην έκδοση 3.7.

Άλλαξε στην έκδοση 3.7.1:

---

**Σημείωση:** In Python 3.7.1 the signatures of all context variables C APIs were **changed** to use *PyObject* pointers instead of *PyContext*, *PyContextVar*, and *PyContextToken*, e.g.:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

See [bpo-34762](#) for more details.

This section details the public C API for the `contextvars` module.

#### type **PyContext**

The C structure used to represent a `contextvars.Context` object.

#### type **PyContextVar**

The C structure used to represent a `contextvars.ContextVar` object.

#### type **PyContextToken**

The C structure used to represent a `contextvars.Token` object.

#### *PyObject* **PyContext\_Type**

The type object representing the *context* type.

#### *PyObject* **PyContextVar\_Type**

The type object representing the *context variable* type.

#### *PyObject* **PyContextToken\_Type**

The type object representing the *context variable token* type.

Type-check macros:

#### int **PyContext\_CheckExact** (*PyObject* \*o)

Return true if *o* is of type *PyContext\_Type*. *o* must not be NULL. This function always succeeds.

#### int **PyContextVar\_CheckExact** (*PyObject* \*o)

Return true if *o* is of type *PyContextVar\_Type*. *o* must not be NULL. This function always succeeds.

#### int **PyContextToken\_CheckExact** (*PyObject* \*o)

Return true if *o* is of type *PyContextToken\_Type*. *o* must not be NULL. This function always succeeds.

Context object management functions:

#### *PyObject* \***PyContext\_New** (void)

*Επιστρεφόμενη τιμή: New reference.* Create a new empty context object. Returns NULL if an error has occurred.

#### *PyObject* \***PyContext\_Copy** (*PyObject* \*ctx)

*Επιστρεφόμενη τιμή: New reference.* Create a shallow copy of the passed *ctx* context object. Returns NULL if an error has occurred.

#### *PyObject* \***PyContext\_CopyCurrent** (void)

*Επιστρεφόμενη τιμή: New reference.* Create a shallow copy of the current thread context. Returns NULL if an error has occurred.

#### int **PyContext\_Enter** (*PyObject* \*ctx)

Set *ctx* as the current context for the current thread. Returns 0 on success, and -1 on error.

#### int **PyContext\_Exit** (*PyObject* \*ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns 0 on success, and -1 on error.

Context variable functions:

#### *PyObject* \***PyContextVar\_New** (const char \*name, *PyObject* \*def)

*Επιστρεφόμενη τιμή: New reference.* Create a new `ContextVar` object. The *name* parameter is used for introspection and debug purposes. The *def* parameter specifies a default value for the context variable, or NULL for no default. If an error has occurred, this function returns NULL.

int **PyContextVar\_Get** (*PyObject* \*var, *PyObject* \*default\_value, *PyObject* \*\*value)

Get the value of a context variable. Returns `-1` if an error has occurred during lookup, and `0` if no error occurred, whether or not a value was found.

If the context variable was found, *value* will be a pointer to it. If the context variable was *not* found, *value* will point to:

- *default\_value*, if not `NULL`;
- the default value of *var*, if not `NULL`;
- `NULL`

Except for `NULL`, the function returns a new reference.

*PyObject* \***PyContextVar\_Set** (*PyObject* \*var, *PyObject* \*value)

*Επιστρεφόμενη τιμή*: New reference. Set the value of *var* to *value* in the current context. Returns a new token object for this change, or `NULL` if an error has occurred.

int **PyContextVar\_Reset** (*PyObject* \*var, *PyObject* \*token)

Reset the state of the *var* context variable to that it was in before *PyContextVar\_Set* () that returned the *token* was called. This function returns `0` on success and `-1` on error.

### 8.6.13 DateTime Objects

Various date and time objects are supplied by the `datetime` module. Before using any of these functions, the header file `datetime.h` must be included in your source (note that this is not included by `Python.h`), and the macro `PyDateTime_IMPORT` must be invoked, usually as part of the module initialisation function. The macro puts a pointer to a C structure into a static variable, `PyDateTimeAPI`, that is used by the following macros.

type **PyDateTime\_Date**

This subtype of *PyObject* represents a Python date object.

type **PyDateTime\_DateTime**

This subtype of *PyObject* represents a Python datetime object.

type **PyDateTime\_Time**

This subtype of *PyObject* represents a Python time object.

type **PyDateTime\_Delta**

This subtype of *PyObject* represents the difference between two datetime values.

*PyTypeObject* **PyDateTime\_DateType**

This instance of *PyTypeObject* represents the Python date type; it is the same object as `datetime.date` in the Python layer.

*PyTypeObject* **PyDateTime\_DateTimeType**

This instance of *PyTypeObject* represents the Python datetime type; it is the same object as `datetime.datetime` in the Python layer.

*PyTypeObject* **PyDateTime\_TimeType**

This instance of *PyTypeObject* represents the Python time type; it is the same object as `datetime.time` in the Python layer.

*PyTypeObject* **PyDateTime\_DeltaType**

This instance of *PyTypeObject* represents Python type for the difference between two datetime values; it is the same object as `datetime.timedelta` in the Python layer.

*PyTypeObject* **PyDateTime\_TZInfoType**

This instance of *PyTypeObject* represents the Python time zone info type; it is the same object as `datetime.tzinfo` in the Python layer.

Macro for access to the UTC singleton:



***PyObject* \*PyDateTime\_TimeZone\_UTC**

Returns the time zone singleton representing UTC, the same object as `datetime.timezone.utc`.

Νέο στην έκδοση 3.7.

Type-check macros:

**int PyDate\_Check (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DateType* or a subtype of *PyDateTime\_DateType*. *ob* must not be NULL. This function always succeeds.

**int PyDate\_CheckExact (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DateType*. *ob* must not be NULL. This function always succeeds.

**int PyDateTime\_Check (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DateTimeType* or a subtype of *PyDateTime\_DateTimeType*. *ob* must not be NULL. This function always succeeds.

**int PyDateTime\_CheckExact (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DateTimeType*. *ob* must not be NULL. This function always succeeds.

**int PyTime\_Check (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_TimeType* or a subtype of *PyDateTime\_TimeType*. *ob* must not be NULL. This function always succeeds.

**int PyTime\_CheckExact (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_TimeType*. *ob* must not be NULL. This function always succeeds.

**int PyDelta\_Check (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DeltaType* or a subtype of *PyDateTime\_DeltaType*. *ob* must not be NULL. This function always succeeds.

**int PyDelta\_CheckExact (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_DeltaType*. *ob* must not be NULL. This function always succeeds.

**int PyTZInfo\_Check (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_TZInfoType* or a subtype of *PyDateTime\_TZInfoType*. *ob* must not be NULL. This function always succeeds.

**int PyTZInfo\_CheckExact (*PyObject* \*ob)**

Return true if *ob* is of type *PyDateTime\_TZInfoType*. *ob* must not be NULL. This function always succeeds.

Macros to create objects:

***PyObject* \*PyDate\_FromDate (int year, int month, int day)**

*Επιστρεφόμενη τιμή: New reference.* Return a `datetime.date` object with the specified year, month and day.

***PyObject* \*PyDateTime\_FromDateAndTime (int year, int month, int day, int hour, int minute, int second, int usecond)**

*Επιστρεφόμενη τιμή: New reference.* Return a `datetime.datetime` object with the specified year, month, day, hour, minute, second and microsecond.

***PyObject* \*PyDateTime\_FromDateAndTimeAndFold (int year, int month, int day, int hour, int minute, int second, int usecond, int fold)**

*Επιστρεφόμενη τιμή: New reference.* Return a `datetime.datetime` object with the specified year, month, day, hour, minute, second, microsecond and fold.

Νέο στην έκδοση 3.6.

*PyObject* \***PyTime\_FromTime** (int hour, int minute, int second, int usecond)

*Επιστρεφόμενη τιμή:* *New reference.* Return a `datetime.time` object with the specified hour, minute, second and microsecond.

*PyObject* \***PyTime\_FromTimeAndFold** (int hour, int minute, int second, int usecond, int fold)

*Επιστρεφόμενη τιμή:* *New reference.* Return a `datetime.time` object with the specified hour, minute, second, microsecond and fold.

Νέο στην έκδοση 3.6.

*PyObject* \***PyDelta\_FromDSU** (int days, int seconds, int useconds)

*Επιστρεφόμενη τιμή:* *New reference.* Return a `datetime.timedelta` object representing the given number of days, seconds and microseconds. Normalization is performed so that the resulting number of microseconds and seconds lie in the ranges documented for `datetime.timedelta` objects.

*PyObject* \***PyTimeZone\_FromOffset** (*PyObject* \*offset)

*Επιστρεφόμενη τιμή:* *New reference.* Return a `datetime.timezone` object with an unnamed fixed offset represented by the *offset* argument.

Νέο στην έκδοση 3.7.

*PyObject* \***PyTimeZone\_FromOffsetAndName** (*PyObject* \*offset, *PyObject* \*name)

*Επιστρεφόμενη τιμή:* *New reference.* Return a `datetime.timezone` object with a fixed offset represented by the *offset* argument and with *tzname* *name*.

Νέο στην έκδοση 3.7.

Macros to extract fields from date objects. The argument must be an instance of `PyDateTime_Date`, including subclasses (such as `PyDateTime_DateTime`). The argument must not be NULL, and the type is not checked:

int **PyDateTime\_GET\_YEAR** (*PyDateTime\_Date* \*o)

Return the year, as a positive int.

int **PyDateTime\_GET\_MONTH** (*PyDateTime\_Date* \*o)

Return the month, as an int from 1 through 12.

int **PyDateTime\_GET\_DAY** (*PyDateTime\_Date* \*o)

Return the day, as an int from 1 through 31.

Macros to extract fields from datetime objects. The argument must be an instance of `PyDateTime_DateTime`, including subclasses. The argument must not be NULL, and the type is not checked:

int **PyDateTime\_DATE\_GET\_HOUR** (*PyDateTime\_DateTime* \*o)

Return the hour, as an int from 0 through 23.

int **PyDateTime\_DATE\_GET\_MINUTE** (*PyDateTime\_DateTime* \*o)

Return the minute, as an int from 0 through 59.

int **PyDateTime\_DATE\_GET\_SECOND** (*PyDateTime\_DateTime* \*o)

Return the second, as an int from 0 through 59.

int **PyDateTime\_DATE\_GET\_MICROSECOND** (*PyDateTime\_DateTime* \*o)

Return the microsecond, as an int from 0 through 999999.

int **PyDateTime\_DATE\_GET\_FOLD** (*PyDateTime\_DateTime* \*o)

Return the fold, as an int from 0 through 1.

Νέο στην έκδοση 3.6.

*PyObject* \***PyDateTime\_DATE\_GET\_TZINFO** (*PyDateTime\_DateTime* \*o)

Return the tzinfo (which may be None).

Νέο στην έκδοση 3.10.

Macros to extract fields from time objects. The argument must be an instance of `PyDateTime_Time`, including subclasses. The argument must not be NULL, and the type is not checked:

**int PyDateTime\_TIME\_GET\_HOUR** (*PyDateTime\_Time* \*o)

Return the hour, as an int from 0 through 23.

**int PyDateTime\_TIME\_GET\_MINUTE** (*PyDateTime\_Time* \*o)

Return the minute, as an int from 0 through 59.

**int PyDateTime\_TIME\_GET\_SECOND** (*PyDateTime\_Time* \*o)

Return the second, as an int from 0 through 59.

**int PyDateTime\_TIME\_GET\_MICROSECOND** (*PyDateTime\_Time* \*o)

Return the microsecond, as an int from 0 through 999999.

**int PyDateTime\_TIME\_GET\_FOLD** (*PyDateTime\_Time* \*o)

Return the fold, as an int from 0 through 1.

Νέο στην έκδοση 3.6.

**PyObject\* PyDateTime\_TIME\_GET\_TZINFO** (*PyDateTime\_Time* \*o)

Return the tzinfo (which may be None).

Νέο στην έκδοση 3.10.

Macros to extract fields from time delta objects. The argument must be an instance of *PyDateTime\_Delta*, including subclasses. The argument must not be NULL, and the type is not checked:

**int PyDateTime\_DELTA\_GET\_DAYS** (*PyDateTime\_Delta* \*o)

Return the number of days, as an int from -999999999 to 999999999.

Νέο στην έκδοση 3.3.

**int PyDateTime\_DELTA\_GET\_SECONDS** (*PyDateTime\_Delta* \*o)

Return the number of seconds, as an int from 0 through 86399.

Νέο στην έκδοση 3.3.

**int PyDateTime\_DELTA\_GET\_MICROSECONDS** (*PyDateTime\_Delta* \*o)

Return the number of microseconds, as an int from 0 through 999999.

Νέο στην έκδοση 3.3.

Macros for the convenience of modules implementing the DB API:

**PyObject\* PyDateTime\_FromTimestamp** (*PyObject* \*args)

*Επιστρεφόμενη τιμή:* New reference. Create and return a new `datetime.datetime` object given an argument tuple suitable for passing to `datetime.datetime.fromtimestamp()`.

**PyObject\* PyDate\_FromTimestamp** (*PyObject* \*args)

*Επιστρεφόμενη τιμή:* New reference. Create and return a new `datetime.date` object given an argument tuple suitable for passing to `datetime.date.fromtimestamp()`.

## 8.6.14 Objects for Type Hinting

Various built-in types for type hinting are provided. Currently, two types exist – `GenericAlias` and `Union`. Only `GenericAlias` is exposed to C.

**PyObject\* Py\_GenericAlias** (*PyObject* \*origin, *PyObject* \*args)

*Μέρος του Σταθερό ABI από την έκδοση 3.9.* Create a `GenericAlias` object. Equivalent to calling the Python class `types.GenericAlias`. The *origin* and *args* arguments set the `GenericAlias`'s `__origin__` and `__args__` attributes respectively. *origin* should be a *PyTypeObject\**, and *args* can be a *PyTupleObject\** or any *PyObject\**. If *args* passed is not a tuple, a 1-tuple is automatically constructed and `__args__` is set to `(args,)`. Minimal checking is done for the arguments, so the function will succeed even if *origin* is not a type. The `GenericAlias`'s `__parameters__` attribute is constructed lazily from `__args__`. On failure, an exception is raised and NULL is returned.

Here's an example of how to make an extension type generic:

```
...
static PyMethodDef my_obj_methods[] = {
    // Other methods.
    ...
    {"__class_getitem__", Py_GenericAlias, METH_O|METH_CLASS, "See PEP 585"}
    ...
}
```

**Δείτε επίσης:**

The data model method `__class_getitem__()`.

Νέο στην έκδοση 3.9.

*PyTypeObject* **Py\_GenericAliasType**

*Μέρος του Σταθερό ABI από την έκδοση 3.9.* The C type of the object returned by `Py_GenericAlias()`. Equivalent to `types.GenericAlias` in Python.

Νέο στην έκδοση 3.9.

---

## Initialization, Finalization, and Threads

---

See also *Python Initialization Configuration*.

### 9.1 Before Python Initialization

In an application embedding Python, the `Py_Initialize()` function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

The following functions can be safely called before Python is initialized:

- Configuration functions:

- `PyImport_AppendInittab()`
- `PyImport_ExtendInittab()`
- `PyInitFrozenExtensions()`
- `PyMem_SetAllocator()`
- `PyMem_SetupDebugHooks()`
- `PyObject_SetArenaAllocator()`
- `Py_SetPath()`
- `Py_SetProgramName()`
- `Py_SetPythonHome()`
- `Py_SetStandardStreamEncoding()`
- `PySys_AddWarnOption()`
- `PySys_AddXOption()`
- `PySys_ResetWarnOptions()`

- Informative functions:

- `Py_IsInitialized()`
- `PyMem_GetAllocator()`
- `PyObject_GetArenaAllocator()`

- `Py_GetBuildInfo()`
- `Py_GetCompiler()`
- `Py_GetCopyright()`
- `Py_GetPlatform()`
- `Py_GetVersion()`

- Utilities:

- `Py_DecodeLocale()`

- Memory allocators:

- `PyMem_RawMalloc()`
  - `PyMem_RawRealloc()`
  - `PyMem_RawCalloc()`
  - `PyMem_RawFree()`

---

**Σημείωση:** The following functions **should not be called** before `Py_Initialize():Py_EncodeLocale()`, `Py_GetPath()`, `Py_GetPrefix()`, `Py_GetExecPrefix()`, `Py_GetProgramFullPath()`, `Py_GetPythonHome()`, `Py_GetProgramName()` and `PyEval_InitThreads()`.

---

## 9.2 Global configuration variables

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example, `-b` sets `Py_BytesWarningFlag` to 1 and `-bb` sets `Py_BytesWarningFlag` to 2.

### int `Py_BytesWarningFlag`

Issue a warning when comparing `bytes` or `bytearray` with `str` or `bytes` with `int`. Issue an error if greater or equal to 2.

Set by the `-b` option.

### int `Py_DebugFlag`

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the `-d` option and the `PYTHONDEBUG` environment variable.

### int `Py_DontWriteBytecodeFlag`

If set to non-zero, Python won't try to write `.pyc` files on the import of source modules.

Set by the `-B` option and the `PYTHONDONTWRITEBYTECODE` environment variable.

### int `Py_FrozenFlag`

Suppress error messages when calculating the module search path in `Py_GetPath()`.

Private flag used by `_freeze_module` and `frozenmain` programs.

### int `Py_HashRandomizationFlag`

Set to 1 if the `PYTHONHASHSEED` environment variable is set to a non-empty string.

If the flag is non-zero, read the `PYTHONHASHSEED` environment variable to initialize the secret hash seed.

**int Py\_IgnoreEnvironmentFlag**

Ignore all PYTHON\* environment variables, e.g. PYTHONPATH and PYTHONHOME, that might be set.

Set by the `-E` and `-I` options.

**int Py\_InspectFlag**

When a script is passed as first argument or the `-c` option is used, enter interactive mode after executing the script or the command, even when `sys.stdin` does not appear to be a terminal.

Set by the `-i` option and the PYTHONINSPECT environment variable.

**int Py\_InteractiveFlag**

Set by the `-i` option.

**int Py\_IsolatedFlag**

Run Python in isolated mode. In isolated mode `sys.path` contains neither the script's directory nor the user's site-packages directory.

Set by the `-I` option.

Νέο στην έκδοση 3.4.

**int Py\_LegacyWindowsFSEncodingFlag**

If the flag is non-zero, use the `mbcs` encoding with `replace` error handler, instead of the UTF-8 encoding with `surrogatepass` error handler, for the *filesystem encoding and error handler*.

Set to 1 if the PYTHONLEGACYWINDOWSFSENCODING environment variable is set to a non-empty string.

See [PEP 529](#) for more details.

Availability: Windows.

**int Py\_LegacyWindowsStdioFlag**

If the flag is non-zero, use `io.FileIO` instead of `io._WindowsConsoleIO` for `sys` standard streams.

Set to 1 if the PYTHONLEGACYWINDOWSTDIO environment variable is set to a non-empty string.

See [PEP 528](#) for more details.

Availability: Windows.

**int Py\_NoSiteFlag**

Disable the import of the module `site` and the site-dependent manipulations of `sys.path` that it entails. Also disable these manipulations if `site` is explicitly imported later (call `site.main()` if you want them to be triggered).

Set by the `-S` option.

**int Py\_NoUserSiteDirectory**

Don't add the user `site-packages` directory to `sys.path`.

Set by the `-s` and `-I` options, and the PYTHONNOUSERSITE environment variable.

**int Py\_OptimizeFlag**

Set by the `-O` option and the PYTHONOPTIMIZE environment variable.

**int Py\_QuietFlag**

Don't display the copyright and version messages even in interactive mode.

Set by the `-q` option.

Νέο στην έκδοση 3.2.

**int Py\_UnbufferedStdioFlag**

Force the `stdout` and `stderr` streams to be unbuffered.

Set by the `-u` option and the PYTHONUNBUFFERED environment variable.



**int `Py_VerboseFlag`**

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the `-v` option and the `PYTHONVERBOSE` environment variable.

## 9.3 Initializing and finalizing the interpreter

**void `Py_Initialize()`**

*Μέρος του Σταθερό ABI.* Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (`sys.modules`), and creates the fundamental modules `builtins`, `__main__` and `sys`. It also initializes the module search path (`sys.path`). It does not set `sys.argv`; use `PySys_SetArgvEx()` for that. This is a no-op when called for a second time (without calling `Py_FinalizeEx()` first). There is no return value; it is a fatal error if the initialization fails.

---

**Σημείωση:** On Windows, changes the console mode from `O_TEXT` to `O_BINARY`, which will also affect non-Python uses of the console using the C Runtime.

---

**void `Py_InitializeEx`(int initsigs)**

*Μέρος του Σταθερό ABI.* This function works like `Py_Initialize()` if `initsigs` is 1. If `initsigs` is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

**int `Py_IsInitialized()`**

*Μέρος του Σταθερό ABI.* Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After `Py_FinalizeEx()` is called, this returns false until `Py_Initialize()` is called again.

**int `Py_FinalizeEx()`**

*Μέρος του Σταθερό ABI από την έκδοση 3.6.* Undo all initializations made by `Py_Initialize()` and subsequent use of Python/C API functions, and destroy all sub-interpreters (see `Py_NewInterpreter()` below) that were created and not yet destroyed since the last call to `Py_Initialize()`. Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling `Py_Initialize()` again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

**Bugs and caveats:** The destruction of modules and objects in modules is done in random order; this may cause destructors (`__del__()` methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls `Py_Initialize()` and `Py_FinalizeEx()` more than once.

Raises an auditing event `cpython._PySys_ClearAuditHooks` with no arguments.

Νέο στην έκδοση 3.6.

**void `Py_Finalize()`**

*Μέρος του Σταθερό ABI.* This is a backwards-compatible version of `Py_FinalizeEx()` that disregards the return value.

## 9.4 Process-wide parameters

int **Py\_SetStandardStreamEncoding** (const char \*encoding, const char \*errors)

This API is kept for backward compatibility: setting `PyConfig.stdio_encoding` and `PyConfig.stdio_errors` should be used instead, see *Python Initialization Configuration*.

This function should be called before `Py_Initialize()`, if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in `str.encode()`.

It overrides `PYTHONIOENCODING` values, and allows embedding code to control IO encoding when the environment variable does not work.

`encoding` and/or `errors` may be `NULL` to use `PYTHONIOENCODING` and/or default values (depending on other settings).

Note that `sys.stderr` always uses the «backslashreplace» error handler, regardless of this (or any other) setting.

If `Py_FinalizeEx()` is called, this function will need to be called again in order to affect subsequent calls to `Py_Initialize()`.

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized).

Νέο στην έκδοση 3.4.

Αποσύρθηκε στην έκδοση 3.11.

void **Py\_SetProgramName** (const wchar\_t \*name)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.program_name` should be used instead, see *Python Initialization Configuration*.

This function should be called before `Py_Initialize()` is called for the first time, if it is called at all. It tells the interpreter the value of the `argv[0]` argument to the `main()` function of the program (converted to wide characters). This is used by `Py_GetPath()` and some other functions below to find the Python run-time libraries relative to the interpreter executable. The default value is `'python'`. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

Αποσύρθηκε στην έκδοση 3.11.

wchar\_t \***Py\_GetProgramName** ()

*Μέρος του Σταθερό ABI.* Return the program name set with `Py_SetProgramName()`, or the default. The returned string points into static storage; the caller should not modify its value.

This function should not be called before `Py_Initialize()`, otherwise it returns `NULL`.

Άλλαξε στην έκδοση 3.10: It now returns `NULL` if called before `Py_Initialize()`.

wchar\_t \***Py\_GetPrefix** ()

*Μέρος του Σταθερό ABI.* Return the `prefix` for installed platform-independent files. This is derived through a number of complicated rules from the program name set with `Py_SetProgramName()` and some environment variables; for example, if the program name is `'/usr/local/bin/python'`, the prefix is `'/usr/local'`. The returned string points into static storage; the caller should not modify its value. This corresponds to the `prefix` variable in the top-level Makefile and the `--prefix` argument to the `configure` script at build time. The value is available to Python code as `sys.prefix`. It is only useful on Unix. See also the next function.

This function should not be called before `Py_Initialize()`, otherwise it returns `NULL`.

Άλλαξε στην έκδοση 3.10: It now returns `NULL` if called before `Py_Initialize()`.

wchar\_t \***Py\_GetExecPrefix**()

*Μέρος του Σταθερό ABI.* Return the *exec-prefix* for installed platform-dependent files. This is derived through a number of complicated rules from the program name set with *Py\_SetProgramName()* and some environment variables; for example, if the program name is `"/usr/local/bin/python"`, the *exec-prefix* is `"/usr/local"`. The returned string points into static storage; the caller should not modify its value. This corresponds to the `exec_prefix` variable in the top-level Makefile and the `--exec-prefix` argument to the `configure` script at build time. The value is available to Python code as `sys.exec_prefix`. It is only useful on Unix.

Background: The *exec-prefix* differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the `/usr/local/plat` subtree while platform independent may be installed in `/usr/local`.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and *exec-prefix* are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the `mount` or `automount` programs to share `/usr/local` between platforms while having `/usr/local/plat` be a different filesystem for each platform.

This function should not be called before *Py\_Initialize()*, otherwise it returns NULL.

Άλλαξε στην έκδοση 3.10: It now returns NULL if called before *Py\_Initialize()*.

wchar\_t \***Py\_GetProgramFullPath**()

*Μέρος του Σταθερό ABI.* Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by *Py\_SetProgramName()* above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.executable`.

This function should not be called before *Py\_Initialize()*, otherwise it returns NULL.

Άλλαξε στην έκδοση 3.10: It now returns NULL if called before *Py\_Initialize()*.

wchar\_t \***Py\_GetPath**()

*Μέρος του Σταθερό ABI.* Return the default module search path; this is computed from the program name (set by *Py\_SetProgramName()* above) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is `':'` on Unix and macOS,  `';'`  on Windows. The returned string points into static storage; the caller should not modify its value. The list `sys.path` is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

This function should not be called before *Py\_Initialize()*, otherwise it returns NULL.

Άλλαξε στην έκδοση 3.10: It now returns NULL if called before *Py\_Initialize()*.

void **Py\_SetPath**(const wchar\_t\*)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* This API is kept for backward compatibility: setting *PyConfig.module\_search\_paths* and *PyConfig.module\_search\_paths\_set* should be used instead, see *Python Initialization Configuration*.

Set the default module search path. If this function is called before *Py\_Initialize()*, then *Py\_GetPath()* won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is `':'` on Unix and macOS,  `';'`  on Windows.

This also causes `sys.executable` to be set to the program full path (see *Py\_GetProgramFullPath()*) and for `sys.prefix` and `sys.exec_prefix` to be empty. It

is up to the caller to modify these if required after calling `Py_Initialize()`.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

The path argument is copied internally, so the caller may free it after the call completes.

Αλλάξε στην έκδοση 3.8: The program full path is now used for `sys.executable`, instead of the program name.

Αποσύρθηκε στην έκδοση 3.11.

const char **\*Py\_GetVersion** ()

*Μέρος του Σταθερό ABI.* Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.version`.

See also the `Py_Version` constant.

const char **\*Py\_GetPlatform** ()

*Μέρος του Σταθερό ABI.* Return the platform identifier for the current platform. On Unix, this is formed from the «official» name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On macOS, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.platform`.

const char **\*Py\_GetCopyright** ()

*Μέρος του Σταθερό ABI.* Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.copyright`.

const char **\*Py\_GetCompiler** ()

*Μέρος του Σταθερό ABI.* Return an indication of the compiler used to build the current Python version, in square brackets, for example:

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

const char **\*Py\_GetBuildInfo** ()

*Μέρος του Σταθερό ABI.* Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

void **PySys\_SetArgvEx** (int argc, wchar\_t \*\*argv, int updatepath)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.argv`, `PyConfig.parse_argv` and `PyConfig.safe_path` should be used instead, see *Python Initialization Configuration*.

Set `sys.argv` based on `argc` and `argv`. These parameters are similar to those passed to the program's `main()` function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in

`argv` can be an empty string. If this function fails to initialize `sys.argv`, a fatal condition is signalled using `Py_FatalError()`.

If `updatepath` is zero, this is all the function does. If `updatepath` is non-zero, the function also modifies `sys.path` according to the following algorithm:

- If the name of an existing script is passed in `argv[0]`, the absolute path of the directory where the script is located is prepended to `sys.path`.
- Otherwise (that is, if `argc` is 0 or `argv[0]` doesn't point to an existing file name), an empty string is prepended to `sys.path`, which is the same as prepending the current working directory (`"."`).

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

See also `PyConfig.orig_argv` and `PyConfig.argv` members of the *Python Initialization Configuration*.

---

**Σημείωση:** It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as `updatepath`, and update `sys.path` themselves if desired. See CVE-2008-5983.

On versions before 3.1.3, you can achieve the same effect by manually popping the first `sys.path` element after having called `PySys_SetArgv()`, for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

---

Νέο στην έκδοση 3.1.3.

Αποσύρθηκε στην έκδοση 3.11.

void **PySys\_SetArgv** (int argc, wchar\_t \*\*argv)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.argv` and `PyConfig.parse_argv` should be used instead, see *Python Initialization Configuration*.

This function works like `PySys_SetArgvEx()` with `updatepath` set to 1 unless the **python** interpreter was started with the `-I`.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

See also `PyConfig.orig_argv` and `PyConfig.argv` members of the *Python Initialization Configuration*.

Άλλαξε στην έκδοση 3.4: The `updatepath` value depends on `-I`.

Αποσύρθηκε στην έκδοση 3.11.

void **Py\_SetPythonHome** (const wchar\_t \*home)

*Μέρος του Σταθερό ABI.* This API is kept for backward compatibility: setting `PyConfig.home` should be used instead, see *Python Initialization Configuration*.

Set the default «home» directory, that is, the location of the standard Python libraries. See `PYTHONHOME` for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

Αποσύρθηκε στην έκδοση 3.11.

wchar\_t \***Py\_GetPythonHome** ()

*Μέρος του Σταθερό ABI.* Return the default «home», that is, the value set by a previous call to `Py_SetPythonHome()`, or the value of the `PYTHONHOME` environment variable if it is set.

This function should not be called before `Py_Initialize()`, otherwise it returns `NULL`.

Αλλάξε στην έκδοση 3.10: It now returns NULL if called before `Py_Initialize()`.

## 9.5 Thread State and the Global Interpreter Lock

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see `sys.setswitchinterval()`). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called *PyThreadState*. There's also one global variable pointing to the current *PyThreadState*: it can be retrieved using `PyThreadState_Get()`.

### 9.5.1 Releasing the GIL from extension code

Most extension code manipulating the *GIL* has the following simple structure:

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The `Py_BEGIN_ALLOW_THREADS` macro opens a new block and declares a hidden local variable; the `Py_END_ALLOW_THREADS` macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

**Σημείωση:** Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard `zlib` and `hashlib` modules release the GIL when compressing or hashing data.



### 9.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the `threading` module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The `PyGILState_Ensure()` and `PyGILState_Release()` functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the `PyGILState_*` functions assume there is only one global interpreter (created automatically by `Py_Initialize()`). Python supports the creation of additional interpreters (using `Py_NewInterpreter()`), but mixing multiple interpreters and the `PyGILState_*` API is unsupported.

### 9.5.3 Cautions about `fork()`

Another important thing to note about threads is their behaviour in the face of the C `fork()` call. On most systems with `fork()`, after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the «current» thread remains means any locks held by other threads will never be released. Python solves this for `os.fork()` by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as `pthread_atfork()` would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling `fork()` directly rather than through `os.fork()` (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork. `PyOS_AfterFork_Child()` tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which `os.fork()` does. This means finalizing all other `PyThreadState` objects belonging to the current interpreter and all other `PyInterpreterState` objects. Due to this and the special nature of the «main» interpreter, `fork()` should only be called in that interpreter's «main» thread, where the CPython global runtime was originally initialized. The only exception is if `exec()` will be called immediately after.



## 9.5.4 High-level API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

type **PyInterpreterState**

*Μέρος του Περιορισμένο API (ως μια αδιαφανής κατασκευή).* This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

type **PyThreadState**

*Μέρος του Περιορισμένο API (ως μια αδιαφανής κατασκευή).* This data structure represents the state of a single thread. The only public data member is:

*PyInterpreterState* \*interp

This thread's interpreter state.

void **PyEval\_InitThreads** ()

*Μέρος του Σταθερό ABI.* Deprecated function which does nothing.

In Python 3.6 and older, this function created the GIL if it didn't exist.

Άλλαξε στην έκδοση 3.9: The function now does nothing.

Άλλαξε στην έκδοση 3.7: This function is now called by *Py\_Initialize* (), so you don't have to call it yourself anymore.

Άλλαξε στην έκδοση 3.2: This function cannot be called before *Py\_Initialize* () anymore.

Αποσύρθηκε στην έκδοση 3.9.

int **PyEval\_ThreadsInitialized** ()

*Μέρος του Σταθερό ABI.* Returns a non-zero value if *PyEval\_InitThreads* () has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

Άλλαξε στην έκδοση 3.7: The *GIL* is now initialized by *Py\_Initialize* ().

Αποσύρθηκε στην έκδοση 3.9.

*PyThreadState* \***PyEval\_SaveThread** ()

*Μέρος του Σταθερό ABI.* Release the global interpreter lock (if it has been created) and reset the thread state to NULL, returning the previous thread state (which is not NULL). If the lock has been created, the current thread must have acquired it.

void **PyEval\_RestoreThread** (*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI.* Acquire the global interpreter lock (if it has been created) and set the thread state to *tstate*, which must not be NULL. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

---

**Σημείωση:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use *\_Py\_IsFinalizing* () or *sys.is\_finalizing* () to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

*PyThreadState* \***PyThreadState\_Get** ()

*Μέρος του Σταθερό ABI.* Return the current thread state. The global interpreter lock must be held. When the current thread state is NULL, this issues a fatal error (so that the caller needn't check for NULL).

*PyThreadState* \***PyThreadState\_Swap** (*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI.* Swap the current thread state with the thread state given by the argument *tstate*, which may be NULL. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

*PyGILState\_STATE* **PyGILState\_Ensure** ()

*Μέρος του Σταθερό ABI.* Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the global interpreter lock. This may be called as many times as desired by a thread as long as each call is matched with a call to *PyGILState\_Release* (). In general, other thread-related APIs may be used between *PyGILState\_Ensure* () and *PyGILState\_Release* () calls as long as the thread state is restored to its previous state before the *Release* (). For example, normal usage of the *Py\_BEGIN\_ALLOW\_THREADS* and *Py\_END\_ALLOW\_THREADS* macros is acceptable.

The return value is an opaque «handle» to the thread state when *PyGILState\_Ensure* () was called, and must be passed to *PyGILState\_Release* () to ensure Python is left in the same state. Even though recursive calls are allowed, these handles *cannot* be shared - each unique call to *PyGILState\_Ensure* () must save the handle for its call to *PyGILState\_Release* ().

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

---

**Σημείωση:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use *\_Py\_IsFinalizing* () or *sys.is\_finalizing* () to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

void **PyGILState\_Release** (*PyGILState\_STATE*)

*Μέρος του Σταθερό ABI.* Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding *PyGILState\_Ensure* () call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to *PyGILState\_Ensure* () must be matched by a call to *PyGILState\_Release* () on the same thread.

*PyThreadState* \***PyGILState\_GetThisThreadState** ()

*Μέρος του Σταθερό ABI.* Get the current thread state for this thread. May return NULL if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

int **PyGILState\_Check** ()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

Νέο στην έκδοση 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

**Py\_BEGIN\_ALLOW\_THREADS**

*Μέρος του Σταθερό ABI.* This macro expands to { *PyThreadState* \*\_save; \_save = *PyEval\_SaveThread* (); . Note that it contains an opening brace; it must be matched with a following *Py\_END\_ALLOW\_THREADS* macro. See above for further discussion of this macro.

**Py\_END\_ALLOW\_THREADS**

*Μέρος του Σταθερό ABI.* This macro expands to *PyEval\_RestoreThread* (\_save); }. Note that it contains a closing brace; it must be matched with an earlier *Py\_BEGIN\_ALLOW\_THREADS* macro. See above for further discussion of this macro.

**Py\_BLOCK\_THREADS**

*Μέρος του Σταθερό ABI.* This macro expands to `PyEval_RestoreThread(_save)`; it is equivalent to `Py_END_ALLOW_THREADS` without the closing brace.

**Py\_UNBLOCK\_THREADS**

*Μέρος του Σταθερό ABI.* This macro expands to `_save = PyEval_SaveThread()`; it is equivalent to `Py_BEGIN_ALLOW_THREADS` without the opening brace and variable declaration.

**9.5.5 Low-level API**

All of the following functions must be called after `Py_Initialize()`.

Αλλάξε στην έκδοση 3.7: `Py_Initialize()` now initializes the *GIL*.

*PyInterpreterState* \***PyInterpreterState\_New**()

*Μέρος του Σταθερό ABI.* Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Raises an auditing event `cpython.PyInterpreterState_New` with no arguments.

void **PyInterpreterState\_Clear**(*PyInterpreterState* \*interp)

*Μέρος του Σταθερό ABI.* Reset all information in an interpreter state object. The global interpreter lock must be held.

Raises an auditing event `cpython.PyInterpreterState_Clear` with no arguments.

void **PyInterpreterState\_Delete**(*PyInterpreterState* \*interp)

*Μέρος του Σταθερό ABI.* Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to `PyInterpreterState_Clear()`.

*PyThreadState* \***PyThreadState\_New**(*PyInterpreterState* \*interp)

*Μέρος του Σταθερό ABI.* Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

void **PyThreadState\_Clear**(*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI.* Reset all information in a thread state object. The global interpreter lock must be held.

Αλλάξε στην έκδοση 3.9: This function now calls the `PyThreadState.on_delete` callback. Previously, that happened in `PyThreadState_Delete()`.

void **PyThreadState\_Delete**(*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI.* Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to `PyThreadState_Clear()`.

void **PyThreadState\_DeleteCurrent**(void)

Destroy the current thread state and release the global interpreter lock. Like `PyThreadState_Delete()`, the global interpreter lock need not be held. The thread state must have been reset with a previous call to `PyThreadState_Clear()`.

*PyFrameObject* \***PyThreadState\_GetFrame**(*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Get the current frame of the Python thread state *tstate*.

Return a *strong reference*. Return NULL if no frame is currently executing.

See also `PyEval_GetFrame()`.

*tstate* must not be NULL.

Νέο στην έκδοση 3.9.

`uint64_t PyThreadState_GetID (PyThreadState *tstate)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Get the unique thread state identifier of the Python thread state *tstate*.

*tstate* must not be NULL.

Νέο στην έκδοση 3.9.

`PyInterpreterState *PyThreadState_GetInterpreter (PyThreadState *tstate)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Get the interpreter of the Python thread state *tstate*.

*tstate* must not be NULL.

Νέο στην έκδοση 3.9.

`void PyThreadState_EnterTracing (PyThreadState *tstate)`

Suspend tracing and profiling in the Python thread state *tstate*.

Resume them using the `PyThreadState_LeaveTracing()` function.

Νέο στην έκδοση 3.11.

`void PyThreadState_LeaveTracing (PyThreadState *tstate)`

Resume tracing and profiling in the Python thread state *tstate* suspended by the `PyThreadState_EnterTracing()` function.

See also `PyEval_SetTrace()` and `PyEval_SetProfile()` functions.

Νέο στην έκδοση 3.11.

`PyInterpreterState *PyInterpreterState_Get (void)`

Μέρος του Σταθερό ABI από την έκδοση 3.9. Get the current interpreter.

Issue a fatal error if there no current Python thread state or no current interpreter. It cannot return NULL.

The caller must hold the GIL.

Νέο στην έκδοση 3.9.

`int64_t PyInterpreterState_GetID (PyInterpreterState *interp)`

Μέρος του Σταθερό ABI από την έκδοση 3.7. Return the interpreter's unique ID. If there was any error in doing so then `-1` is returned and an error is set.

The caller must hold the GIL.

Νέο στην έκδοση 3.7.

`PyObject *PyInterpreterState_GetDict (PyInterpreterState *interp)`

Μέρος του Σταθερό ABI από την έκδοση 3.8. Return a dictionary in which interpreter-specific data may be stored. If this function returns NULL then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for `PyModule_GetState()`, which extensions should use to store interpreter-specific state information.

Νέο στην έκδοση 3.8.

`typedef PyObject *(*_PyFrameEvalFunction)(PyThreadState *tstate, _PyInterpreterFrame *frame, int throwflag)`

Type of a frame evaluation function.

The *throwflag* parameter is used by the `throw()` method of generators: if non-zero, handle the current exception.

Άλλαξε στην έκδοση 3.9: The function now takes a *tstate* parameter.

Άλλαξε στην έκδοση 3.11: The *frame* parameter changed from `PyFrameObject*` to `_PyInterpreterFrame*`.

---

`_PyFrameEvalFunction _PyInterpreterState_GetEvalFrameFunc (PyInterpreterState *interp)`

Get the frame evaluation function.

See the [PEP 523](#) «Adding a frame evaluation API to CPython».

Νέο στην έκδοση 3.9.

`void _PyInterpreterState_SetEvalFrameFunc (PyInterpreterState *interp, _PyFrameEvalFunction eval_frame)`

Set the frame evaluation function.

See the [PEP 523](#) «Adding a frame evaluation API to CPython».

Νέο στην έκδοση 3.9.

`PyObject *PyThreadState_GetDict ()`

*Επιστρεφόμενη τιμή: Borrowed reference. Μέρος του Σταθερό ABI.* Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

`int PyThreadState_SetAsyncExc (unsigned long id, PyObject *exc)`

*Μέρος του Σταθερό ABI.* Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

Άλλαξε στην έκδοση 3.7: The type of the *id* parameter changed from long to unsigned long.

`void PyEval_AcquireThread (PyThreadState *tstate)`

*Μέρος του Σταθερό ABI.* Acquire the global interpreter lock and set the current thread state to *tstate*, which must not be NULL. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

---

**Σημείωση:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use `_Py_IsFinalizing()` or `sys.is_finalizing()` to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

Άλλαξε στην έκδοση 3.8: Updated to be consistent with `PyEval_RestoreThread()`, `Py_END_ALLOW_THREADS()`, and `PyGILState_Ensure()`, and terminate the current thread if called while the interpreter is finalizing.

`PyEval_RestoreThread()` is a higher-level function which is always available (even when threads have not been initialized).

`void PyEval_ReleaseThread (PyThreadState *tstate)`

*Μέρος του Σταθερό ABI.* Reset the current thread state to NULL and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be NULL, is only used to check that it represents the current thread state — if it isn't, a fatal error is reported.

`PyEval_SaveThread()` is a higher-level function which is always available (even when threads have not been initialized).

`void PyEval_AcquireLock ()`

*Μέρος του Σταθερό ABI.* Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

Αποσύρθηκε στην έκδοση 3.2: This function does not update the current thread state. Please use `PyEval_RestoreThread()` or `PyEval_AcquireThread()` instead.

**Σημείωση:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use `_Py_IsFinalizing()` or `sys.is_finalizing()` to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

Άλλαξε στην έκδοση 3.8: Updated to be consistent with `PyEval_RestoreThread()`, `Py_END_ALLOW_THREADS()`, and `PyGILState_Ensure()`, and terminate the current thread if called while the interpreter is finalizing.

void **PyEval\_ReleaseLock** ()

*Μέρος του Σταθερό ABI.* Release the global interpreter lock. The lock must have been created earlier.

Αποσύρθηκε στην έκδοση 3.2: This function does not update the current thread state. Please use `PyEval_SaveThread()` or `PyEval_ReleaseThread()` instead.

## 9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The «main» interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The `PyInterpreterState_Main()` function returns a pointer to its state.

You can switch between sub-interpreters using the `PyThreadState_Swap()` function. You can create and destroy them using the following functions:

`PyThreadState *Py_NewInterpreter` ()

*Μέρος του Σταθερό ABI.* Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules `builtins`, `__main__` and `sys`. The table of loaded modules (`sys.modules`) and the module search path (`sys.path`) are also separate. The new environment has no `sys.argv` variable. It has new standard I/O stream file objects `sys.stdin`, `sys.stdout` and `sys.stderr` (however these refer to the same underlying file descriptors).

The return value points to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, `NULL` is returned; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state. (Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns; however, unlike most other Python/C API functions, there needn't be a current thread state on entry.)

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. `PyModule_FromDefAndSpec()`, a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g. `PyModule_Create()`, the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's `init` function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see *Bugs and caveats* below).

Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling `Py_FinalizeEx()` and `Py_Initialize()`; in that case, the



extension's `initmodule` function is called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

void **Py\_EndInterpreter** (*PyThreadState* \*tstate)

*Μέρος του Σταθερό ABI.* Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is `NULL`. All thread states associated with this interpreter are destroyed. (The global interpreter lock must be held before calling this function and is still held when it returns.) *Py\_FinalizeEx()* will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

## 9.6.1 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect — for example, using low-level file operations like `os.close()` they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with `PyGILState_*` APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching *PyGILState\_Ensure()* and *PyGILState\_Release()* calls. Furthermore, extensions (such as `ctypes`) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

## 9.7 Asynchronous Notifications

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int **Py\_AddPendingCall** (int (\*func)(void\*), void \*arg)

*Μέρος του Σταθερό ABI.* Schedule a function to be called from the main interpreter thread. On success, 0 is returned and *func* is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

- on a *bytecode* boundary;
- with the main thread holding the *global interpreter lock* (*func* can therefore use the full C API).

*func* must return 0 on success, or -1 on failure with an exception set. *func* won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

To call this function in a subinterpreter, the caller must hold the GIL. Otherwise, the function *func* can be scheduled to be called from the wrong interpreter.



**Προειδοποίηση:** This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the [PyGILState API](#).

Νέο στην έκδοση 3.1.

Αλλάξε στην έκδοση 3.9: If this function is called in a subinterpreter, the function *func* is now scheduled to be called from the subinterpreter, rather than being called from the main interpreter. Each subinterpreter now has its own list of scheduled calls.

## 9.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

typedef int (**Py\_tracefunc**)(PyObject \*obj, PyFrameObject \*frame, int what, PyObject \*arg)

The type of the trace function registered using `PyEval_SetProfile()` and `PyEval_SetTrace()`. The first parameter is the object passed to the registration function as *obj*, *frame* is the frame object to which the event pertains, *what* is one of the constants `PyTrace_CALL`, `PyTrace_EXCEPTION`, `PyTrace_LINE`, `PyTrace_RETURN`, `PyTrace_C_CALL`, `PyTrace_C_EXCEPTION`, `PyTrace_C_RETURN`, or `PyTrace_OPCODE`, and *arg* depends on the value of *what*:

Value of <i>what</i>	Meaning of <i>arg</i>
<code>PyTrace_CALL</code>	Always <code>Py_None</code> .
<code>PyTrace_EXCEPTION</code>	Exception information as returned by <code>sys.exc_info()</code> .
<code>PyTrace_LINE</code>	Always <code>Py_None</code> .
<code>PyTrace_RETURN</code>	Value being returned to the caller, or <code>NULL</code> if caused by an exception.
<code>PyTrace_C_CALL</code>	Function object being called.
<code>PyTrace_C_EXCEPTION</code>	Function object being called.
<code>PyTrace_C_RETURN</code>	Function object being called.
<code>PyTrace_OPCODE</code>	Always <code>Py_None</code> .

### int `PyTrace_CALL`

The value of the *what* parameter to a `Py_tracefunc` function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

### int `PyTrace_EXCEPTION`

The value of the *what* parameter to a `Py_tracefunc` function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

### int `PyTrace_LINE`

The value passed as the *what* parameter to a `Py_tracefunc` function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting `f_trace_lines` to 0 on that frame.

int **PyTrace\_RETURN**

The value for the *what* parameter to *Py\_tracefunc* functions when a call is about to return.

int **PyTrace\_C\_CALL**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function is about to be called.

int **PyTrace\_C\_EXCEPTION**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function has raised an exception.

int **PyTrace\_C\_RETURN**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function has returned.

int **PyTrace\_OPCODE**

The value for the *what* parameter to *Py\_tracefunc* functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting *f\_trace\_opcodes* to 1 on the frame.

void **PyEval\_SetProfile** (*Py\_tracefunc* func, *PyObject* \*obj)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or NULL. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except *PyTrace\_LINE*, *PyTrace\_OPCODE* and *PyTrace\_EXCEPTION*.

See also the `sys.setprofile()` function.

The caller must hold the *GIL*.

void **PyEval\_SetTrace** (*Py\_tracefunc* func, *PyObject* \*obj)

Set the tracing function to *func*. This is similar to *PyEval\_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval\_SetTrace()* will not receive *PyTrace\_C\_CALL*, *PyTrace\_C\_EXCEPTION* or *PyTrace\_C\_RETURN* as a value for the *what* parameter.

See also the `sys.settrace()` function.

The caller must hold the *GIL*.

## 9.9 Advanced Debugger Support

These functions are only intended to be used by advanced debugging tools.

*PyInterpreterState* \***PyInterpreterState\_Head** ()

Return the interpreter state object at the head of the list of all such objects.

*PyInterpreterState* \***PyInterpreterState\_Main** ()

Return the main interpreter state object.

*PyInterpreterState* \***PyInterpreterState\_Next** (*PyInterpreterState* \*interp)

Return the next interpreter state object after *interp* from the list of all such objects.

*PyThreadState* \***PyInterpreterState\_ThreadHead** (*PyInterpreterState* \*interp)

Return the pointer to the first *PyThreadState* object in the list of threads associated with the interpreter *interp*.

*PyThreadState* \***PyThreadState\_Next** (*PyThreadState* \*tstate)

Return the next thread state object after *tstate* from the list of all such objects belonging to the same *PyInterpreterState* object.

## 9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (`threading.local`). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a `void*` value per thread.

The GIL does *not* need to be held when calling these functions; they supply their own locking.

Note that `Python.h` does not include the declaration of the TLS APIs, you need to include `pythread.h` to use thread-local storage.

---

**Σημείωση:** None of these API functions handle memory management on behalf of the `void*` values. You need to allocate and deallocate them yourself. If the `void*` values happen to be `PyObject*`, these functions don't do refcount operations on them either.

---

### 9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type `Py_tss_t` instead of `int` to represent thread keys.

Νέο στην έκδοση 3.7.

**Δείτε επίσης:**

«A New C-API for Thread-Local Storage in CPython» ([PEP 539](#))

type `Py_tss_t`

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure.

When `Py_LIMITED_API` is not defined, static allocation of this type by `Py_tss_NEEDS_INIT` is allowed.

`Py_tss_NEEDS_INIT`

This macro expands to the initializer for `Py_tss_t` variables. Note that this macro won't be defined with `Py_LIMITED_API`.

### Dynamic Allocation

Dynamic allocation of the `Py_tss_t`, required in extension modules built with `Py_LIMITED_API`, where static allocation of this type is not possible due to its implementation being opaque at build time.

`Py_tss_t *PyThread_tss_alloc()`

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return a value which is the same state as a value initialized with `Py_tss_NEEDS_INIT`, or NULL in the case of dynamic allocation failure.

void `PyThread_tss_free(Py_tss_t *key)`

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Free the given `key` allocated by `PyThread_tss_alloc()`, after first calling `PyThread_tss_delete()` to ensure any associated thread locals have been unassigned. This is a no-op if the `key` argument is NULL.

---

**Σημείωση:** A freed key becomes a dangling pointer. You should reset the key to NULL.

---

## Methods

The parameter *key* of these functions must not be `NULL`. Moreover, the behaviors of `PyThread_tss_set()` and `PyThread_tss_get()` are undefined if the given `Py_tss_t` has not been initialized by `PyThread_tss_create()`.

int **PyThread\_tss\_is\_created** (`Py_tss_t` \*key)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return a non-zero value if the given `Py_tss_t` has been initialized by `PyThread_tss_create()`.

int **PyThread\_tss\_create** (`Py_tss_t` \*key)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the *key* argument is not initialized by `Py_tss_NEEDS_INIT`. This function can be called repeatedly on the same key – calling it on an already initialized key is a no-op and immediately returns success.

void **PyThread\_tss\_delete** (`Py_tss_t` \*key)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by `PyThread_tss_create()`. This function can be called repeatedly on the same key – calling it on an already destroyed key is a no-op.

int **PyThread\_tss\_set** (`Py_tss_t` \*key, void \*value)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return a zero value to indicate successfully associating a `void*` value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a `void*` value.

void \***PyThread\_tss\_get** (`Py_tss_t` \*key)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Return the `void*` value associated with a TSS key in the current thread. This returns `NULL` if no value is associated with the key in the current thread.

## 9.10.2 Thread Local Storage (TLS) API

Αποσύρθηκε στην έκδοση 3.7: This API is superseded by *Thread Specific Storage (TSS) API*.

---

**Σημείωση:** This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to `int`. On such platforms, `PyThread_create_key()` will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

---

Due to the compatibility problem noted above, this version of the API should not be used in new code.

int **PyThread\_create\_key** ()

*Μέρος του Σταθερό ABI.*

void **PyThread\_delete\_key** (int key)

*Μέρος του Σταθερό ABI.*

int **PyThread\_set\_key\_value** (int key, void \*value)

*Μέρος του Σταθερό ABI.*

void \***PyThread\_get\_key\_value** (int key)

*Μέρος του Σταθερό ABI.*

void **PyThread\_delete\_key\_value** (int key)

*Μέρος του Σταθερό ABI.*

void **PyThread\_ReInitTLS** ()

*Μέρος του Σταθερό ABI.*



---

## Python Initialization Configuration

---

Νέο στην έκδοση 3.8.

Python can be initialized with `Py_InitializeFromConfig()` and the `PyConfig` structure. It can be preinitialized with `Py_PreInitialize()` and the `PyPreConfig` structure.

There are two kinds of configuration:

- The *Python Configuration* can be used to build a customized Python which behaves as the regular Python. For example, environment variables and command line arguments are used to configure Python.
- The *Isolated Configuration* can be used to embed Python into an application. It isolates Python from the system. For example, environment variables are ignored, the LC\_CTYPE locale is left unchanged and no signal handler is registered.

The `Py_RunMain()` function can be used to write a customized Python program.

See also *Initialization, Finalization, and Threads*.

**Δείτε επίσης:**

**PEP 587** «Python Initialization Configuration».

### 10.1 Example

Example of customized Python always running in isolated mode:

```
int main(int argc, char **argv)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config.isolated = 1;

    /* Decode command line arguments.
       Implicitly preinitialize Python (in isolated mode). */
    status = PyConfig_SetBytesArgv(&config, argc, argv);
    if (PyStatus_Exception(status)) {
        goto exception;
    }
}
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```
}

status = Py_InitializeFromConfig(&config);
if (PyStatus_Exception(status)) {
    goto exception;
}
PyConfig_Clear(&config);

return Py_RunMain();

exception:
PyConfig_Clear(&config);
if (PyStatus_IsExit(status)) {
    return status.exitcode;
}
/* Display the error message and exit the process with
   non-zero exit code */
Py_ExitStatusException(status);
}
```

## 10.2 PyWideStringList

type **PyWideStringList**

List of `wchar_t*` strings.

If *length* is non-zero, *items* must be non-NULL and all strings must be non-NULL.

Methods:

*PyStatus* **PyWideStringList\_Append** (*PyWideStringList* \*list, const `wchar_t` \*item)

Append *item* to *list*.

Python must be preinitialized to call this function.

*PyStatus* **PyWideStringList\_Insert** (*PyWideStringList* \*list, *Py\_ssize\_t* index, const `wchar_t` \*item)

Insert *item* into *list* at *index*.

If *index* is greater than or equal to *list* length, append *item* to *list*.

*index* must be greater than or equal to 0.

Python must be preinitialized to call this function.

Structure fields:

*Py\_ssize\_t* **length**

List length.

`wchar_t` \*\***items**

List items.



## 10.3 PyStatus

type **PyStatus**

Structure to store an initialization function status: success, error or exit.

For an error, it can store the C function name which created the error.

Structure fields:

int **exitcode**

Exit code. Argument passed to `exit()`.

const char \***err\_msg**

Error message.

const char \***func**

Name of the function which created an error, can be NULL.

Functions to create a status:

*PyStatus* **PyStatus\_Ok** (void)

Success.

*PyStatus* **PyStatus\_Error** (const char \*err\_msg)

Initialization error with a message.

*err\_msg* must not be NULL.

*PyStatus* **PyStatus\_NoMemory** (void)

Memory allocation failure (out of memory).

*PyStatus* **PyStatus\_Exit** (int exitcode)

Exit Python with the specified exit code.

Functions to handle a status:

int **PyStatus\_Exception** (*PyStatus* status)

Is the status an error or an exit? If true, the exception must be handled; by calling *Py\_ExitStatusException()* for example.

int **PyStatus\_IsError** (*PyStatus* status)

Is the result an error?

int **PyStatus\_IsExit** (*PyStatus* status)

Is the result an exit?

void **Py\_ExitStatusException** (*PyStatus* status)

Call `exit(exitcode)` if *status* is an exit. Print the error message and exit with a non-zero exit code if *status* is an error. Must only be called if `PyStatus_Exception(status)` is non-zero.

---

**Σημείωση:** Internally, Python uses macros which set `PyStatus.func`, whereas functions to create a status set `func` to NULL.

---

Example:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
}
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

    return PyStatus_Ok();
}

int main(int argc, char **argv)
{
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
    PyMem_Free(ptr);
    return 0;
}

```

## 10.4 PyPreConfig

type **PyPreConfig**

Structure used to preinitialize Python.

Function to initialize a preconfiguration:

void **PyPreConfig\_InitPythonConfig** (*PyPreConfig* \*preconfig)

Initialize the preconfiguration with *Python Configuration*.

void **PyPreConfig\_InitIsolatedConfig** (*PyPreConfig* \*preconfig)

Initialize the preconfiguration with *Isolated Configuration*.

Structure fields:

int **allocator**

Name of the Python memory allocators:

- PYMEM\_ALLOCATOR\_NOT\_SET (0): don't change memory allocators (use defaults).
- PYMEM\_ALLOCATOR\_DEFAULT (1): *default memory allocators*.
- PYMEM\_ALLOCATOR\_DEBUG (2): *default memory allocators with debug hooks*.
- PYMEM\_ALLOCATOR\_MALLOC (3): use `malloc()` of the C library.
- PYMEM\_ALLOCATOR\_MALLOC\_DEBUG (4): force usage of `malloc()` with *debug hooks*.
- PYMEM\_ALLOCATOR\_PYMALLOC (5): *Python pymalloc memory allocator*.
- PYMEM\_ALLOCATOR\_PYMALLOC\_DEBUG (6): *Python pymalloc memory allocator with debug hooks*.

PYMEM\_ALLOCATOR\_PYMALLOC and PYMEM\_ALLOCATOR\_PYMALLOC\_DEBUG are not supported if Python is configured using `--without-pymalloc`.

See *Memory Management*.

Default: PYMEM\_ALLOCATOR\_NOT\_SET.

int **configure\_locale**

Set the LC\_CTYPE locale to the user preferred locale.

If equals to 0, set *coerce\_c\_locale* and *coerce\_c\_locale\_warn* members to 0.

See the *locale encoding*.

Default: 1 in Python config, 0 in isolated config.

**int `coerce_c_locale`**

If equals to 2, coerce the C locale.

If equals to 1, read the LC\_CTYPE locale to decide if it should be coerced.

See the *locale encoding*.

Default: -1 in Python config, 0 in isolated config.

**int `coerce_c_locale_warn`**

If non-zero, emit a warning if the C locale is coerced.

Default: -1 in Python config, 0 in isolated config.

**int `dev_mode`**

Python Development Mode: see *PyConfig.dev\_mode*.

Default: -1 in Python mode, 0 in isolated mode.

**int `isolated`**

Isolated mode: see *PyConfig.isolated*.

Default: 0 in Python mode, 1 in isolated mode.

**int `legacy_windows_fs_encoding`**

If non-zero:

- Set *PyPreConfig.utf8\_mode* to 0,
- Set *PyConfig.filesystem\_encoding* to "mbcs",
- Set *PyConfig.filesystem\_errors* to "replace".

Initialized the from PYTHONLEGACYWINDOWSFSENCODING environment variable value.

Only available on Windows. `#ifdef MS_WINDOWS` macro can be used for Windows specific code.

Default: 0.

**int `parse_argv`**

If non-zero, *Py\_PreInitializeFromArgs()* and *Py\_PreInitializeFromBytesArgs()* parse their `argv` argument the same way the regular Python parses command line arguments: see Command Line Arguments.

Default: 1 in Python config, 0 in isolated config.

**int `use_environment`**

Use environment variables? See *PyConfig.use\_environment*.

Default: 1 in Python config and 0 in isolated config.

**int `utf8_mode`**

If non-zero, enable the Python UTF-8 Mode.

Set to 0 or 1 by the `-X utf8` command line option and the PYTHONUTF8 environment variable.

Also set to 1 if the LC\_CTYPE locale is C or POSIX.

Default: -1 in Python config and 0 in isolated config.

## 10.5 Preinitialize Python with PyPreConfig

The preinitialization of Python:

- Set the Python memory allocators (*PyPreConfig*.*allocator*)
- Configure the LC\_CTYPE locale (*locale encoding*)
- Set the Python UTF-8 Mode (*PyPreConfig*.*utf8\_mode*)

The current preconfiguration (*PyPreConfig* type) is stored in *\_PyRuntime.preconfig*.

Functions to preinitialize Python:

*PyStatus* **Py\_PreInitialize** (const *PyPreConfig* \*preconfig)

Preinitialize Python from *preconfig* preconfiguration.

*preconfig* must not be NULL.

*PyStatus* **Py\_PreInitializeFromBytesArgs** (const *PyPreConfig* \*preconfig, int argc, char \*const \*argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (bytes strings) if *parse\_argv* of *preconfig* is non-zero.

*preconfig* must not be NULL.

*PyStatus* **Py\_PreInitializeFromArgs** (const *PyPreConfig* \*preconfig, int argc, wchar\_t \*const \*argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (wide strings) if *parse\_argv* of *preconfig* is non-zero.

*preconfig* must not be NULL.

The caller is responsible to handle exceptions (error or exit) using *PyStatus\_Exception()* and *Py\_ExitStatusException()*.

For *Python Configuration* (*PyPreConfig\_InitPythonConfig()*), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the `-X utf8` command line option enables the Python UTF-8 Mode.

*PyMem\_SetAllocator()* can be called after *Py\_PreInitialize()* and before *Py\_InitializeFromConfig()* to install a custom memory allocator. It can be called before *Py\_PreInitialize()* if *PyPreConfig.allocator* is set to *PYMEM\_ALLOCATOR\_NOT\_SET*.

Python memory allocation functions like *PyMem\_RawMalloc()* must not be used before the Python preinitialization, whereas calling directly *malloc()* and *free()* is always safe. *Py\_DecodeLocale()* must not be called before the Python preinitialization.

Example using the preinitialization to enable the Python UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}

/* at this point, Python speaks UTF-8 */

Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

## 10.6 PyConfig

type **PyConfig**

Structure containing most parameters to configure Python.

When done, the `PyConfig_Clear()` function must be used to release the configuration memory.

Structure methods:

void **PyConfig\_InitPythonConfig** (*PyConfig* \*config)

Initialize configuration with the *Python Configuration*.

void **PyConfig\_InitIsolatedConfig** (*PyConfig* \*config)

Initialize configuration with the *Isolated Configuration*.

*PyStatus* **PyConfig\_SetString** (*PyConfig* \*config, wchar\_t \*const \*config\_str, const wchar\_t \*str)

Copy the wide character string *str* into \*config\_str.

*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetBytesString** (*PyConfig* \*config, wchar\_t \*const \*config\_str, const char \*str)

Decode *str* using `Py_DecodeLocale()` and set the result into \*config\_str.

*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetArgv** (*PyConfig* \*config, int argc, wchar\_t \*const \*argv)

Set command line arguments (*argv* member of *config*) from the *argv* list of wide character strings.

*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetBytesArgv** (*PyConfig* \*config, int argc, char \*const \*argv)

Set command line arguments (*argv* member of *config*) from the *argv* list of bytes strings. Decode bytes using `Py_DecodeLocale()`.

*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetWideStringList** (*PyConfig* \*config, *PyWideStringList* \*list, *Py\_ssize\_t* length, wchar\_t \*\*items)

Set the list of wide strings *list* to *length* and *items*.

*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_Read** (*PyConfig* \*config)

Read all Python configuration.

Fields which are already initialized are left unchanged.

Fields for *path configuration* are no longer calculated or modified when calling this function, as of Python 3.11.

The `PyConfig_Read()` function only parses `PyConfig.argv` arguments once: `PyConfig.parse_argv` is set to 2 after arguments are parsed. Since Python arguments are stripped from `PyConfig.argv`, parsing arguments twice would parse the application options as Python options.

*Preinitialize Python* if needed.

Αλλάξε στην έκδοση 3.10: The `PyConfig.argv` arguments are now only parsed once, `PyConfig.parse_argv` is set to 2 after arguments are parsed, and arguments are only parsed if `PyConfig.parse_argv` equals 1.

Αλλάξε στην έκδοση 3.11: `PyConfig_Read()` no longer calculates all paths, and so fields listed under *Python Path Configuration* may no longer be updated until `Py_InitializeFromConfig()` is called.

void **PyConfig\_Clear** (*PyConfig* \*config)

Release configuration memory.

Most *PyConfig* methods *preinitialize Python* if needed. In that case, the Python preinitialization configuration (*PyPreConfig*) is based on the *PyConfig*. If configuration fields which are in common with *PyPreConfig* are tuned, they must be set before calling a *PyConfig* method:

- *PyConfig.dev\_mode*
- *PyConfig.isolated*
- *PyConfig.parse\_argv*
- *PyConfig.use\_environment*

Moreover, if *PyConfig\_SetArgv()* or *PyConfig\_SetBytesArgv()* is used, this method must be called before other methods, since the preinitialization configuration depends on command line arguments (if *parse\_argv* is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using *PyStatus\_Exception()* and *Py\_ExitStatusException()*.

Structure fields:

*PyWideStringList* **argv**

Command line arguments: `sys.argv`.

Set *parse\_argv* to 1 to parse *argv* the same way the regular Python parses Python command line arguments and then to strip Python arguments from *argv*.

If *argv* is empty, an empty string is added to ensure that `sys.argv` always exists and is never empty.

Default: NULL.

See also the *orig\_argv* member.

int **safe\_path**

If equals to zero, *Py\_RunMain()* prepends a potentially unsafe path to `sys.path` at startup:

- If *argv[0]* is equal to `L"-m"` (`python -m module`), prepend the current working directory.
- If running a script (`python script.py`), prepend the script's directory. If it's a symbolic link, resolve symbolic links.
- Otherwise (`python -c code` and `python`), prepend an empty string, which means the current working directory.

Set to 1 by the `-P` command line option and the `PYTHONSAFEPATH` environment variable.

Default: 0 in Python config, 1 in isolated config.

Νέο στην έκδοση 3.11.

wchar\_t \***base\_exec\_prefix**

`sys.base_exec_prefix`.

Default: NULL.

Part of the *Python Path Configuration* output.

wchar\_t \***base\_executable**

Python base executable: `sys._base_executable`.

Set by the `__PYENVN__LAUNCHER__` environment variable.

Set from *PyConfig.executable* if NULL.

Default: NULL.

Part of the *Python Path Configuration* output.

wchar\_t \***base\_prefix**  
 sys.base\_prefix.

Default: NULL.

Part of the *Python Path Configuration* output.

int **buffered\_stdio**

If equals to 0 and *configure\_c\_stdio* is non-zero, disable buffering on the C streams stdout and stderr.

Set to 0 by the `-u` command line option and the PYTHONUNBUFFERED environment variable.

stdin is always opened in buffered mode.

Default: 1.

int **bytes\_warning**

If equals to 1, issue a warning when comparing bytes or bytearray with str, or comparing bytes with int.

If equal or greater to 2, raise a BytesWarning exception in these cases.

Incremented by the `-b` command line option.

Default: 0.

int **warn\_default\_encoding**

If non-zero, emit a EncodingWarning warning when io.TextIOWrapper uses its default encoding. See io-encoding-warning for details.

Default: 0.

Νέο στην έκδοση 3.10.

int **code\_debug\_ranges**

If equals to 0, disables the inclusion of the end line and column mappings in code objects. Also disables traceback printing carets to specific error locations.

Set to 0 by the PYTHONNODEBUGRANGES environment variable and by the `-X no_debug_ranges` command line option.

Default: 1.

Νέο στην έκδοση 3.11.

wchar\_t \***check\_hash\_pycs\_mode**

Control the validation behavior of hash-based .pyc files: value of the `--check-hash-based-pycs` command line option.

Valid values:

- L"always": Hash the source file for invalidation regardless of value of the "check\_source" flag.
- L"never": Assume that hash-based pycs always are valid.
- L"default": The "check\_source" flag in hash-based pycs determines invalidation.

Default: L"default".

See also [PEP 552](#) «Deterministic pycs».

int **configure\_c\_stdio**

If non-zero, configure C standard streams:

- On Windows, set the binary mode (O\_BINARY) on stdin, stdout and stderr.
- If *buffered\_stdio* equals zero, disable buffering of stdin, stdout and stderr streams.
- If *interactive* is non-zero, enable stream buffering on stdin and stdout (only stdout on Windows).



Default: 1 in Python config, 0 in isolated config.

**int `dev_mode`**

If non-zero, enable the Python Development Mode.

Set to 1 by the `-X dev` option and the `PYTHONDEVMODE` environment variable.

Default: -1 in Python mode, 0 in isolated mode.

**int `dump_refs`**

Dump Python references?

If non-zero, dump all objects which are still alive at exit.

Set to 1 by the `PYTHONDUMPREFS` environment variable.

Need a special build of Python with the `Py_TRACE_REFS` macro defined: see the `configure --with-trace-refs` option.

Default: 0.

**wchar\_t \*`exec_prefix`**

The site-specific directory prefix where the platform-dependent Python files are installed: `sys.exec_prefix`.

Default: NULL.

Part of the *Python Path Configuration* output.

**wchar\_t \*`executable`**

The absolute path of the executable binary for the Python interpreter: `sys.executable`.

Default: NULL.

Part of the *Python Path Configuration* output.

**int `faulthandler`**

Enable faulthandler?

If non-zero, call `faulthandler.enable()` at startup.

Set to 1 by `-X faulthandler` and the `PYTHONFAULTHANDLER` environment variable.

Default: -1 in Python mode, 0 in isolated mode.

**wchar\_t \*`filesystem_encoding`**

*Filesystem encoding*: `sys.getfilesystemencoding()`.

On macOS, Android and VxWorks: use "utf-8" by default.

On Windows: use "utf-8" by default, or "mbcs" if *legacy\_windows\_fs\_encoding* of *PyPreConfig* is non-zero.

Default encoding on other platforms:

- "utf-8" if *PyPreConfig.utf8\_mode* is non-zero.
- "ascii" if Python detects that `nl_langinfo(CODESET)` announces the ASCII encoding, whereas the `mbstowcs()` function decodes from a different encoding (usually Latin1).
- "utf-8" if `nl_langinfo(CODESET)` returns an empty string.
- Otherwise, use the *locale encoding*: `nl_langinfo(CODESET)` result.

At Python startup, the encoding name is normalized to the Python codec name. For example, "ANSI\_X3.4-1968" is replaced with "ascii".

See also the *filesystem\_errors* member.

wchar\_t \***filesystem\_errors**

*Filesystem error handler:* `sys.getfilesystemencodeerrors()`.

On Windows: use "surrogatepass" by default, or "replace" if *legacy\_windows\_fs\_encoding* of *PyPreConfig* is non-zero.

On other platforms: use "surrogateescape" by default.

Supported error handlers:

- "strict"
- "surrogateescape"
- "surrogatepass" (only supported with the UTF-8 encoding)

See also the *filesystem\_encoding* member.

unsigned long **hash\_seed**

int **use\_hash\_seed**

Randomized hash function seed.

If *use\_hash\_seed* is zero, a seed is chosen randomly at Python startup, and *hash\_seed* is ignored.

Set by the PYTHONHASHSEED environment variable.

Default *use\_hash\_seed* value: -1 in Python mode, 0 in isolated mode.

wchar\_t \***home**

Python home directory.

If *Py\_SetPythonHome()* has been called, use its argument if it is not NULL.

Set by the PYTHONHOME environment variable.

Default: NULL.

Part of the *Python Path Configuration* input.

int **import\_time**

If non-zero, profile import time.

Set the 1 by the -X `importtime` option and the PYTHONPROFILEIMPORTTIME environment variable.

Default: 0.

int **inspect**

Enter interactive mode after executing a script or a command.

If greater than 0, enable inspect: when a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when `sys.stdin` does not appear to be a terminal.

Incremented by the -i command line option. Set to 1 if the PYTHONINSPECT environment variable is non-empty.

Default: 0.

int **install\_signal\_handlers**

Install Python signal handlers?

Default: 1 in Python mode, 0 in isolated mode.

int **interactive**

If greater than 0, enable the interactive mode (REPL).

Incremented by the -i command line option.

Default: 0.

**int `isolated`**

If greater than 0, enable isolated mode:

- Set `safe_path` to 1: don't prepend a potentially unsafe path to `sys.path` at Python startup.
- Set `use_environment` to 0.
- Set `user_site_directory` to 0: don't add the user site directory to `sys.path`.
- Python REPL doesn't import `readline` nor enable default readline configuration on interactive prompts.

Set to 1 by the `-I` command line option.

Default: 0 in Python mode, 1 in isolated mode.

See also `PyPreConfig.isolated`.

**int `legacy_windows_stdio`**

If non-zero, use `io.FileIO` instead of `io._WindowsConsoleIO` for `sys.stdin`, `sys.stdout` and `sys.stderr`.

Set to 1 if the `PYTHONLEGACYWINDOWSSTDIO` environment variable is set to a non-empty string.

Only available on Windows. `#ifdef MS_WINDOWS` macro can be used for Windows specific code.

Default: 0.

See also the [PEP 528](#) (Change Windows console encoding to UTF-8).

**int `malloc_stats`**

If non-zero, dump statistics on *Python pymalloc memory allocator* at exit.

Set to 1 by the `PYTHONMALLOCSTATS` environment variable.

The option is ignored if Python is configured using the `--without-pymalloc` option.

Default: 0.

**wchar\_t \*`platlibdir`**

Platform library directory name: `sys.platlibdir`.

Set by the `PYTHONPLATLIBDIR` environment variable.

Default: value of the `PLATLIBDIR` macro which is set by the `configure --with-platlibdir` option (default: "lib", or "DLLs" on Windows).

Part of the *Python Path Configuration* input.

Νέο στην έκδοση 3.9.

Άλλαξε στην έκδοση 3.11: This macro is now used on Windows to locate the standard library extension modules, typically under `DLLs`. However, for compatibility, note that this value is ignored for any non-standard layouts, including in-tree builds and virtual environments.

**wchar\_t \*`pythonpath_env`**

Module search paths (`sys.path`) as a string separated by `DELIM` (`os.pathsep`).

Set by the `PYTHONPATH` environment variable.

Default: `NULL`.

Part of the *Python Path Configuration* input.

***PyWideStringList* `module_search_paths`**

**int module\_search\_paths\_set**

Module search paths: `sys.path`.

If `module_search_paths_set` is equal to 0, `Py_InitializeFromConfig()` will replace `module_search_paths` and sets `module_search_paths_set` to 1.

Default: empty list (`module_search_paths`) and 0 (`module_search_paths_set`).

Part of the *Python Path Configuration* output.

**int optimization\_level**

Compilation optimization level:

- 0: Peephole optimizer, set `__debug__` to True.
- 1: Level 0, remove assertions, set `__debug__` to False.
- 2: Level 1, strip docstrings.

Incremented by the `-O` command line option. Set to the `PYTHONOPTIMIZE` environment variable value.

Default: 0.

***PyWideStringList* orig\_argv**

The list of the original command line arguments passed to the Python executable: `sys.orig_argv`.

If `orig_argv` list is empty and `argv` is not a list only containing an empty string, `PyConfig_Read()` copies `argv` into `orig_argv` before modifying `argv` (if `parse_argv` is non-zero).

See also the `argv` member and the `Py_GetArgcArgv()` function.

Default: empty list.

Νέο στην έκδοση 3.10.

**int parse\_argv**

Parse command line arguments?

If equals to 1, parse `argv` the same way the regular Python parses command line arguments, and strip Python arguments from `argv`.

The `PyConfig_Read()` function only parses `PyConfig.argv` arguments once: `PyConfig.parse_argv` is set to 2 after arguments are parsed. Since Python arguments are stripped from `PyConfig.argv`, parsing arguments twice would parse the application options as Python options.

Default: 1 in Python mode, 0 in isolated mode.

Άλλαξε στην έκδοση 3.10: The `PyConfig.argv` arguments are now only parsed if `PyConfig.parse_argv` equals to 1.

**int parser\_debug**

Parser debug mode. If greater than 0, turn on parser debugging output (for expert only, depending on compilation options).

Incremented by the `-d` command line option. Set to the `PYTHONDEBUG` environment variable value.

Default: 0.

**int pathconfig\_warnings**

If non-zero, calculation of path configuration is allowed to log warnings into `stderr`. If equals to 0, suppress these warnings.

Default: 1 in Python mode, 0 in isolated mode.

Part of the *Python Path Configuration* input.

Άλλαξε στην έκδοση 3.11: Now also applies on Windows.

**wchar\_t \*prefix**

The site-specific directory prefix where the platform independent Python files are installed: `sys.prefix`.

Default: NULL.

Part of the *Python Path Configuration* output.

**wchar\_t \*program\_name**

Program name used to initialize *executable* and in early error messages during Python initialization.

- If `Py_SetProgramName()` has been called, use its argument.
- On macOS, use `PYTHONEXECUTABLE` environment variable if set.
- If the `WITH_NEXT_FRAMEWORK` macro is defined, use `__PYENVV_LAUNCHER__` environment variable if set.
- Use `argv[0]` of *argv* if available and non-empty.
- Otherwise, use `L"python"` on Windows, or `L"python3"` on other platforms.

Default: NULL.

Part of the *Python Path Configuration* input.

**wchar\_t \*pycache\_prefix**

Directory where cached `.pyc` files are written: `sys.pycache_prefix`.

Set by the `-X pycache_prefix=PATH` command line option and the `PYTHONPYCACHEPREFIX` environment variable.

If NULL, `sys.pycache_prefix` is set to None.

Default: NULL.

**int quiet**

Quiet mode. If greater than 0, don't display the copyright and version at Python startup in interactive mode.

Incremented by the `-q` command line option.

Default: 0.

**wchar\_t \*run\_command**

Value of the `-c` command line option.

Used by `Py_RunMain()`.

Default: NULL.

**wchar\_t \*run\_filename**

Filename passed on the command line: trailing command line argument without `-c` or `-m`. It is used by the `Py_RunMain()` function.

For example, it is set to `script.py` by the `python3 script.py arg` command line.

See also the `PyConfig.skip_source_first_line` option.

Default: NULL.

**wchar\_t \*run\_module**

Value of the `-m` command line option.

Used by `Py_RunMain()`.

Default: NULL.

**int `show_ref_count`**

Show total reference count at exit?

Set to 1 by `-X showrefcount` command line option.

Need a debug build of Python (the `Py_REF_DEBUG` macro must be defined).

Default: 0.

**int `site_import`**

Import the `site` module at startup?

If equal to zero, disable the import of the module `site` and the site-dependent manipulations of `sys.path` that it entails.

Also disable these manipulations if the `site` module is explicitly imported later (call `site.main()` if you want them to be triggered).

Set to 0 by the `-S` command line option.

`sys.flags.no_site` is set to the inverted value of `site_import`.

Default: 1.

**int `skip_source_first_line`**

If non-zero, skip the first line of the `PyConfig.run_filename` source.

It allows the usage of non-Unix forms of `#!cmd`. This is intended for a DOS specific hack only.

Set to 1 by the `-x` command line option.

Default: 0.

**wchar\_t \*`stdio_encoding`****wchar\_t \*`stdio_errors`**

Encoding and encoding errors of `sys.stdin`, `sys.stdout` and `sys.stderr` (but `sys.stderr` always uses "backslashreplace" error handler).

If `Py_SetStandardStreamEncoding()` has been called, use its `error` and `errors` arguments if they are not NULL.

Use the `PYTHONIOENCODING` environment variable if it is non-empty.

Default encoding:

- "UTF-8" if `PyPreConfig.utf8_mode` is non-zero.
- Otherwise, use the *locale encoding*.

Default error handler:

- On Windows: use "surrogateescape".
- "surrogateescape" if `PyPreConfig.utf8_mode` is non-zero, or if the `LC_CTYPE` locale is «C» or «POSIX».
- "strict" otherwise.

**int `tracemalloc`**

Enable tracemalloc?

If non-zero, call `tracemalloc.start()` at startup.

Set by `-X tracemalloc=N` command line option and by the `PYTHONTRACEMALLOC` environment variable.

Default: -1 in Python mode, 0 in isolated mode.

**int `use_environment`**

Use environment variables?

If equals to zero, ignore the environment variables.

Set to 0 by the `-E` environment variable.

Default: 1 in Python config and 0 in isolated config.

**int `user_site_directory`**

If non-zero, add the user site directory to `sys.path`.

Set to 0 by the `-s` and `-I` command line options.

Set to 0 by the `PYTHONNOUSERSITE` environment variable.

Default: 1 in Python mode, 0 in isolated mode.

**int `verbose`**

Verbose mode. If greater than 0, print a message each time a module is imported, showing the place (filename or built-in module) from which it is loaded.

If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Incremented by the `-v` command line option.

Set to the `PYTHONVERBOSE` environment variable value.

Default: 0.

***PyWideStringList* `warnoptions`**

Options of the `warnings` module to build warnings filters, lowest to highest priority: `sys.warnoptions`.

The `warnings` module adds `sys.warnoptions` in the reverse order: the last *PyConfig.warnoptions* item becomes the first item of `warnings.filters` which is checked first (highest priority).

The `-W` command line options adds its value to *warnoptions*, it can be used multiple times.

The `PYTHONWARNINGS` environment variable can also be used to add warning options. Multiple options can be specified, separated by commas (,).

Default: empty list.

**int `write_bytecode`**

If equal to 0, Python won't try to write `.pyc` files on the import of source modules.

Set to 0 by the `-B` command line option and the `PYTHONDONTWRITEBYTECODE` environment variable.

`sys.dont_write_bytecode` is initialized to the inverted value of *write\_bytecode*.

Default: 1.

***PyWideStringList* `xoptions`**

Values of the `-X` command line options: `sys._xoptions`.

Default: empty list.

If *parse\_argv* is non-zero, *argv* arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from *argv*.

The *xoptions* options are parsed to set other options: see the `-X` command line option.

Αλλάξε στην έκδοση 3.9: The `show_alloc_count` field has been removed.



## 10.7 Initialization with PyConfig

Function to initialize Python:

**PyStatus Py\_InitializeFromConfig** (const *PyConfig* \*config)

Initialize Python from *config* configuration.

The caller is responsible to handle exceptions (error or exit) using *PyStatus\_Exception()* and *Py\_ExitStatusException()*.

If *PyImport\_FrozenModules()*, *PyImport\_AppendInittab()* or *PyImport\_ExtendInittab()* are used, they must be set or called after Python preinitialization and before the Python initialization. If Python is initialized multiple times, *PyImport\_AppendInittab()* or *PyImport\_ExtendInittab()* must be called before each Python initialization.

The current configuration (PyConfig type) is stored in *PyInterpreterState.config*.

Example setting the program name:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name. Implicitly preinitialize Python. */
    status = PyConfig_SetString(&config, &config.program_name,
                               L"/path/to/my_program");
    if (PyStatus_Exception(status)) {
        goto exception;
    }

    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto exception;
    }
    PyConfig_Clear(&config);
    return;

exception:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
}
```

More complete example modifying the default configuration, read the configuration, and then override some parameters. Note that since 3.11, many parameters are not calculated until initialization, and so values cannot be read from the configuration structure. Any values set before initialize is called will be left unchanged by initialization:

```
PyStatus init_python(const char *program_name)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).

       Implicitly preinitialize Python. */
    status = PyConfig_SetBytesString(&config, &config.program_name,
                                     program_name);
    if (PyStatus_Exception(status)) {
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

    goto done;
}

/* Read all configuration at once */
status = PyConfig_Read(&config);
if (PyStatus_Exception(status)) {
    goto done;
}

/* Specify sys.path explicitly */
/* If you want to modify the default set of paths, finish
   initialization first and then use PySys_GetObject("path") */
config.module_search_paths_set = 1;
status = PyWideStringList_Append(&config.module_search_paths,
                                L"/path/to/stdlib");
if (PyStatus_Exception(status)) {
    goto done;
}
status = PyWideStringList_Append(&config.module_search_paths,
                                L"/path/to/more/modules");
if (PyStatus_Exception(status)) {
    goto done;
}

/* Override executable computed by PyConfig_Read() */
status = PyConfig_SetString(&config, &config.executable,
                            L"/path/to/my_executable");
if (PyStatus_Exception(status)) {
    goto done;
}

status = Py_InitializeFromConfig(&config);

done:
PyConfig_Clear(&config);
return status;
}

```

## 10.8 Isolated Configuration

`PyPreConfig_InitIsolatedConfig()` and `PyConfig_InitIsolatedConfig()` functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environment variables, command line arguments (`PyConfig.argv` is not parsed) and user site directory. The C standard streams (ex: `stdout`) and the `LC_CTYPE` locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration to determine paths that are unspecified. Ensure `PyConfig.home` is specified to avoid computing the default path configuration.

## 10.9 Python Configuration

`PyPreConfig_InitPythonConfig()` and `PyConfig_InitPythonConfig()` functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (**PEP 538**) and Python UTF-8 Mode (**PEP 540**) depending on the `LC_CTYPE` locale, `PYTHONUTF8` and `PYTHONCOERCECLOCALE` environment variables.

## 10.10 Python Path Configuration

`PyConfig` contains multiple fields for the path configuration:

- Path configuration inputs:
  - `PyConfig.home`
  - `PyConfig.platlibdir`
  - `PyConfig.pathconfig_warnings`
  - `PyConfig.program_name`
  - `PyConfig.pythonpath_env`
  - current working directory: to get absolute paths
  - `PATH` environment variable to get the program full path (from `PyConfig.program_name`)
  - `__PYENV_LAUNCHER__` environment variable
  - (Windows only) Application paths in the registry under «SoftwarePythonPythonCoreX.YPythonPath» of `HKEY_CURRENT_USER` and `HKEY_LOCAL_MACHINE` (where X.Y is the Python version).
- Path configuration output fields:
  - `PyConfig.base_exec_prefix`
  - `PyConfig.base_executable`
  - `PyConfig.base_prefix`
  - `PyConfig.exec_prefix`
  - `PyConfig.executable`
  - `PyConfig.module_search_paths_set`, `PyConfig.module_search_paths`
  - `PyConfig.prefix`

If at least one «output field» is not set, Python calculates the path configuration to fill unset fields. If `module_search_paths_set` is equal to 0, `module_search_paths` is overridden and `module_search_paths_set` is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. `module_search_paths` is considered as set if `module_search_paths_set` is set to 1. In this case, `module_search_paths` will be used without modification.

Set `pathconfig_warnings` to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If `base_prefix` or `base_exec_prefix` fields are not set, they inherit their value from `prefix` and `exec_prefix` respectively.

`Py_RunMain()` and `Py_Main()` modify `sys.path`:

- If `run_filename` is set and is a directory which contains a `__main__.py` script, prepend `run_filename` to `sys.path`.
- If `isolated` is zero:
  - If `run_module` is set, prepend the current directory to `sys.path`. Do nothing if the current directory cannot be read.
  - If `run_filename` is set, prepend the directory of the filename to `sys.path`.
  - Otherwise, prepend an empty string to `sys.path`.

If `site_import` is non-zero, `sys.path` can be modified by the `site` module. If `user_site_directory` is non-zero and the user's site-package directory exists, the `site` module appends the user's site-package directory to `sys.path`.

The following configuration files are used by the path configuration:

- `pyvenv.cfg`
- `._pth` file (ex: `python._pth`)
- `pybuilddir.txt` (Unix only)

If a `._pth` file is present:

- Set `isolated` to 1.
- Set `use_environment` to 0.
- Set `site_import` to 0.
- Set `safe_path` to 1.

The `__PYENVN_LAUNCHER__` environment variable is used to set `PyConfig.base_executable`

## 10.11 Py\_RunMain()

int **Py\_RunMain** (void)

Execute the command (`PyConfig.run_command`), the script (`PyConfig.run_filename`) or the module (`PyConfig.run_module`) specified on the command line or in the configuration.

By default and when if `-i` option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the `exit()` function.

See [Python Configuration](#) for an example of customized Python always running in isolated mode using `Py_RunMain()`.

## 10.12 Py\_GetArgcArgv()

void **Py\_GetArgcArgv** (int \*argc, wchar\_t \*\*\*argv)

Get the original command line arguments, before Python modified them.

See also `PyConfig.orig_argv` member.

## 10.13 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of [PEP 432](#):

- «Core» initialization phase, «bare minimum Python»:
  - Builtin types;
  - Builtin exceptions;
  - Builtin and frozen modules;
  - The `sys` module is only partially initialized (ex: `sys.path` doesn't exist yet).
- «Main» initialization phase, Python is fully initialized:
  - Install and configure `importlib`;
  - Apply the *Path Configuration*;
  - Install signal handlers;
  - Finish `sys` module initialization (ex: create `sys.stdout` and `sys.path`);
  - Enable optional features like `faulthandler` and `tracemalloc`;
  - Import the `site` module;
  - etc.

Private provisional API:

- `PyConfig._init_main`: if set to 0, `Py_InitializeFromConfig()` stops at the «Core» initialization phase.
- `PyConfig._isolated_interpreter`: if non-zero, disallow threads, subprocesses and fork.

*PyStatus* **`_Py_InitializeMain`** (void)

Move to the «Main» initialization phase, finish the Python initialization.

No module is imported during the «Core» phase and the `importlib` module is not configured: the *Path Configuration* is only applied during the «Main» phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom `sys.meta_path` importer or an import hook, etc.

It may become possible to calculate the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the [PEP 432](#) motivation.

The «Core» phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between «Core» and «Main» initialization phases:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config._init_main = 0;

    /* ... customize 'config' configuration ... */

    status = Py_InitializeFromConfig(&config);
    PyConfig_Clear(&config);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
}
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```
/* Use sys.stderr because sys.stdout is only created
   by _Py_InitializeMain() */
int res = PyRun_SimpleString(
    "import sys; "
    "print('Run Python code before _Py_InitializeMain', "
    "file=sys.stderr)");
if (res < 0) {
    exit(1);
}

/* ... put more configuration code here ... */

status = _Py_InitializeMain();
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}
}
```

---

Memory Management

---

## 11.1 Overview

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: `malloc()`, `calloc()`, `realloc()` and `free()`. This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.



In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

#### Δείτε επίσης:

The `PYTHONMALLOC` environment variable can be used to configure the memory allocators used by Python.

The `PYTHONMALLOCSTATS` environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

## 11.2 Allocator Domains

All allocating functions belong to one of three different «domains» (see also *PyMemAllocatorDomain*). These domains represent different allocation strategies and are optimized for different purposes. The specific details on how every domain allocates memory or what internal functions each domain calls is considered an implementation detail, but for debugging purposes a simplified table can be found at [here](#). There is no hard requirement to use the memory returned by the allocation functions belonging to a given domain for only the purposes hinted by that domain (although this is the recommended practice). For example, one could use the memory returned by *PyMem\_RawMalloc()* for allocating Python objects or the memory returned by *PyObject\_Malloc()* for allocating memory for buffers.

The three allocation domains are:

- Raw domain: intended for allocating memory for general-purpose memory buffers where the allocation *must* go to the system allocator or where the allocator can operate without the *GIL*. The memory is requested directly to the system.
- «Mem» domain: intended for allocating memory for Python buffers and general-purpose memory buffers where the allocation must be performed with the *GIL* held. The memory is taken from the Python private heap.
- Object domain: intended for allocating memory belonging to Python objects. The memory is taken from the Python private heap.

When freeing memory previously allocated by the allocating functions belonging to a given domain, the matching specific deallocating functions must be used. For example, *PyMem\_Free()* must be used to free memory allocated using *PyMem\_Malloc()*.

## 11.3 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, the *GIL* does not need to be held.

The *default raw memory allocator* uses the following functions: `malloc()`, `calloc()`, `realloc()` and `free()`; call `malloc(1)` (or `calloc(1, 1)`) when requesting zero bytes.

Νέο στην έκδοση 3.4.

`void *PyMem_RawMalloc (size_t n)`

Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawMalloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyMem\_RawCalloc** (size\_t nelem, size\_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawCalloc(1, 1)` had been called instead.

Νέο στην έκδοση 3.5.

void **\*PyMem\_RawRealloc** (void \*p, size\_t n)

Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyMem_RawMalloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to `PyMem_RawMalloc()`, `PyMem_RawRealloc()` or `PyMem_RawCalloc()`.

If the request fails, `PyMem_RawRealloc()` returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyMem\_RawFree** (void \*p)

Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyMem_RawMalloc()`, `PyMem_RawRealloc()` or `PyMem_RawCalloc()`. Otherwise, or if `PyMem_RawFree(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

## 11.4 Memory Interface

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The *default memory allocator* uses the *pymalloc memory allocator*.

**Προειδοποίηση:** The *GIL* must be held when using these functions.

Άλλαξε στην έκδοση 3.6: The default allocator is now `pymalloc` instead of `system malloc()`.

void **\*PyMem\_Malloc** (size\_t n)

*Μέρος του Σταθερό ABI.* Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyMem\_Calloc** (size\_t nelem, size\_t elsize)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Calloc(1, 1)` had been called instead.

Νέο στην έκδοση 3.5.

void **\*PyMem\_Realloc** (void \*p, size\_t n)

*Μέρος του Σταθερό ABI.* Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is NULL, the call is equivalent to `PyMem_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless *p* is NULL, it must have been returned by a previous call to `PyMem_Malloc()`, `PyMem_Realloc()` or `PyMem_Calloc()`.

If the request fails, `PyMem_Realloc()` returns NULL and *p* remains a valid pointer to the previous memory area.

void **PyMem\_Free** (void \**p*)

*Μέρος του Σταθερό ABI.* Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyMem_Malloc()`, `PyMem_Realloc()` or `PyMem_Calloc()`. Otherwise, or if `PyMem_Free(p)` has been called before, undefined behavior occurs.

If *p* is NULL, no operation is performed.

The following type-oriented macros are provided for convenience. Note that *TYPE* refers to any C type.

**PyMem\_New** (TYPE, *n*)

Same as `PyMem_Malloc()`, but allocates (*n* \* `sizeof(TYPE)`) bytes of memory. Returns a pointer cast to `TYPE*`. The memory will not have been initialized in any way.

**PyMem\_Resize** (*p*, TYPE, *n*)

Same as `PyMem_Realloc()`, but the memory block is resized to (*n* \* `sizeof(TYPE)`) bytes. Returns a pointer cast to `TYPE*`. On return, *p* will be a pointer to the new memory area, or NULL in the event of failure.

This is a C preprocessor macro; *p* is always reassigned. Save the original value of *p* to avoid losing memory when handling errors.

void **PyMem\_Del** (void \**p*)

Same as `PyMem_Free()`.

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- `PyMem_MALLOC(size)`
- `PyMem_NEW(type, size)`
- `PyMem_REALLOC(ptr, size)`
- `PyMem_RESIZE(ptr, type, size)`
- `PyMem_FREE(ptr)`
- `PyMem_DEL(ptr)`

## 11.5 Object allocators

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

---

**Σημείωση:** There is no guarantee that the memory returned by these allocators can be successfully cast to a Python object when intercepting the allocating functions in this domain by the methods described in the [Customize Memory Allocators](#) section.

---

The *default object allocator* uses the *pymalloc memory allocator*.

**Προειδοποίηση:** The *GIL* must be held when using these functions.

void **\*PyObject\_Malloc** (size\_t n)

*Μέρος του Σταθερό ABI.* Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyObject\_Calloc** (size\_t nelem, size\_t elsize)

*Μέρος του Σταθερό ABI από την έκδοση 3.7.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Calloc(1, 1)` had been called instead.

Νέο στην έκδοση 3.5.

void **\*PyObject\_Realloc** (void \*p, size\_t n)

*Μέρος του Σταθερό ABI.* Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyObject_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to `PyObject_Malloc()`, `PyObject_Realloc()` or `PyObject_Calloc()`.

If the request fails, `PyObject_Realloc()` returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyObject\_Free** (void \*p)

*Μέρος του Σταθερό ABI.* Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyObject_Malloc()`, `PyObject_Realloc()` or `PyObject_Calloc()`. Otherwise, or if `PyObject_Free(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

## 11.6 Default Memory Allocators

Default memory allocators:

Configuration	Name	PyMem_RawMalloc	PyMem_Malloc	PyObject_Malloc
Release build	"pymalloc"	malloc	pymalloc	pymalloc
Debug build	"pymalloc_debug"	malloc + debug	pymalloc + debug	pymalloc + debug
Release build, without pymalloc	"malloc"	malloc	malloc	malloc
Debug build, without pymalloc	"malloc_debug"	malloc + debug	malloc + debug	malloc + debug

Legend:

- Name: value for `PYTHONMALLOC` environment variable.
- malloc: system allocators from the standard C library, C functions: `malloc()`, `calloc()`, `realloc()` and `free()`.

- `pymalloc`: *pymalloc memory allocator*.
- «+ debug»: with *debug hooks on the Python memory allocators*.
- «Debug build»: Python build in debug mode.

## 11.7 Customize Memory Allocators

Νέο στην έκδοση 3.4.

type **PyMemAllocatorEx**

Structure used to describe a memory block allocator. The structure has the following fields:

Field	Meaning
<code>void *ctx</code>	user context passed as first argument
<code>void* malloc(void *ctx, size_t size)</code>	allocate a memory block
<code>void* calloc(void *ctx, size_t nelem, size_t elsize)</code>	allocate a memory block initialized with zeros
<code>void* realloc(void *ctx, void *ptr, size_t new_size)</code>	allocate or resize a memory block
<code>void free(void *ctx, void *ptr)</code>	free a memory block

Αλλάξε στην έκδοση 3.5: The `PyMemAllocator` structure was renamed to *PyMemAllocatorEx* and a new `calloc` field was added.

type **PyMemAllocatorDomain**

Enum used to identify an allocator domain. Domains:

**PYMEM\_DOMAIN\_RAW**

Functions:

- `PyMem_RawMalloc()`
- `PyMem_RawRealloc()`
- `PyMem_RawCalloc()`
- `PyMem_RawFree()`

**PYMEM\_DOMAIN\_MEM**

Functions:

- `PyMem_Malloc()`,
- `PyMem_Realloc()`
- `PyMem_Calloc()`
- `PyMem_Free()`

**PYMEM\_DOMAIN\_OBJ**

Functions:

- `PyObject_Malloc()`
- `PyObject_Realloc()`
- `PyObject_Calloc()`
- `PyObject_Free()`

void **PyMem\_GetAllocator** (*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* \*allocator)

Get the memory block allocator of the specified domain.

void **PyMem\_SetAllocator** (*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* \*allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the *PYMEM\_DOMAIN\_RAW* domain, the allocator must be thread-safe: the *GIL* is not held when the allocator is called.

If the new allocator is not a hook (does not call the previous allocator), the *PyMem\_SetupDebugHooks()* function must be called to reinstall the debug hooks on top on the new allocator.

See also *PyPreConfig.allocator* and *Preinitialize Python with PyPreConfig*.

**Προειδοποίηση:** *PyMem\_SetAllocator()* does have the following contract:

- It can be called after *Py\_PreInitialize()* and before *Py\_InitializeFromConfig()* to install a custom memory allocator. There are no restrictions over the installed allocator other than the ones imposed by the domain (for instance, the Raw Domain allows the allocator to be called without the GIL held). See *the section on allocator domains* for more information.
- If called after Python has finish initializing (after *Py\_InitializeFromConfig()* has been called) the allocator **must** wrap the existing allocator. Substituting the current allocator for some other arbitrary one is **not supported**.

void **PyMem\_SetupDebugHooks** (void)

Setup *debug hooks in the Python memory allocators* to detect memory errors.

## 11.8 Debug hooks on the Python memory allocators

When Python is built in debug mode, the *PyMem\_SetupDebugHooks()* function is called at the *Python preinitialization* to setup debug hooks on Python memory allocators to detect memory errors.

The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode (ex: PYTHONMALLOC=debug).

The *PyMem\_SetupDebugHooks()* function can be used to set debug hooks after calling *PyMem\_SetAllocator()*.

These debug hooks fill dynamically allocated memory blocks with special, recognizable bit patterns. Newly allocated memory is filled with the byte 0xCD (PYMEM\_CLEANBYTE), freed memory is filled with the byte 0xDD (PYMEM\_DEADBYTE). Memory blocks are surrounded by «forbidden bytes» filled with the byte 0xFD (PYMEM\_FORBIDDENBYTE). Strings of these bytes are unlikely to be valid addresses, floats, or ASCII strings.

Runtime checks:

- Detect API violations. For example, detect if *PyObject\_Free()* is called on a memory block allocated by *PyMem\_Malloc()*.
- Detect write before the start of the buffer (buffer underflow).
- Detect write after the end of the buffer (buffer overflow).
- Check that the *GIL* is held when allocator functions of *PYMEM\_DOMAIN\_OBJ* (ex: *PyObject\_Malloc()*) and *PYMEM\_DOMAIN\_MEM* (ex: *PyMem\_Malloc()*) domains are called.

On error, the debug hooks use the *tracemalloc* module to get the traceback where a memory block was allocated. The traceback is only displayed if *tracemalloc* is tracing Python memory allocations and the memory block was traced.

Let  $S = \text{sizeof}(\text{size\_t})$ .  $2*S$  bytes are added at each end of each block of  $N$  bytes requested. The memory layout is like so, where  $p$  represents the address returned by a malloc-like or realloc-like function ( $p[i:j]$  means the slice of bytes from  $* (p+i)$  inclusive up to  $* (p+j)$  exclusive; note that the treatment of negative indices differs from a Python slice):

**p[-2\*S:-S]**

Number of bytes originally asked for. This is a `size_t`, big-endian (easier to read in a memory dump).

**p[-S]**

API identifier (ASCII character):

- 'r' for `PYMEM_DOMAIN_RAW`.
- 'm' for `PYMEM_DOMAIN_MEM`.
- 'o' for `PYMEM_DOMAIN_OBJ`.

**p[-S+1:0]**

Copies of `PYMEM_FORBIDDENBYTE`. Used to catch under- writes and reads.

**p[0:N]**

The requested memory, filled with copies of `PYMEM_CLEANBYTE`, used to catch reference to uninitialized memory. When a realloc-like function is called requesting a larger memory block, the new excess bytes are also filled with `PYMEM_CLEANBYTE`. When a free-like function is called, these are overwritten with `PYMEM_DEADBYTE`, to catch reference to freed memory. When a realloc-like function is called requesting a smaller memory block, the excess old bytes are also filled with `PYMEM_DEADBYTE`.

**p[N:N+S]**

Copies of `PYMEM_FORBIDDENBYTE`. Used to catch over- writes and reads.

**p[N+S:N+2\*S]**

Only used if the `PYMEM_DEBUG_SERIALNO` macro is defined (not defined by default).

A serial number, incremented by 1 on each call to a malloc-like or realloc-like function. Big-endian `size_t`. If «bad memory» is detected later, the serial number gives an excellent way to set a breakpoint on the next run, to capture the instant at which this block was passed out. The static function `bumpserialno()` in `obmalloc.c` is the only place the serial number is incremented, and exists so you can set such a breakpoint easily.

A realloc-like or free-like function first checks that the `PYMEM_FORBIDDENBYTE` bytes at each end are intact. If they've been altered, diagnostic output is written to `stderr`, and the program is aborted via `Py_FatalError()`. The other main failure mode is provoking a memory error when a program reads up one of the special bit patterns and tries to use it as an address. If you get in a debugger then and look at the object, you're likely to see that it's entirely filled with `PYMEM_DEADBYTE` (meaning freed memory is getting used) or `PYMEM_CLEANBYTE` (meaning uninitialized memory is getting used).

Αλλάξε στην έκδοση 3.6: The `PyMem_SetupDebugHooks()` function now also works on Python compiled in release mode. On error, the debug hooks now use `tracemalloc` to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of `PYMEM_DOMAIN_OBJ` and `PYMEM_DOMAIN_MEM` domains are called.

Αλλάξε στην έκδοση 3.8: Byte patterns `0xCB` (`PYMEM_CLEANBYTE`), `0xDB` (`PYMEM_DEADBYTE`) and `0xFB` (`PYMEM_FORBIDDENBYTE`) have been replaced with `0xCD`, `0xDD` and `0xFD` to use the same values than Windows CRT `debug malloc()` and `free()`.

## 11.9 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called «arenas» with a fixed size of either 256 KiB on 32-bit platforms or 1 MiB on 64-bit platforms. It falls back to `PyMem_RawMalloc()` and `PyMem_RawRealloc()` for allocations larger than 512 bytes.

*pymalloc* is the *default allocator* of the `PYMEM_DOMAIN_MEM` (ex: `PyMem_Malloc()`) and `PYMEM_DOMAIN_OBJ` (ex: `PyObject_Malloc()`) domains.

The arena allocator uses the following functions:

- `VirtualAlloc()` and `VirtualFree()` on Windows,
- `mmap()` and `munmap()` if available,



- `malloc()` and `free()` otherwise.

This allocator is disabled if Python is configured with the `--without-pymalloc` option. It can also be disabled at runtime using the `PYTHONMALLOC` environment variable (ex: `PYTHONMALLOC=malloc`).

### 11.9.1 Customize pymalloc Arena Allocator

Νέο στην έκδοση 3.4.

type **PyObjectArenaAllocator**

Structure used to describe an arena allocator. The structure has three fields:

Field	Meaning
<code>void *ctx</code>	user context passed as first argument
<code>void* alloc(void *ctx, size_t size)</code>	allocate an arena of size bytes
<code>void free(void *ctx, void *ptr, size_t size)</code>	free an arena

void **PyObject\_GetArenaAllocator** (*PyObjectArenaAllocator* \*allocator)

Get the arena allocator.

void **PyObject\_SetArenaAllocator** (*PyObjectArenaAllocator* \*allocator)

Set the arena allocator.

## 11.10 tracemalloc C API

Νέο στην έκδοση 3.7.

int **PyTraceMalloc\_Track** (unsigned int domain, uintptr\_t ptr, size\_t size)

Track an allocated memory block in the `tracemalloc` module.

Return 0 on success, return -1 on error (failed to allocate memory to store the trace). Return -2 if `tracemalloc` is disabled.

If memory block is already tracked, update the existing trace.

int **PyTraceMalloc\_Untrack** (unsigned int domain, uintptr\_t ptr)

Untrack an allocated memory block in the `tracemalloc` module. Do nothing if the block was not tracked.

Return -2 if `tracemalloc` is disabled, otherwise return 0.

## 11.11 Examples

Here is the example from section [Overview](#), rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2);      /* Right -- allocated via malloc() */
free(buf1);      /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with `PyObject_New`, `PyObject_NewVar` and `PyObject_Del()`.

These will be explained in the next chapter on defining and implementing new object types in C.

## Object Implementation Support

This chapter describes the functions, types, and macros used when defining new object types.

## 12.1 Allocating Objects on the Heap

*PyObject* \***\_PyObject\_New** (*PyTypeObject* \*type)

*Επιστρεφόμενη τιμή:* New reference.

*PyVarObject* \***\_PyObject\_NewVar** (*PyTypeObject* \*type, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* New reference.

*PyObject* \***PyObject\_Init** (*PyObject* \*op, *PyTypeObject* \*type)

*Επιστρεφόμενη τιμή:* Borrowed reference. Μέρος του Σταθερό ABI. Initialize a newly allocated object *op* with its type and initial reference. Returns the initialized object. If *type* indicates that the object participates in the cyclic garbage detector, it is added to the detector's set of observed objects. Other fields of the object are not affected.

*PyVarObject* \***PyObject\_InitVar** (*PyVarObject* \*op, *PyTypeObject* \*type, *Py\_ssize\_t* size)

*Επιστρεφόμενη τιμή:* Borrowed reference. Μέρος του Σταθερό ABI. This does everything *PyObject\_Init()* does, and also initializes the length information for a variable-size object.

**PyObject\_New** (TYPE, typeobj)

Allocate a new Python object using the C structure type *TYPE* and the Python type object *typeobj* (*PyTypeObject*\*). Fields not defined by the Python object header are not initialized. The caller will own the only reference to the object (i.e. its reference count will be one). The size of the memory allocation is determined from the *tp\_basicsize* field of the type object.

**PyObject\_NewVar** (TYPE, typeobj, size)

Allocate a new Python object using the C structure type *TYPE* and the Python type object *typeobj* (*PyTypeObject*\*). Fields not defined by the Python object header are not initialized. The allocated memory allows for the *TYPE* structure plus *size* (*Py\_ssize\_t*) fields of the size given by the *tp\_itemsize* field of *typeobj*. This is useful for implementing objects like tuples, which are able to determine their size at construction time. Embedding the array of fields into the same allocation decreases the number of allocations, improving the memory management efficiency.

void **PyObject\_Del** (void \*op)

Releases memory allocated to an object using *PyObject\_New* or *PyObject\_NewVar*. This is normally called from the *tp\_dealloc* handler specified in the object's type. The fields of the object should not be accessed after this call as the memory is no longer a valid Python object.

*PyObject\_Py\_NoneStruct*

Object which is visible in Python as `None`. This should only be accessed using the *Py\_None* macro, which evaluates to a pointer to this object.

**Δείτε επίσης:**

*PyModule\_Create()*

To allocate and create extension modules.

## 12.2 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

### 12.2.1 Base object types and macros

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the *PyObject* and *PyVarObject* types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects.

type **PyObject**

*Μέρος του Περιορισμένου API. (Μόνο ορισμένα μέλη αποτελούν μέρος του σταθερού ABI.)* All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal «release» build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a *PyObject*, but every pointer to a Python object can be cast to a *PyObject\**. Access to the members must be done by using the macros *Py\_REFCNT* and *Py\_TYPE*.

type **PyVarObject**

*Μέρος του Περιορισμένου API. (Μόνο ορισμένα μέλη αποτελούν μέρος του σταθερού ABI.)* This is an extension of *PyObject* that adds the *ob\_size* field. This is only used for objects that have some notion of *length*. This type does not often appear in the Python/C API. Access to the members must be done by using the macros *Py\_REFCNT*, *Py\_TYPE*, and *Py\_SIZE*.

**PyObject\_HEAD**

This is a macro used when declaring new types which represent objects without a varying length. The *PyObject\_HEAD* macro expands to:

```
PyObject ob_base;
```

See documentation of *PyObject* above.

**PyObject\_VAR\_HEAD**

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The *PyObject\_VAR\_HEAD* macro expands to:

```
PyVarObject ob_base;
```

See documentation of *PyVarObject* above.

`int Py_Is (PyObject *x, PyObject *y)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Test if the *x* object is the *y* object, the same as `x is y` in Python.

Νέο στην έκδοση 3.10.

`int Py_IsNone (PyObject *x)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Test if an object is the `None` singleton, the same as `x is None` in Python.

Νέο στην έκδοση 3.10.

`int Py_IsTrue (PyObject *x)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Test if an object is the `True` singleton, the same as `x is True` in Python.

Νέο στην έκδοση 3.10.

`int Py_IsFalse (PyObject *x)`

Μέρος του Σταθερό ABI από την έκδοση 3.10. Test if an object is the `False` singleton, the same as `x is False` in Python.

Νέο στην έκδοση 3.10.

`PyTypeObject *Py_TYPE (PyObject *o)`

Get the type of the Python object *o*.

Return a *borrowed reference*.

Use the `Py_SET_TYPE ()` function to set an object type.

Άλλαξε στην έκδοση 3.11: `Py_TYPE ()` is changed to an inline static function. The parameter type is no longer `const PyObject*`.

`int Py_IS_TYPE (PyObject *o, PyTypeObject *type)`

Return non-zero if the object *o* type is *type*. Return zero otherwise. Equivalent to: `Py_TYPE(o) == type`.

Νέο στην έκδοση 3.9.

`void Py_SET_TYPE (PyObject *o, PyTypeObject *type)`

Set the object *o* type to *type*.

Νέο στην έκδοση 3.9.

`Py_ssize_t Py_REFCNT (PyObject *o)`

Get the reference count of the Python object *o*.

Use the `Py_SET_REFCNT ()` function to set an object reference count.

Άλλαξε στην έκδοση 3.11: The parameter type is no longer `const PyObject*`.

Άλλαξε στην έκδοση 3.10: `Py_REFCNT ()` is changed to the inline static function.

`void Py_SET_REFCNT (PyObject *o, Py_ssize_t refcnt)`

Set the object *o* reference counter to *refcnt*.

Νέο στην έκδοση 3.9.

`Py_ssize_t Py_SIZE (PyVarObject *o)`

Get the size of the Python object *o*.

Use the `Py_SET_SIZE ()` function to set an object size.

Άλλαξε στην έκδοση 3.11: `Py_SIZE ()` is changed to an inline static function. The parameter type is no longer `const PyVarObject*`.

void **Py\_SET\_SIZE** (*PyVarObject* \*o, *Py\_ssize\_t* size)

Set the object *o* size to *size*.

Νέο στην έκδοση 3.9.

**PyObject\_HEAD\_INIT** (type)

This is a macro which expands to initialization values for a new *PyObject* type. This macro expands to:

```
_PyObject_EXTRA_INIT  
1, type,
```

**PyVarObject\_HEAD\_INIT** (type, size)

This is a macro which expands to initialization values for a new *PyVarObject* type, including the *ob\_size* field. This macro expands to:

```
_PyObject_EXTRA_INIT  
1, type, size,
```

## 12.2.2 Implementing functions and methods

type **PyCFunction**

*Μέρος του Σταθερό ABI.* Type of the functions used to implement most Python callables in C. Functions of this type take two *PyObject\** parameters and return one such value. If the return value is NULL, an exception shall have been set. If not NULL, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

The function signature is:

```
PyObject *PyCFunction(PyObject *self,  
                      PyObject *args);
```

type **PyCFunctionWithKeywords**

*Μέρος του Σταθερό ABI.* Type of the functions used to implement Python callables in C with signature *METH\_VARARGS* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *PyCFunctionWithKeywords(PyObject *self,  
                                  PyObject *args,  
                                  PyObject *kwargs);
```

type **\_PyCFunctionFast**

Type of the functions used to implement Python callables in C with signature *METH\_FASTCALL*. The function signature is:

```
PyObject *_PyCFunctionFast(PyObject *self,  
                           PyObject *const *args,  
                           Py_ssize_t nargs);
```

type **\_PyCFunctionFastWithKeywords**

Type of the functions used to implement Python callables in C with signature *METH\_FASTCALL* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *_PyCFunctionFastWithKeywords(PyObject *self,  
                                       PyObject *const *args,  
                                       Py_ssize_t nargs,  
                                       PyObject *kwnames);
```

type **PyCMethod**

Type of the functions used to implement Python callables in C with signature *METH\_METHOD* | *METH\_FASTCALL* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *PyCMethod(PyObject *self,
                    PyTypeObject *defining_class,
                    PyObject *const *args,
                    Py_ssize_t nargs,
                    PyObject *kwnames)
```

Νέο στην έκδοση 3.9.

#### type **PyMethodDef**

*Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών).* Structure used to describe a method of an extension type. This structure has four fields:

**const char \*ml\_name**

Name of the method.

*PyCFunction* **ml\_meth**

Pointer to the C implementation.

**int ml\_flags**

Flags bits indicating how the call should be constructed.

**const char \*ml\_doc**

Points to the contents of the docstring.

The *ml\_meth* is a C function pointer. The functions may be of different types, but they always return *PyObject\**. If the function is not of the *PyCFunction*, the compiler will require a cast in the method table. Even though *PyCFunction* defines the first parameter as *PyObject\**, it is common that the method implementation uses the specific C type of the *self* object.

The *ml\_flags* field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are these calling conventions:

#### **METH\_VARARGS**

This is the typical calling convention, where the methods have the type *PyCFunction*. The function expects two *PyObject\** values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using *PyArg\_ParseTuple()* or *PyArg\_UnpackTuple()*.

#### **METH\_KEYWORDS**

Can only be used in certain combinations with other flags: *METH\_VARARGS* | *METH\_KEYWORDS*, *METH\_FASTCALL* | *METH\_KEYWORDS* and *METH\_METHOD* | *METH\_FASTCALL* | *METH\_KEYWORDS*.

#### **METH\_VARARGS** | **METH\_KEYWORDS**

Methods with these flags must be of type *PyCFunctionWithKeywords*. The function expects three parameters: *self*, *args*, *kwargs* where *kwargs* is a dictionary of all the keyword arguments or possibly NULL if there are no keyword arguments. The parameters are typically processed using *PyArg\_ParseTupleAndKeywords()*.

#### **METH\_FASTCALL**

Fast calling convention supporting only positional arguments. The methods have the type *\_PyCFunctionFast*. The first parameter is *self*, the second parameter is a C array of *PyObject\** values indicating the arguments and the third parameter is the number of arguments (the length of the array).

Νέο στην έκδοση 3.7.

Άλλαξε στην έκδοση 3.10: *METH\_FASTCALL* is now part of the *stable ABI*.

#### **METH\_FASTCALL** | **METH\_KEYWORDS**

Extension of *METH\_FASTCALL* supporting also keyword arguments, with methods of type *\_PyCFunctionFastWithKeywords*. Keyword arguments are passed the same way as in the *vectorcall protocol*: there is an additional fourth *PyObject\** parameter which is a tuple representing the names of the

keyword arguments (which are guaranteed to be strings) or possibly `NULL` if there are no keywords. The values of the keyword arguments are stored in the *args* array, after the positional arguments.

Νέο στην έκδοση 3.7.

#### **METH\_METHOD**

Can only be used in the combination with other flags: `METH_METHOD` | `METH_FASTCALL` | `METH_KEYWORDS`.

#### **METH\_METHOD | METH\_FASTCALL | METH\_KEYWORDS**

Extension of `METH_FASTCALL` | `METH_KEYWORDS` supporting the *defining class*, that is, the class that contains the method in question. The defining class might be a superclass of `Py_TYPE(self)`.

The method needs to be of type `PyCMethod`, the same as for `METH_FASTCALL` | `METH_KEYWORDS` with *defining\_class* argument added after *self*.

Νέο στην έκδοση 3.9.

#### **METH\_NOARGS**

Methods without parameters don't need to check whether arguments are given if they are listed with the `METH_NOARGS` flag. They need to be of type `PyCFunction`. The first parameter is typically named *self* and will hold a reference to the module or object instance. In all cases the second parameter will be `NULL`.

The function must have 2 parameters. Since the second parameter is unused, `Py_UNUSED` can be used to prevent a compiler warning.

#### **METH\_O**

Methods with a single object argument can be listed with the `METH_O` flag, instead of invoking `PyArg_ParseTuple()` with a "O" argument. They have the type `PyCFunction`, with the *self* parameter, and a `PyObject*` parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

#### **METH\_CLASS**

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the `classmethod()` built-in function.

#### **METH\_STATIC**

The method will be passed `NULL` as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the `staticmethod()` built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

#### **METH\_COEXIST**

The method will be loaded in place of existing definitions. Without `METH_COEXIST`, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq\_contains* slot, for example, would generate a wrapped method named `__contains__()` and preclude the loading of a corresponding `PyCFunction` with the same name. With the flag defined, the `PyCFunction` will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to `PyCFunctions` are optimized more than wrapper object calls.

*PyObject\** **PyCMethod\_New** (*PyMethodDef* \*ml, *PyObject* \*self, *PyObject* \*module, *PyTypeObject* \*cls)

Επιστρεφόμενη τιμή: *New reference*. Μέρος του Σταθερό ABI από την έκδοση 3.9. Turn *ml* into a Python *callable* object. The caller must ensure that *ml* outlives the *callable*. Typically, *ml* is defined as a static variable.

The *self* parameter will be passed as the *self* argument to the C function in `ml->ml_meth` when invoked. *self* can be `NULL`.

The *callable* object's `__module__` attribute can be set from the given *module* argument. *module* should be a Python string, which will be used as name of the module the function is defined in. If unavailable, it can be set to `None` or `NULL`.



**Δείτε επίσης:**

`function.__module__`

The `cls` parameter will be passed as the *defining\_class* argument to the C function. Must be set if `METH_METHOD` is set on `ml->ml_flags`.

Νέο στην έκδοση 3.9.

*PyObject* \***PyCFunction\_NewEx** (*PyMethodDef* \*ml, *PyObject* \*self, *PyObject* \*module)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του **Σταθερό ABI**. Equivalent to `PyCMethod_New(ml, self, module, NULL)`.

*PyObject* \***PyCFunction\_New** (*PyMethodDef* \*ml, *PyObject* \*self)

*Επιστρεφόμενη τιμή:* New reference. Μέρος του **Σταθερό ABI** από την έκδοση 3.4. Equivalent to `PyCMethod_New(ml, self, NULL, NULL)`.

### 12.2.3 Accessing attributes of extension types

type **PyMemberDef**

*Μέρος του Σταθερό ABI (συμπεριλαμβανομένων όλων των μελών).* Structure which describes an attribute of a type which corresponds to a C struct member. Its fields are:

Field	C Type	Meaning
name	const char *	name of the member
type	int	the type of the member in the C struct
offset	Py_ssize_t	the offset in bytes that the member is located on the type's object struct
flags	int	flag bits indicating if the field should be read-only or writable
doc	const char *	points to the contents of the docstring

`type` can be one of many `T_` macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type.

Macro name	C type
<code>T_SHORT</code>	short
<code>T_INT</code>	int
<code>T_LONG</code>	long
<code>T_FLOAT</code>	float
<code>T_DOUBLE</code>	double
<code>T_STRING</code>	const char *
<code>T_OBJECT</code>	<code>PyObject *</code>
<code>T_OBJECT_EX</code>	<code>PyObject *</code>
<code>T_CHAR</code>	char
<code>T_BYTE</code>	char
<code>T_UBYTE</code>	unsigned char
<code>T_UINT</code>	unsigned int
<code>T_USHORT</code>	unsigned short
<code>T_ULONG</code>	unsigned long
<code>T_BOOL</code>	char
<code>T_LONGLONG</code>	long long
<code>T_ULONGLONG</code>	unsigned long long
<code>T_PYSSIZET</code>	<code>Py_ssize_t</code>

`T_OBJECT` and `T_OBJECT_EX` differ in that `T_OBJECT` returns `None` if the member is `NULL` and `T_OBJECT_EX` raises an `AttributeError`. Try to use `T_OBJECT_EX` over `T_OBJECT` because `T_OBJECT_EX` handles use of the `del` statement on that attribute more correctly than `T_OBJECT`.

flags can be 0 for write and read access or `READONLY` for read-only access. Using `T_STRING` for type implies `READONLY`. `T_STRING` data is interpreted as UTF-8. Only `T_OBJECT` and `T_OBJECT_EX` members can be deleted. (They are set to `NULL`).

Heap allocated types (created using `PyType_FromSpec()` or similar), `PyMemberDef` may contain definitions for the special members `__dictoffset__`, `__weaklistoffset__` and `__vectorcalloffset__`, corresponding to `tp_dictoffset`, `tp_weaklistoffset` and `tp_vectorcall_offset` in type objects. These must be defined with `T_PYSSIZET` and `READONLY`, for example:

```
static PyMemberDef spam_type_members[] = {
    {"__dictoffset__", T_PYSSIZET, offsetof(Spam_object, dict), READONLY},
    {NULL} /* Sentinel */
};
```

`PyObject* PyMember_GetOne` (const char \*obj\_addr, struct *PyMemberDef* \*m)

Get an attribute belonging to the object at address *obj\_addr*. The attribute is described by `PyMemberDef` *m*. Returns `NULL` on error.

int `PyMember_SetOne` (char \*obj\_addr, struct *PyMemberDef* \*m, *PyObject* \*o)

Set an attribute belonging to the object at address *obj\_addr* to object *o*. The attribute to set is described by `PyMemberDef` *m*. Returns 0 if successful and a negative value on failure.

type `PyGetSetDef`

Μέρος του **Σταθερό ABI** (συμπεριλαμβανομένων όλων των μελών). Structure to define property-like access for a type. See also description of the `PyTypeObject.tp_getset` slot.

Field	C Type	Meaning
name	const char *	attribute name
get	getter	C function to get the attribute
set	setter	optional C function to set or delete the attribute, if omitted the attribute is readonly
doc	const char *	optional docstring
closure	void *	optional user data pointer, providing additional data for getter and setter

The `get` function takes one `PyObject*` parameter (the instance) and a user data pointer (the associated closure):

```
typedef PyObject *(*getter) (PyObject *, void *);
```

It should return a new reference on success or `NULL` with a set exception on failure.

set functions take two `PyObject*` parameters (the instance and the value to be set) and a user data pointer (the associated closure):

```
typedef int (*setter) (PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is `NULL`. Should return 0 on success or -1 with a set exception on failure.

## 12.3 Type Objects

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the *PyTypeObject* structure. Type objects can be handled using any of the `PyObject_*` or `PyType_*` functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the *Examples* section provides at-a-glance insight into the meaning and use of *PyTypeObject*.

### 12.3.1 Quick Reference

«tp slots»

PyTypeObject Slot <small>Σελίδα 242, 1</small>	Type	special methods/attrs	Info <small>Σελίδα 242, 2</small>				
			C	T	D	I	
<R> <i>tp_name</i>	const char *	<code>__name__</code>	X	X			
<i>tp_basicsize</i>	<i>Py_ssize_t</i>		X	X			X
<i>tp_itemsize</i>	<i>Py_ssize_t</i>			X			X
<i>tp_dealloc</i>	destructor		X	X			X
<i>tp_vectorcall_offset</i>	<i>Py_ssize_t</i>			X			X
( <i>tp_getattr</i> )	<i>getattrfunc</i>	<code>__getattr__</code> , <code>__getattribute__</code>					G
( <i>tp_setattr</i> )	<i>setattrfunc</i>	<code>__setattr__</code> , <code>__delattr__</code>					G
<i>tp_as_async</i>	<i>PyAsyncMethods</i> *	<i>sub-slots</i>					%
<i>tp_repr</i>	<i>reprfunc</i>	<code>__repr__</code>	X	X			X
<i>tp_as_number</i>	<i>PyNumberMethods</i> *	<i>sub-slots</i>					%
<i>tp_as_sequence</i>	<i>PySequenceMethods</i> *	<i>sub-slots</i>					%
<i>tp_as_mapping</i>	<i>PyMappingMethods</i> *	<i>sub-slots</i>					%
<i>tp_hash</i>	<i>hashfunc</i>	<code>__hash__</code>	X				G
<i>tp_call</i>	<i>ternaryfunc</i>	<code>__call__</code>		X			X
<i>tp_str</i>	<i>reprfunc</i>	<code>__str__</code>	X				X
<i>tp_getattro</i>	<i>getattrofunc</i>	<code>__getattr__</code> , <code>__getattribute__</code>	X	X			G
<i>tp_setattro</i>	<i>setattrofunc</i>	<code>__setattr__</code> , <code>__delattr__</code>	X	X			G
<i>tp_as_buffer</i>	<i>PyBufferProcs</i> *						%
<i>tp_flags</i>	unsigned long		X	X			?
<i>tp_doc</i>	const char *	<code>__doc__</code>	X	X			
<i>tp_traverse</i>	<i>traverseproc</i>			X			G
<i>tp_clear</i>	<i>inquiry</i>			X			G
<i>tp_richcompare</i>	<i>richcmpfunc</i>	<code>__lt__</code> , <code>__le__</code> , <code>__eq__</code> , <code>__ne__</code> , <code>__gt__</code> , <code>__ge__</code>	X				G
<i>tp_weaklistoffset</i>	<i>Py_ssize_t</i>			X			?
<i>tp_iter</i>	<i>getiterfunc</i>	<code>__iter__</code>					X
<i>tp_iternext</i>	<i>iternextfunc</i>	<code>__next__</code>					X
<i>tp_methods</i>	<i>PyMethodDef</i> []		X	X			
<i>tp_members</i>	<i>PyMemberDef</i> []			X			
<i>tp_getset</i>	<i>PyGetSetDef</i> []		X	X			
<i>tp_base</i>	<i>PyTypeObject</i> *	<code>__base__</code>				X	
<i>tp_dict</i>	<i>PyObject</i> *	<code>__dict__</code>				?	
<i>tp_descr_get</i>	<i>descrgetfunc</i>	<code>__get__</code>					X
<i>tp_descr_set</i>	<i>descrsetfunc</i>	<code>__set__</code> , <code>__delete__</code>					X

συνέχεια στην επόμενη σελίδα

Πίνακας 1 – συνεχίζεται από την προηγούμενη σελίδα

PyTypeObject Slot <sup>Σελίδα 242, 1</sup>	Type	special methods/attrs	Info <sup>2</sup>				
			C	T	D	I	
<code>tp_dictoffset</code>	<code>Py_ssize_t</code>			X			?
<code>tp_init</code>	<code>initproc</code>	<code>__init__</code>	X	X			X
<code>tp_alloc</code>	<code>allocfunc</code>		X		?		?
<code>tp_new</code>	<code>newfunc</code>	<code>__new__</code>	X	X	?		?
<code>tp_free</code>	<code>freefunc</code>		X	X	?		?
<code>tp_is_gc</code>	<code>inquiry</code>			X			X
<code>&lt;tp_bases&gt;</code>	<code>PyObject *</code>	<code>__bases__</code>				~	
<code>&lt;tp_mro&gt;</code>	<code>PyObject *</code>	<code>__mro__</code>				~	
<code>[tp_cache]</code>	<code>PyObject *</code>						
<code>[tp_subclasses]</code>	<code>PyObject *</code>	<code>__subclasses__</code>					
<code>[tp_weaklist]</code>	<code>PyObject *</code>						
<code>(tp_del)</code>	<code>destructor</code>						
<code>[tp_version_tag]</code>	<code>unsigned int</code>						
<code>tp_finalize</code>	<code>destructor</code>	<code>__del__</code>					X
<code>tp_vectorcall</code>	<code>vectorcallfunc</code>						

## sub-slots

Slot	Type	special methods
<code>am_await</code>	<code>unaryfunc</code>	<code>__await__</code>
<code>am_aiter</code>	<code>unaryfunc</code>	<code>__aiter__</code>
<code>am_anext</code>	<code>unaryfunc</code>	<code>__anext__</code>
<code>am_send</code>	<code>sendfunc</code>	
<code>nb_add</code>	<code>binaryfunc</code>	<code>__add__</code> <code>__radd__</code>
<code>nb_inplace_add</code>	<code>binaryfunc</code>	<code>__iadd__</code>
<code>nb_subtract</code>	<code>binaryfunc</code>	<code>__sub__</code> <code>__rsub__</code>
<code>nb_inplace_subtract</code>	<code>binaryfunc</code>	<code>__isub__</code>
<code>nb_multiply</code>	<code>binaryfunc</code>	<code>__mul__</code> <code>__rmul__</code>
<code>nb_inplace_multiply</code>	<code>binaryfunc</code>	<code>__imul__</code>
<code>nb_remainder</code>	<code>binaryfunc</code>	<code>__mod__</code> <code>__rmod__</code>
<code>nb_inplace_remainder</code>	<code>binaryfunc</code>	<code>__imod__</code>

συνέχεια στην επόμενη σελίδα

<sup>1</sup> ( ): A slot name in parentheses indicates it is (effectively) deprecated.

&lt;&gt;: Names in angle brackets should be initially set to NULL and treated as read-only.

[]: Names in square brackets are for internal use only.

&lt;R&gt; (as a prefix) means the field is required (must be non-NULL).

<sup>2</sup> Columns:«O»: set on `PyBaseObject_Type`«T»: set on `PyType_Type`

«D»: default (if slot is set to NULL)

X - `PyType_Ready` sets this value if it is NULL~ - `PyType_Ready` always sets this value (it should be NULL)? - `PyType_Ready` may set this value depending on other slots

Also see the inheritance column ("I").

«I»: inheritance

X - type slot is inherited via `*PyType_Ready*` if defined with a `*NULL*` value

% - the slots of the sub-struct are inherited individually

G - inherited, but only in combination with other slots; see the slot's description

? - it's complicated; see the slot's description

Note that some slots are effectively inherited through the normal attribute lookup chain.

Πίνακας 2 – συνεχίζεται από την προηγούμενη σελίδα

Slot	Type	special methods
<i>nb_divmod</i>	<i>binaryfunc</i>	<code>__divmod__</code> <code>__rdivmod__</code>
<i>nb_power</i>	<i>ternaryfunc</i>	<code>__pow__</code> <code>__rpow__</code>
<i>nb_inplace_power</i>	<i>ternaryfunc</i>	<code>__ipow__</code>
<i>nb_negative</i>	<i>unaryfunc</i>	<code>__neg__</code>
<i>nb_positive</i>	<i>unaryfunc</i>	<code>__pos__</code>
<i>nb_absolute</i>	<i>unaryfunc</i>	<code>__abs__</code>
<i>nb_bool</i>	<i>inquiry</i>	<code>__bool__</code>
<i>nb_invert</i>	<i>unaryfunc</i>	<code>__invert__</code>
<i>nb_lshift</i>	<i>binaryfunc</i>	<code>__lshift__</code> <code>__rlshift__</code>
<i>nb_inplace_lshift</i>	<i>binaryfunc</i>	<code>__ilshift__</code>
<i>nb_rshift</i>	<i>binaryfunc</i>	<code>__rshift__</code> <code>__rrshift__</code>
<i>nb_inplace_rshift</i>	<i>binaryfunc</i>	<code>__irshift__</code>
<i>nb_and</i>	<i>binaryfunc</i>	<code>__and__</code> <code>__rand__</code>
<i>nb_inplace_and</i>	<i>binaryfunc</i>	<code>__iand__</code>
<i>nb_xor</i>	<i>binaryfunc</i>	<code>__xor__</code> <code>__rxor__</code>
<i>nb_inplace_xor</i>	<i>binaryfunc</i>	<code>__ixor__</code>
<i>nb_or</i>	<i>binaryfunc</i>	<code>__or__</code> <code>__ror__</code>
<i>nb_inplace_or</i>	<i>binaryfunc</i>	<code>__ior__</code>
<i>nb_int</i>	<i>unaryfunc</i>	<code>__int__</code>
<i>nb_reserved</i>	<b>void *</b>	
<i>nb_float</i>	<i>unaryfunc</i>	<code>__float__</code>
<i>nb_floor_divide</i>	<i>binaryfunc</i>	<code>__floordiv__</code>
<i>nb_inplace_floor_divide</i>	<i>binaryfunc</i>	<code>__ifloordiv__</code>
<i>nb_true_divide</i>	<i>binaryfunc</i>	<code>__truediv__</code>
<i>nb_inplace_true_divide</i>	<i>binaryfunc</i>	<code>__itruediv__</code>
<i>nb_index</i>	<i>unaryfunc</i>	<code>__index__</code>
<i>nb_matrix_multiply</i>	<i>binaryfunc</i>	<code>__matmul__</code> <code>__rmatmul__</code>
<i>nb_inplace_matrix_multiply</i>	<i>binaryfunc</i>	<code>__imatmul__</code>
<i>mp_length</i>	<i>lenfunc</i>	<code>__len__</code>
<i>mp_subscript</i>	<i>binaryfunc</i>	<code>__getitem__</code>
<i>mp_ass_subscript</i>	<i>objobjargproc</i>	<code>__setitem__</code> , <code>__delitem__</code>
<i>sq_length</i>	<i>lenfunc</i>	<code>__len__</code>
<i>sq_concat</i>	<i>binaryfunc</i>	<code>__add__</code>
<i>sq_repeat</i>	<i>ssizeargfunc</i>	<code>__mul__</code>
<i>sq_item</i>	<i>ssizeargfunc</i>	<code>__getitem__</code>
<i>sq_ass_item</i>	<i>ssizeobjargproc</i>	<code>__setitem__</code> <code>__delitem__</code>
<i>sq_contains</i>	<i>objobjproc</i>	<code>__contains__</code>
<i>sq_inplace_concat</i>	<i>binaryfunc</i>	<code>__iadd__</code>
<i>sq_inplace_repeat</i>	<i>ssizeargfunc</i>	<code>__imul__</code>
<i>bf_getbuffer</i>	<i>getbufferproc()</i>	
<i>bf_releasebuffer</i>	<i>releasebufferproc()</i>	



## slot typedefs

typedef	Parameter Types	Return Type
<i>allocfunc</i>	<i>PyTypeObject</i> * <i>Py_ssize_t</i>	<i>PyObject</i> *
<i>destructor</i>	<i>PyObject</i> *	void
<i>freefunc</i>	void *	void
<i>traverseproc</i>	<i>PyObject</i> * <i>visitproc</i> void *	int
<i>newfunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<i>initproc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	int
<i>reprfunc</i>	<i>PyObject</i> *	<i>PyObject</i> *
<i>getattrfunc</i>	<i>PyObject</i> * <i>const char</i> *	<i>PyObject</i> *
<i>setattrfunc</i>	<i>PyObject</i> * <i>const char</i> * <i>PyObject</i> *	int
<i>getattrofunc</i>	<i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<i>setattrofunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	int
<i>descrgetfunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<i>descrsetfunc</i>	<i>PyObject</i> *	int
<b>12.3. Type Objects</b>	<i>PyObject</i> * <i>PyObject</i> *	<b>245</b>
<i>hashfunc</i>	<i>PyObject</i> *	<i>Py_hash_t</i>
<i>richcmpfunc</i>		<i>PyObject</i> *

See *Slot Type typedefs* below for more detail.

### 12.3.2 PyTypeObject Definition

The structure definition for *PyTypeObject* can be found in `Include/object.h`. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
    PyObject_VAR_HEAD
    const char *tp_name; /* For printing, in format "<module>.<name>" */
    Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */

    /* Methods to implement standard operations */

    destructor tp_dealloc;
    Py_ssize_t tp_vectorcall_offset;
    getattrofunc tp_getattr;
    setattrofunc tp_setattr;
    PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                   or tp_reserved (Python 3) */
    reprfunc tp_repr;

    /* Method suites for standard classes */

    PyNumberMethods *tp_as_number;
    PySequenceMethods *tp_as_sequence;
    PyMappingMethods *tp_as_mapping;

    /* More standard operations (here for binary compatibility) */

    hashfunc tp_hash;
    ternaryfunc tp_call;
    reprfunc tp_str;
    getattrofunc tp_getattro;
    setattrofunc tp_setattro;

    /* Functions to access object as input/output buffer */
    PyBufferProcs *tp_as_buffer;

    /* Flags to define presence of optional/expanded features */
    unsigned long tp_flags;

    const char *tp_doc; /* Documentation string */

    /* Assigned meaning in release 2.0 */
    /* call function for all accessible objects */
    traverseproc tp_traverse;

    /* delete references to contained objects */
    inquiry tp_clear;

    /* Assigned meaning in release 2.1 */
    /* rich comparisons */
    richcmpfunc tp_richcompare;

    /* weak reference enabler */
    Py_ssize_t tp_weaklistoffset;

    /* Iterators */
    getiterfunc tp_iter;
    iternextfunc tp_iternext;
}
```

(συνέχεια στην επόμενη σελίδα)



(συνεχίζεται από την προηγούμενη σελίδα)

```

/* Attribute descriptor and subclassing stuff */
struct PyMethodDef *tp_methods;
struct PyMemberDef *tp_members;
struct PyGetSetDef *tp_getset;
// Strong reference on a heap type, borrowed reference on a static type
struct _typeobject *tp_base;
PyObject *tp_dict;
descrgetfunc tp_descr_get;
descrsetfunc tp_descr_set;
Py_ssize_t tp_dictoffset;
initproc tp_init;
allocfunc tp_alloc;
newfunc tp_new;
freefunc tp_free; /* Low-level free-memory routine */
inquiry tp_is_gc; /* For PyObject_IS_GC */
PyObject *tp_bases;
PyObject *tp_mro; /* method resolution order */
PyObject *tp_cache;
PyObject *tp_subclasses;
PyObject *tp_weaklist;
destructor tp_del;

/* Type attribute cache version tag. Added in version 2.6 */
unsigned int tp_version_tag;

destructor tp_finalize;
vectorcallfunc tp_vectorcall;
} PyTypeObject;

```

### 12.3.3 PyObject Slots

The type object structure extends the *PyVarObject* structure. The *ob\_size* field is used for dynamic types (created by *type\_new()*, usually called from a class statement). Note that *PyType\_Type* (the metatype) initializes *tp\_itemsize*, which means that its instances (i.e. type objects) *must* have the *ob\_size* field.

#### *Py\_ssize\_t* *PyObject.ob\_refcnt*

*Μέρος του Σταθερό ABI.* This is the type object's reference count, initialized to 1 by the *PyObject\_HEAD\_INIT* macro. Note that for *statically allocated type objects*, the type's instances (objects whose *ob\_type* points back to the type) do *not* count as references. But for *dynamically allocated type objects*, the instances *do* count as references.

#### Inheritance:

This field is not inherited by subtypes.

#### *PyTypeObject* \**PyObject.ob\_type*

*Μέρος του Σταθερό ABI.* This is the type's type, in other words its metatype. It is initialized by the argument to the *PyObject\_HEAD\_INIT* macro, and its value should normally be *&PyType\_Type*. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass *NULL* to the *PyObject\_HEAD\_INIT* macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. *PyType\_Ready()* checks if *ob\_type* is *NULL*, and if so, initializes it to the *ob\_type* field of the base class. *PyType\_Ready()* will not change this field if it is non-zero.

**Inheritance:**

This field is inherited by subtypes.

*PyObject* \**PyObject*.**`_ob_next`**

*PyObject* \**PyObject*.**`_ob_prev`**

These fields are only present when the macro `Py_TRACE_REFS` is defined (see the configure `--with-trace-refs` option).

Their initialization to `NULL` is taken care of by the `PyObject_HEAD_INIT` macro. For *statically allocated objects*, these fields always remain `NULL`. For *dynamically allocated objects*, these two fields are used to link the object into a doubly linked list of *all* live objects on the heap.

This could be used for various debugging purposes; currently the only uses are the `sys.getobjects()` function and to print the objects that are still alive at the end of a run when the environment variable `PYTHONDUMPREFS` is set.

**Inheritance:**

These fields are not inherited by subtypes.

### 12.3.4 PyVarObject Slots

*Py\_ssize\_t* *PyVarObject*.**`ob_size`**

Μέρος του Σταθερό ABI. For *statically allocated type objects*, this should be initialized to zero. For *dynamically allocated type objects*, this field has a special internal meaning.

**Inheritance:**

This field is not inherited by subtypes.

### 12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If *PyType\_Ready()* may set a value when the field is set to `NULL` then there will also be a «Default» section. (Note that many fields set on *PyBaseObject\_Type* and *PyType\_Type* effectively act as defaults.)

`const char` \**PyTypeObject*.**`tp_name`**

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named `T` defined in module `M` in subpackage `Q` in package `P` should have the *tp\_name* initializer `"P.Q.M.T"`.

For *dynamically allocated type objects*, this should just be the type name, and the module name explicitly stored in the type dict as the value for key `'__module__'`.

For *statically allocated type objects*, the *tp\_name* field should contain a dot. Everything before the last dot is made accessible as the `__module__` attribute, and everything after the last dot is made accessible as the `__name__` attribute.

If no dot is present, the entire *tp\_name* field is made accessible as the `__name__` attribute, and the `__module__` attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with `pydoc`.

This field must not be `NULL`. It is the only required field in *PyTypeObject()* (other than potentially *tp\_itemsize*).

**Inheritance:**

This field is not inherited by subtypes.

*Py\_ssize\_t* *PyObject.tp\_basicsize*

*Py\_ssize\_t* *PyObject.tp\_itemsize*

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero *tp\_itemsize* field, types with variable-length instances have a non-zero *tp\_itemsize* field. For a type with fixed-length instances, all instances have the same size, given in *tp\_basicsize*.

For a type with variable-length instances, the instances must have an *ob\_size* field, and the instance size is *tp\_basicsize* plus N times *tp\_itemsize*, where N is the «length» of the object. The value of N is typically stored in the instance's *ob\_size* field. There are exceptions: for example, ints use a negative *ob\_size* to indicate a negative number, and N is `abs(ob_size)` there. Also, the presence of an *ob\_size* field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful *ob\_size* field).

The basic size includes the fields in the instance declared by the macro *PyObject\_HEAD* or *PyObject\_VAR\_HEAD* (whichever is used to declare the instance struct) and this in turn includes the *\_ob\_prev* and *\_ob\_next* fields if they are present. This means that the only correct way to get an initializer for the *tp\_basicsize* is to use the `sizeof` operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of *tp\_basicsize*. Example: suppose a type implements an array of double. *tp\_itemsize* is `sizeof(double)`. It is the programmer's responsibility that *tp\_basicsize* is a multiple of `sizeof(double)` (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be NULL.

#### Inheritance:

These fields are inherited separately by subtypes. If the base type has a non-zero *tp\_itemsize*, it is generally not safe to set *tp\_itemsize* to a different non-zero value in a subtype (though this depends on the implementation of the base type).

*destructor PyObject.tp\_dealloc*

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons `None` and `Ellipsis`). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the *Py\_DECREF()* and *Py\_XDECREF()* macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type's *tp\_free* function. If the type is not subtypable (doesn't have the *Py\_TPFLAGS\_BASETYPE* flag bit set), it is permissible to call the object deallocator directly instead of via *tp\_free*. The object deallocator should be the one used to allocate the instance; this is normally *PyObject\_Del()* if the instance was allocated using *PyObject\_New* or *PyObject\_NewVar*, or *PyObject\_GC\_Del()* if the instance was allocated using *PyObject\_GC\_New* or *PyObject\_GC\_NewVar*.

If the type supports garbage collection (has the *Py\_TPFLAGS\_HAVE\_GC* flag bit set), the destructor should call *PyObject\_GC\_UnTrack()* before clearing any member fields.

```
static void foo_dealloc(foo_object *self) {
    PyObject_GC_UnTrack(self);
    Py_CLEAR(self->ref);
    Py_TYPE(self)->tp_free((PyObject *)self);
}
```

Finally, if the type is heap allocated (*Py\_TPFLAGS\_HEAPTYPE*), the deallocator should release the owned reference to its type object (via *Py\_DECREF()*) after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is:

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
    // free references and buffers here
    tp->tp_free(self);
    Py_DECREF(tp);
}
```

**Inheritance:**

This field is inherited by subtypes.

*Py\_ssize\_t* *PyTypeObject*.**tp\_vectorcall\_offset**

An optional offset to a per-instance function that implements calling the object using the *vectorcall protocol*, a more efficient alternative of the simpler *tp\_call*.

This field is only used if the flag *Py\_TPFLAGS\_HAVE\_VECTORCALL* is set. If so, this must be a positive integer containing the offset in the instance of a *vectorcallfunc* pointer.

The *vectorcallfunc* pointer may be NULL, in which case the instance behaves as if *Py\_TPFLAGS\_HAVE\_VECTORCALL* was not set: calling the instance falls back to *tp\_call*.

Any class that sets *Py\_TPFLAGS\_HAVE\_VECTORCALL* must also set *tp\_call* and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting *tp\_call* to *PyVectorcall\_Call()*.

**Προειδοποίηση:** It is not recommended for *mutable heap types* to implement the vectorcall protocol. When a user sets `__call__` in Python code, only *tp\_call* is updated, likely making it inconsistent with the vectorcall function.

Αλλάξε στην έκδοση 3.8: Before version 3.8, this slot was named *tp\_print*. In Python 2.x, it was used for printing to a file. In Python 3.0 to 3.7, it was unused.

**Inheritance:**

This field is always inherited. However, the *Py\_TPFLAGS\_HAVE\_VECTORCALL* flag is not always inherited. If it's not, then the subclass won't use *vectorcall*, except when *PyVectorcall\_Call()* is explicitly called. This is in particular the case for types without the *Py\_TPFLAGS\_IMMUTABLETYPE* flag set (including subclasses defined in Python).

*getattrfunc* *PyTypeObject*.**tp\_getattr**

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the *tp\_getattro* function, but taking a C string instead of a Python string object to give the attribute name.

**Inheritance:**

Group: *tp\_getattr*, *tp\_getattro*

This field is inherited by subtypes together with *tp\_getattro*: a subtype inherits both *tp\_getattr* and *tp\_getattro* from its base type when the subtype's *tp\_getattr* and *tp\_getattro* are both NULL.

*setattrfunc* *PyTypeObject*.**tp\_setattr**

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the *tp\_setattro* function, but taking a C string instead of a Python string object to give the attribute name.

**Inheritance:**

Group: *tp\_setattr*, *tp\_setattro*

This field is inherited by subtypes together with *tp\_setattro*: a subtype inherits both *tp\_setattr* and *tp\_setattro* from its base type when the subtype's *tp\_setattr* and *tp\_setattro* are both NULL.

*PyAsyncMethods* \*PyTypeObject.tp\_as\_async

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

Νέο στην έκδοση 3.5: Formerly known as `tp_compare` and `tp_reserved`.

**Inheritance:**

The `tp_as_async` field is not inherited, but the contained fields are inherited individually.

*reprfunc* PyTypeObject.tp\_repr

An optional pointer to a function that implements the built-in function `repr()`.

The signature is the same as for *PyObject\_Repr()*:

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to `eval()`, given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '`<`' and ending with '`>`' from which both the type and the value of the object can be deduced.

**Inheritance:**

This field is inherited by subtypes.

**Default:**

When this field is not set, a string of the form `<%s object at %p>` is returned, where `%s` is replaced by the type name, and `%p` by the object's memory address.

*PyNumberMethods* \*PyTypeObject.tp\_as\_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

**Inheritance:**

The `tp_as_number` field is not inherited, but the contained fields are inherited individually.

*PySequenceMethods* \*PyTypeObject.tp\_as\_sequence

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

**Inheritance:**

The `tp_as_sequence` field is not inherited, but the contained fields are inherited individually.

*PyMappingMethods* \*PyTypeObject.tp\_as\_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

**Inheritance:**

The `tp_as_mapping` field is not inherited, but the contained fields are inherited individually.

*hashfunc* PyTypeObject.tp\_hash

An optional pointer to a function that implements the built-in function `hash()`.

The signature is the same as for *PyObject\_Hash()*:

```
Py_hash_t tp_hash(PyObject *);
```

The value `-1` should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return `-1`.

When this field is not set (and `tp_richcompare` is not set), an attempt to take the hash of the object raises `TypeError`. This is the same as setting it to *PyObject\_HashNotImplemented()*.

This field can be set explicitly to `PyObject_HashNotImplemented()` to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of `__hash__ = None` at the Python level, causing `isinstance(o, collections.Hashable)` to correctly return `False`. Note that the converse is also true - setting `__hash__ = None` on a class at the Python level will result in the `tp_hash` slot being set to `PyObject_HashNotImplemented()`.

**Inheritance:**

Group: `tp_hash`, `tp_richcompare`

This field is inherited by subtypes together with `tp_richcompare`: a subtype inherits both of `tp_richcompare` and `tp_hash`, when the subtype's `tp_richcompare` and `tp_hash` are both `NULL`.

*ternaryfunc* `PyTypeObject.tp_call`

An optional pointer to a function that implements calling the object. This should be `NULL` if the object is not callable. The signature is the same as for `PyObject_Call()`:

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

**Inheritance:**

This field is inherited by subtypes.

*reprfunc* `PyTypeObject.tp_str`

An optional pointer to a function that implements the built-in operation `str()`. (Note that `str` is a type now, and `str()` calls the constructor for that type. This constructor calls `PyObject_Str()` to do the actual work, and `PyObject_Str()` will call this handler.)

The signature is the same as for `PyObject_Str()`:

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a «friendly» string representation of the object, as this is the representation that will be used, among other things, by the `print()` function.

**Inheritance:**

This field is inherited by subtypes.

**Default:**

When this field is not set, `PyObject_Repr()` is called to return a string representation.

*getattrfunc* `PyTypeObject.tp_getattro`

An optional pointer to the get-attribute function.

The signature is the same as for `PyObject_GetAttr()`:

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to `PyObject_GenericGetAttr()`, which implements the normal way of looking for object attributes.

**Inheritance:**

Group: `tp_getattr`, `tp_getattro`

This field is inherited by subtypes together with `tp_getattr`: a subtype inherits both `tp_getattr` and `tp_getattro` from its base type when the subtype's `tp_getattr` and `tp_getattro` are both `NULL`.

**Default:**

`PyBaseObject_Type` uses `PyObject_GenericGetAttr()`.

*setattrfunc* `PyTypeObject.tp_setattro`

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for `PyObject_SetAttr()`:

```
int tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to NULL to delete an attribute must be supported. It is usually convenient to set this field to `PyObject_GenericSetAttr()`, which implements the normal way of setting object attributes.

#### Inheritance:

Group: `tp_setattr`, `tp_setattro`

This field is inherited by subtypes together with `tp_setattr`: a subtype inherits both `tp_setattr` and `tp_setattro` from its base type when the subtype's `tp_setattr` and `tp_setattro` are both NULL.

#### Default:

`PyBaseObject_Type` uses `PyObject_GenericSetAttr()`.

`PyBufferProcs *PyTypeObject.tp_as_buffer`

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

#### Inheritance:

The `tp_as_buffer` field is not inherited, but the contained fields are inherited individually.

unsigned long `PyTypeObject.tp_flags`

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via `tp_as_number`, `tp_as_sequence`, `tp_as_mapping`, and `tp_as_buffer`) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

#### Inheritance:

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The `Py_TPFLAGS_HAVE_GC` flag bit is inherited together with the `tp_traverse` and `tp_clear` fields, i.e. if the `Py_TPFLAGS_HAVE_GC` flag bit is clear in the subtype and the `tp_traverse` and `tp_clear` fields in the subtype exist and have NULL values.

#### Default:

`PyBaseObject_Type` uses `Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE`.

#### Bit Masks:

The following bit masks are currently defined; these can be ORed together using the `|` operator to form the value of the `tp_flags` field. The macro `PyType_HasFeature()` takes a type and a flags value, *tp* and *f*, and checks whether `tp->tp_flags & f` is non-zero.

#### `Py_TPFLAGS_HEAPTYPE`

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using `PyType_FromSpec()`. In this case, the `ob_type` field of its instances is considered a reference to the type, and the type object is INCREf'ed when a new instance is created, and DECREf'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's `ob_type` gets INCREf'ed or DECREf'ed).

#### Inheritance:

???

#### `Py_TPFLAGS_BASETYPE`

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a «final» class in Java).

#### Inheritance:



???

**Py\_TPFLAGS\_READY**

This bit is set when the type object has been fully initialized by `PyType_Ready()`.

**Inheritance:**

???

**Py\_TPFLAGS\_READYING**

This bit is set while `PyType_Ready()` is in the process of initializing the type object.

**Inheritance:**

???

**Py\_TPFLAGS\_HAVE\_GC**

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using `PyObject_GC_New` and destroyed using `PyObject_GC_Del()`. More information in section *Supporting Cyclic Garbage Collection*. This bit also implies that the GC-related fields `tp_traverse` and `tp_clear` are present in the type object.

**Inheritance:**

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

The `Py_TPFLAGS_HAVE_GC` flag bit is inherited together with the `tp_traverse` and `tp_clear` fields, i.e. if the `Py_TPFLAGS_HAVE_GC` flag bit is clear in the subtype and the `tp_traverse` and `tp_clear` fields in the subtype exist and have NULL values.

**Py\_TPFLAGS\_DEFAULT**

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: `Py_TPFLAGS_HAVE_STACKLESS_EXTENSION`.

**Inheritance:**

???

**Py\_TPFLAGS\_METHOD\_DESCRIPTOR**

This bit indicates that objects behave like unbound methods.

If this flag is set for `type(meth)`, then:

- `meth.__get__(obj, cls)(*args, **kwds)` (with `obj` not None) must be equivalent to `meth(obj, *args, **kwds)`.
- `meth.__get__(None, cls)(*args, **kwds)` must be equivalent to `meth(*args, **kwds)`.

This flag enables an optimization for typical method calls like `obj.meth()`: it avoids creating a temporary «bound method» object for `obj.meth`.

Νέο στην έκδοση 3.8.

**Inheritance:**

This flag is never inherited by types without the `Py_TPFLAGS_IMMUTABLETYPE` flag set. For extension types, it is inherited whenever `tp_descr_get` is inherited.

**Py\_TPFLAGS\_LONG\_SUBCLASS****Py\_TPFLAGS\_LIST\_SUBCLASS****Py\_TPFLAGS\_TUPLE\_SUBCLASS****Py\_TPFLAGS\_BYTES\_SUBCLASS**



**Py\_TPFLAGS\_UNICODE\_SUBCLASS****Py\_TPFLAGS\_DICT\_SUBCLASS****Py\_TPFLAGS\_BASE\_EXC\_SUBCLASS****Py\_TPFLAGS\_TYPE\_SUBCLASS**

These flags are used by functions such as *PyLong\_Check()* to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like *PyObject\_IsInstance()*. Custom types that inherit from built-ins should have their *tp\_flags* set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

**Py\_TPFLAGS\_HAVE\_FINALIZE**

This bit is set when the *tp\_finalize* slot is present in the type structure.

Νέο στην έκδοση 3.4.

Αποσύρθηκε στην έκδοση 3.8: This flag isn't necessary anymore, as the interpreter assumes the *tp\_finalize* slot is always present in the type structure.

**Py\_TPFLAGS\_HAVE\_VECTORCALL**

This bit is set when the class implements the *vectorcall protocol*. See *tp\_vectorcall\_offset* for details.

**Inheritance:**

This bit is inherited for types with the *Py\_TPFLAGS\_IMMUTABLETYPE* flag set, if *tp\_call* is also inherited.

Νέο στην έκδοση 3.9.

**Py\_TPFLAGS\_IMMUTABLETYPE**

This bit is set for type objects that are immutable: type attributes cannot be set nor deleted.

*PyType\_Ready()* automatically applies this flag to *static types*.

**Inheritance:**

This flag is not inherited.

Νέο στην έκδοση 3.10.

**Py\_TPFLAGS\_DISALLOW\_INSTANTIATION**

Disallow creating instances of the type: set *tp\_new* to NULL and don't create the *\_\_new\_\_* key in the type dictionary.

The flag must be set before creating the type, not after. For example, it must be set before *PyType\_Ready()* is called on the type.

The flag is set automatically on *static types* if *tp\_base* is NULL or *&PyBaseObject\_Type* and *tp\_new* is NULL.

**Inheritance:**

This flag is not inherited. However, subclasses will not be instantiable unless they provide a non-NULL *tp\_new* (which is only possible via the C API).

---

**Σημείωση:** To disallow instantiating a class directly but allow instantiating its subclasses (e.g. for an *abstract base class*), do not use this flag. Instead, make *tp\_new* only succeed for subclasses.

---

Νέο στην έκδοση 3.10.

**Py\_TPFLAGS\_MAPPING**

This bit indicates that instances of the class may match mapping patterns when used as the subject of a match block. It is automatically set when registering or subclassing `collections.abc.Mapping`, and unset when registering `collections.abc.Sequence`.

---

**Σημείωση:** `Py_TPFLAGS_MAPPING` and `Py_TPFLAGS_SEQUENCE` are mutually exclusive; it is an error to enable both flags simultaneously.

---

**Inheritance:**

This flag is inherited by types that do not already set `Py_TPFLAGS_SEQUENCE`.

**Δείτε επίσης:**

**PEP 634** – Structural Pattern Matching: Specification

Νέο στην έκδοση 3.10.

**Py\_TPFLAGS\_SEQUENCE**

This bit indicates that instances of the class may match sequence patterns when used as the subject of a match block. It is automatically set when registering or subclassing `collections.abc.Sequence`, and unset when registering `collections.abc.Mapping`.

---

**Σημείωση:** `Py_TPFLAGS_MAPPING` and `Py_TPFLAGS_SEQUENCE` are mutually exclusive; it is an error to enable both flags simultaneously.

---

**Inheritance:**

This flag is inherited by types that do not already set `Py_TPFLAGS_MAPPING`.

**Δείτε επίσης:**

**PEP 634** – Structural Pattern Matching: Specification

Νέο στην έκδοση 3.10.

`const char *PyTypeObject.tp_doc`

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the `__doc__` attribute on the type and instances of the type.

**Inheritance:**

This field is *not* inherited by subtypes.

*traverseproc* `PyTypeObject.tp_traverse`

An optional pointer to a traversal function for the garbage collector. This is only used if the `Py_TPFLAGS_HAVE_GC` flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

The `tp_traverse` pointer is used by the garbage collector to detect reference cycles. A typical implementation of a `tp_traverse` function simply calls `Py_VISIT()` on each of the instance's members that are Python objects that the instance owns. For example, this is function `local_traverse()` from the `_thread` extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
}
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```
Py_VISIT(self->kw);
Py_VISIT(self->dict);
return 0;
}
```

Note that `Py_VISIT()` is called only on those members that can participate in reference cycles. Although there is also a `self->key` member, it can only be `NULL` or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the `gc` module's `get_referents()` function will include it.

**Προειδοποίηση:** When implementing `tp_traverse`, only the members that the instance *owns* (by having *strong references* to them) must be visited. For instance, if an object supports weak references via the `tp_weaklist` slot, the pointer supporting the linked list (what `tp_weaklist` points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that `Py_VISIT()` requires the `visit` and `arg` parameters to `local_traverse()` to have these specific names; don't name them just anything.

Instances of *heap-allocated types* hold a reference to their type. Their traversal function must therefore either visit `Py_TYPE(self)`, or delegate this responsibility by calling `tp_traverse` of another heap-allocated type (such as a heap-allocated superclass). If they do not, the type object may not be garbage-collected.

Αλλάξε στην έκδοση 3.9: Heap-allocated types are expected to visit `Py_TYPE(self)` in `tp_traverse`. In earlier versions of Python, due to [bug 40217](#), doing this may lead to crashes in subclasses.

#### Inheritance:

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

This field is inherited by subtypes together with `tp_clear` and the `Py_TPFLAGS_HAVE_GC` flag bit: the flag bit, `tp_traverse`, and `tp_clear` are all inherited from the base type if they are all zero in the subtype.

#### *inquiry* `PyTypeObject.tp_clear`

An optional pointer to a clear function for the garbage collector. This is only used if the `Py_TPFLAGS_HAVE_GC` flag bit is set. The signature is:

```
int tp_clear(PyObject *);
```

The `tp_clear` member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all `tp_clear` functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a `tp_clear` function. For example, the tuple type does not implement a `tp_clear` function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the `tp_clear` functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing `tp_clear`.

Implementations of `tp_clear` should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to `NULL`, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->dict);
}
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

    return 0;
}

```

The `Py_CLEAR()` macro should be used, because clearing references is delicate: the reference to the contained object must not be released (via `Py_DECREF()`) until after the pointer to the contained object is set to `NULL`. This is because releasing the reference may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference *self* again, it's important that the pointer to the contained object be `NULL` at that time, so that *self* knows the contained object can no longer be used. The `Py_CLEAR()` macro performs the operations in a safe order.

Note that `tp_clear` is not *always* called before an instance is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and `tp_dealloc` is called directly.

Because the goal of `tp_clear` functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's `tp_dealloc` function to invoke `tp_clear`.

More information about Python's garbage collection scheme can be found in section [Supporting Cyclic Garbage Collection](#).

#### Inheritance:

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

This field is inherited by subtypes together with `tp_traverse` and the `Py_TPFLAGS_HAVE_GC` flag bit: the flag bit, `tp_traverse`, and `tp_clear` are all inherited from the base type if they are all zero in the subtype.

#### *richcmpfunc* `PyTypeObject.tp_richcompare`

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by `PyTypeObject`.

The function should return the result of the comparison (usually `Py_True` or `Py_False`). If the comparison is undefined, it must return `Py_NotImplemented`, if another error occurred it must return `NULL` and set an exception condition.

The following constants are defined to be used as the third argument for `tp_richcompare` and for `PyObject_RichCompare()`:

Constant	Comparison
<code>Py_LT</code>	<code>&lt;</code>
<code>Py_LE</code>	<code>&lt;=</code>
<code>Py_EQ</code>	<code>==</code>
<code>Py_NE</code>	<code>!=</code>
<code>Py_GT</code>	<code>&gt;</code>
<code>Py_GE</code>	<code>&gt;=</code>

The following macro is defined to ease writing rich comparison functions:

**Py\_RETURN\_RICHCOMPARE** (VAL\_A, VAL\_B, op)

Return `Py_True` or `Py_False` from the function, depending on the result of a comparison. VAL\_A and VAL\_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for `PyObject_RichCompare()`.

The returned value is a new *strong reference*.

On error, sets an exception and returns NULL from the function.

Νέο στην έκδοση 3.7.

#### Inheritance:

Group: `tp_hash`, `tp_richcompare`

This field is inherited by subtypes together with `tp_hash`: a subtype inherits `tp_richcompare` and `tp_hash` when the subtype's `tp_richcompare` and `tp_hash` are both NULL.

#### Default:

`PyBaseObject_Type` provides a `tp_richcompare` implementation, which may be inherited. However, if only `tp_hash` is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

`Py_ssize_t PyObject.tp_weaklistoffset`

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by `PyObject_ClearWeakRefs()` and the `PyWeakref_*` functions. The instance structure needs to include a field of type `PyObject*` which is initialized to NULL.

Do not confuse this field with `tp_weaklist`; that is the list head for weak references to the type object itself.

#### Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via `tp_weaklistoffset`, this should not be a problem.

When a type defined by a class statement has no `__slots__` declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the `tp_weaklistoffset` of that slot's offset.

When a type's `__slots__` declaration contains a slot named `__weakref__`, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's `tp_weaklistoffset`.

When a type's `__slots__` declaration does not contain a slot named `__weakref__`, the type inherits its `tp_weaklistoffset` from its base type.

*getterfunc* `PyTypeObject.tp_iter`

An optional pointer to a function that returns an *iterator* for the object. Its presence normally signals that the instances of this type are *iterable* (although sequences may be iterable without this function).

This function has the same signature as `PyObject_GetIter()`:

```
PyObject *tp_iter(PyObject *self);
```

**Inheritance:**

This field is inherited by subtypes.

*iternextfunc* `PyTypeObject.tp_iternext`

An optional pointer to a function that returns the next item in an *iterator*. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return NULL; a `StopIteration` exception may or may not be set. When another error occurs, it must return NULL too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the `tp_iter` function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as `PyIter_Next()`.

**Inheritance:**

This field is inherited by subtypes.

struct `PyMethodDef *PyTypeObject.tp_methods`

An optional pointer to a static NULL-terminated array of `PyMethodDef` structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see `tp_dict` below) containing a method descriptor.

**Inheritance:**

This field is not inherited by subtypes (methods are inherited through a different mechanism).

struct `PyMemberDef *PyTypeObject.tp_members`

An optional pointer to a static NULL-terminated array of `PyMemberDef` structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see `tp_dict` below) containing a member descriptor.

**Inheritance:**

This field is not inherited by subtypes (members are inherited through a different mechanism).

struct `PyGetSetDef *PyTypeObject.tp_getset`

An optional pointer to a static NULL-terminated array of `PyGetSetDef` structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see `tp_dict` below) containing a getset descriptor.

**Inheritance:**

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

*PyObject* \**PyTypeObject*.**tp\_base**

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

**Σημείωση:** Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be «address constants». Function designators like *PyType\_GenericNew()*, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary “&” operator applied to a non-static variable like *PyBaseObject\_Type* is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, *tp\_base* should be set in the extension module’s init function.

**Inheritance:**

This field is not inherited by subtypes (obviously).

**Default:**

This field defaults to *&PyBaseObject\_Type* (which to Python programmers is known as the type object).

*PyObject* \**PyTypeObject*.**tp\_dict**

The type’s dictionary is stored here by *PyType\_Ready()*.

This field should normally be initialized to NULL before *PyType\_Ready* is called; it may also be initialized to a dictionary containing initial attributes for the type. Once *PyType\_Ready()* has initialized the type, extra attributes for the type may be added to this dictionary only if they don’t correspond to overloaded operations (like *\_\_add\_\_()*).

**Inheritance:**

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

**Default:**

If this field is NULL, *PyType\_Ready()* will assign a new dictionary to it.

**Προειδοποίηση:** It is not safe to use *PyDict\_SetItem()* on or otherwise modify *tp\_dict* with the dictionary C-API.

*descrgetfunc* *PyTypeObject*.**tp\_descr\_get**

An optional pointer to a «descriptor get» function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

**Inheritance:**

This field is inherited by subtypes.

*descrsetfunc* *PyTypeObject*.**tp\_descr\_set**

An optional pointer to a function for setting and deleting a descriptor’s value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to `NULL` to delete the value.

**Inheritance:**

This field is inherited by subtypes.

*Py\_ssize\_t* *PyObject*.**tp\_dictoffset**

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by *PyObject\_GenericGetAttr()*.

Do not confuse this field with *tp\_dict*; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the *end* of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of `str` or `tuple`. Note that the *tp\_basicsize* field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes, *tp\_dictoffset* should be set to `-4` to indicate that the dictionary is at the very end of the structure.

The *tp\_dictoffset* should be regarded as write-only. To get the pointer to the dictionary call *PyObject\_GenericGetDict()*. Calling *PyObject\_GenericGetDict()* may need to allocate memory for the dictionary, so it is may be more efficient to call *PyObject\_GetAttr()* when accessing an attribute on the object.

**Inheritance:**

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via *tp\_dictoffset*, this should not be a problem.

When a type defined by a class statement has no `__slots__` declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the *tp\_dictoffset* is set to that slot's offset.

When a type defined by a class statement has a `__slots__` declaration, the type inherits its *tp\_dictoffset* from its base type.

(Adding a slot named `__dict__` to the `__slots__` declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like `__weakref__` though.)

**Default:**

This slot has no default. For *static types*, if the field is `NULL` then no `__dict__` gets created for instances.

*initproc* *PyObject*.**tp\_init**

An optional pointer to an instance initialization function.

This function corresponds to the `__init__()` method of classes. Like `__init__()`, it is possible to create an instance without calling `__init__()`, and it is possible to reinitialize an instance by calling its `__init__()` method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The *self* argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to `__init__()`.

The *tp\_init* function, if not `NULL`, is called when an instance is created normally by calling its type, after the type's *tp\_new* function has returned an instance of the type. If the *tp\_new* function returns an instance of some other type that is not a subtype of the original type, no *tp\_init* function is called; if *tp\_new* returns an instance of a subtype of the original type, the subtype's *tp\_init* is called.

Returns 0 on success, `-1` and sets an exception on error.



**Inheritance:**

This field is inherited by subtypes.

**Default:**

For *static types* this field does not have a default.

*allocfunc* `PyTypeObject.tp_alloc`

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

**Inheritance:**

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

**Default:**

For dynamic subtypes, this field is always set to `PyType_GenericAlloc()`, to force a standard heap allocation strategy.

For static subtypes, `PyBaseObject_Type` uses `PyType_GenericAlloc()`. That is the recommended value for all statically defined types.

*newfunc* `PyTypeObject.tp_new`

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwargs);
```

The *subtype* argument is the type of the object being created; the *args* and *kwargs* arguments represent positional and keyword arguments of the call to the type. Note that *subtype* doesn't have to equal the type whose `tp_new` function is called; it may be a subtype of that type (but not an unrelated type).

The `tp_new` function should call `subtype->tp_alloc(subtype, nitems)` to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the `tp_init` handler. A good rule of thumb is that for immutable types, all initialization should take place in `tp_new`, while for mutable types, most initialization should be deferred to `tp_init`.

Set the `Py_TPFLAGS_DISALLOW_INSTANTIATION` flag to disallow creating instances of the type in Python.

**Inheritance:**

This field is inherited by subtypes, except it is not inherited by *static types* whose `tp_base` is `NULL` or `&PyBaseObject_Type`.

**Default:**

For *static types* this field has no default. This means if the slot is defined as `NULL`, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

*freefunc* `PyTypeObject.tp_free`

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is `PyObject_Free()`.

**Inheritance:**

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

**Default:**

In dynamic subtypes, this field is set to a deallocator suitable to match `PyType_GenericAlloc()` and the value of the `Py_TPFLAGS_HAVE_GC` flag bit.

For static subtypes, `PyBaseObject_Type` uses `PyObject_Del()`.

*inquiry* `PyTypeObject.tp_is_gc`

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's `tp_flags` field, and check the `Py_TPFLAGS_HAVE_GC` flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype, `PyType_Type`, defines this function to distinguish between statically and *dynamically allocated types*.)

**Inheritance:**

This field is inherited by subtypes.

**Default:**

This slot has no default. If this field is NULL, `Py_TPFLAGS_HAVE_GC` is used as the functional equivalent.

*PyObject\** `PyTypeObject.tp_bases`

Tuple of base types.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is *initialized*.

For dynamically created classes, the `Py_tp_bases` slot can be used instead of the *bases* argument of `PyType_FromSpecWithBases()`. The argument form is preferred.

**Προειδοποίηση:** Multiple inheritance does not work well for statically defined types. If you set `tp_bases` to a tuple, Python will not raise an error, but some slots will only be inherited from the first base.

**Inheritance:**

This field is not inherited.

*PyObject\** `PyTypeObject.tp_mro`

Tuple containing the expanded set of base types, starting with the type itself and ending with `object`, in Method Resolution Order.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is *initialized*.

**Inheritance:**

This field is not inherited; it is calculated fresh by `PyType_Ready()`.

*PyObject\** `PyTypeObject.tp_cache`

Unused. Internal use only.

**Inheritance:**

This field is not inherited.

*PyObject\** `PyTypeObject.tp_subclasses`

List of weak references to subclasses. Internal use only.

**Inheritance:**

This field is not inherited.

*PyObject* \**PyTypeObject*.**tp\_weaklist**

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

**Inheritance:**

This field is not inherited.

*destructor* *PyTypeObject*.**tp\_del**

This field is deprecated. Use *tp\_finalize* instead.

unsigned int *PyTypeObject*.**tp\_version\_tag**

Used to index into the method cache. Internal use only.

**Inheritance:**

This field is not inherited.

*destructor* *PyTypeObject*.**tp\_finalize**

An optional pointer to an instance finalization function. Its signature is:

```
void tp_finalize(PyObject *self);
```

If *tp\_finalize* is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

*tp\_finalize* should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);

    /* ... */

    /* Restore the saved exception. */
    PyErr_Restore(error_type, error_value, error_traceback);
}
```

Also, note that, in a garbage collected Python, *tp\_dealloc* may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which *tp\_dealloc* is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called *tp\_dealloc* will not violate any assumptions of the library.

**Inheritance:**

This field is inherited by subtypes.

Νέο στην έκδοση 3.4.

Άλλαξε στην έκδοση 3.8: Before version 3.8 it was necessary to set the *Py\_TPFLAGS\_HAVE\_FINALIZE* flags bit in order for this field to be used. This is no longer required.

**Δείτε επίσης:**

«Safe object finalization» (**PEP 442**)

*vectorcallfunc* *PyObject*.`tp_vectorcall`

Vectorcall function to use for calls of this type object. In other words, it is used to implement *vectorcall* for `type.__call__`. If `tp_vectorcall` is NULL, the default call implementation using `__new__()` and `__init__()` is used.

**Inheritance:**

This field is never inherited.

Νέο στην έκδοση 3.9: (the field exists since 3.8 but it's only used since 3.9)

## 12.3.6 Static Types

Traditionally, types defined in C code are *static*, that is, a static *PyObject* structure is defined directly in code and initialized using *PyType\_Ready()*.

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state.

Also, since *PyObject* is only part of the *Limited API* as an opaque struct, any extension modules using static types must be compiled for a specific Python minor version.

## 12.3.7 Heap Types

An alternative to *static types* is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's `class` statement. Heap types have the *Py\_TPFLAGS\_HEAPTYPE* flag set.

This is done by filling a *PyType\_Spec* structure and calling *PyType\_FromSpec()*, *PyType\_FromSpecWithBases()*, or *PyType\_FromModuleAndSpec()*.

## 12.4 Number Object Structures

type **PyNumberMethods**

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Number Protocol* section.

Here is the structure definition:

```
typedef struct {
    binaryfunc nb_add;
    binaryfunc nb_subtract;
    binaryfunc nb_multiply;
    binaryfunc nb_remainder;
    binaryfunc nb_divmod;
    ternaryfunc nb_power;
    unaryfunc nb_negative;
    unaryfunc nb_positive;
    unaryfunc nb_absolute;
    inquiry nb_bool;
    unaryfunc nb_invert;
    binaryfunc nb_lshift;
    binaryfunc nb_rshift;
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

binaryfunc nb_and;
binaryfunc nb_xor;
binaryfunc nb_or;
unaryfunc nb_int;
void *nb_reserved;
unaryfunc nb_float;

binaryfunc nb_inplace_add;
binaryfunc nb_inplace_subtract;
binaryfunc nb_inplace_multiply;
binaryfunc nb_inplace_remainder;
ternaryfunc nb_inplace_power;
binaryfunc nb_inplace_lshift;
binaryfunc nb_inplace_rshift;
binaryfunc nb_inplace_and;
binaryfunc nb_inplace_xor;
binaryfunc nb_inplace_or;

binaryfunc nb_floor_divide;
binaryfunc nb_true_divide;
binaryfunc nb_inplace_floor_divide;
binaryfunc nb_inplace_true_divide;

unaryfunc nb_index;

binaryfunc nb_matrix_multiply;
binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;

```

**Σημείωση:** Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return `Py_NotImplemented`, if another error occurred they must return `NULL` and set an exception.

**Σημείωση:** The `nb_reserved` field should always be `NULL`. It was previously called `nb_long`, and was renamed in Python 3.0.1.

*binaryfunc* `PyNumberMethods.nb_add`

*binaryfunc* `PyNumberMethods.nb_subtract`

*binaryfunc* `PyNumberMethods.nb_multiply`

*binaryfunc* `PyNumberMethods.nb_remainder`

*binaryfunc* `PyNumberMethods.nb_divmod`

*ternaryfunc* `PyNumberMethods.nb_power`

*unaryfunc* `PyNumberMethods.nb_negative`

*unaryfunc* `PyNumberMethods.nb_positive`

*unaryfunc* `PyNumberMethods.nb_absolute`

*inquiry* `PyNumberMethods.nb_bool`

*unaryfunc* `PyNumberMethods.nb_invert`

*binaryfunc* *PyNumberMethods*.**nb\_lshift**  
*binaryfunc* *PyNumberMethods*.**nb\_rshift**  
*binaryfunc* *PyNumberMethods*.**nb\_and**  
*binaryfunc* *PyNumberMethods*.**nb\_xor**  
*binaryfunc* *PyNumberMethods*.**nb\_or**  
*unaryfunc* *PyNumberMethods*.**nb\_int**  
*void \***PyNumberMethods*.**nb\_reserved**  
*unaryfunc* *PyNumberMethods*.**nb\_float**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_add**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_subtract**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_multiply**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_remainder**  
*ternaryfunc* *PyNumberMethods*.**nb\_inplace\_power**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_lshift**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_rshift**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_and**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_xor**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_or**  
*binaryfunc* *PyNumberMethods*.**nb\_floor\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_true\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_floor\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_true\_divide**  
*unaryfunc* *PyNumberMethods*.**nb\_index**  
*binaryfunc* *PyNumberMethods*.**nb\_matrix\_multiply**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_matrix\_multiply**

## 12.5 Mapping Object Structures

type **PyMappingMethods**

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

*lenfunc* *PyMappingMethods*.**mp\_length**

This function is used by *PyMapping\_Size()* and *PyObject\_Size()*, and has the same signature. This slot may be set to NULL if the object has no defined length.

*binaryfunc* *PyMappingMethods*.**mp\_subscript**

This function is used by *PyObject\_GetItem()* and *PySequence\_GetSlice()*, and has the same signature as *PyObject\_GetItem()*. This slot must be filled for the *PyMapping\_Check()* function to return 1, it can be NULL otherwise.

*objobjargproc* *PyMappingMethods*.**mp\_ass\_subscript**

This function is used by *PyObject\_SetItem()*, *PyObject\_DelItem()*, *PySequence\_SetSlice()* and *PySequence\_DelSlice()*. It has the same signature as *PyObject\_SetItem()*, but *v* can also be set to NULL to delete an item. If this slot is NULL, the object does not support item assignment and deletion.

## 12.6 Sequence Object Structures

type **PySequenceMethods**

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

*lenfunc* *PySequenceMethods*.**sq\_length**

This function is used by *PySequence\_Size()* and *PyObject\_Size()*, and has the same signature. It is also used for handling negative indices via the *sq\_item* and the *sq\_ass\_item* slots.

*binaryfunc* *PySequenceMethods*.**sq\_concat**

This function is used by *PySequence\_Concat()* and has the same signature. It is also used by the `+` operator, after trying the numeric addition via the *nb\_add* slot.

*ssizeargfunc* *PySequenceMethods*.**sq\_repeat**

This function is used by *PySequence\_Repeat()* and has the same signature. It is also used by the `*` operator, after trying numeric multiplication via the *nb\_multiply* slot.

*ssizeargfunc* *PySequenceMethods*.**sq\_item**

This function is used by *PySequence\_GetItem()* and has the same signature. It is also used by *PyObject\_GetItem()*, after trying the subscription via the *mp\_subscript* slot. This slot must be filled for the *PySequence\_Check()* function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the *sq\_length* slot is filled, it is called and the sequence length is used to compute a positive index which is passed to *sq\_item*. If *sq\_length* is NULL, the index is passed as is to the function.

*ssizeobjargproc* *PySequenceMethods*.**sq\_ass\_item**

This function is used by *PySequence\_SetItem()* and has the same signature. It is also used by *PyObject\_SetItem()* and *PyObject\_DelItem()*, after trying the item assignment and deletion via the *mp\_ass\_subscript* slot. This slot may be left to NULL if the object does not support item assignment and deletion.

*objobjproc* *PySequenceMethods*.**sq\_contains**

This function may be used by *PySequence\_Contains()* and has the same signature. This slot may be left to NULL, in this case *PySequence\_Contains()* simply traverses the sequence until it finds a match.

*binaryfunc* *PySequenceMethods*.**sq\_inplace\_concat**

This function is used by *PySequence\_InPlaceConcat()* and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case *PySequence\_InPlaceConcat()* will fall back to *PySequence\_Concat()*. It is also used by the augmented assignment `+=`, after trying numeric in-place addition via the *nb\_inplace\_add* slot.

*ssizeargfunc* *PySequenceMethods*.**sq\_inplace\_repeat**

This function is used by *PySequence\_InPlaceRepeat()* and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case *PySequence\_InPlaceRepeat()* will fall back to *PySequence\_Repeat()*. It is also used by the augmented assignment `*=`, after trying numeric in-place multiplication via the *nb\_inplace\_multiply* slot.

## 12.7 Buffer Object Structures

type **PyBufferProcs**

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

*getbufferproc* **PyBufferProcs.bf\_getbuffer**

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function **MUST** take these steps:

- (1) Check if the request can be met. If not, raise `BufferError`, set `view->obj` to `NULL` and return `-1`.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set `view->obj` to *exporter* and increment `view->obj`.
- (5) Return `0`.

If *exporter* is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets `view->obj` to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, `view->obj` will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the *Py\_buffer* structure belongs to the exporter and must remain valid until there are no consumers left. *format*, *shape*, *strides*, *suboffsets* and *internal* are read-only for the consumer.

*PyBuffer\_FillInfo()* provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

*PyObject\_GetBuffer()* is the interface for the consumer that wraps this function.

*releasebufferproc* **PyBufferProcs.bf\_releasebuffer**

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, *PyBufferProcs.bf\_releasebuffer* may be `NULL`. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is `0`, free all memory associated with *view*.

The exporter **MUST** use the *internal* field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer **MAY** pass a copy of the original buffer as the *view* argument.

This function **MUST NOT** decrement `view->obj`, since that is done automatically in *PyBuffer\_Release()* (this scheme is useful for breaking reference cycles).

*PyBuffer\_Release()* is the interface for the consumer that wraps this function.



## 12.8 Async Object Structures

Νέο στην έκδοση 3.5.

type **PyAsyncMethods**

This structure holds pointers to the functions required to implement *awaitable* and *asynchronous iterator* objects.

Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
    sendfunc am_send;
} PyAsyncMethods;
```

*unaryfunc* **PyAsyncMethods.am\_await**

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an *iterator*, i.e. *PyIter\_Check()* must return 1 for it.

This slot may be set to NULL if an object is not an *awaitable*.

*unaryfunc* **PyAsyncMethods.am\_aiter**

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an *asynchronous iterator* object. See *\_\_anext\_\_()* for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

*unaryfunc* **PyAsyncMethods.am\_anext**

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an *awaitable* object. See *\_\_anext\_\_()* for details. This slot may be set to NULL.

*sendfunc* **PyAsyncMethods.am\_send**

The signature of this function is:

```
PySendResult am_send(PyObject *self, PyObject *arg, PyObject **result);
```

See *PyIter\_Send()* for details. This slot may be set to NULL.

Νέο στην έκδοση 3.10.

## 12.9 Slot Type typedefs

typedef *PyObject* \*(\***allocfunc**)(*PyTypeObject* \*cls, *Py\_ssize\_t* nitems)

*Μέρος του Σταθερό ABI.* The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with *ob\_refcnt* set to 1 and *ob\_type* set to the type argument. If the type's *tp\_itemsize* is non-zero, the object's *ob\_size* field should be initialized to *nitems* and the length of the allocated memory block should be *tp\_basicsize* + *nitems*\**tp\_itemsize*, rounded

up to a multiple of `sizeof(void*)`; otherwise, `nitems` is not used and the length of the block should be `tp_basicsize`.

This function should not do any other instance initialization, not even to allocate additional memory; that should be done by `tp_new`.

typedef void (\***destructor**)(PyObject\*)

Μέρος του Σταθερό ABI.

typedef void (\***freefunc**)(void\*)

See `tp_free`.

typedef PyObject \*(\***newfunc**)(PyObject\*, PyObject\*, PyObject\*)

Μέρος του Σταθερό ABI. See `tp_new`.

typedef int (\***initproc**)(PyObject\*, PyObject\*, PyObject\*)

Μέρος του Σταθερό ABI. See `tp_init`.

typedef PyObject \*(\***reprfunc**)(PyObject\*)

Μέρος του Σταθερό ABI. See `tp_repr`.

typedef PyObject \*(\***getattrfunc**)(PyObject \*self, char \*attr)

Μέρος του Σταθερό ABI. Return the value of the named attribute for the object.

typedef int (\***setattrfunc**)(PyObject \*self, char \*attr, PyObject \*value)

Μέρος του Σταθερό ABI. Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.

typedef PyObject \*(\***getattrofunc**)(PyObject \*self, PyObject \*attr)

Μέρος του Σταθερό ABI. Return the value of the named attribute for the object.

See `tp_getattro`.

typedef int (\***setattrofunc**)(PyObject \*self, PyObject \*attr, PyObject \*value)

Μέρος του Σταθερό ABI. Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.

See `tp_setattro`.

typedef PyObject \*(\***descrgetfunc**)(PyObject\*, PyObject\*, PyObject\*)

Μέρος του Σταθερό ABI. See `tp_descr_get`.

typedef int (\***descrsetfunc**)(PyObject\*, PyObject\*, PyObject\*)

Μέρος του Σταθερό ABI. See `tp_descr_set`.

typedef Py\_hash\_t (\***hashfunc**)(PyObject\*)

Μέρος του Σταθερό ABI. See `tp_hash`.

typedef PyObject \*(\***richcmpfunc**)(PyObject\*, PyObject\*, int)

Μέρος του Σταθερό ABI. See `tp_richcompare`.

typedef PyObject \*(\***getiterfunc**)(PyObject\*)

Μέρος του Σταθερό ABI. See `tp_iter`.

typedef PyObject \*(\***iternextfunc**)(PyObject\*)

Μέρος του Σταθερό ABI. See `tp_iternext`.

typedef Py\_ssize\_t (\***lenfunc**)(PyObject\*)

Μέρος του Σταθερό ABI.

typedef int (\***getbufferproc**)(PyObject\*, Py\_buffer\*, int)

typedef void (\***releasebufferproc**)(PyObject\*, Py\_buffer\*)

```
typedef PyObject *(*unaryfunc)(PyObject*)
    Μέρος του Σταθερό ABI.
```

```
typedef PyObject *(*binaryfunc)(PyObject*, PyObject*)
    Μέρος του Σταθερό ABI.
```

```
typedef PySendResult (*sendfunc)(PyObject*, PyObject*, PyObject**))
    See am_send.
```

```
typedef PyObject *(*ternaryfunc)(PyObject*, PyObject*, PyObject*)
    Μέρος του Σταθερό ABI.
```

```
typedef PyObject *(*ssizeargfunc)(PyObject*, Py_ssize_t)
    Μέρος του Σταθερό ABI.
```

```
typedef int (*ssizeobjargproc)(PyObject*, Py_ssize_t, PyObject*)
    Μέρος του Σταθερό ABI.
```

```
typedef int (*objobjproc)(PyObject*, PyObject*)
    Μέρος του Σταθερό ABI.
```

```
typedef int (*objobjargproc)(PyObject*, PyObject*, PyObject*)
    Μέρος του Σταθερό ABI.
```

## 12.10 Examples

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see [defining-new-types](#) and [new-types-topics](#).

A basic *static type*:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

```
static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    "mymod.MyObject",           /* tp_name */
    sizeof(MyObject),           /* tp_basicsize */
    0,                           /* tp_itemsize */
    (destructor)myobj_dealloc,   /* tp_dealloc */
    0,                           /* tp_vectorcall_offset */
    0,                           /* tp_getattr */
    0,                           /* tp_setattr */
    0,                           /* tp_as_async */
    (reprfunc)myobj_repr,       /* tp_repr */
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

0,                /* tp_as_number */
0,                /* tp_as_sequence */
0,                /* tp_as_mapping */
0,                /* tp_hash */
0,                /* tp_call */
0,                /* tp_str */
0,                /* tp_getattro */
0,                /* tp_setattro */
0,                /* tp_as_buffer */
0,                /* tp_flags */
PyDoc_STR("My objects"), /* tp_doc */
0,                /* tp_traverse */
0,                /* tp_clear */
0,                /* tp_richcompare */
0,                /* tp_weaklistoffset */
0,                /* tp_iter */
0,                /* tp_iternext */
0,                /* tp_methods */
0,                /* tp_members */
0,                /* tp_getset */
0,                /* tp_base */
0,                /* tp_dict */
0,                /* tp_descr_get */
0,                /* tp_descr_set */
0,                /* tp_dictoffset */
0,                /* tp_init */
0,                /* tp_alloc */
myobj_new,        /* tp_new */
};

```

A type that supports weakrefs, instance dicts, and hashing:

```

typedef struct {
    PyObject_HEAD
    const char *data;
    PyObject *inst_dict;
    PyObject *weakreflist;
} PyObject;

static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_weaklistoffset = offsetof(MyObject, weakreflist),
    .tp_dictoffset = offsetof(MyObject, inst_dict),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE | Py_TPFLAGS_HAVE_GC,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
    .tp_hash = (hashfunc)myobj_hash,
    .tp_richcompare = PyBaseObject_Type.tp_richcompare,
};

```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func) using `Py_TPFLAGS_DISALLOW_INSTANTIATION` flag:

```
typedef struct {
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```

PyUnicodeObject raw;
char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = PyDoc_STR("my custom str"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_DISALLOW_INSTANTIATION,
    .tp_repr = (reprfunc)myobj_repr,
};

```

The simplest *static type* with fixed-length instances:

```

typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};

```

The simplest *static type* with variable-length instances:

```

typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};

```

## 12.11 Supporting Cyclic Garbage Collection

Python's support for detecting and collecting garbage which involves circular references requires support from object types which are «containers» for other objects which may also be containers. Types which do not store references to other objects, or which only store references to atomic types (such as numbers or strings), do not need to provide any explicit support for garbage collection.

To create a container type, the *tp\_flags* field of the type object must include the *Py\_TPFLAGS\_HAVE\_GC* and provide an implementation of the *tp\_traverse* handler. If instances of the type are mutable, a *tp\_clear* implementation must also be provided.

### *Py\_TPFLAGS\_HAVE\_GC*

Objects with a type with this flag set must conform with the rules documented here. For convenience these objects will be referred to as container objects.

Constructors for container types must conform to two rules:

1. The memory for the object must be allocated using *PyObject\_GC\_New* or *PyObject\_GC\_NewVar*.
2. Once all the fields which may contain references to other containers are initialized, it must call *PyObject\_GC\_Track()*.

Similarly, the deallocator for the object must conform to a similar pair of rules:

1. Before fields which refer to other containers are invalidated, `PyObject_GC_UnTrack()` must be called.
2. The object's memory must be deallocated using `PyObject_GC_Del()`.

**Προειδοποίηση:** If a type adds the `Py_TPFLAGS_HAVE_GC`, then it *must* implement at least a `tp_traverse` handler or explicitly use one from its subclass or subclasses.

When calling `PyType_Ready()` or some of the APIs that indirectly call it like `PyType_FromSpecWithBases()` or `PyType_FromSpec()` the interpreter will automatically populate the `tp_flags`, `tp_traverse` and `tp_clear` fields if the type inherits from a class that implements the garbage collector protocol and the child class does *not* include the `Py_TPFLAGS_HAVE_GC` flag.

**PyObject\_GC\_New** (TYPE, typeobj)

Analogous to `PyObject_New` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

**PyObject\_GC\_NewVar** (TYPE, typeobj, size)

Analogous to `PyObject_NewVar` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

**PyObject\_GC\_Resize** (TYPE, op, newsize)

Resize an object allocated by `PyObject_NewVar`. Returns the resized object of type TYPE\* (refers to any C type) or NULL on failure.

*op* must be of type `PyVarObject*` and must not be tracked by the collector yet. *newsize* must be of type `Py_ssize_t`.

void **PyObject\_GC\_Track** (*PyObject* \*op)

*Μέρος του Σταθερό ABI*. Adds the object *op* to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the `tp_traverse` handler become valid, usually near the end of the constructor.

int **PyObject\_IS\_GC** (*PyObject* \*obj)

Returns non-zero if the object implements the garbage collector protocol, otherwise returns 0.

The object cannot be tracked by the garbage collector if this function returns 0.

int **PyObject\_GC\_IsTracked** (*PyObject* \*op)

*Μέρος του Σταθερό ABI από την έκδοση 3.9*. Returns 1 if the object type of *op* implements the GC protocol and *op* is being currently tracked by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_tracked()`.

Νέο στην έκδοση 3.9.

int **PyObject\_GC\_IsFinalized** (*PyObject* \*op)

*Μέρος του Σταθερό ABI από την έκδοση 3.9*. Returns 1 if the object type of *op* implements the GC protocol and *op* has been already finalized by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_finalized()`.

Νέο στην έκδοση 3.9.

void **PyObject\_GC\_Del** (void \*op)

*Μέρος του Σταθερό ABI*. Releases memory allocated to an object using `PyObject_GC_New` or `PyObject_GC_NewVar`.

void **PyObject\_GC\_UnTrack** (void \*op)

*Μέρος του Σταθερό ABI*. Remove the object *op* from the set of container objects tracked by the collector. Note that `PyObject_GC_Track()` can be called again on this object to add it back to the set of tracked objects. The deallocator (`tp_dealloc` handler) should call this for the object before any of the fields used by the `tp_traverse` handler become invalid.

Άλλαξε στην έκδοση 3.8: The `_PyObject_GC_TRACK()` and `_PyObject_GC_UNTRACK()` macros have been removed from the public C API.

The `tp_traverse` handler accepts a function parameter of this type:

```
typedef int (*visitproc)(PyObject *object, void *arg)
```

*Μέρος του Σταθερό ABI.* Type of the visitor function passed to the `tp_traverse` handler. The function should be called with an object to traverse as `object` and the third parameter to the `tp_traverse` handler as `arg`. The Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The `tp_traverse` handler must have the following type:

```
typedef int (*traverseproc)(PyObject *self, visitproc visit, void *arg)
```

*Μέρος του Σταθερό ABI.* Traversal function for a container object. Implementations must call the `visit` function for each object directly contained by `self`, with the parameters to `visit` being the contained object and the `arg` value passed to the handler. The `visit` function must not be called with a NULL object argument. If `visit` returns a non-zero value that value should be returned immediately.

To simplify writing `tp_traverse` handlers, a `Py_VISIT()` macro is provided. In order to use this macro, the `tp_traverse` implementation must name its arguments exactly `visit` and `arg`:

```
void Py_VISIT(PyObject *o)
```

If `o` is not NULL, call the `visit` callback, with arguments `o` and `arg`. If `visit` returns a non-zero value, then return it. Using this macro, `tp_traverse` handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The `tp_clear` handler must be of the `inquiry` type, or NULL if the object is immutable.

```
typedef int (*inquiry)(PyObject *self)
```

*Μέρος του Σταθερό ABI.* Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after calling this method (don't just call `Py_DECREF()` on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

### 12.11.1 Controlling the Garbage Collector State

The C-API provides the following functions for controlling garbage collection runs.

```
Py_ssize_t PyGC_Collect(void)
```

*Μέρος του Σταθερό ABI.* Perform a full garbage collection, if the garbage collector is enabled. (Note that `gc.collect()` runs it unconditionally.)

Returns the number of collected + unreachable objects which cannot be collected. If the garbage collector is disabled or already collecting, returns 0 immediately. Errors during garbage collection are passed to `sys.unraisablehook`. This function does not raise exceptions.

```
int PyGC_Enable(void)
```

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Enable the garbage collector: similar to `gc.enable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Νέο στην έκδοση 3.10.

`int PyGC_Disable` (void)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Disable the garbage collector: similar to `gc.disable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Νέο στην έκδοση 3.10.

`int PyGC_IsEnabled` (void)

*Μέρος του Σταθερό ABI από την έκδοση 3.10.* Query the state of the garbage collector: similar to `gc.isenabled()`. Returns the current state, 0 for disabled and 1 for enabled.

Νέο στην έκδοση 3.10.



## API and ABI Versioning

CPython exposes its version number in the following macros. Note that these correspond to the version code is **built** with, not necessarily the version used at **run time**.

See *C API Stability* for a discussion of API and ABI stability across versions.

### **PY\_MAJOR\_VERSION**

The 3 in 3.4.1a2.

### **PY\_MINOR\_VERSION**

The 4 in 3.4.1a2.

### **PY\_MICRO\_VERSION**

The 1 in 3.4.1a2.

### **PY\_RELEASE\_LEVEL**

The a in 3.4.1a2. This can be 0xA for alpha, 0xB for beta, 0xC for release candidate or 0xF for final.

### **PY\_RELEASE\_SERIAL**

The 2 in 3.4.1a2. Zero for final releases.

### **PY\_VERSION\_HEX**

The Python version number encoded in a single integer.

The underlying version information can be found by treating it as a 32 bit number in the following manner:

Bytes	Bits (big endian order)	Meaning	Value for 3.4.1a2
1	1-8	PY_MAJOR_VERSION	0x03
2	9-16	PY_MINOR_VERSION	0x04
3	17-24	PY_MICRO_VERSION	0x01
4	25-28	PY_RELEASE_LEVEL	0xA
	29-32	PY_RELEASE_SERIAL	0x2

Thus 3.4.1a2 is hexversion 0x030401a2 and 3.10.0 is hexversion 0x030a00f0.

Use this for numeric comparisons, e.g. `if PY_VERSION_HEX >= ...`

This version is also available via the symbol *Py\_Version*.

const unsigned long **Py\_Version**

*Μέρος του Σταθερό ABI από την έκδοση 3.11.* The Python runtime version number encoded in a single constant integer, with the same format as the `PY_VERSION_HEX` macro. This contains the Python version used at run time.

Νέο στην έκδοση 3.11.

All the given macros are defined in `Include/patchlevel.h`.

>>>

Το προεπιλεγμένο Python prompt του διαδραστικού shell. Συχνά εμφανίζεται για παραδείγματα κώδικα που μπορούν να εκτελεστούν διαδραστικά στον interpreter.

...

Μπορεί να αναφέρεται σε:

- Το προεπιλεγμένο Python prompt του διαδραστικού shell κατά την εισαγωγή του κώδικα για ένα μπλοκ κώδικα με εσοχή, όταν βρίσκεται μέσα σε ένα ζεύγος ταιριασμένων αριστερών και δεξιών delimiters (παρενθέσεις, αγκύλες, άγκιστρα ή τριπλά εισαγωγικά), ή μετά τον καθορισμό ενός decorator.
- Η ενσωματωμένη σταθερά Ellipsis.

### 2to3

Ένα εργαλείο που προσπαθεί να μετατρέψει τον κώδικα Python 2.x σε κώδικα Python 3.x διαχειρίζοντας τις περισσότερες ασυμβατότητες που μπορούν να εντοπιστούν αναλύοντας την πηγή και διασχίζοντας το δέντρο ανάλυσης.

2to3 είναι διαθέσιμο στην στάνταρ βιβλιοθήκη ως `lib2to3`, παρέχεται ένα σημείο εισόδου ως `Tools/scripts/2to3`. Βλ. `2to3-reference`.

### αφηρημένη βασική κλάση

Οι αφηρημένες βασικές κλάσεις συμπληρώνουν το *duck-typing* παρέχοντας έναν τρόπο ορισμού interfaces όταν άλλες τεχνικές όπως η `hasattr()` θα ήταν αδέξιες ή ανεπαίσθητα λανθασμένες (για παράδειγμα με magic methods). Τα ABC (abstract base class) εισάγουν εικονικές υποκλάσεις, οι οποίες είναι κλάσεις που δεν κληρονομούνται από μια κλάση, αλλά εξακολουθούν να αναγνωρίζονται από το `isinstance()` και από το `issubclass()` βλ. την τεκμηρίωση του module `abc`. Η Python διαθέτει πολλά ενσωματωμένα ABC για δομές δεδομένων (στο module `collections.abc`), αριθμούς (στο module `numbers`), ροές (στο module μονάδα `io`), εισαγωγή finders και loaders (στο module `importlib.abc`). Μπορείτε να δημιουργήσετε τα δικά σας ABC με το module `abc`.

### annotation

Μια ετικέτα που σχετίζεται με μια μεταβλητή, ένα χαρακτηριστικό κλάσης ή μια παράμετρος συνάρτησης ή τιμή που επιστρέφεται, που χρησιμοποιείται κατά σύμβαση ως *type hint*.

Δεν είναι δυνατή η πρόσβαση στα annotations των τοπικών μεταβλητών κατά το χρόνο εκτέλεσης, αλλά τα annotations των global μεταβλητών, των χαρακτηριστικών κλάσης και των συναρτήσεων αποθηκεύονται στο ειδικό χαρακτηριστικό `__annotations__` των modules, των κλάσεων και των συναρτήσεων, αντίστοιχα.

Βλ. *variable annotation*, *function annotation*, [PEP 484](#) και [PEP 526](#), τα οποία περιγράφουν την λειτουργικότητα. Επίσης βλ. *annotations-howto* για τις βέλτιστες πρακτικές δουλεύοντας με annotations.

### όρισμα

Μια τιμή μεταβιβάζεται σε μία *function* (ή *method*) κατά την κλήση της συνάρτησης. Υπάρχουν δύο είδη ορισμάτων:

- *keyword argument*: ένα όρισμα πριν από ένα αναγνωριστικό (π.χ. `name=`) σε μια κλήση συνάρτησης ή περνώντας το ως τιμή σε ένα λεξικό πριν από `**`. Για παράδειγμα, το 3 και το 5 αποτελούν ορίσματα λέξεων-κλειδιών στις ακόλουθες κλήσεις προς `complex()`:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

- *positional argument*: ένα όρισμα που δεν είναι όρισμα keyword. Τα ορίσματα θέσης μπορούν να εμφανίζονται στην αρχής μιας λίστας ορισμάτων ή/και να μεταβιβάζονται ως στοιχεία ενός *iterable* πριν από `*`. Για παράδειγμα, το 3 και το 5 αποτελούν ορίσματα θέσης στις παρακάτω κλήσεις:

```
complex(3, 5)
complex(*(3, 5))
```

Τα ορίσματα εκχωρούνται στις ονομασμένες τοπικές μεταβλητές στο σώμα μια συνάρτησης. Βλ. την ενότητα *calls* για τους κανόνες που διέπουν αυτήν την εκχώρηση. Συντακτικά, οποιαδήποτε έκφραση μπορεί να χρησιμοποιηθεί για να αναπαραστήσει ένα όρισμα” η αξιολογούμενη τιμή εκχωρείται σε μια τοπική μεταβλητή.

Βλ. επίσης την εγγραφή του γλωσσариού για το *parameter*, την FAQ ερώτηση στο η διαφορά μεταξύ ορισμάτων και παραμέτρων, και [PEP 362](#).

### ασύγχρονος διαχειριστής context

Ένα αντικείμενο που ελέγχει το ορατό περιβάλλον σε μια δήλωση `async with` ορίζοντας τις μεθόδους `__aenter__()` και `__aexit__()`. Που εισήχθη από [PEP 492](#).

### ασύγχρονος generator

Μια συνάρτηση που επιστρέφει έναν *asynchronous generator iterator*. Μοιάζει με μια συνάρτηση *coroutine* που ορίζεται με `async def` εκτός από ότι περιέχει εκφράσεις `yield` για την παραγωγή μιας σειράς τιμών που μπορούν να χρησιμοποιηθούν σε έναν `async for` βρόχο.

Συνήθως αναφέρεται σε μια συνάρτηση ασύγχρονου generator, αλλά μπορεί να αναφέρεται σε έναν *asynchronous generator iterator* σε ορισμένα contexts. Σε περιπτώσεις όπου το επιδιωκόμενο νόημα δεν είναι σαφές, με την χρήση των πλήρων όρων αποφεύγεται η ασάφεια.

Μια συνάρτηση ασύγχρονου generator μπορεί να περιέχει εκφράσεις `await`, καθώς και δηλώσεις `async for`, και `async with`.

### ασύγχρονος generator iterator

Ένα αντικείμενο που δημιουργήθηκε από μια συνάρτηση *asynchronous generator*.

Αυτός είναι ένας *asynchronous iterator* που όταν καλείται χρησιμοποιώντας την μέθοδο `__anext__()` επιστρέφει ένα αναμενόμενο αντικείμενο που θα εκτελέσει στο σώμα της συνάρτησης του ασύγχρονου generator μέχρι την επόμενη `yield` έκφραση.

Each `yield` temporarily suspends processing, remembering the location execution state (including local variables and pending try-statements). When the *asynchronous generator iterator* effectively resumes with another awaitable returned by `__anext__()`, it picks up where it left off. See [PEP 492](#) and [PEP 525](#).

### ασύγχρονος iterable

Ένα αντικείμενο, που μπορεί να χρησιμοποιηθεί σε μια δήλωση `async for`. Πρέπει να επιστρέφει ένα *asynchronous iterator* από την μέθοδο `__aiter__()`. Που εισήχθη από [PEP 492](#).

### ασύγχρονος iterator

Ένα αντικείμενο που υλοποιεί τις μεθόδους `__aiter__()` και `__anext__()`. Η μέθοδος `__anext__()` πρέπει να επιστρέφει ένα *awaitable* αντικείμενο. Το `async for` επιλύει τα αναμενόμενα που επιστρέφονται από τη μέθοδο `__anext__()` ενός ασύγχρονου iterator έως ότου εγείρει μια εξαίρεση `StopAsyncIteration`. Εισήχθη από [PEP 492](#).

**χαρακτηριστικό**

Μια τιμή που σχετίζεται με ένα αντικείμενο που συνήθως αναφέρεται με όνομα χρησιμοποιώντας εκφράσεις με κουκκίδες. Για παράδειγμα, εάν ένα αντικείμενο *o* έχει ένα χαρακτηριστικό *a* θα αναφέρεται ως *o.a*.

Είναι δυνατό να δώσουμε σε ένα αντικείμενο ένα χαρακτηριστικό που το όνομα του δεν είναι αναγνωριστικό όπως ορίζεται από `identifiers`, για παράδειγμα χρησιμοποιώντας `setattr()`, αν επιτρέπεται από το αντικείμενο. Ένα τέτοιο χαρακτηριστικό δεν θα είναι προσβάσιμο χρησιμοποιώντας τις τελείες, και αντί αυτού θα πρέπει να ανακτηθεί χρησιμοποιώντας `getattr()`.

**awaitable**

Ένα αντικείμενο που μπορεί να χρησιμοποιηθεί στην έκφραση `await`. Μπορεί να είναι *coroutine* ή ένα αντικείμενο με μια `__await__()` μέθοδο. Βλ. επίσης [PEP 492](#).

**BDFL**

Ακρωνύμιο του *Benevolent Dictator For Life*, καλοκάγαθος δικτάτορας της ζωής, δηλαδή [Guido van Rossum](#), ο δημιουργός της Python.

**δυναδικό αρχείο**

Ένα *file object* ικανό να διαβάζει και να γράφει *δυναδικού τύπου αντικείμενα*. Παραδείγματα δυναδικών αρχείων είναι αρχεία που ανοίγουν σε δυναδική λειτουργία ('rb', 'wb' ή 'rb+'), `sys.stdin.buffer`, `sys.stdout.buffer`, και στιγμιотύπων των `io.BytesIO` και `gzip.GzipFile`.

Βλ. επίσης *text file* για ένα αντικείμενο τύπου αρχείο ικανό να διαβάσει και να γράψει `str` αντικείμενα.

**δανεική αναφορά**

Στο C API της Python, μια δανεική αναφορά είναι μια αναφορά σε ένα αντικείμενο, όπου ο κώδικας που χρησιμοποιεί το αντικείμενο δεν κατέχει την αναφορά. Γίνεται ένας αχρησιμοποίητος δείκτης εάν το αντικείμενο καταστραφεί. Για παράδειγμα, μια διαδικασία *garbage collection* μπορεί να αφαιρέσει το τελευταίο *strong reference* από το αντικείμενο και έτσι να το καταστρέψει.

Συνίσταται η κλήση του `Py_INCREF()` στο *δανεική αναφορά* με σκοπό να μετατραπεί σε ένα *ισχυρή αναφορά* επιτόπου, εκτός όταν το αντικείμενο δεν μπορεί να καταστραφεί πριν από την τελευταία χρήση της δανεικής αναφοράς. Η συνάρτηση `Py_NewRef()` μπορεί να χρησιμοποιηθεί ώστε να δημιουργηθεί ένα *ισχυρή αναφορά*.

**bytes-like αντικείμενα**

Ένα αντικείμενο που υποστηρίζει το *Buffer Protocol* και μπορεί να εξάγει ένα *C-contiguous* buffer. Αυτό περιλαμβάνει όλα τα αντικείμενα `bytes`, `bytearray`, και `array.array`, καθώς και πολλά κοινά `memoryview` αντικείμενα. Τα δυναδικού τύπου (bytes-like) αντικείμενα μπορούν να χρησιμοποιηθούν για διάφορες λειτουργίες που διαχειρίζονται δυναδικά δεδομένα" αυτά περιλαμβάνουν συμπίεση αποθήκευση σε δυναδικό αρχείο και αποστολή μέσω `socket`.

Ορισμένες λειτουργίες χρειάζονται τα δυναδικά δεδομένα να είναι μεταβλητά. Η τεκμηρίωση συχνά αναφέρεται σε αυτά ως «δυναδικά αντικείμενα ανάγνωσης-εγγραφής» (read-write bytes-like objects). Παραδείγματα μεταβλητών αντικειμένων προσωρινής αποθήκευσης περιέχουν `bytearray` και ένα `memoryview` ενός `bytearray`. Άλλες λειτουργίες απαιτούν την αποθήκευση των δυναδικών δεδομένων σε αμετάβλητα αντικείμενα («δυναδικά αντικείμενα μόνο ανάγνωσης» (read-only bytes-like objects) παραδείγματα αυτών περιέχουν `bytes` και ένα `memoryview` ενός `bytes` αντικειμένου.

**bytecode**

Ο πηγαίος κώδικας της Python μεταγλωττίζεται σε *bytecode*, η εσωτερική αναπαράσταση ενός προγράμματος Python στον διερμηνέα CPython. Το *bytecode* αποθηκεύεται επίσης προσωρινά ως `.pyc` αρχεία ώστε η εκτέλεση του ίδιου αρχείου να είναι γρηγορότερη την δεύτερη φορά εκτέλεσης (μπορεί να αποφευχθεί η εκ νέου μεταγλώττιση από τον πηγαίο κώδικα σε *bytecode*). Αυτή η «ενδιάμεση γλώσσα» λέγεται ότι τρέχει σε μια *virtual machine* που εκτελεί τον κώδικα μηχανής που αντιστοιχεί σε κάθε *bytecode*. Λάβετε υπόψη ότι τα *bytecode* δεν αναμένεται να λειτουργούν μεταξύ διαφορετικών εικονικών μηχανών Python, ούτε να είναι σταθερά μεταξύ των εκδόσεων της Python.

Μια λίστα από οδηγίες σχετικά με τα *bytecode* μπορεί να βρεθεί στην τεκμηρίωση για το module `dis`.

**callable**

Ένα callable είναι ένα αντικείμενο που μπορεί να καλεστεί, πιθανά με ένα σύνολο ορισμάτων (βλ. *argument*), με την παρακάτω σύνταξη:

```
callable(argument1, argument2, argumentN)
```

Μια *function*, και κατ' επέκταση μια *method* είναι callable. Ένα στιγμιότυπο μια κλάσης που υλοποιεί τη μέθοδο `__call__()` είναι επίσης callable.

### callback

Μια subroutine συνάρτηση η οποία μεταβιβάζεται ως όρισμα που θα εκτελεστεί κάποια στιγμή στο μέλλον.

### κλάση

Ένα πρότυπο για τη δημιουργία αντικειμένων που ορίζονται από το χρήστη. Οι ορισμοί κλάσεων συνήθως περιέχουν ορισμούς μεθόδων που λειτουργούν σε στιγμιότυπα της κλάσης.

### μεταβλητή κλάσης

Μια μεταβλητή που ορίζεται σε μια κλάση και προορίζεται να τροποποιηθεί μόνο σε επίπεδο κλάσης (δηλ. όχι σε ένα στιγμιότυπο μιας κλάσης).

### μιγαδικός αριθμός

Μια επέκταση του γνωστού συστήματος πραγματικών αριθμών στο οποίο όλοι οι αριθμοί εκφράζονται ως άθροισμα ενός πραγματικού μέρους και ενός φανταστικού μέρους. Οι φανταστικοί αριθμοί είναι πραγματικά πολλαπλάσια της φανταστικής μονάδα (η τετραγωνική ρίζα του  $-1$ ), που συχνά γράφονται  $i$  στα μαθηματικά ή  $j$  στη μηχανική. Η Python έχει ενσωματωμένη υποστήριξη για μιγαδικούς αριθμούς, οι οποίοι γράφονται με αυτόν τον τελευταίο συμβολισμό" το φανταστικό μέρος γράφεται με το επίθημα  $j$ , π.χ.,  $3+1j$ . Για να αποκτήσετε πρόσβαση σε σύνθετα ισοδύναμα το module `math`, χρησιμοποιήστε το `cmath`. Η χρήση μιγαδικών αριθμών είναι ένα αρκετά προηγμένο μαθηματικό χαρακτηριστικό. εάν δεν γνωρίζετε την ανάγκη τους, είναι σχεδόν σίγουρο ότι μπορείτε να τα αγνοήσετε με ασφάλεια.

### διαχειριστής context

Ένα αντικείμενο που ελέγχει το περιβάλλον που εμφανίζεται σε μια δήλωση `with` ορίζοντας τις μεθόδους `__enter__()` και `__exit__()`. Βλ. [PEP 343](#).

### context μεταβλητή

Μια μεταβλητή που μπορεί να έχει πολλές διαφορετικές τιμές ανάλογα με το context. Αυτό είναι κοινό στο Thread-Local Storage όπου κάθε εκτέλεση του νήματος μπορεί να έχει διαφορετική τιμή για μια μεταβλητή. Παρόλα αυτά, με τις context μεταβλητές, μπορεί να υπάρχουν πολλά περιβάλλοντα σε ένα νήμα εκτέλεσης και η κύρια χρήση για τις context μεταβλητές είναι η παρακολούθηση των μεταβλητών σε ταυτόχρονες διεργασίες. Βλ. `contextvars`.

### contiguous

Ένα buffer θεωρείται contiguous ακριβώς εάν είναι είτε *C-contiguous* είτε *Fortran contiguous*. Το buffer μηδενικών διαστάσεων είναι C και Fortran contiguous. Σε μονοδιάστατους πίνακες, τα στοιχεία πρέπει να τοποθετούνται στη μνήμη το ένα δίπλα στο άλλο, με σειρά αύξησης των δεικτών ξεκινώντας από το μηδέν. Σε πολυδιάστατους C-contiguous πίνακες, ο τελευταίος δείκτης μεταβάλλεται ταχύτερα όταν επισκέπτονται τα στοιχεία σε σειρά διεύθυνσης μνήμης. Ωστόσο, σε Fortran contiguous πίνακες, ο πρώτος δείκτης μεταβάλλεται πιο γρήγορα.

### coroutine

Οι coroutines είναι μια πιο γενικευμένη μορφή subroutines. Οι subroutines εισάγονται σε ένα σημείο και εξάγονται σε άλλο σημείο. Οι coroutines μπορεί να εισαχθούν, να εξαχθούν και να συνεχιστούν σε πολλά διαφορετικά σημεία. Μπορούν να υλοποιηθούν με την δήλωση `async def`. Βλ. επίσης [PEP 492](#).

### coroutine συνάρτηση

Μια συνάρτηση που επιστρέφει ένα *coroutine* αντικείμενο. Μια συνάρτηση coroutine μπορεί να ορίζεται από τη δήλωση `async def`, και μπορεί να περιέχει `await`, `async for`, και `async with` λέξεις κλειδιά. Αυτές εισήχθησαν από το [PEP 492](#).

### CPython

Η κανονική υλοποίηση της γλώσσας προγραμματισμού Python, όπως διανέμεται στο [python.org](https://python.org). Ο όρος «CPython» χρησιμοποιείται όταν είναι απαραίτητο για την διάκριση αυτής της υλοποίησης από άλλες όπως η *Jython* ή η *IronPython*.

**decorator**

Μια συνάρτηση που επιστρέφει μια άλλη συνάρτηση, συνήθως εφαρμόζεται ως μετασχηματισμός συνάρτησης χρησιμοποιώντας την `@wrapper` σύνταξη. Συνηθισμένα παραδείγματα για τους decorators είναι `classmethod()` και `staticmethod()`.

Η σύνταξη του decorator είναι απλώς καλλωπιστική, οι ακόλουθοι δύο ορισμοί συναρτήσεων είναι σημασιολογικά ισοδύναμοι:

```
def f(arg):
    ...
f = staticmethod(f)

@staticmethod
def f(arg):
    ...
```

Η ίδια έννοια υπάρχει για τις κλάσεις, αλλά χρησιμοποιείται λιγότερο συχνά εκεί. Βλ. την τεκμηρίωση για function definitions και class definitions για περισσότερα σχετικά με τους decorators.

**descriptor**

Κάθε αντικείμενο που ορίζει τις μεθόδους `__get__()`, `__set__()`, ή `__delete__()`. Όταν ένα χαρακτηριστικό κλάσης είναι descriptor, η ειδική δεσμευτική του συμπεριφορά ενεργοποιείται κατά την αναζήτηση χαρακτηριστικών. Κανονικά, χρησιμοποιώντας `a.b` για να λάβετε, να ορίσετε ή να διαγράψετε ένα χαρακτηριστικό αναζητά το αντικείμενο με το όνομα `b` στο λεξικό της κλάσης για `a`, αλλά εάν το `b` είναι descriptor, καλείται η αντίστοιχη μέθοδος descriptor. Η κατανόηση των descriptors είναι το κλειδί για την καλύτερη κατανόηση της Python γιατί αυτό αποτελεί την βάση για πολλά χαρακτηριστικά όπως συναρτήσεις, μεθόδους, ιδιότητες, μέθοδοι κλάσης στατικές μέθοδοι, και αναφορά σε σούπερ κλάσεις.

Για περισσότερες πληροφορίες αναφορικά με τις μεθόδους των descriptors, βλ. [see descriptors](#) ή το Πρακτικός οδηγός για τη χρήση του Descriptor.

**λεξικό**

Ένα προσεταιριστικός πίνακα, όπου αυθαίρετα κλειδιά αντιστοιχίζονται σε τιμές. Τα κλειδιά μπορεί να είναι οποιοδήποτε αντικείμενο με μεθόδους `__hash__()` και `__eq__()`. Ονομάζεται ως hash στο Perl.

**κατανόηση λεξικού**

Ένα συμπαγής τρόπος για να επεξεργαστείτε όλα ή μέρος των στοιχείων σε ένα επαναληπτικό και να επιστραφεί ένα με λεξικό με τα αποτελέσματα. `results = {n: n ** 2 for n in range(10)}` δημιουργεί ένα λεξικό που περιέχει το κλειδί `n` που αντιστοιχίζεται με την τιμή `n ** 2`. Βλ. [comprehensions](#).

**όψη λεξικού**

Τα αντικείμενα που επιστρέφονται από `dict.keys()`, `dict.values()`, και `dict.items()` καλούνται όψεις λεξικού. Αυτές παρέχουν μια δυναμική όψη των των εγγραφών του λεξικού, που σημαίνει ότι όταν το λεξικό μεταβάλλεται, η όψη αντικατοπτρίζει αυτές τις αλλαγές. Για να αναγκάσετε την όψη λεξικού να γίνει μια πλήρης λίστα χρησιμοποιήστε το `list(dictview)`. Βλ. [dict-views](#).

**docstring**

A string literal which appears as the first expression in a class, function or module. While ignored when the suite is executed, it is recognized by the compiler and put into the `__doc__` attribute of the enclosing class, function or module. Since it is available via introspection, it is the canonical place for documentation of the object.

**duck-typing**

Ένα στυλ προγραμματισμού που δεν εξετάζει τον τύπο ενός αντικειμένου για να προσδιορίσει αν έχει τη σωστή διεπαφή αντίθετα, η μέθοδος ή το χαρακτηριστικό καλείται απλώς ή χρησιμοποιείται («If it looks like a duck and quacks like a duck, it must be a duck.») Δίνοντας έμφαση στις διεπαφές και όχι σε συγκεκριμένους τύπους, ο καλά σχεδιασμένος κώδικας βελτιώνει την ευελιξία του επιτρέποντας την πολυμορφική υποκατάσταση. Ο τύπος duck-typing αποφεύγει δοκιμές χρησιμοποιώντας `type()` ή `isinstance()`. (Σημείωση, ωστόσο, ότι ο τύπος πάπιας *duck-typing* μπορεί να συμπληρωθεί με *abstract base classes*.) Αντί αυτού, συνήθως χρησιμοποιεί δοκιμές `hasattr()` ή προγραμματισμό *EAFP*.



**EAFP**

Πιο εύκολο να ζητήσεις συγχώρεση παρά άδεια. Αυτό το κοινό στυλ προγραμματισμού σε Python προϋποθέτει την ύπαρξη έγκυρων κλειδιών ή χαρακτηριστικών και συλλαμβάνει εξαιρέσεις εάν η υπόθεση αποδεχθεί εσφαλμένη. Αυτό το καθαρό και γρήγορο στυλ χαρακτηρίζεται από την παρουσία πολλών δηλώσεων `try` και `except`. Η τεχνική έρχεται σε αντίθεση με το στυλ που είναι *LBYL* κοινό σε πολλές άλλες γλώσσες, όπως η C.

**έκφραση**

Ένα κομμάτι σύνταξης που μπορεί να αξιολογηθεί σε κάποια τιμή. Με άλλα λόγια, μια έκφραση είναι μια συσσώρευση στοιχείων έκφρασης όπως κυριολεξία, ονόματα, πρόσβαση χαρακτηριστικών, τελεστές ή κλήσεις συναρτήσεων που όλες επιστρέφουν μια τιμή. Σε αντίθεση με πολλές άλλες γλώσσες, δεν είναι όλες οι γλωσσικές δομές εκφράσεις. Υπάρχουν επίσης *statements* που δεν μπορούν να χρησιμοποιηθούν ως εκφράσεις, όπως το `while`. Οι αναθέσεις τιμών είναι επίσης δηλώσεις όχι εκφράσεις.

**module επέκτασης**

Ένα module γραμμένο σε C ή C++, που χρησιμοποιείται από το C API της Python για να αλληλεπιδράσουν με τον πυρήνα και με τον κώδικα του χρήστη.

**f-string**

Οι κυριολεκτικές συμβολοσειρές χρησιμοποιούν με πρόθεμα `'f'` ή `'F'` ονομάζονται συνήθως «f-strings» που είναι συντομογραφία του formatted string literals. Βλ. επίσης [PEP 498](#).

**αντικείμενο αρχείου**

Ένα αντικείμενο που εκθέτει ένα API προσανατολισμένο σε αρχείο (με μεθόδους όπως `read()` ή `write()`) σε έναν υποκείμενο πόρο. Ανάλογα με τον τρόπο που δημιουργήθηκε, ένα αντικείμενο αρχείου μπορεί να μεσολαβήσει στην πρόσβαση σε ένα πραγματικό αρχείο στο δίσκο ή σε άλλο τύπο συσκευής αποθήκευσης ή επικοινωνίας (για παράδειγμα τυπική είσοδος/ έξοδος, in-memory buffers, sockets, pipes, κλπ.). Αντικείμενα αρχείου ονομάζονται επίσης *file-like objects* ή *streams*.

Στην πραγματικότητα υπάρχουν τρεις κατηγορίες αντικειμένων αρχείου raw *δυναμικά αρχεία*, buffered *δυναμικά αρχεία* και *αρχεία κειμένου*. Οι διεπαφές τους ορίζονται στην ενότητα `io`. Ο κανονικός τρόπος για να δημιουργήσετε ένα αντικείμενο αρχείου είναι χρησιμοποιώντας την συνάρτηση `open()`.

**αντικείμενο που μοιάζει με αρχείο**

Ένα συνώνυμο με το *file object*.

**κωδικοποίηση συστήματος αρχείων και χειριστής σφαλμάτων**

Η κωδικοποίηση και ο χειριστής σφαλμάτων χρησιμοποιείται από την Python για την αποκωδικοποίηση των bytes από το λειτουργικό σύστημα και την κωδικοποίηση σε Unicode για το λειτουργικό σύστημα.

Η κωδικοποίηση συστήματος αρχείων μπορεί να εγγυηθεί την επιτυχημένη αποκωδικοποίηση όλων των bytes κάτω από 128. Εάν η κωδικοποίηση συστήματος αρχείων δεν παρέχει αυτήν την εγγύηση, οι συναρτήσεις API μπορούν να εγείρουν ένα `UnicodeError`.

Οι συναρτήσεις `sys.getfilesystemencoding()` και `sys.getfilesystemencodeerrors()` μπορούν να χρησιμοποιηθούν για να λάβετε την κωδικοποίηση του συστήματος αρχείων και του χειριστή σφαλμάτων.

Ο *filesystem encoding and error handler* διαμορφώνονται κατά την εκκίνηση της Python από τη συνάρτηση `PyConfig_Read()` βλ. `filesystem_encoding` και `filesystem_errors` μέλη του `PyConfig`.

Βλ. επίσης το *locale encoding*.

**finder**

Ένα αντικείμενο που προσπαθεί να βρει το *loader* για ένα module που εισήχθη.

Since Python 3.3, there are two types of finder: *meta path finders* for use with `sys.meta_path`, and *path entry finders* for use with `sys.path_hooks`.

See [PEP 302](#), [PEP 420](#) and [PEP 451](#) for much more detail.

**ακέραια διαίρεση**

Η μαθηματική διαίρεση που στρογγυλοποιεί προς τα κάτω στον κοντινότερο ακέραιο. Ο τελεστής ακεραίας διαίρεσης είναι `//`. Για παράδειγμα, η έκφραση `11 // 4` αξιολογείται σε 2 σε αντίθεση με την



τιμή 2.75 που επιστρέφεται από την διαίρεση με υποδιαστολή. Σημείωση ότι `(-11) // 4` κάνει -3 επειδή αυτή είναι η στρογγυλοποίηση *προς τα κάτω* του -2.75. Βλ. [PEP 238](#).

### συνάρτηση

Μια σειρά από δηλώσεις που επιστρέφουν κάποια τιμή σε αυτόν που την κάλεσε. Σε αυτές μπορούν να περαστούν κανένα ή περισσότερα *ορίσματα* που μπορεί να χρησιμοποιηθεί για την εκτέλεση. Βλ. επίσης τις ενότητες *parameter*, *method*, και *the function*.

### συνάρτηση annotation

Ένας *annotation* μιας παραμέτρου συνάρτησης ή μιας τιμής επιστροφής.

Οι συναρτήσεις annotations συχνά χρησιμοποιούνται για *υποδείξεις τύπου*: για παράδειγμα, αυτή η συνάρτηση αναμένεται να πάρει δύο ορίσματα `int` και επίσης αναμένεται να έχει μία επιστρεφόμενη τιμή `int`:

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

Η σύνταξη συνάρτησης annotation αναλύεται στην ενότητα *function*.

Βλ. *variable annotation* και [PEP 484](#), που περιγράφει αυτή την λειτουργικότητα. Επίσης βλ. *annotations-howto* για τις καλύτερες πρακτικές δουλεύοντας με annotations.

### `__future__`

Ένα future statement, `from __future__ import <feature>`, καθοδηγεί τον μεταγλωττιστή να μεταγλωττίσει το τρέχον module χρησιμοποιώντας σύνταξη ή σημασιολογία που θα γίνει η τυπική σε μελλοντική έκδοση της Python. Το module `__future__` τεκμηριώνει τις πιθανές τιμές του *feature*. Με την εισαγωγή αυτής της λειτουργικής μονάδας και την αξιολόγηση των μεταβλητών της, μπορείτε να δείτε τότε μια νέα δυνατότητα προστέθηκε για πρώτη φορά στην γλώσσα και τότε θα γίνει (ή έγινε) η προεπιλογή:

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

### συλλογή απορριμάτων

Η διαδικασία απελευθέρωσης της μνήμης όταν δεν χρησιμοποιείται άλλο. Η Python εκτελεί συλλογή απορριμάτων μέσω καταμέτρησης αναφορών και ενός κυκλικού συλλέκτη σκουπιδιών που είναι σε θέση να ανιχνεύει και να σπάει τους κύκλους αναφοράς. Ο συλλέκτης απορριμάτων μπορεί να ελεγχθεί χρησιμοποιώντας το module `gc`.

### generator

Μια συνάρτηση που επιστρέφει ένα *generator iterator*. Μοιάζει με μια κανονική συνάρτηση εκτός από το ότι περιέχει εκφράσεις `yield` για την παραγωγή μιας σειράς τιμών που μπορούν να χρησιμοποιηθούν σε έναν βρόχο *for* ή που μπορούν να ανακτηθούν μία τη φορά με την συνάρτηση `next()` function.

Συνήθως αναφέρεται σε μια συνάρτηση generator, αλλά μπορεί να αναφέρεται σε έναν *generator iterator* σε μερικά contexts. Σε περιπτώσεις όπου το επιδιωκόμενο νόημα δεν είναι σαφές, η χρήση των πλήρων όρων αποφεύγει την ασάφεια.

### generator iterator

Ένα αντικείμενο που δημιουργείται από μια συνάρτηση *generator*.

Each `yield` temporarily suspends processing, remembering the location execution state (including local variables and pending try-statements). When the *generator iterator* resumes, it picks up where it left off (in contrast to functions which start fresh on every invocation).

### generator έκφραση

Μια έκφραση που επιστρέφει έναν iterator. Μοιάζει με κανονική έκφραση που ακολουθείται από μια πρόταση *for* που ορίζει μια μεταβλητή βρόχου, ένα εύρος και μια προαιρετική πρόταση *if*. Η συνδυασμένη έκφραση δημιουργεί τιμές για μια συνάρτηση εγκλεισμού:

```
>>> sum(i*i for i in range(10))          # sum of squares 0, 1, 4, ... 81
285
```

### γενική συνάρτηση

Μια συνάρτηση που αποτελείται από πολλαπλές συναρτήσεις που υλοποιούν την ίδια λειτουργία για διαφορετικούς τύπους. Ποια υλοποίηση πρέπει να χρησιμοποιηθεί κατά τη διάρκεια μια κλήσης καθορίζεται από τον αλγόριθμο αποστολής.

Βλ. επίσης την καταχώρηση του [single dispatch](#), τον decorator `functools.singledispatch()` και [PEP 443](#).

### γενικός τύπος

Ένας [type](#) που μπορεί να παραμετροποιηθεί συνήθως μια container class, όπως `list` ή `dict`. Χρησιμοποιείται για [type hints](#) και [annotations](#).

Για περισσότερες λεπτομέρειες, βλ. generic alias types [PEP 483](#), [PEP 484](#), [PEP 585](#), και το module `typing`.

### GIL

Βλ. [global interpreter lock](#).

### global interpreter lock

Ο μηχανισμός που χρησιμοποιείται από τον διερμηνέα [CPython](#) για να διασφαλίσει ότι μόνο ένα νήμα εκτελεί Python [bytecode](#) κάθε φορά. Αυτό απλοποιεί την υλοποίηση CPython δημιουργώντας το μοντέλο αντικειμένου (συμπεριλαμβανομένων κρίσιμων ενσωματωμένων τύπων όπως π.χ. `dict`) έμμεσα ασφαλές έναντι ταυτόχρονης πρόσβασης. Το κλειδίωμα ολόκληρου του διερμηνέα διευκολύνει τον διερμηνέα να είναι πολλαπλών νημάτων, εις βάρος του μεγάλου μέρους του παραλληλισμού που παρέχουν οι μηχανές πολλαπλών επεξεργαστών.

Ωστόσο, ορισμένες λειτουργικές μονάδες επέκτασης, είτε τυπικές είτε τρίτων, έχουν σχεδιαστεί έτσι ώστε να απελευθερώνουν το GIL όταν εκτελούν εργασίες εντατικών υπολογισμών όπως συμπίεση ή κατακερματισμός. Επίσης, το GIL απελευθερώνεται πάντα όταν εκτελείτε I/O.

Προηγούμενες προσπάθειες να δημιουργηθεί ένας διερμηνέας «ελεύθερων-νημάτων» (αυτός που κλειδώνει τα κοινόχρηστα δεδομένα με πολύ πιο λεπτομερή ευαισθησία) δεν ήταν επιτυχείς επειδή η απόδοση υποχώρησε στην κοινή περίπτωση ενός επεξεργαστή. Πιστεύεται ότι η υπέρβαση αυτού του προβλήματος απόδοσης θα κάνουν πολύ πιο περίπλοκη και επομένως πιο δαπανηρή στην συντήρηση.

### hash-based pyc

Ένα αρχείο κρυφής μνήμης [bytecode](#) που χρησιμοποιεί τον κατακερματισμό και όχι τον χρόνο τροποποίησης του αντίστοιχου αρχείου προέλευσης για να προσδιορίσει την εγκυρότητα του. Βλ. [pyc-invalidation](#).

### hashable

Ένα αντικείμενο είναι [hashable](#) εάν έχει μια τιμή κατακερματισμού που δεν αλλάζει ποτέ κατά τη διάρκεια της ζωής του (χρειάζεται μια μέθοδο `__hash__()`), και μπορεί να συγκριθεί με άλλα αντικείμενα (χρειάζεται μια μέθοδο `__eq__()`). Τα [hashable](#) αντικείμενα που συγκρίνονται ως προς την ισότητα τους πρέπει να έχουν την ίδια τιμή κατακερματισμού.

Η ύπαρξη [hashable](#) κάνει ένα αντικείμενο να μπορεί να χρησιμοποιηθεί ως κλειδί λεξικού και ως μέλος ενός συνόλου, επειδή αυτές οι δομές δεδομένων χρησιμοποιούν τιμές κατακερματισμού.

Τα περισσότερα από τα αμετάβλητα ενσωματωμένα αντικείμενα της Python μπορούν να κατακερματιστούν τα μεταβλητά κοντέινερ (όπως οι λίστες ή τα λεξικά) δεν είναι τα αμετάβλητα κοντέινερ (όπως `frozensets`) μπορούν να κατακερματιστούν μόνο εάν τα στοιχεία τους είναι κατακερματισμένα. Τα αντικείμενα που είναι στιγμιότυπα κλάσεων που ορίζονται από το χρήστη μπορούν να κατακερματιστούν από προεπιλογή. Όλα συγκρίνονται άνισα εκτός από τον εαυτό τους) και η τιμή κατακερματισμού τους προέρχεται από το `id()`.

### IDLE

Ένα ολοκληρωμένο περιβάλλον ανάπτυξης και μάθησης για την Python. `idle` είναι ένα βασικό περιβάλλον επεξεργασίας και διερμηνέα που συνοδεύεται από την τυπική διανομή της Python.

### immutable

Ένα αντικείμενο με σταθερή τιμή. Τα αμετάβλητα αντικείμενα περιλαμβάνουν αριθμούς, συμβολοσειρές και πλειάδες. Ένα τέτοιο αντικείμενο δεν μπορεί να αλλάξει. Ένα νέο αντικείμενο πρέπει να δημιουργηθεί εάν πρέπει να αποθηκευτεί μια διαφορετική τιμή. Παίζουν σημαντικό ρόλο σε μέρη όπου μια σταθερά απαιτείται, για παράδειγμα ως κλειδί σε ένα λεξικό.

**εισαγόμενο path**

Μια λίστα από τοποθεσίες (ή *καταχωρίσεις διαδρομής*) που μπορούν να αναζητηθούν *path based finder* για να εισαχθούν modules. Κατά την διαδικασία εισαγωγής, αυτή η λίστα με τοποθεσίες συνήθως έρχεται από `sys.path`, αλλά για τα υποπακέτα μπορεί επίσης να έρθει από το χαρακτηριστικό του πακέτου γονέα `__path__`.

**εισαγωγή**

Η διαδικασία κατά την οποία ο κώδικας της Python σε ένα module είναι διαθέσιμη στον κώδικα Python ενός άλλου module.

**εισαγωγέας**

Ένα αντικείμενο μπορεί και να αναζητεί και να φορτώνει ένα module” και ένα *finder* και *loader* αντικείμενο.

**διαδραστικός**

Η Python έχει έναν διαδραστικό διερμηνέα όπου σημαίνει ότι μπορείς να εισάγεις δηλώσεις και εκφράσεις στην εισαγωγή εντολών του διερμηνέα, εκτελώντας τις άμεσα και εμφανίζοντας τα αντικείμενα. Απλώς εκκινήστε την python χωρίς ορίσματα (πιθανώς επιλέγοντας το από το κύριο μενού του υπολογιστή σας). Αποτελεί έναν αποδοτικό τρόπο για να δοκιμάστε νέες ιδέες ή να εξετάστε λειτουργικές μονάδες και πακέτα (θυμηθείτε `help(x)`).

**interpreted**

Η Python είναι μια interpreted γλώσσα, σε αντίθεση με μια μεταγλωττισμένη, αν και η διάκριση μπορεί να είναι και θολή λόγω της παρουσία του bytecode μεταγλωττιστή. Αυτό σημαίνει ότι τα αρχεία προέλευσης μπορούν να εκτελεστούν απευθείας χωρίς να δημιουργηθεί ρητά ένα εκτελέσιμο αρχείο που στην συνέχεια εκτελείται. Οι interpreted γλώσσες συνήθως έχουν μικρότερο κύκλο ανάπτυξης/ εντοπισμού σφαλμάτων από τις μεταγλωττισμένες, αν και τα προγράμματά τους γενικά εκτελούνται πιο αργά. Βλ. επίσης *interactive*.

**τερματισμός λειτουργίας διερμηνέα**

Όταν ζητείται τερματισμός λειτουργίας, ο διερμηνέας της Python εισέρχεται σε μια ειδική φάση όπου απελευθερώνει σταδιακά όλους τους διατιθέμενους πόρους, όπως λειτουργικές μονάδες και πολλαπλές κρίσιμες εσωτερικές δομές. Επίσης πραγματοποιεί αρκετές κλήσεις στο *συλλέκτης σκουπιδιών*. Αυτό μπορεί να ενεργοποιήσει την εκτέλεση κώδικα σε καταστροφείς που ορίζονται από το χρήστη ή σε callbacks ασθενοφών ανταποκρίσεις. Ο κώδικας που εκτελείται κατά τη φάση τερματισμού λειτουργίας μπορεί να συναντήσει διάφορες εξαιρέσεις, καθώς οι πόροι στους οποίους βασίζεται ενδέχεται να μην λειτουργούν πλέον (συνήθη παραδείγματα είναι οι λειτουργικές μονάδες βιβλιοθήκης ή ο μηχανισμός ειδοποιήσεων).

Ο βασικός λόγος τερματισμού λειτουργίας του διερμηνέα είναι ότι το `__main__` module ή ολοκληρώθηκε η εκτέλεση του κώδικα που έτρεχε.

**iterable**

An object capable of returning its members one at a time. Examples of iterables include all sequence types (such as `list`, `str`, and `tuple`) and some non-sequence types like `dict`, *file objects*, and objects of any classes you define with an `__iter__()` method or with a `__getitem__()` method that implements *sequence* semantics.

Τα iterables μπορούν να χρησιμοποιηθούν σε ένα `for` βρόχο και σε πολλά άλλα σημεία όπου χρειάζεται μια ακολουθία (`zip()`, `map()`, ...). Όταν ένα iterable αντικείμενο μεταβιβάζεται ως όρισμα στην ενσωματωμένη συνάρτηση `iter()`, επιστρέφει έναν iterator για αντικείμενο. Αυτός ο iterator είναι καλός για ένα πέρασμα από ένα σύνολο τιμών. Όταν χρησιμοποιείται επαναληπτικά, συνήθως δεν είναι απαραίτητο να καλέσετε το `iter()` ή να ασχοληθείτε μόνοι σας με αντικείμενα iterator. Η δήλωση `for` το κάνει αυτόματα για εσάς, δημιουργώντας μια προσωρινή μεταβλητή χωρίς όνομα για να κρατά τον iterator για την διάρκεια του βρόχου. Βλ. επίσης *iterator*, *sequence*, και *generator*.

**iterator**

Ένα αντικείμενο που αντιπροσωπεύει μια ροή δεδομένων. Επαναλαμβανόμενες κλήσεις προς τη μέθοδο `__next__()` του iterator (ή μεταβίβαση του στην ενσωματωμένη συνάρτηση `next()`) επιστρέφουν διαδοχικά στοιχεία στην ροή. Όταν όχι περισσότερα δεδομένα είναι διαθέσιμα εγείρεται μια εξαίρεση `StopIteration`. Σε αυτό το σημείο, το αντικείμενο iterator εξαντλείται και τυχόν περαιτέρω κλήσεις στη μέθοδο `__next__()` απλώς απλά εγείρουν ξανά το `StopIteration`. Οι iterators πρέπει να έχουν μια μέθοδο `__iter__()` που επιστρέφει το ίδιο το αντικείμενο iterator, έτσι ώστε κάθε

iterator να είναι επίσης iterable και μπορεί να χρησιμοποιηθεί στα περισσότερα μέρη όπου γίνονται αποδεκτοί και άλλοι iterators. Μια αξιοσημείωτη εξαίρεση είναι ο κώδικας που επιχειρεί πολλαπλά περάσματα iteration. Ένα αντικείμενο κοντέινερ (όπως ένα list) παράγει έναν καθαρά νέο iterator κάθε φορά που κάθε φορά που μεταβιβάζεται στην συνάρτηση `iter()` ή τον χρησιμοποιείται σε έναν `for` βρόχο. Εάν επιχειρήσετε αυτό με έναν iterator απλώς θα επιστρέψετε το ίδιο εξαντλημένο αντικείμενο iterator που χρησιμοποιήθηκε στο προηγούμενο πέρασμα iteration, κάνοντας το να φαίνεται σαν ένα άδαιο κοντέινερ.

Περισσότερες πληροφορίες μπορούν να βρεθούν στο `typeiter`.

**Λεπτομέρεια υλοποίησης CPython:** Το CPython δεν εφαρμόζει με συνέπεια την απαίτηση να ορίζει ένας iterator `__iter__()`.

### συνάρτηση key

Μια συνάρτηση κλειδί ή μια συνάρτηση ταξινόμησης είναι μια δυνατότητα κλήσης που επιστρέφει μια τιμή που χρησιμοποιείται για ταξινόμηση ή διάταξη. Για παράδειγμα, `locale.strxfrm()` χρησιμοποιείται για την παραγωγή ενός κλειδιού ταξινόμησης που γνωρίζει τις συμβάσεις ταξινόμησης για συγκεκριμένες τοπικές ρυθμίσεις.

Ένα αριθμός εργαλείων στην Python δέχεται βασικές συναρτήσεις για τον έλεγχο του τρόπου με τον οποίο τα στοιχεία ταξινομούνται ή ομαδοποιούνται. Αυτά περιέχουν `min()`, `max()`, `sorted()`, `list.sort()`, `heapq.merge()`, `heapq.nsmallest()`, `heapq.nlargest()`, και `itertools.groupby()`.

Υπάρχουν διάφοροι τρόποι για να δημιουργήσετε μια συνάρτηση κλειδιού. Για παράδειγμα, η μέθοδος `str.lower()` μπορεί να χρησιμεύσει ως συνάρτηση κλειδί για την περίπτωση μη διάκρισης πεζών-κεφαλαίων. Εναλλακτικά, μια συνάρτηση κλειδιού μπορεί να δημιουργηθεί από μια `lambda` έκφραση όπως `lambda r: (r[0], r[2])`. Επίσης, `operator.attrgetter()`, `operator.itemgetter()` και `operator.methodcaller()` είναι τρεις κατασκευαστές βασικών συναρτήσεων. Βλ. το Ταξινόμηση HOW TO για παραδείγματα δημιουργίας και χρήσης βασικών συναρτήσεων.

### όρισμα keyword

Βλ. [argument](#).

### lambda

Μια ανώνυμη ενσωματωμένη συνάρτηση που αποτελείται από μια μοναδική *expression* η οποία αξιολογείται όταν καλείται η συνάρτηση. Η σύνταξη για τη δημιουργία μιας συνάρτησης `lambda` είναι `lambda [parameters]: expression`

### LBYL

Look before you leap. Αυτό το στυλ κωδικοποίησης ελέγχει ρητά τις προϋποθέσεις πριν πραγματοποιήσει κλήσεις ή αναζητήσεις. Αυτό το στυλ έρχεται σε αντίθεση με την προσέγγιση *EAFP* και χαρακτηρίζεται από την παρουσία πολλών δηλώσεων `if`.

Σε ένα περιβάλλον πολλαπλών νημάτων, η προσέγγιση LBYL μπορεί να διακινδυνεύσει να εισάγει μια συνθήκη αγώνα μεταξύ «the Looking» και «the leaping». Για παράδειγμα ο κώδικας, `if key in mapping: return mapping[key]` μπορεί να αποτύχει εάν ένα άλλο νήμα αφαιρέσει το `key` από το `mapping` μετά τη δοκιμή, αλλά πριν από την αναζήτηση. Αυτό το πρόβλημα μπορεί να λυθεί με κλειδώματα ή χρησιμοποιώντας την προσέγγιση EAFP.

### λίστα

Ένα ενσωματωμένο Python *sequence*. Παρά το όνομα του, μοιάζει περισσότερο με έναν πίνακα σε άλλες γλώσσες παρά με μια συνδεδεμένη λίστα, καθώς η πρόσβαση στα στοιχεία είναι  $O(1)$ .

### list comprehension

Ένα συμπαγής τρόπος για να επεξεργαστείτε όλα ή μέρος των στοιχείων σε μια ακολουθία και να επιστρέψετε μια λίστα με τα αποτελέσματα. `result = ['{:04x}'.format(x) for x in range(256) if x % 2 == 0]` δημιουργεί μια λίστα συμβολοσειρών που περιέχουν ζυγούς δεκαδικούς αριθμούς (0x..) στο εύρος από 0 έως 255. Η πρόταση `if` είναι προαιρετική. Εάν παραλειφθεί, όλα τα στοιχεία στο `range(256)` υποβάλλονται σε επεξεργασία.

### loader

An object that loads a module. It must define a method named `load_module()`. A loader is typically returned by a *finder*. See **PEP 302** for details and `importlib.abc.Loader` for an *abstract base class*.

**τοπική κωδικοποίηση**

Στο Unix, είναι η κωδικοποίηση της τοπικής ρύθμισης LC\_CTYPE. Μπορεί να ρυθμιστεί με `locale.setlocale(locale.LC_CTYPE, new_locale)`.

Στα Windows, είναι η code page ANSI (π.χ. "cp1252").

Στο Android και το VxWorks, η Python χρησιμοποιεί το "utf-8" ως τοπική κωδικοποίηση.

`locale.getencoding()` μπορεί να χρησιμοποιηθεί για την ανάκτηση της τοπικής κωδικοποίησης.

Βλ. επίσης το *filesystem encoding and error handler*.

**μαγική μέθοδος**

Ένα άτυπο συνώνυμο για *special method*.

**mapping**

Ένα αντικείμενο κοντέινερ που υποστηρίζει αυθαίρετες αναζητήσεις κλειδιών και υλοποιεί τις μεθόδους που καθορίζονται στο `collections.abc.Mapping` ή `collections.abc.MutableMapping` abstract base classes. Τα παραδείγματα περιλαμβάνουν `dict`, `collections.defaultdict`, `collections.OrderedDict` και `collections.Counter`.

**meta path finder**

Ένας *finder* που επιστράφηκε με αναζήτηση στο `sys.meta_path`. Οι *finders* μετα-διαδρομής σχετίζονται, αλλά διαφέρουν από τα *finders entry διαδρομής*.

Βλ. `importlib.abc.MetaPathFinder` για τις μεθόδους που υλοποιούν οι meta path finders.

**μετα-κλάση**

Η κλάση μιας κλάσης. Οι ορισμοί κλάσης δημιουργούν ένα όνομα κλάσης, ένα λεξικό κλάσης και μια λίστα βασικών κλάσεων. Η μετα-κλάση είναι υπεύθυνη για την απόκτηση αυτών των τριών ορισμάτων και την δημιουργία της κλάσης. Οι περισσότερες αντικειμενοστρεφείς γλώσσες προγραμματισμού παρέχουν μια προεπιλεγμένη υλοποίηση. Αυτό που κάνει την Python ξεχωριστή είναι ότι είναι δυνατή η δημιουργία προσαρμοσμένων μετακλάσεων. Οι περισσότεροι χρήστες δεν χρειάζονται ποτέ αυτό το εργαλείο, αλλά όταν παραστεί ανάγκη, αυτό το εργαλείο, οι μετα-κλάσεις μπορούν να παρέχουν ισχυρές, κομψές λύσεις. Έχουν χρησιμοποιηθεί για την καταγραφή πρόσβασης χαρακτηριστικών, την προσθήκη ασφάλειας νημάτων, την παρακολούθηση δημιουργίας αντικειμένων, την υλοποίηση *singletons*, και πολλές άλλες εργασίες.

Περισσότερες πληροφορίες μπορούν να βρεθούν στο *metaclasses*.

**μέθοδος**

Μια συνάρτηση που ορίζεται μέσα στο σώμα μιας κλάσης. Εάν καλείται ως χαρακτηριστικό μιας περίπτωσης αυτής της κλάσης, η μέθοδος θα λάβει αντικείμενο περίπτωσης ως πρώτο της *argument* (το οποίο συνήθως ονομάζεται `self`). Βλ. *function* και *nested scope*.

**σειρά ανάλυσης μεθόδων**

Method Resolution Order is the order in which base classes are searched for a member during lookup. See [The Python 2.3 Method Resolution Order](#) for details of the algorithm used by the Python interpreter since the 2.3 release.

**module**

Ένα αντικείμενο που χρησιμεύει ως οργανωτική μονάδα του κώδικα της Python. Τα modules έχουν έναν χώρο ονομάτων που περιέχει αυθαίρετα αντικείμενα Python. Τα modules φορτώνονται στην Python με την διαδικασία *importing*.

Βλ. επίσης *package*.

**τεχνικές προδιαγραφές module**

Ένα namespace που περιέχει τις πληροφορίες που σχετίζονται με την εισαγωγή που χρησιμοποιούνται για την φόρτωση ενός module. Μια περίπτωση του `importlib.machinery.ModuleSpec`.

**MRO**

Βλ. *method resolution order*.

**mutable**

Τα ευμετάβλητα αντικείμενα μπορούν να αλλάξουν τις τιμές αλλά να κρατήσουν τα `id()`. Βλ. επίσης *immutable*.



### named tuple

Ο όρος «named tuple» εφαρμόζεται για οποιονδήποτε τύπο ή κλάση που κληρονομείται από την πλειάδα και των οποίων τα στοιχεία μπορούν να ευρετηριοποιηθούν είναι προσβάσιμα χρησιμοποιώντας επώνυμα χαρακτηριστικά. Ο τύπος ή η κλάση μπορεί να έχει και άλλα χαρακτηριστικά.

Πολλοί ενσωματωμένοι τύποι είναι named tuples, συμπεριλαμβανομένων των τιμών που επιστρέφονται από `time.localtime()` και `os.stat()`. Ένα άλλο παράδειγμα είναι το `sys.float_info`:

```
>>> sys.float_info[1]                # indexed access
1024
>>> sys.float_info.max_exp            # named field access
1024
>>> isinstance(sys.float_info, tuple) # kind of tuple
True
```

Ορισμένες αναγνωρισμένες πλειάδες είναι ενσωματωμένοι τύποι (όπως τα παραπάνω παραδείγματα). Εναλλακτικά, μια αναγνωρισμένη πλειάδα μπορεί να δημιουργηθεί από έναν ορισμό κανονικής κλάσης που κληρονομεί από `tuple` και που ορίζει έγκυρα πεδία. Μια τέτοια κλάση μπορεί να είναι γραμμένη με το `χέρι` ή μπορεί να δημιουργηθεί κληρονομώντας το `typing.NamedTuple`, ή με την `factory` συνάρτηση `collections.namedtuple()`. Οι τελευταίες τεχνικές προσθέτουν επίσης μερικές επιπλέον μεθόδους που μπορεί να μην βρεθούν σε χειρόγραφες ή ενσωματωμένες πλειάδες με όνομα.

### namespace

Το μέρος όπου αποθηκεύεται μια μεταβλητή. Τα namespaces υλοποιούνται ως λεξικά. Υπάρχουν οι τοπικοί, οι καθολικοί και οι ενσωματωμένοι namespaces καθώς και οι ένθετοι namespaces σε αντικείμενα (σε μεθόδους). Για παράδειγμα οι συναρτήσεις `builtins.open` και `os.open()` διακρίνονται από τους χώρους ονομάτων τους. Οι χώροι ονομάτων βοηθούν επίσης την αναγνωσιμότητα και τη συντηρησιμότητα καθιστώντας σαφές ποιο module υλοποιεί μια λειτουργία. Για παράδειγμα, γράφοντας `random.seed()` ή `itertools.islice()` καθιστά σαφές ότι αυτές οι συναρτήσεις υλοποιούνται από τα module `random` και `itertools`, αντίστοιχα.

### πακέτο namespace

A **PEP 420** *package* which serves only as a container for subpackages. Namespace packages may have no physical representation, and specifically are not like a *regular package* because they have no `__init__.py` file.

Βλ. επίσης *module*.

### nested scope

Η δυνατότητα αναφοράς σε μια μεταβλητή σε έναν περικλειόμενο ορισμό. Για παράδειγμα μια συνάρτηση που ορίζεται μέσα σε μια άλλη συνάρτηση μπορεί να αναφέρεται σε μεταβλητές στην εξωτερική συνάρτηση. Σημειώστε ότι τα ένθετα πεδία από προεπιλογή λειτουργούν μόνο για αναφορά και όχι για εκχώρηση. Οι τοπικές μεταβλητές διαβάζονται και γράφονται στο εσωτερικό πεδίο εφαρμογής. Ομοίως, οι καθολικές μεταβλητές διαβάζουν και γράφουν στον καθολικό χώρο ονομάτων. Το `nonlocal` επιτρέπει την εγγραφή σε εξωτερικά πεδία.

### κλάση νέου στυλ

Το παλιό όνομα για το είδος των κλάσεων χρησιμοποιείται πλέον για όλα τα αντικείμενα. Σε παλιότερες εκδόσεις της Python, μόνο οι κλάσεις νέου στυλ μπορούσαν να χρησιμοποιήσουν τις νεότερες, ευέλικτες δυνατότητες της Python όπως `__slots__`, `descriptors`, ιδιότητες `__getattr__()`, μέθοδοι κλάσης, και στατικές μέθοδοι.

### αντικείμενο

Οποιαδήποτε δεδομένα με κατάσταση (χαρακτηριστικά ή τιμή) και καθορισμένη συμπεριφορά (μέθοδοι). Επίσης, η τελική βασική κλάση οποιασδήποτε *new-style class*.

### πακέτο

Ένα Python *module* που μπορεί να περιέχει submodules ή αναδρομικά, υποπακέτα. Τεχνικά, ένα πακέτο είναι μια λειτουργική μονάδα Python με ένα `__path__` χαρακτηριστικό.

Βλ. επίσης *regular package* και *namespace package*.

### παράμετρος

Μια έγκυρη οντότητα σε έναν ορισμό *function* (ή μέθοδος) που καθορίζει ένα *argument* (ή σε ορισμένες

περιπτώσεις, ορίσματα) που μπορεί να δεχθεί η συνάρτηση. Υπάρχουν πέντε είδη παραμέτρων:

- *λέξη-κλειδί ή θέση*: καθορίζει ένα όρισμα που μπορεί να μεταβιβαστεί είτε *θέσεως* ή ως *όρισμα λέξης-κλειδιού*. Αυτό είναι το προεπιλεγμένο είδος παραμέτρου, για παράδειγμα *foo* και *bar* στα ακόλουθα:

```
def func(foo, bar=None): ...
```

- *θέσεως μόνο*: καθορίζει ένα όρισμα που μπορεί να παρέχεται μόνο από τη θέση. Οι παράμετροι μόνο θέσης μπορούν να οριστούν συμπεριλαμβάνοντας έναν χαρακτήρα / στη λίστα παραμέτρων του ορισμού συνάρτησης μετά από αυτές, για παράδειγμα *posonly1* και *posonly2* στα εξής:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

- *λέξης-κλειδί μόνο*: καθορίζει ένα όρισμα που μπορεί να παρέχεται μόνο με λέξη κλειδί. Οι παράμετροι μόνο για λέξη-κλειδί μπορούν να οριστούν συμπεριλαμβάνοντας μια παράμετρο θέσης ή σκέτο \* στη λίστα παραμέτρων του ορισμού συνάρτησης πριν από αυτές, για παράδειγμα *kw\_only1* και *kw\_only2* στα ακόλουθα:

```
def func(arg, *, kw_only1, kw_only2): ...
```

- *μεταβλητή θέσης*: καθορίζει ότι μπορεί να παρασχεθεί μια αυθαίρετη ακολουθία ορισμάτων θέσης (επιπλέον των ορισμάτων θέσης που είναι ήδη αποδεκτά από άλλες παραμέτρους). Μια τέτοια παράμετρος μπορεί να οριστεί προσαρτώντας το όνομα της παραμέτρου με \*, για παράδειγμα *args* στα ακόλουθα:

```
def func(*args, **kwargs): ...
```

- *μεταβλητή λέξη-κλειδί*: καθορίζει ότι μπορούν να παρέχονται αυθαίρετα πολλά ορίσματα λέξης-κλειδιού (επιπλέον των ορισμάτων λέξης κλειδιού που είναι αποδεκτά από άλλες παραμέτρους). Μια τέτοια παράμετρος μπορεί να οριστεί προσαρτώντας το όνομα της παραμέτρου με \*\*, για παράδειγμα *kwargs* όπως παραπάνω.

Οι παράμετροι μπορούν να καθορίσουν τόσο τα προαιρετικά όσο και τα απαιτούμενα ορίσματα, καθώς και προεπιλεγμένες τιμές για ορισμένα προαιρετικά ορίσματα.

Βλ. επίσης την *argument* καταχώριση ευρετηρίου, την ερώτηση FAQ σχετικά με η διαφορά μεταξύ ορισμάτων και παραμέτρων, την κλάση `inspect.Parameter`, την ενότητα *function* και **PEP 362**.

### path entry

Μια μεμονωμένη τοποθεσία στο *import path* την οποία συμβουλεύεται ο *path based finder* για να βρει modules για εισαγωγή.

### path entry finder

Ένας *finder* που επιστρέφεται από έναν καλούμενο στο `sys.path_hooks` (δηλαδή ένα *path entry hook*) που ξέρει πως να εντοπίζει modules με *path entry*.

Βλ. `importlib.abc.PathEntryFinder` για τις μεθόδους που ο entry finder διαδρομής υλοποιεί.

### path entry hook

Ένα καλούμενο στη λίστα `sys.path_hooks`, το οποίο επιστρέφει ένα *path entry finder* εάν ξέρει πως να βρίσκει module σε μια συγκεκριμένη *path entry*.

### path based finder

Ένα από τα προεπιλεγμένα *meta path finders* που αναζητά ένα *import path* για modules.

### path-like αντικείμενο

Ένα αντικείμενο που αντιπροσωπεύει ένα path συστήματος αρχείων. Ένα αντικείμενο path είναι είτε ένα αντικείμενο `str` ή `bytes` που αντιπροσωπεύει ένα path ή ένα αντικείμενο που υλοποιεί το πρωτόκολλο `os.PathLike`. Ένα αντικείμενο που υποστηρίζει το πρωτόκολλο `os.PathLike` μπορεί να μετατραπεί σε path συστήματος αρχείων `str` ή `bytes` καλώντας την συνάρτηση `os.fspath()` τα `os.fsdecode()` και `os.fsencode()` μπορούν να χρησιμοποιηθούν για την εγγύηση ενός αποτελέσματος `str` ή `bytes`, αντίστοιχα. Εισήχθη από τον **PEP 519**.

**PEP**

Πρόταση Βελτίωσης Python. Ένα PEP είναι ένα έγγραφο σχεδιασμού που παρέχει πληροφορίες στην κοινότητα Python ή περιγράφει μια νέα δυνατότητα για την Python ή τις διαδικασίες ή το περιβάλλον της. Τα PEP θα πρέπει να παρέχουν μια συνοπτική τεχνική προδιαγραφή και μια λογική για τα προτεινόμενα χαρακτηριστικά.

Τα PEP προορίζονται να είναι οι κύριοι μηχανισμοί για την πρόταση σημαντικών νέων χαρακτηριστικών, για τη συλλογή πληροφοριών της κοινότητας για ένα ζήτημα και για την τεκμηρίωση των αποφάσεων σχεδιασμού που έχουν εισαχθεί στην Python. Ο συγγραφέας του PEP είναι υπεύθυνος για την οικοδόμηση συναίνεσης εντός της κοινότητας και την τεκμηρίωση αντίθετων απόψεων.

Βλ. [PEP 1](#).

**τιμήμα**

Ένα σύνολο από αρχεία σε έναν μόνο κατάλογο (ενδεχομένως αποθηκευμένο σε αρχείο *zip*) που συμβάλλουν σε ένα namespace πακέτο, όπως ορίζεται στο [PEP 420](#).

**όρισμα θέσης**

Βλ. [argument](#).

**provisional API**

Ένα provisional API είναι αυτό που έχει εσκεμμένα εξαιρεθεί από τις backwards εγγυήσεις συμβατότητας της τυπικής βιβλιοθήκης. Αν και δεν αναμένονται σημαντικές αλλαγές σε τέτοιες διεπαφές, εφόσον επισημαίνονται ως προσωρινές, αλλαγές μη backwards συμβατότητας (μέχρι και κατάργηση της διεπαφής) μπορεί να προκύψουν εάν κριθεί απαραίτητο από τους βασικούς προγραμματιστές. Τέτοιες αλλαγές δεν θα γίνουν άσκοπα – θα συμβούν μόνο εάν αποκαλυφθούν σοβαρά θεμελιώδη ελαττώματα που παραλείφθηκαν πριν από τη συμπερίληψη του API.

Ακόμη και για provisional API, οι μη backwards συμβατές αλλαγές θεωρούνται «λύση έσχατης ανάγκης»- θα εξακολουθεί να γίνεται κάθε προσπάθεια για να βρεθεί μια λύση backwards συμβατή σε τυχόν εντοπισμένα προβλήματα.

Αυτή η διαδικασία επιτρέπει στην τυπική βιβλιοθήκη να συνεχίσει να εξελίσσεται με την πάροδο του χρόνου, χωρίς να κλειδώνει προβληματικά σφάλματα σχεδιασμού για εκτεταμένες χρονικές περιόδους. Βλ. [PEP 411](#) για περισσότερες λεπτομέρειες.

**provisional πακέτο**

Βλ. [provisional API](#).

**Python 3000**

Ψευδώνυμο για το σύνολο εκδόσεων Python 3.x (επινοήθηκε πριν από πολύ καιρό όταν η κυκλοφορία της έκδοσης 3 ήταν κάτι στο μακρινό μέλλον.) Αυτό ονομάζεται επίσης ως συντομογραφία «Py3k».

**Pythonic**

Μια ιδέα ή ένα κομμάτι κώδικα που ακολουθεί πιστά τα πιο κοινά ιδιώματα της γλώσσας Python, αντί να υλοποιεί κώδικα χρησιμοποιώντας έννοιες κοινές σε άλλες γλώσσες. Για παράδειγμα, ένα κοινό ιδίωμα στην Python είναι να κάνει μια επανάληψη πάνω από όλα τα στοιχεία ενός iterable χρησιμοποιώντας μια δήλωση `for`. Πολλές άλλες γλώσσες που δεν έχουν αυτόν τον τύπο κατασκευής, έτσι οι άνθρωποι που δεν είναι εξοικειωμένοι με την Python χρησιμοποιούν μερικές φορές έναν αριθμητικό μετρητή:

```
for i in range(len(food)) :
    print (food[i])
```

Αντίθετα, μια πιο καθαρή μέθοδος Pythonic:

```
for piece in food:
    print (piece)
```

**αναγνωρισμένο όνομα**

Ένα όνομα με κουκκίδες που δείχνει τη «διαδρομή» από το καθολικό εύρος ενός module σε μια κλάση, συνάρτηση ή μέθοδο που ορίζεται σε αυτήν την ενότητα, όπως ορίζεται στο [PEP 3155](#). Για συναρτήσεις και κλάσεις ανώτατου επιπέδου, το αναγνωρισμένο όνομα είναι ίδιο με το όνομα του αντικειμένου:



```
>>> class C:
...     class D:
...         def meth(self):
...             pass
...
>>> C.__qualname__
'C'
>>> C.D.__qualname__
'C.D'
>>> C.D.meth.__qualname__
'C.D.meth'
```

Όταν χρησιμοποιείται για αναφορά σε modules, το πλήρως αναγνωρισμένο όνομα σημαίνει ολόκληρο το διακεκομμένο path προς το module, συμπεριλαμβανομένων τυχόν γονικών πακέτων π.χ. `email.mime.text`:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

### πλήθος αναφοράς

The number of references to an object. When the reference count of an object drops to zero, it is deallocated. Reference counting is generally not visible to Python code, but it is a key element of the *CPython* implementation. Programmers can call the `sys.getrefcount()` function to return the reference count for a particular object.

### κανονικό πακέτο

Ένα παραδοσιακό *package*, όπως ένας κατάλογος που περιέχει ένα `__init__.py` αρχείο.

Βλ. επίσης *namespace package*.

### `__slots__`

Μια δήλωση μέσα σε μια κλάση που εξοικονομεί μνήμη δηλώνοντας εκ των προτέρων χώρο για παράδειγμα χαρακτηριστικά και εξαλείφοντας λεξικά στιγμιотύπων. Αν και δημοφιλής, η τεχνική είναι κάπως δύσκολο να γίνει σωστή και προορίζεται καλύτερα για σπάνιες περιπτώσεις όπου υπάρχει μεγάλος αριθμός στιγμιотύπων σε μια εφαρμογή κρίσιμης-μνήμης.

### ακολουθία

An *iterable* which supports efficient element access using integer indices via the `__getitem__()` special method and defines a `__len__()` method that returns the length of the sequence. Some built-in sequence types are `list`, `str`, `tuple`, and `bytes`. Note that `dict` also supports `__getitem__()` and `__len__()`, but is considered a mapping rather than a sequence because the lookups use arbitrary *immutable* keys rather than integers.

Η αφηρημένη βασική κλάση `collections.abc.Sequence` ορίζει μια πολύ πιο πλούσια διεπαφή που ξεπερνά τα απλά `__getitem__()` και `__len__()`, `adding count()`, `index()`, `__contains__()`, και `__reversed__()`. Οι τύποι που υλοποιούν αυτήν την διευρυμένη διεπαφή μπορούν να καταχωρηθούν ρητά χρησιμοποιώντας `register()`. Για περισσότερη τεκμηρίωση σχετικά με τις μεθόδους ακολουθίας γενικά, ανατρέξτε στο Common Sequence Operations.

### set comprehension

Ένας συμπαγής τρόπος για να επεξεργαστείτε όλα ή μέρος των στοιχείων σε ένα iterable και να επιστραφεί ένα σύνολο με τα αποτελέσματα. `results = {c for c in 'abracadabra' if c not in 'abc'}` δημιουργεί το σύνολο συμβολοσειρών `{'r', 'd'}`. Βλ. *comprehensions*.

### μοναδικό dispatch

Μια μορφή dispatch *generic function* όπου η υλοποίηση επιλέγεται με βάση τον τύπο ενός μεμονωμένου ορίσματος.

### slice

Ένα αντικείμενο που συνήθως περιέχει ένα τμήμα μιας ακολουθίας *sequence*. Δημιουργείται ένα slice χρησιμοποιώντας τη σημείωση subscript, `[]` με άνω και κάτω τελείες μεταξύ αριθμών όταν δίνονται

πολλοί, όπως στο `variable_name[1:3:5]`. Η σημείωση αγκύλης (subscript) χρησιμοποιεί εσωτερικά αντικείμενα `slice`.

#### ειδική μέθοδος

Μια μέθοδος που καλείται σιωπηρά από την Python για να εκτελέσει μια συγκεκριμένη λειτουργία σε έναν τύπο, όπως η προσθήκη. Τέτοιες μέθοδοι έχουν ονόματα που ξεκινούν και τελειώνουν με διπλές κάτω παύλες. Οι ειδικές μέθοδοι τεκμηριώνονται στο `specialnames`.

#### δήλωση

Μια πρόταση είναι μέρος μιας σουίτας (ένα «μπλοκ» κώδικα). Μια πρόταση είναι είτε ένας *expression* είτε μια από πολλές δομές με μια λέξη-κλειδί όπως `if`, `while` ή `for`.

#### ελεγκτής στατικού τύπου

Ένα εξωτερικό εργαλείο όπου διαβάσει τον Python κώδικα και τον αναλύει, αναζητώντας προβλήματα όπως λανθασμένοι τύποι. Βλ. επίσης *type hints* και το module `typing`.

#### strong reference

Στο C API της Python, μια ισχυρή αναφορά είναι μια αναφορά σε ένα αντικείμενο που ανήκει στον κώδικα που περιέχει την αναφορά. Η ισχυρή αναφορά λαμβάνεται καλώντας το `Py_INCREF()` όταν η αναφορά δημιουργείται και απελευθερώνεται με `Py_DECREF()` όταν διαγραφεί η αναφορά.

Η συνάρτηση `Py_NewRef()` μπορεί να χρησιμοποιηθεί για τη δημιουργία ισχυρής αναφοράς σε ένα αντικείμενο. Συνήθως, η συνάρτηση `Py_DECREF()` πρέπει να καλείται στην ισχυρή αναφορά πριν βγει από το εύρος της ισχυρής αναφοράς, για να αποφευχθεί η διαρροή μιας αναφοράς.

Βλ. επίσης *borrowed reference*.

#### κωδικοποίηση κειμένου

Μια συμβολοσειρά στην Python είναι μια ακολουθία σημείων κώδικα Unicode (στο εύρος U+0000–U+10FFFF). Για να αποθηκεύσετε ή να μεταφέρετε μια συμβολοσειρά, πρέπει να σειριοποιηθεί ως δυαδική ακολουθία.

Η σειριοποίηση μιας συμβολοσειράς σε μια δυαδική ακολουθία είναι γνωστή ως «κωδικοποίηση», και η αναδημιουργία της συμβολοσειράς από την δυαδική ακολουθία είναι γνωστή ως «αποκωδικοποίηση».

Υπάρχει μια ποικιλία διαφορετικής σειριοποίησης κειμένου codecs, οι οποίοι συλλογικά αναφέρονται ως «κωδικοποιήσεις κειμένου».

#### αρχείο κειμένου

Ένα *file object* ικανό να διαβάζει και να γράφει αντικείμενα `str`. Συχνά, ένα αρχείο κειμένου αποκτά πραγματικά πρόσβαση σε μια ροή δυαδική ροή δεδομένων και χειρίζεται αυτόματα την *text encoding*. Παραδείγματα αρχείων κειμένου είναι αρχεία που ανοίγουν σε λειτουργία κειμένου ('r' ή 'w'), `sys.stdin`, `sys.stdout`, και στιγμιότυπα του `io.StringIO`.

Βλ. επίσης *binary file* για ένα αντικείμενο αρχείου με δυνατότητα ανάγνωσης και εγγραφής *δυαδικά αντικείμενα*.

#### συμβολοσειρά τριπλών εισαγωγικών

Μια συμβολοσειρά που δεσμεύεται από τρεις περιπτώσεις είτε ενός εισαγωγικού (») ή μιας αποστρόφου ("). Αν και δεν παρέχουν καμία λειτουργικότητα που δεν είναι διαθέσιμη με συμβολοσειρές με μονά εισαγωγικά, είναι χρήσιμες για διαφόρους λόγους. Σας επιτρέπουν να συμπεριλάβετε μονά και διπλά εισαγωγικά χωρίς διαφυγή σε μια συμβολοσειρά και μπορούν να εκτείνονται σε πολλές γραμμές χωρίς τη χρήση του χαρακτήρα συνέχεια, καθιστώντας τα ιδιαίτερα χρήσιμα κατά τη σύνταξη εγγράφων με συμβολοσειρές.

#### τύπος

The type of a Python object determines what kind of object it is; every object has a type. An object's type is accessible as its `__class__` attribute or can be retrieved with `type(obj)`.

#### type alias

Ένα συνώνυμο για έναν τύπο, που δημιουργείται με την ανάθεση τύπου σε ένα αναγνωριστικό.

Τα type aliases είναι χρήσιμα για την απλοποίηση *type alias*. Για παράδειγμα:

```
def remove_gray_shades(
    colors: list[tuple[int, int, int]]) -> list[tuple[int, int, int]]:
    pass
```

μπορεί να γίνει πιο ευανάγνωστο όπως:

```
Color = tuple[int, int, int]

def remove_gray_shades(colors: list[Color]) -> list[Color]:
    pass
```

Βλ. `typing` και **PEP 484**, που περιγράφει αυτήν την λειτουργικότητα.

### type hint

Ένας *annotation* που καθορίζει τον αναμενόμενο τύπο για μια μεταβλητή, ένα χαρακτηριστικό κλάσης ή μια παράμετρο συνάρτησης ή τιμή επιστροφής.

Οι υποδείξεις τύπων (type hints) είναι προαιρετικές και δεν επιβάλλονται από την Python, αλλά είναι χρήσιμες για *static type checkers*. Μπορούν επίσης να βοηθήσουν τους IDEs με τη συμπλήρωση και την αναδιαμόρφωση κώδικα.

Υποδείξεις τύπου (type hints) για καθολικές μεταβλητές, χαρακτηριστικά κλάσης και συναρτήσεις, αλλά όχι τοπικές μεταβλητές, μπορούν να προσπελαστούν χρησιμοποιώντας το `typing.get_type_hints()`.

Βλ. `typing` και **PEP 484**, που περιγράφει αυτήν την λειτουργικότητα.

### καθολικές νέες γραμμές

Ένα τρόπος ερμηνείας ροών κειμένου στον οποίο όλα τα ακόλουθα αναγνωρίζονται ως λήξεις μιας γραμμής: η σύμβαση τέλους γραμμής του Unix `'\n'`, η σύμβαση των Windows `'\r\n'`, και την παλιά σύμβαση Macintosh `'\r'`. Βλ. **PEP 278** και **PEP 3116**, καθώς και `bytes.splitlines()` για πρόσθετη χρήση.

### annotation μεταβλητής

Ένας *annotation* μια μεταβλητής ή ενός χαρακτηριστικού κλάσης.

Όταν annotating μια μεταβλητή ή ένα χαρακτηριστικό κλάσης, η ανάθεση είναι προαιρετική:

```
class C:
    field: 'annotation'
```

Τα annotations μεταβλητών χρησιμοποιούνται συνήθως για *type hints*: για παράδειγμα αυτή η μεταβλητή αναμένεται να λάβει τιμές `int`:

```
count: int = 0
```

Η σύνταξη annotation μεταβλητής περιγράφεται στην ενότητα `annassign`.

Βλ. *function annotation*, **PEP 484** και **PEP 526**, που περιγράφουν αυτή τη λειτουργία. Δείτε επίσης `annotations-howto` για βέλτιστες πρακτικές σχετικά με την εργασία με σχολιασμούς.

### virtual environment

Ένα συνεργατικά απομονωμένο περιβάλλον χρόνου εκτέλεσης που επιτρέπει στους χρήστες και τις εφαρμογές της Python να εγκαταστήσουν και να αναβαθμίσουν πακέτα διανομής Python χωρίς να παρεμβαίνουν στη συμπεριφορά άλλων εφαρμογών Python που εκτελούνται στο ίδιο σύστημα.

Βλ. επίσης `venv`.

### virtual machine

Ένας υπολογιστής ορίζεται εξ ολοκλήρου από το λογισμικό. Η εικονική μηχανή της Python εκτελεί το *bytecode* που εκπέμπεται από τον μεταγλωττιστή `bytecode`.

### Zen της Python

Κατάλογος σχεδιαστικών αρχών και φιλοσοφιών που είναι χρήσιμες για την κατανόηση και τη χρήση

της γλώσσας. Ο κατάλογος μπορεί να βρεθεί πληκτρολογώντας `«import this»` στην διαδραστική κονσόλα.

## ΠΑΡΑΡΤΗΜΑ Β'

---

### About these documents

---

These documents are generated from [reStructuredText](#) sources by [Sphinx](#), a document processor specifically written for the Python documentation.

Η ανάπτυξη των εγγράφων και των εργαλείων τους είναι εξ' ολοκλήρου εθελοντική προσπάθεια, όπως και η ίδια η Python. Εάν θέλετε να συνεισφέρετε, ρίξτε μια ματιά στη σελίδα [reporting-bugs](#) για πληροφορίες σχετικές με το πως να το κάνετε. Καινούριοι εθελοντές είναι πάντα ευπρόσδεκτοι!

Πολλές ευχαριστίες πηγαίνουν στους:

- Fred L. Drake, Jr., the creator of the original Python documentation toolset and writer of much of the content;
- το [Docutils](#) πρότζεκτ για την δημιουργία των εφαρμογών reStructuredText και Docutils·
- Fredrik Lundh για το δικό του Alternative Python Reference πρότζεκτ από το οποίο το Sphinx πήρε πολύ καλές ιδέες.

### B'.1 Contributors to the Python Documentation

Πολλοί άνθρωποι έχουν συνεισφέρει στη γλώσσα Python, την βιβλιοθήκη της Python, και τα έγγραφα της Python. Δείτε [Misc/ACKS](#) στις πηγές διανομής της Python για μια λίστα των συντελεστών.

Μόνο με τη συμβολή και τις συνεισφορές της κοινότητας της Python, η Python έχει τέτοια υπέροχα έγγραφα – Σας ευχαριστούμε!



## Γ'.1 Η ιστορία του λογισμικού

Python was created in the early 1990s by Guido van Rossum at Stichting Mathematisch Centrum (CWI, see <https://www.cwi.nl/>) in the Netherlands as a successor of a language called ABC. Guido remains Python's principal author, although it includes many contributions from others.

In 1995, Guido continued his work on Python at the Corporation for National Research Initiatives (CNRI, see <https://www.cnri.reston.va.us/>) in Reston, Virginia where he released several versions of the software.

In May 2000, Guido and the Python core development team moved to BeOpen.com to form the BeOpen PythonLabs team. In October of the same year, the PythonLabs team moved to Digital Creations (now Zope Corporation; see <https://www.zope.org/>). In 2001, the Python Software Foundation (PSF, see <https://www.python.org/psf/>) was formed, a non-profit organization created specifically to own Python-related Intellectual Property. Zope Corporation is a sponsoring member of the PSF.

All Python releases are Open Source (see <https://opensource.org/> for the Open Source Definition). Historically, most, but not all, Python releases have also been GPL-compatible; the table below summarizes the various releases.

Έκδοση	Προερχόμενη από	Έτος	Ιδιοκτησία	GPL compatible?
0.9.0 έως 1.2	δ/υ	1991-1995	CWI	ναι
1.3 έως 1.5.2	1.2	1995-1999	CNRI	ναι
1.6	1.5.2	2000	CNRI	όχι
2.0	1.6	2000	BeOpen.com	όχι
1.6.1	1.6	2001	CNRI	όχι
2.1	2.0+1.6.1	2001	PSF	όχι
2.0.1	2.0+1.6.1	2001	PSF	ναι
2.1.1	2.1+2.0.1	2001	PSF	ναι
2.1.2	2.1.1	2002	PSF	ναι
2.1.3	2.1.2	2002	PSF	ναι
2.2 και πάνω	2.1.1	2001-σήμερα	PSF	ναι

**Σημείωση:** GPL-compatible doesn't mean that we're distributing Python under the GPL. All Python licenses, unlike the GPL, let you distribute a modified version without making your changes open source. The GPL-compatible licenses make it possible to combine Python with other software that is released under the GPL; the others don't.

Χάρη, στους πολλούς εξωτερικούς εθελοντές που εργάστηκαν κάτω από τις οδηγίες του Guido, αυτές οι εκδόσεις έγιναν εφικτές.

## Γ'.2 Όροι και προϋποθέσεις για την πρόσβαση ή την χρήση της Python με άλλους τρόπους

Python software and documentation are licensed under the *PSF License Agreement*.

Starting with Python 3.8.6, examples, recipes, and other code in the documentation are dual licensed under the PSF License Agreement and the *Zero-Clause BSD license*.

Κάποιο λογισμικό που είναι ενσωματωμένο στην Python είναι υπό διαφορετικές άδειες χρήσης. Οι άδειες παρατίθενται με κώδικα που εμπίπτει σε αυτήν την άδεια. Δείτε *Άδειες και Ευχαριστίες για Ενσωματωμένο Λογισμικό* για μια ελλιπή λίστα αυτών των αδειών.

### Γ'.2.1 PSF LICENSE AGREEMENT FOR PYTHON 3.11.14

1. This LICENSE AGREEMENT is between the Python Software Foundation,  
→ ("PSF"), and  
the Individual or Organization ("Licensee") accessing and otherwise  
→ using Python  
3.11.14 software in source or binary form and its associated  
→ documentation.
2. Subject to the terms and conditions of this License Agreement, PSF  
→ hereby  
grants Licensee a nonexclusive, royalty-free, world-wide license to  
→ reproduce,  
analyze, test, perform and/or display publicly, prepare derivative  
→ works,  
distribute, and otherwise use Python 3.11.14 alone or in any derivative  
version, provided, however, that PSF's License Agreement and PSF's  
→ notice of  
copyright, i.e., "Copyright © 2001-2023 Python Software Foundation; All  
→ Rights  
Reserved" are retained in Python 3.11.14 alone or in any derivative  
→ version  
prepared by Licensee.
3. In the event Licensee prepares a derivative work that is based on or  
incorporates Python 3.11.14 or any part thereof, and wants to make the  
derivative work available to others as provided herein, then Licensee  
→ hereby  
agrees to include in any such work a brief summary of the changes made  
→ to Python  
3.11.14.
4. PSF is making Python 3.11.14 available to Licensee on an "AS IS" basis.  
PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY  
→ OF  
EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY  
→ REPRESENTATION OR  
WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR  
→ THAT THE  
USE OF PYTHON 3.11.14 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.



5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.11.14 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 3.11.14, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
7. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between PSF and Licensee. This License Agreement does not grant permission to use PSF trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
8. By copying, installing or otherwise using Python 3.11.14, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## Γ'.2.2 ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ BEOPEN.COM ΓΙΑ PYTHON 2.0

### ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ ΑΝΟΙΧΤΟΥ ΚΩΔΙΚΑ BEOPEN PYTHON ΕΚΔΟΣΗ 1

1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
3. BeOpen is making the Software available to Licensee on an "AS IS" basis. BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
5. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at <http://www.pythonlabs.com/logos.html> may be used according to the permissions granted on that web page.

7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

### Γ'.2.3 ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ CNRI ΓΙΑ PYTHON 1.6.1

1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the internet using the following URL: <http://hdl.handle.net/1895.22/1013>."
3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.

8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## Γ'.2.4 ΣΥΜΦΩΝΙΑ ΑΔΕΙΑΣ CWI ΓΙΑ PYTHON 0.9.0 ΕΩΣ 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## Γ'.2.5 ZERO-CLAUSE BSD LICENSE FOR CODE IN THE PYTHON 3.11.14 DOCUMENTATION

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## Γ'.3 Άδειες και Ευχαριστίες για Ενσωματωμένο Λογισμικό

Αυτή η ενότητα είναι μια ημιτελής, αλλά αυξανόμενη λίστα αδειών και ευχαριστιών για λογισμικό τρίτων, που ενσωματώνεται στην διανομή της Python.

### Γ'.3.1 Mersenne Twister

The `_random` module includes code based on a download from <http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/MT2002/emt19937ar.html>. The following are the verbatim comments from the original code:

```
A C-program for MT19937, with initialization improved 2002/1/26.
Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init_genrand(seed)
or init_by_array(init_key, key_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura,
All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.

3. The names of its contributors may not be used to endorse or promote
   products derived from this software without specific prior written
   permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome.
http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html
email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)
```

### Γ'.3.2 Sockets

Η ενότητα `socket` χρησιμοποιεί τις συναρτήσεις `getaddrinfo()`, και `getnameinfo()`, τα οποία έχουν υλοποιηθεί σε διαφορετικά αρχεία από το WIDE Έργο, <https://www.wide.ad.jp/>.

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project.  
All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

### Γ'.3.3 Ασύγχρονες socket υπηρεσίες

The `asynchat` and `asyncore` modules contain the following notice:

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

### Γ'.3.4 Διαχείριση Cookie

Η ενότητα `http.cookies` περιέχει την παρακάτω ειδοποίηση:

```
Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>

    All Rights Reserved

Permission to use, copy, modify, and distribute this software
and its documentation for any purpose and without fee is hereby
granted, provided that the above copyright notice appear in all
copies and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of
Timothy O'Malley not be used in advertising or publicity
pertaining to distribution of the software without specific, written
prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS
SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR
ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,
WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR
PERFORMANCE OF THIS SOFTWARE.
```

### Γ'.3.5 Ανίχνευση εκτέλεσης

Η ενότητα `trace` περιέχει την παρακάτω ειδοποίηση:

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...
err... reserved and offered to the public under the terms of the
Python 2.2 license.
Author: Zooko O'Whielacronx
http://zooko.com/
mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.
Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and
its associated documentation for any purpose without fee is hereby
granted, provided that the above copyright notice appears in all copies,
and that both that copyright notice and this permission notice appear in
supporting documentation, and that the name of neither Automatrix,
Bioreason or Mojam Media be used in advertising or publicity pertaining to
distribution of the software without specific, written prior permission.
```

### Γ'.3.6 Συναρτήσεις UUencode και UUdecode

Η ενότητα uu περιέχει την παρακάτω ειδοποίηση:

```
Copyright 1994 by Lance Ellinghouse
Cathedral City, California Republic, United States of America.
    All Rights Reserved
Permission to use, copy, modify, and distribute this software and its
documentation for any purpose and without fee is hereby granted,
provided that the above copyright notice appear in all copies and that
both that copyright notice and this permission notice appear in
supporting documentation, and that the name of Lance Ellinghouse
not be used in advertising or publicity pertaining to distribution
of the software without specific, written prior permission.
LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO
THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND
FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE
FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN
ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT
OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:
- Use binascii module to do the actual line-by-line conversion
  between ascii and binary. This results in a 1000-fold speedup. The C
  version is still 5 times faster, though.
- Arguments more compliant with Python standard
```

### Γ'.3.7 Κλήσεις Απομακρυσμένης Διαδικασίας XML

Η ενότητα xmlrpc.client περιέχει την παρακάτω ειδοποίηση:

```
The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB
Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its
associated documentation, you agree that you have read, understood,
and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and
its associated documentation for any purpose and without fee is
hereby granted, provided that the above copyright notice appears in
all copies, and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of
Secret Labs AB or the author not be used in advertising or publicity
pertaining to distribution of the software without specific, written
prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD
TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-
ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR
BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY
DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,
WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE
OF THIS SOFTWARE.
```

### Γ'.3.8 test\_epoll

Η ενότητα `test.test_epoll` περιέχει την παρακάτω ειδοποίηση:

```
Copyright (c) 2001-2006 Twisted Matrix Laboratories.
```

```
Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:
```

```
The above copyright notice and this permission notice shall be
included in all copies or substantial portions of the Software.
```

```
THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE
LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION
OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION
WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

### Γ'.3.9 Επιλογή kqueue

Η ενότητα `select` περιέχει την παρακάτω ειδοποίηση για την `kqueue` διεπαφή:

```
Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes
All rights reserved.
```

```
Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
```

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

```
THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS ``AS IS'' AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```



### Γ'.3.10 SipHash24

Το αρχείο `Python/pyhash.c` περιέχει την υλοποίηση του Marek Majkowski του αλγορίθμου του Dan Bernstein, SipHash24. Αυτό περιέχει την παρακάτω σημείωση:

```
<MIT License>
Copyright (c) 2013  Marek Majkowski <marek@popcount.org>

Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
</MIT License>

Original location:
  https://github.com/majek/csiphash/

Solution inspired by code from:
  Samuel Neves (supercop/crypto_auth/siphash24/little)
  djb (supercop/crypto_auth/siphash24/little2)
  Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)
```

### Γ'.3.11 strtod και dtoa

Το αρχείο `Python/dtoa.c`, που παρέχει τις συναρτήσεις `dtoa` και `strtod` της C για μετατροπή των C doubles προς και από strings, προέρχεται από το ομώνυμο αρχείο του David M. Gay, προς το παρόν διαθέσιμο από <https://web.archive.org/web/20220517033456/http://www.netlib.org/fp/dtoa.c>. Το αρχικό αρχείο, όπως ανακτήθηκε στις 16 Μαρτίου, 2009, περιέχει τα ακόλουθα πνευματικά δικαιώματα και την ειδοποίηση αδειοδότησης:

```
/*****
 *
 * The author of this software is David M. Gay.
 *
 * Copyright (c) 1991, 2000, 2001 by Lucent Technologies.
 *
 * Permission to use, copy, modify, and distribute this software for any
 * purpose without fee is hereby granted, provided that this entire notice
 * is included in all copies of any software which is or includes a copy
 * or modification of this software and in all copies of the supporting
 * documentation for such software.
 *
 * THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
 * WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY
 * REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY
 * OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.
 *****/
```

## Γ'.3.12 OpenSSL

Οι μονάδες `hashlib`, `posix`, `ssl`, `crypt` χρησιμοποιούν την βιβλιοθήκη OpenSSL για επιπλέον απόδοση, εάν διατίθενται από το λειτουργικό σύστημα. Επιπλέον, τα προγράμματα εγκατάστασης για την Python για Windows και macOS, ενδέχεται να περιλαμβάνουν ένα αντίγραφο των βιβλιοθηκών OpenSSL, επομένως συμπεριλαμβάνουμε ένα αντίγραφο της άδειας OpenSSL εδώ. Για την έκδοση OpenSSL 3.0 και για νεότερες εκδόσεις που προέρχονται από αυτή, ισχύει η άδεια Apache v2:

Apache License  
Version 2.0, January 2004  
<https://www.apache.org/licenses/>

### TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

#### 1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.
3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.
4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:
  - (a) You must give any other recipients of the Work or Derivative Works a copy of this License; and
  - (b) You must cause any modified files to carry prominent notices stating that You changed the files; and
  - (c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
  - (d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.
6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.
7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.
8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.
9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

### Γ'.3.13 expat

Η επέκταση pyexpat δημιουργείται χρησιμοποιώντας ένα συμπεριλαμβανόμενο αντίγραφο των πηγών expat, εκτός εάν η έκδοση έχει την ρύθμιση `--with-system-expat`:

```
Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd
and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:

The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT.
IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY
CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT,
TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE
SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

### Γ'.3.14 libffi

Η επέκταση `_ctypes` είναι κατασκευασμένη χρησιμοποιώντας ένα συμπεριλαμβανόμενο αντίγραφο των πηγών libffi, εκτός εάν η έκδοση έχει την ρύθμιση `--with-system-libffi`:

```
Copyright (c) 1996-2008 Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
``Software''), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:

The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT
HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY,
WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER
DEALINGS IN THE SOFTWARE.
```

### Γ'.3.15 zlib

Η επέκταση zlib δημιουργείται χρησιμοποιώντας ένα συμπεριλαμβανόμενου αντίγραφο των πηγών zlib, εάν η έκδοση του zlib που βρίσκεται στο σύστημα είναι πολύ παλιά για να χρησιμοποιηθεί για την κατασκευή:

```
Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler
```

```
This software is provided 'as-is', without any express or implied
warranty. In no event will the authors be held liable for any damages
arising from the use of this software.
```

```
Permission is granted to anyone to use this software for any purpose,
including commercial applications, and to alter it and redistribute it
freely, subject to the following restrictions:
```

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

```
Jean-loup Gailly
jloup@gzip.org
```

```
Mark Adler
madler@alumni.caltech.edu
```

### Γ'.3.16 cfuhash

Η υλοποίηση του πίνακα κατακερματισμού που χρησιμοποιείται από το `tracemalloc` βασίζεται στο έργο `cfuhash`:

```
Copyright (c) 2005 Don Owens
All rights reserved.
```

```
This code is released under the BSD license:
```

```
Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
```

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

```
THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
```

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```
(INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR
SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
OF THE POSSIBILITY OF SUCH DAMAGE.
```

### Γ'.3.17 libmpdec

The `_decimal` module is built using an included copy of the libmpdec library unless the build is configured `--with-system-libmpdec`:

```
Copyright (c) 2008-2020 Stefan Krah. All rights reserved.
```

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

```
THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

### Γ'.3.18 W3C C14N σουίτα δοκιμής

H σουίτα δοκιμής C14N 2.0 στο πακέτο `test` (`Lib/test/xmltestdata/c14n-20/`) ανακτήθηκε από τον ιστότοπο του W3C <https://www.w3.org/TR/xml-c14n2-testcases/> και διανέμεται με την άδεια 3 ρήτρων BSD:

```
Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang),
All Rights Reserved.
```

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of works must retain the original copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the original copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the W3C nor the names of its contributors may be used to endorse or promote products derived from this work without

(συνέχεια στην επόμενη σελίδα)

(συνεχίζεται από την προηγούμενη σελίδα)

```
specific prior written permission.
```

```
THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

### Γ'.3.19 Audioop

Το module `audioop` χρησιμοποιεί ως βάση κώδικα του αρχείου `g771.c` του έργου Sox. <https://sourceforge.net/projects/sox/files/sox/12.17.7/sox-12.17.7.tar.gz>

Αυτό ο πηγαίος κώδικας είναι προϊόν της Sun Microsystems, Inc. και παρέχεται για απεριόριστη χρήση. Οι χρήστες μπορούν να αντιγράψουν ή να τροποποιήσουν αυτόν τον πηγαίο κώδικα χωρίς χρέωση.

Ο ΠΗΓΑΙΟΣ ΚΩΔΙΚΑΣ ΤΟΥ SUN ΠΑΡΕΧΕΤΑΙ ΟΠΩΣ ΕΧΕΙ ΧΩΡΙΣ ΚΑΝΕΝΟΣ ΕΙΔΟΥΣ ΕΓΓΥΗΣΕΙΣ ΣΥΜΠΕΡΙΛΑΜΒΑΝΟΜΕΝΩΝ ΕΓΓΥΗΣΕΩΝ ΣΧΕΔΙΑΣΜΟΥ, ΕΜΠΟΡΕΥΣΙΜΟΤΗΤΑΣ ΚΑΙ ΚΑΤΑΛΛΗΛΟΤΗΤΑΣ ΓΙΑ ΣΥΓΚΕΚΡΙΜΕΝΟ ΣΚΟΠΟ Ή ΠΟΥ ΠΡΟΚΥΠΤΕΙ ΑΠΟ ΚΑΠΟΙΑ ΠΟΡΕΙΑ ΣΥΝΑΛΛΑΓΗΣ, ΧΡΗΣΗΣ Ή ΕΜΠΟΡΙΚΗΣ ΠΡΑΚΤΙΚΗΣ.

Ο πηγαίος κώδικας του Sun παρέχεται χωρίς την υποστήριξη και χωρίς καμία υποχρέωση εκ μέρους της Sun Microsystems, Inc. να βοηθήσει στην χρήση, στη διόρθωση, τροποποίηση ή βελτίωση του.

SUN MICROSYSTEMS, INC. SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS, TRADE SECRETS OR ANY PATENTS BY THIS SOFTWARE OR ANY PART THEREOF.

Σε καμία περίπτωση η Sun Microsystems, Inc. δεν φέρει ευθύνη για τυχόν απώλεια εσόδων ή κερδών ή άλλες ειδικές, έμμεσες και επακόλουθες ζημιές, ακόμη και αν η Sun έχει ενημερωθεί για την πιθανότητα τέτοιων ζημιών.

Sun Microsystems, Inc. 2550 Garcia Avenue Mountain View, Καλιφόρνια 94043

### Γ'.3.20 asyncio

Μέρη της ενότητας `asyncio` ενσωματώνονται από το `uvloop 0.16`, η οποία διανέμεται με άδεια MIT:

```
Copyright (c) 2015-2021 MagicStack Inc. http://magic.io
```

```
Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:
```

```
The above copyright notice and this permission notice shall be
included in all copies or substantial portions of the Software.
```

(συνέχεια στην επόμενη σελίδα)



(συνεχίζεται από την προηγούμενη σελίδα)

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.



---

### Copyright

---

Η Python και αυτή η τεκμηρίωση είναι:

Copyright © 2001-2023 Python Software Foundation. Όλα τα δικαιώματα διατηρούνται.

Copyright © 2000 BeOpen.com. Όλα τα δικαιώματα διατηρούνται.

Copyright © 1995-2000 Corporation for National Research Initiatives. Όλα τα δικαιώματα διατηρούνται.

Copyright © 1991-1995 Stichting Mathematisch Centrum. Όλα τα δικαιώματα διατηρούνται.

---

Ανατρέξτε στο [Ιστορία και Άδεια](#) για πλήρης πληροφόρηση σχετικά με την άδεια χρήσης και τις εξουσιοδοτήσεις.



## μη-αλφαβητικά

- ..., [281](#)
- 2to3, [281](#)
- >>>, [281](#)
- BDFL, [283](#)
- CO\_FUTURE\_DIVISION (*C var*), [45](#)
- CPython, [284](#)
- Capsule
  - object, [169](#)
- C-contiguous, [106, 284](#)
- EAFP, [286](#)
- EOFError (*built-in exception*), [156](#)
- Fortran contiguous, [106, 284](#)
- GIL, [288](#)
- IDLE, [288](#)
- KeyboardInterrupt (*built-in exception*), [56](#)
- LBYL, [290](#)
- LONG\_MAX (*C macro*), [116](#)
- METH\_CLASS (*C macro*), [238](#)
- METH\_COEXIST (*C macro*), [238](#)
- METH\_FASTCALL (*C macro*), [237](#)
- METH\_KEYWORDS (*C macro*), [237](#)
- METH\_METHOD (*C macro*), [238](#)
- METH\_NOARGS (*C macro*), [238](#)
- METH\_O (*C macro*), [238](#)
- METH\_STATIC (*C macro*), [238](#)
- METH\_VARARGS (*C macro*), [237](#)
- MRO, [291](#)
- MethodType (*in module types*), [152, 153](#)
- ModuleType (*in module types*), [157](#)
- None
  - object, [115](#)
- OverflowError (*built-in exception*), [116, 118](#)
- PATH, [12](#)
- PEP, [294](#)
- PYMEM\_DOMAIN\_MEM (*C macro*), [228](#)
- PYMEM\_DOMAIN\_OBJ (*C macro*), [228](#)
- PYMEM\_DOMAIN\_RAW (*C macro*), [228](#)
- PYTHONCOERCECLOCALE, [219](#)
- PYTHONDEBUG, [180, 213](#)
- PYTHONDEVMODE, [210](#)
- PYTHONDONTWRITEBYTECODE, [180, 216](#)
- PYTHONDUMPREFS, [210, 248](#)
- PYTHONEXECUTABLE, [214](#)
- PYTHONFAULTHANDLER, [210](#)
- PYTHONHASHSEED, [180, 211](#)
- PYTHONHOME, [12, 181, 186, 211](#)
- PYTHONINSPECT, [181, 211](#)
- PYTHONIOENCODING, [183, 215](#)
- PYTHONLEGACYWINDOWSFSENCODING, [181, 205](#)
- PYTHONLEGACYWINDOWSTDIO, [181, 212](#)
- PYTHONMALLOC, [224, 227, 229, 231](#)
- PYTHONMALLOCSTATS, [212, 224](#)
- PYTHONNODEBUGRANGES, [209](#)
- PYTHONNOUSERSITE, [181, 216](#)
- PYTHONOPTIMIZE, [181, 213](#)
- PYTHONPATH, [12, 181, 212](#)
- PYTHONPLATLIBDIR, [212](#)
- PYTHONPROFILEIMPORTTIME, [211](#)
- PYTHONPYCACHEPREFIX, [214](#)
- PYTHONSAFEPATH, [208](#)
- PYTHONTRACEMALLOC, [215](#)
- PYTHONUNBUFFERED, [181, 209](#)
- PYTHONUTF8, [205, 219](#)
- PYTHONVERBOSE, [182, 216](#)
- PYTHONWARNINGS, [216](#)
- PY\_MAJOR\_VERSION (*C macro*), [279](#)
- PY\_MICRO\_VERSION (*C macro*), [279](#)
- PY\_MINOR\_VERSION (*C macro*), [279](#)
- PY\_RELEASE\_LEVEL (*C macro*), [279](#)
- PY\_RELEASE\_SERIAL (*C macro*), [279](#)
- PY\_SSIZE\_T\_MAX (*C macro*), [117](#)
- PY\_VECTORCALL\_ARGUMENTS\_OFFSET (*C macro*), [92](#)
- PY\_VERSION\_HEX (*C macro*), [279](#)
- PyAIter\_Check (*C function*), [102](#)
- PyASCIIObject (*C type*), [126](#)
- PyAnySet\_Check (*C function*), [150](#)
- PyAnySet\_CheckExact (*C function*), [150](#)
- PyArg\_Parse (*C function*), [78](#)
- PyArg\_ParseTuple (*C function*), [78](#)
- PyArg\_ParseTupleAndKeywords (*C function*), [78](#)
- PyArg\_UnpackTuple (*C function*), [78](#)
- PyArg\_VaParse (*C function*), [78](#)
- PyArg\_VaParseTupleAndKeywords (*C function*), [78](#)

- PyArg\_ValidateKeywordArguments (C function), 78
- PyAsyncMethods (C type), 271
- PyAsyncMethods.am\_aiter (C member), 271
- PyAsyncMethods.am\_anext (C member), 271
- PyAsyncMethods.am\_await (C member), 271
- PyAsyncMethods.am\_send (C member), 271
- PyBUF\_ANY\_CONTIGUOUS (C macro), 107
- PyBUF\_CONTIG (C macro), 107
- PyBUF\_CONTIG\_RO (C macro), 107
- PyBUF\_C\_CONTIGUOUS (C macro), 107
- PyBUF\_FORMAT (C macro), 106
- PyBUF\_FULL (C macro), 107
- PyBUF\_FULL\_RO (C macro), 107
- PyBUF\_F\_CONTIGUOUS (C macro), 107
- PyBUF\_INDIRECT (C macro), 106
- PyBUF\_MAX\_NDIM (C macro), 105
- PyBUF\_ND (C macro), 106
- PyBUF\_READ (C macro), 167
- PyBUF\_RECORDS (C macro), 107
- PyBUF\_RECORDS\_RO (C macro), 107
- PyBUF\_SIMPLE (C macro), 106
- PyBUF\_STRIDED (C macro), 107
- PyBUF\_STRIDED\_RO (C macro), 107
- PyBUF\_STRIDES (C macro), 106
- PyBUF\_WRITABLE (C macro), 106
- PyBUF\_WRITE (C macro), 167
- PyBool\_Check (C function), 118
- PyBool\_FromLong (C function), 119
- PyBool\_Type (C var), 118
- PyBufferProcs (C type), 103, 270
- PyBufferProcs.bf\_getbuffer (C member), 270
- PyBufferProcs.bf\_releasebuffer (C member), 270
- PyBuffer\_FillContiguousStrides (C function), 110
- PyBuffer\_FillInfo (C function), 110
- PyBuffer\_FromContiguous (C function), 109
- PyBuffer\_GetPointer (C function), 109
- PyBuffer\_IsContiguous (C function), 109
- PyBuffer\_Release (C function), 109
- PyBuffer\_SizeFromFormat (C function), 109
- PyBuffer\_ToContiguous (C function), 109
- PyByteArrayObject (C type), 124
- PyByteArray\_AS\_STRING (C function), 125
- PyByteArray\_AsString (C function), 125
- PyByteArray\_Check (C function), 125
- PyByteArray\_CheckExact (C function), 125
- PyByteArray\_Concat (C function), 125
- PyByteArray\_FromObject (C function), 125
- PyByteArray\_FromStringAndSize (C function), 125
- PyByteArray\_GET\_SIZE (C function), 125
- PyByteArray\_Resize (C function), 125
- PyByteArray\_Size (C function), 125
- PyByteArray\_Type (C var), 124
- PyBytesObject (C type), 122
- PyBytes\_AS\_STRING (C function), 124
- PyBytes\_AsString (C function), 123
- PyBytes\_AsStringAndSize (C function), 124
- PyBytes\_Check (C function), 122
- PyBytes\_CheckExact (C function), 123
- PyBytes\_Concat (C function), 124
- PyBytes\_ConcatAndDel (C function), 124
- PyBytes\_FromFormat (C function), 123
- PyBytes\_FromFormatV (C function), 123
- PyBytes\_FromObject (C function), 123
- PyBytes\_FromString (C function), 123
- PyBytes\_FromStringAndSize (C function), 123
- PyBytes\_GET\_SIZE (C function), 123
- PyBytes\_Size (C function), 123
- PyBytes\_Type (C var), 122
- PyCFunction (C type), 236
- PyCFunctionWithKeywords (C type), 236
- PyCFunction\_New (C function), 239
- PyCFunction\_NewEx (C function), 239
- PyCMethod (C type), 236
- PyCMethod\_New (C function), 238
- PyCallIter\_Check (C function), 165
- PyCallIter\_New (C function), 165
- PyCallIter\_Type (C var), 165
- PyCallable\_Check (C function), 96
- PyCapsule (C type), 169
- PyCapsule\_CheckExact (C function), 169
- PyCapsule\_Destructor (C type), 169
- PyCapsule\_GetContext (C function), 169
- PyCapsule\_GetDestructor (C function), 169
- PyCapsule\_GetName (C function), 169
- PyCapsule\_GetPointer (C function), 169
- PyCapsule\_Import (C function), 169
- PyCapsule\_IsValid (C function), 170
- PyCapsule\_New (C function), 169
- PyCapsule\_SetContext (C function), 170
- PyCapsule\_SetDestructor (C function), 170
- PyCapsule\_SetName (C function), 170
- PyCapsule\_SetPointer (C function), 170
- PyCellObject (C type), 154
- PyCell\_Check (C function), 154
- PyCell\_GET (C function), 154
- PyCell\_Get (C function), 154
- PyCell\_New (C function), 154
- PyCell\_SET (C function), 154
- PyCell\_Set (C function), 154
- PyCell\_Type (C var), 154
- PyCodeObject (C type), 154
- PyCode\_Addr2Line (C function), 155
- PyCode\_Addr2Location (C function), 155
- PyCode\_Check (C function), 154
- PyCode\_GetCellvars (C function), 155
- PyCode\_GetCode (C function), 155
- PyCode\_GetFreevars (C function), 156
- PyCode\_GetNumFree (C function), 154
- PyCode\_GetVarnames (C function), 155
- PyCode\_New (C function), 155
- PyCode\_NewEmpty (C function), 155

- PyCode\_NewWithPosOnlyArgs (*C function*), 155
- PyCode\_Type (*C var*), 154
- PyCodec\_BackslashReplaceErrors (*C function*), 85
- PyCodec\_Decode (*C function*), 84
- PyCodec\_Decoder (*C function*), 84
- PyCodec\_Encode (*C function*), 84
- PyCodec\_Encoder (*C function*), 84
- PyCodec\_IgnoreErrors (*C function*), 85
- PyCodec\_IncrementalDecoder (*C function*), 85
- PyCodec\_IncrementalEncoder (*C function*), 85
- PyCodec\_KnownEncoding (*C function*), 84
- PyCodec\_LookupError (*C function*), 85
- PyCodec\_NameReplaceErrors (*C function*), 85
- PyCodec\_Register (*C function*), 84
- PyCodec\_RegisterError (*C function*), 85
- PyCodec\_ReplaceErrors (*C function*), 85
- PyCodec\_StreamReader (*C function*), 85
- PyCodec\_StreamWriter (*C function*), 85
- PyCodec\_StrictErrors (*C function*), 85
- PyCodec\_Unregister (*C function*), 84
- PyCodec\_XMLCharRefReplaceErrors (*C function*), 85
- PyCompactUnicodeObject (*C type*), 126
- PyCompilerFlags (*C struct*), 44
- PyCompilerFlags.cf\_feature\_version (*C member*), 45
- PyCompilerFlags.cf\_flags (*C member*), 44
- PyComplexObject (*C type*), 122
- PyComplex\_AsCComplex (*C function*), 122
- PyComplex\_Check (*C function*), 122
- PyComplex\_CheckExact (*C function*), 122
- PyComplex\_FromCComplex (*C function*), 122
- PyComplex\_FromDoubles (*C function*), 122
- PyComplex\_ImagAsDouble (*C function*), 122
- PyComplex\_RealAsDouble (*C function*), 122
- PyComplex\_Type (*C var*), 122
- PyConfig (*C type*), 207
- PyConfig\_Clear (*C function*), 207
- PyConfig\_InitIsolatedConfig (*C function*), 207
- PyConfig\_InitPythonConfig (*C function*), 207
- PyConfig\_Read (*C function*), 207
- PyConfig\_SetArgv (*C function*), 207
- PyConfig\_SetBytesArgv (*C function*), 207
- PyConfig\_SetBytesString (*C function*), 207
- PyConfig\_SetString (*C function*), 207
- PyConfig\_SetWideStringList (*C function*), 207
- PyConfig.argv (*C member*), 208
- PyConfig.base\_exec\_prefix (*C member*), 208
- PyConfig.base\_executable (*C member*), 208
- PyConfig.base\_prefix (*C member*), 208
- PyConfig.buffered\_stdio (*C member*), 209
- PyConfig.bytes\_warning (*C member*), 209
- PyConfig.check\_hash\_pycs\_mode (*C member*), 209
- PyConfig.code\_debug\_ranges (*C member*), 209
- PyConfig.configure\_c\_stdio (*C member*), 209
- PyConfig.dev\_mode (*C member*), 210
- PyConfig.dump\_refs (*C member*), 210
- PyConfig.exec\_prefix (*C member*), 210
- PyConfig.executable (*C member*), 210
- PyConfig.fault\_handler (*C member*), 210
- PyConfig.filesystem\_encoding (*C member*), 210
- PyConfig.filesystem\_errors (*C member*), 210
- PyConfig.hash\_seed (*C member*), 211
- PyConfig.home (*C member*), 211
- PyConfig.import\_time (*C member*), 211
- PyConfig.inspect (*C member*), 211
- PyConfig.install\_signal\_handlers (*C member*), 211
- PyConfig.interactive (*C member*), 211
- PyConfig.isolated (*C member*), 211
- PyConfig.legacy\_windows\_stdio (*C member*), 212
- PyConfig.malloc\_stats (*C member*), 212
- PyConfig.module\_search\_paths (*C member*), 212
- PyConfig.module\_search\_paths\_set (*C member*), 212
- PyConfig.optimization\_level (*C member*), 213
- PyConfig.orig\_argv (*C member*), 213
- PyConfig.parse\_argv (*C member*), 213
- PyConfig.parser\_debug (*C member*), 213
- PyConfig.pathconfig\_warnings (*C member*), 213
- PyConfig.platlibdir (*C member*), 212
- PyConfig.prefix (*C member*), 213
- PyConfig.program\_name (*C member*), 214
- PyConfig.pycache\_prefix (*C member*), 214
- PyConfig.pythonpath\_env (*C member*), 212
- PyConfig.quiet (*C member*), 214
- PyConfig.run\_command (*C member*), 214
- PyConfig.run\_filename (*C member*), 214
- PyConfig.run\_module (*C member*), 214
- PyConfig.safe\_path (*C member*), 208
- PyConfig.show\_ref\_count (*C member*), 214
- PyConfig.site\_import (*C member*), 215
- PyConfig.skip\_source\_first\_line (*C member*), 215
- PyConfig.stdio\_encoding (*C member*), 215
- PyConfig.stdio\_errors (*C member*), 215
- PyConfig.tracemalloc (*C member*), 215
- PyConfig.use\_environment (*C member*), 215
- PyConfig.use\_hash\_seed (*C member*), 211
- PyConfig.user\_site\_directory (*C member*), 216
- PyConfig.verbose (*C member*), 216

PyConfig.warn\_default\_encoding (C member), 209  
PyConfig.warnoptions (C member), 216  
PyConfig.write\_bytecode (C member), 216  
PyConfig.xoptions (C member), 216  
PyContext (C type), 173  
PyContextToken (C type), 173  
PyContextToken\_CheckExact (C function), 173  
PyContextToken\_Type (C var), 173  
PyContextVar (C type), 173  
PyContextVar\_CheckExact (C function), 173  
PyContextVar\_Get (C function), 173  
PyContextVar\_New (C function), 173  
PyContextVar\_Reset (C function), 174  
PyContextVar\_Set (C function), 174  
PyContextVar\_Type (C var), 173  
PyContext\_CheckExact (C function), 173  
PyContext\_Copy (C function), 173  
PyContext\_CopyCurrent (C function), 173  
PyContext\_Enter (C function), 173  
PyContext\_Exit (C function), 173  
PyContext\_New (C function), 173  
PyContext\_Type (C var), 173  
PyCoroutineObject (C type), 172  
PyCoroutine\_CheckExact (C function), 172  
PyCoroutine\_New (C function), 172  
PyCoroutine\_Type (C var), 172  
PyDateTime\_Check (C function), 175  
PyDateTime\_CheckExact (C function), 175  
PyDateTime\_DATE\_GET\_FOLD (C function), 176  
PyDateTime\_DATE\_GET\_HOUR (C function), 176  
PyDateTime\_DATE\_GET\_MICROSECOND (C function), 176  
PyDateTime\_DATE\_GET\_MINUTE (C function), 176  
PyDateTime\_DATE\_GET\_SECOND (C function), 176  
PyDateTime\_DATE\_GET\_TZINFO (C function), 176  
PyDateTime\_DELTA\_GET\_DAYS (C function), 177  
PyDateTime\_DELTA\_GET\_MICROSECONDS (C function), 177  
PyDateTime\_DELTA\_GET\_SECONDS (C function), 177  
PyDateTime\_Date (C type), 174  
PyDateTime\_DateTime (C type), 174  
PyDateTime\_DateTimeType (C var), 174  
PyDateTime\_DateType (C var), 174  
PyDateTime\_Delta (C type), 174  
PyDateTime\_DeltaType (C var), 174  
PyDateTime\_FromDateAndTime (C function), 175  
PyDateTime\_FromDateAndTimeAndFold (C function), 175  
PyDateTime\_FromTimestamp (C function), 177  
PyDateTime\_GET\_DAY (C function), 176  
PyDateTime\_GET\_MONTH (C function), 176  
PyDateTime\_GET\_YEAR (C function), 176  
PyDateTime\_TIME\_GET\_FOLD (C function), 177  
PyDateTime\_TIME\_GET\_HOUR (C function), 176  
PyDateTime\_TIME\_GET\_MICROSECOND (C function), 177  
PyDateTime\_TIME\_GET\_MINUTE (C function), 177  
PyDateTime\_TIME\_GET\_SECOND (C function), 177  
PyDateTime\_TIME\_GET\_TZINFO (C function), 177  
PyDateTime\_TZInfoType (C var), 174  
PyDateTime\_Time (C type), 174  
PyDateTime\_TimeType (C var), 174  
PyDateTime\_TimeZone\_UTC (C var), 174  
PyDate\_Check (C function), 175  
PyDate\_CheckExact (C function), 175  
PyDate\_FromDate (C function), 175  
PyDate\_FromTimestamp (C function), 177  
PyDelta\_Check (C function), 175  
PyDelta\_CheckExact (C function), 175  
PyDelta\_FromDSU (C function), 176  
PyDescr\_IsData (C function), 165  
PyDescr\_NewClassMethod (C function), 165  
PyDescr\_NewGetSet (C function), 165  
PyDescr\_NewMember (C function), 165  
PyDescr\_NewMethod (C function), 165  
PyDescr\_NewWrapper (C function), 165  
PyDictObject (C type), 147  
PyDictProxy\_New (C function), 147  
PyDict\_Check (C function), 147  
PyDict\_CheckExact (C function), 147  
PyDict\_Clear (C function), 147  
PyDict\_Contains (C function), 147  
PyDict\_Copy (C function), 147  
PyDict\_DelItem (C function), 148  
PyDict\_DelItemString (C function), 148  
PyDict\_GetItem (C function), 148  
PyDict\_GetItemString (C function), 148  
PyDict\_GetItemWithError (C function), 148  
PyDict\_Items (C function), 148  
PyDict\_Keys (C function), 148  
PyDict\_Merge (C function), 149  
PyDict\_MergeFromSeq2 (C function), 150  
PyDict\_New (C function), 147  
PyDict\_Next (C function), 149  
PyDict\_SetDefault (C function), 148  
PyDict\_SetItem (C function), 148  
PyDict\_SetItemString (C function), 148  
PyDict\_Size (C function), 149  
PyDict\_Type (C var), 147  
PyDict\_Update (C function), 149  
PyDict\_Values (C function), 149  
PyDoc\_STR (C macro), 6  
PyDoc\_STRVAR (C macro), 6  
PyErr\_BadArgument (C function), 50  
PyErr\_BadInternalCall (C function), 52  
PyErr\_CheckSignals (C function), 56  
PyErr\_Clear (C function), 10, 12, 49



- PyErr\_ExceptionMatches (*C function*), 12, 54  
 PyErr\_Fetch (*C function*), 54  
 PyErr\_Format (*C function*), 50  
 PyErr\_FormatV (*C function*), 50  
 PyErr\_GetExcInfo (*C function*), 55  
 PyErr\_GetHandledException (*C function*), 55  
 PyErr\_GivenExceptionMatches (*C function*), 54  
 PyErr\_NewException (*C function*), 57  
 PyErr\_NewExceptionWithDoc (*C function*), 57  
 PyErr\_NoMemory (*C function*), 50  
 PyErr\_NormalizeException (*C function*), 54  
 PyErr\_Occurred (*C function*), 10, 53  
 PyErr\_Print (*C function*), 50  
 PyErr\_PrintEx (*C function*), 49  
 PyErr\_ResourceWarning (*C function*), 53  
 PyErr\_Restore (*C function*), 54  
 PyErr\_SetExcFromWindowsErr (*C function*), 51  
 PyErr\_SetExcFromWindowsErrWithFilename (*C function*), 52  
 PyErr\_SetExcFromWindowsErrWithFilenameObject (*C function*), 51  
 PyErr\_SetExcFromWindowsErrWithFilenameObjects (*C function*), 52  
 PyErr\_SetExcInfo (*C function*), 55  
 PyErr\_SetFromErrno (*C function*), 50  
 PyErr\_SetFromErrnoWithFilename (*C function*), 51  
 PyErr\_SetFromErrnoWithFilenameObject (*C function*), 51  
 PyErr\_SetFromErrnoWithFilenameObjects (*C function*), 51  
 PyErr\_SetFromWindowsErr (*C function*), 51  
 PyErr\_SetFromWindowsErrWithFilename (*C function*), 51  
 PyErr\_SetHandledException (*C function*), 55  
 PyErr\_SetImportError (*C function*), 52  
 PyErr\_SetImportErrorSubclass (*C function*), 52  
 PyErr\_SetInterrupt (*C function*), 56  
 PyErr\_SetInterruptEx (*C function*), 56  
 PyErr\_SetNone (*C function*), 50  
 PyErr\_SetObject (*C function*), 50  
 PyErr\_SetString (*C function*), 10, 50  
 PyErr\_SyntaxLocation (*C function*), 52  
 PyErr\_SyntaxLocationEx (*C function*), 52  
 PyErr\_SyntaxLocationObject (*C function*), 52  
 PyErr\_WarnEx (*C function*), 53  
 PyErr\_WarnExplicit (*C function*), 53  
 PyErr\_WarnExplicitObject (*C function*), 53  
 PyErr\_WarnFormat (*C function*), 53  
 PyErr\_WriteUnraisable (*C function*), 50  
 PyEval\_AcquireLock (*C function*), 193  
 PyEval\_AcquireThread (*C function*), 193  
 PyEval\_AcquireThread(), 189  
 PyEval\_EvalCode (*C function*), 44  
 PyEval\_EvalCodeEx (*C function*), 44  
 PyEval\_EvalFrame (*C function*), 44  
 PyEval\_EvalFrameEx (*C function*), 44  
 PyEval\_GetBuiltins (*C function*), 83  
 PyEval\_GetFrame (*C function*), 83  
 PyEval\_GetFuncDesc (*C function*), 84  
 PyEval\_GetFuncName (*C function*), 84  
 PyEval\_GetGlobals (*C function*), 83  
 PyEval\_GetLocals (*C function*), 83  
 PyEval\_InitThreads (*C function*), 189  
 PyEval\_InitThreads(), 182  
 PyEval\_MergeCompilerFlags (*C function*), 44  
 PyEval\_ReleaseLock (*C function*), 194  
 PyEval\_ReleaseThread (*C function*), 193  
 PyEval\_ReleaseThread(), 189  
 PyEval\_RestoreThread (*C function*), 187, 189  
 PyEval\_RestoreThread(), 189  
 PyEval\_SaveThread (*C function*), 187, 189  
 PyEval\_SaveThread(), 189  
 PyEval\_SetProfile (*C function*), 197  
 PyEval\_SetTrace (*C function*), 197  
 PyEval\_ThreadsInitialized (*C function*), 189  
 PyExc\_ArithmeticError (*C var*), 59  
 PyExc\_AssertionError (*C var*), 59  
 PyExc\_AttributeError (*C var*), 59  
 PyExc\_BaseException (*C var*), 59  
 PyExc\_BlockingIOError (*C var*), 59  
 PyExc\_BrokenPipeError (*C var*), 59  
 PyExc\_BufferError (*C var*), 59  
 PyExc\_BytesWarning (*C var*), 61  
 PyExc\_ChildProcessError (*C var*), 59  
 PyExc\_ConnectionAbortedError (*C var*), 59  
 PyExc\_ConnectionError (*C var*), 59  
 PyExc\_ConnectionRefusedError (*C var*), 59  
 PyExc\_ConnectionResetError (*C var*), 59  
 PyExc\_DeprecationWarning (*C var*), 61  
 PyExc\_EOFError (*C var*), 59  
 PyExc\_EnvironmentError (*C var*), 61  
 PyExc\_Exception (*C var*), 59  
 PyExc\_FileExistsError (*C var*), 59  
 PyExc\_FileNotFoundError (*C var*), 59  
 PyExc\_FloatingPointError (*C var*), 59  
 PyExc\_FutureWarning (*C var*), 61  
 PyExc\_GeneratorExit (*C var*), 59  
 PyExc\_IOError (*C var*), 61  
 PyExc\_ImportError (*C var*), 59  
 PyExc\_ImportWarning (*C var*), 61  
 PyExc\_IndentationError (*C var*), 59  
 PyExc\_IndexError (*C var*), 59  
 PyExc\_InterruptedError (*C var*), 59  
 PyExc\_IsADirectoryError (*C var*), 59  
 PyExc\_KeyError (*C var*), 59  
 PyExc\_KeyboardInterrupt (*C var*), 59  
 PyExc\_LookupError (*C var*), 59  
 PyExc\_MemoryError (*C var*), 59  
 PyExc\_ModuleNotFoundError (*C var*), 59  
 PyExc\_NameError (*C var*), 59  
 PyExc\_NotADirectoryError (*C var*), 59  
 PyExc\_NotImplementedError (*C var*), 59  
 PyExc\_OSError (*C var*), 59

PyExc\_OverflowError (*C var*), 59  
PyExc\_PendingDeprecationWarning (*C var*), 61  
PyExc\_PermissionError (*C var*), 59  
PyExc\_ProcessLookupError (*C var*), 59  
PyExc\_RecursionError (*C var*), 59  
PyExc\_ReferenceError (*C var*), 59  
PyExc\_ResourceWarning (*C var*), 61  
PyExc\_RuntimeError (*C var*), 59  
PyExc\_RuntimeWarning (*C var*), 61  
PyExc\_StopAsyncIteration (*C var*), 59  
PyExc\_StopIteration (*C var*), 59  
PyExc\_SyntaxError (*C var*), 59  
PyExc\_SyntaxWarning (*C var*), 61  
PyExc\_SystemError (*C var*), 59  
PyExc\_SystemExit (*C var*), 59  
PyExc\_TabError (*C var*), 59  
PyExc\_TimeoutError (*C var*), 59  
PyExc\_TypeError (*C var*), 59  
PyExc\_UnboundLocalError (*C var*), 59  
PyExc\_UnicodeDecodeError (*C var*), 59  
PyExc\_UnicodeEncodeError (*C var*), 59  
PyExc\_UnicodeError (*C var*), 59  
PyExc\_UnicodeTranslateError (*C var*), 59  
PyExc\_UnicodeWarning (*C var*), 61  
PyExc\_UserWarning (*C var*), 61  
PyExc\_ValueError (*C var*), 59  
PyExc\_Warning (*C var*), 61  
PyExc\_WindowsError (*C var*), 61  
PyExc\_ZeroDivisionError (*C var*), 59  
PyException\_GetCause (*C function*), 57  
PyException\_GetContext (*C function*), 57  
PyException\_GetTraceback (*C function*), 57  
PyException\_SetCause (*C function*), 57  
PyException\_SetContext (*C function*), 57  
PyException\_SetTraceback (*C function*), 57  
PyFile\_FromFd (*C function*), 156  
PyFile\_GetLine (*C function*), 156  
PyFile\_SetOpenCodeHook (*C function*), 156  
PyFile\_WriteObject (*C function*), 157  
PyFile\_WriteString (*C function*), 157  
PyFloatObject (*C type*), 119  
PyFloat\_AS\_DOUBLE (*C function*), 119  
PyFloat\_AsDouble (*C function*), 119  
PyFloat\_Check (*C function*), 119  
PyFloat\_CheckExact (*C function*), 119  
PyFloat\_FromDouble (*C function*), 119  
PyFloat\_FromString (*C function*), 119  
PyFloat\_GetInfo (*C function*), 119  
PyFloat\_GetMax (*C function*), 119  
PyFloat\_GetMin (*C function*), 120  
PyFloat\_Pack2 (*C function*), 120  
PyFloat\_Pack4 (*C function*), 120  
PyFloat\_Pack8 (*C function*), 120  
PyFloat\_Type (*C var*), 119  
PyFloat\_Unpack2 (*C function*), 120  
PyFloat\_Unpack4 (*C function*), 121  
PyFloat\_Unpack8 (*C function*), 121  
PyFrameObject (*C type*), 170  
PyFrame\_Check (*C function*), 170  
PyFrame\_GetBack (*C function*), 171  
PyFrame\_GetBuiltins (*C function*), 171  
PyFrame\_GetCode (*C function*), 171  
PyFrame\_GetGenerator (*C function*), 171  
PyFrame\_GetGlobals (*C function*), 171  
PyFrame\_GetLasti (*C function*), 171  
PyFrame\_GetLineNumber (*C function*), 171  
PyFrame\_GetLocals (*C function*), 171  
PyFrame\_Type (*C var*), 170  
PyFrozenSet\_Check (*C function*), 150  
PyFrozenSet\_CheckExact (*C function*), 150  
PyFrozenSet\_New (*C function*), 151  
PyFrozenSet\_Type (*C var*), 150  
PyFunctionObject (*C type*), 152  
PyFunction\_Check (*C function*), 152  
PyFunction\_GetAnnotations (*C function*), 152  
PyFunction\_GetClosure (*C function*), 152  
PyFunction\_GetCode (*C function*), 152  
PyFunction\_GetDefaults (*C function*), 152  
PyFunction\_GetGlobals (*C function*), 152  
PyFunction\_GetModule (*C function*), 152  
PyFunction\_New (*C function*), 152  
PyFunction\_NewWithQualName (*C function*), 152  
PyFunction\_SetAnnotations (*C function*), 153  
PyFunction\_SetClosure (*C function*), 152  
PyFunction\_SetDefaults (*C function*), 152  
PyFunction\_Type (*C var*), 152  
PyGC\_Collect (*C function*), 277  
PyGC\_Disable (*C function*), 277  
PyGC\_Enable (*C function*), 277  
PyGC\_IsEnabled (*C function*), 278  
PyGILState\_Check (*C function*), 190  
PyGILState\_Ensure (*C function*), 190  
PyGILState\_GetThisThreadState (*C function*), 190  
PyGILState\_Release (*C function*), 190  
PyGenObject (*C type*), 172  
PyGen\_Check (*C function*), 172  
PyGen\_CheckExact (*C function*), 172  
PyGen\_New (*C function*), 172  
PyGen\_NewWithQualName (*C function*), 172  
PyGen\_Type (*C var*), 172  
PyGetSetDef (*C type*), 240  
PyHash\_FuncDef (*C type*), 83  
PyHash\_FuncDef.hash\_bits (*C member*), 83  
PyHash\_FuncDef.name (*C member*), 83  
PyHash\_FuncDef.seed\_bits (*C member*), 83  
PyHash\_GetFuncDef (*C function*), 83  
PyImport\_AddModule (*C function*), 69  
PyImport\_AddModuleObject (*C function*), 69  
PyImport\_AppendInittab (*C function*), 71  
PyImport\_ExecCodeModule (*C function*), 69  
PyImport\_ExecCodeModuleEx (*C function*), 70  
PyImport\_ExecCodeModuleObject (*C function*), 70

- PyImport\_ExecCodeModuleWithPathnames (C function), 70
- PyImport\_ExtendInittab (C function), 71
- PyImport\_FrozenModules (C var), 71
- PyImport\_GetImporter (C function), 70
- PyImport\_GetMagicNumber (C function), 70
- PyImport\_GetMagicTag (C function), 70
- PyImport\_GetModule (C function), 70
- PyImport\_GetModuleDict (C function), 70
- PyImport\_Import (C function), 69
- PyImport\_ImportFrozenModule (C function), 71
- PyImport\_ImportFrozenModuleObject (C function), 71
- PyImport\_ImportModule (C function), 68
- PyImport\_ImportModuleEx (C function), 68
- PyImport\_ImportModuleLevel (C function), 69
- PyImport\_ImportModuleLevelObject (C function), 69
- PyImport\_ImportModuleNoBlock (C function), 68
- PyImport\_ReloadModule (C function), 69
- PyIndex\_Check (C function), 99
- PyInstanceMethod\_Check (C function), 153
- PyInstanceMethod\_Function (C function), 153
- PyInstanceMethod\_GET\_FUNCTION (C function), 153
- PyInstanceMethod\_New (C function), 153
- PyInstanceMethod\_Type (C var), 153
- PyInterpreterState (C type), 189
- PyInterpreterState\_Clear (C function), 191
- PyInterpreterState\_Delete (C function), 191
- PyInterpreterState\_Get (C function), 192
- PyInterpreterState\_GetDict (C function), 192
- PyInterpreterState\_GetID (C function), 192
- PyInterpreterState\_Head (C function), 197
- PyInterpreterState\_Main (C function), 197
- PyInterpreterState\_New (C function), 191
- PyInterpreterState\_Next (C function), 197
- PyInterpreterState\_ThreadHead (C function), 197
- PyIter\_Check (C function), 102
- PyIter\_Next (C function), 102
- PyIter\_Send (C function), 103
- PyListObject (C type), 146
- PyList\_Append (C function), 146
- PyList\_AsTuple (C function), 147
- PyList\_Check (C function), 146
- PyList\_CheckExact (C function), 146
- PyList\_GET\_ITEM (C function), 146
- PyList\_GET\_SIZE (C function), 146
- PyList\_GetItem (C function), 9, 146
- PyList\_GetSlice (C function), 147
- PyList\_Insert (C function), 146
- PyList\_New (C function), 146
- PyList\_Reverse (C function), 147
- PyList\_SET\_ITEM (C function), 146
- PyList\_SetItem (C function), 8, 146
- PyList\_SetSlice (C function), 147
- PyList\_Size (C function), 146
- PyList\_Sort (C function), 147
- PyList\_Type (C var), 146
- PyLongObject (C type), 115
- PyLong\_AsDouble (C function), 118
- PyLong\_AsLong (C function), 116
- PyLong\_AsLongAndOverflow (C function), 117
- PyLong\_AsLongLong (C function), 117
- PyLong\_AsLongLongAndOverflow (C function), 117
- PyLong\_AsSize\_t (C function), 117
- PyLong\_AsSsize\_t (C function), 117
- PyLong\_AsUnsignedLong (C function), 117
- PyLong\_AsUnsignedLongLong (C function), 117
- PyLong\_AsUnsignedLongLongMask (C function), 118
- PyLong\_AsUnsignedLongMask (C function), 118
- PyLong\_AsVoidPtr (C function), 118
- PyLong\_Check (C function), 115
- PyLong\_CheckExact (C function), 115
- PyLong\_FromDouble (C function), 116
- PyLong\_FromLong (C function), 115
- PyLong\_FromLongLong (C function), 116
- PyLong\_FromSize\_t (C function), 116
- PyLong\_FromSsize\_t (C function), 116
- PyLong\_FromString (C function), 116
- PyLong\_FromUnicodeObject (C function), 116
- PyLong\_FromUnsignedLong (C function), 116
- PyLong\_FromUnsignedLongLong (C function), 116
- PyLong\_FromVoidPtr (C function), 116
- PyLong\_Type (C var), 115
- PyMODINIT\_FUNC (C macro), 4
- PyMappingMethods (C type), 268
- PyMappingMethods.mp\_ass\_subscript (C member), 269
- PyMappingMethods.mp\_length (C member), 268
- PyMappingMethods.mp\_subscript (C member), 268
- PyMapping\_Check (C function), 101
- PyMapping\_DelItem (C function), 101
- PyMapping\_DelItemString (C function), 102
- PyMapping\_GetItemString (C function), 101
- PyMapping\_HasKey (C function), 102
- PyMapping\_HasKeyString (C function), 102
- PyMapping\_Items (C function), 102
- PyMapping\_Keys (C function), 102
- PyMapping\_Length (C function), 101
- PyMapping\_SetItemString (C function), 101
- PyMapping\_Size (C function), 101
- PyMapping\_Values (C function), 102
- PyMarshal\_ReadLastObjectFromFile (C function), 72
- PyMarshal\_ReadLongFromFile (C function), 72

- `PyMarshal_ReadObjectFromFile` (*C function*), 72
- `PyMarshal_ReadObjectFromString` (*C function*), 72
- `PyMarshal_ReadShortFromFile` (*C function*), 72
- `PyMarshal_WriteLongToFile` (*C function*), 72
- `PyMarshal_WriteObjectToFile` (*C function*), 72
- `PyMarshal_WriteObjectToString` (*C function*), 72
- `PyMemAllocatorDomain` (*C type*), 228
- `PyMemAllocatorEx` (*C type*), 228
- `PyMem_Calloc` (*C function*), 225
- `PyMem_Del` (*C function*), 226
- `PyMem_Free` (*C function*), 226
- `PyMem_GetAllocator` (*C function*), 228
- `PyMem_Malloc` (*C function*), 225
- `PyMem_New` (*C macro*), 226
- `PyMem_RawCalloc` (*C function*), 224
- `PyMem_RawFree` (*C function*), 225
- `PyMem_RawMalloc` (*C function*), 224
- `PyMem_RawRealloc` (*C function*), 225
- `PyMem_Realloc` (*C function*), 225
- `PyMem_Resize` (*C macro*), 226
- `PyMem_SetAllocator` (*C function*), 228
- `PyMem_SetupDebugHooks` (*C function*), 229
- `PyMemberDef` (*C type*), 239
- `PyMember_GetOne` (*C function*), 240
- `PyMember_SetOne` (*C function*), 240
- `PyMemoryView_Check` (*C function*), 167
- `PyMemoryView_FromBuffer` (*C function*), 167
- `PyMemoryView_FromMemory` (*C function*), 167
- `PyMemoryView_FromObject` (*C function*), 167
- `PyMemoryView_GET_BASE` (*C function*), 167
- `PyMemoryView_GET_BUFFER` (*C function*), 167
- `PyMemoryView_GetContiguous` (*C function*), 167
- `PyMethodDef` (*C type*), 237
- `PyMethodDef.ml_doc` (*C member*), 237
- `PyMethodDef.ml_flags` (*C member*), 237
- `PyMethodDef.ml_meth` (*C member*), 237
- `PyMethodDef.ml_name` (*C member*), 237
- `PyMethod_Check` (*C function*), 153
- `PyMethod_Function` (*C function*), 153
- `PyMethod_GET_FUNCTION` (*C function*), 153
- `PyMethod_GET_SELF` (*C function*), 154
- `PyMethod_New` (*C function*), 153
- `PyMethod_Self` (*C function*), 153
- `PyMethod_Type` (*C var*), 153
- `PyModuleDef` (*C type*), 158
- `PyModuleDef_Init` (*C function*), 160
- `PyModuleDef_Slot` (*C type*), 160
- `PyModuleDef_Slot.slot` (*C member*), 160
- `PyModuleDef_Slot.value` (*C member*), 160
- `PyModuleDef.m_base` (*C member*), 158
- `PyModuleDef.m_clear` (*C member*), 159
- `PyModuleDef.m_doc` (*C member*), 158
- `PyModuleDef.m_free` (*C member*), 159
- `PyModuleDef.m_methods` (*C member*), 159
- `PyModuleDef.m_name` (*C member*), 158
- `PyModuleDef.m_size` (*C member*), 158
- `PyModuleDef.m_slots` (*C member*), 159
- `PyModuleDef.m_slots.m_reload` (*C member*), 159
- `PyModuleDef.m_traverse` (*C member*), 159
- `PyModule_AddFunctions` (*C function*), 162
- `PyModule_AddIntConstant` (*C function*), 163
- `PyModule_AddIntMacro` (*C macro*), 163
- `PyModule_AddObject` (*C function*), 162
- `PyModule_AddObjectRef` (*C function*), 162
- `PyModule_AddStringConstant` (*C function*), 163
- `PyModule_AddStringMacro` (*C macro*), 163
- `PyModule_AddType` (*C function*), 164
- `PyModule_Check` (*C function*), 157
- `PyModule_CheckExact` (*C function*), 157
- `PyModule_Create` (*C function*), 160
- `PyModule_Create2` (*C function*), 160
- `PyModule_ExecDef` (*C function*), 161
- `PyModule_FromDefAndSpec` (*C function*), 161
- `PyModule_FromDefAndSpec2` (*C function*), 161
- `PyModule_GetDef` (*C function*), 158
- `PyModule_GetDict` (*C function*), 157
- `PyModule_GetFilename` (*C function*), 158
- `PyModule_GetFilenameObject` (*C function*), 158
- `PyModule_GetName` (*C function*), 158
- `PyModule_GetNameObject` (*C function*), 157
- `PyModule_GetState` (*C function*), 158
- `PyModule_New` (*C function*), 157
- `PyModule_NewObject` (*C function*), 157
- `PyModule_SetDocString` (*C function*), 162
- `PyModule_Type` (*C var*), 157
- `PyNumberMethods` (*C type*), 266
- `PyNumberMethods.nb_absolute` (*C member*), 267
- `PyNumberMethods.nb_add` (*C member*), 267
- `PyNumberMethods.nb_and` (*C member*), 268
- `PyNumberMethods.nb_bool` (*C member*), 267
- `PyNumberMethods.nb_divmod` (*C member*), 267
- `PyNumberMethods.nb_float` (*C member*), 268
- `PyNumberMethods.nb_floor_divide` (*C member*), 268
- `PyNumberMethods.nb_index` (*C member*), 268
- `PyNumberMethods.nb_inplace_add` (*C member*), 268
- `PyNumberMethods.nb_inplace_and` (*C member*), 268
- `PyNumberMethods.nb_inplace_floor_divide` (*C member*), 268
- `PyNumberMethods.nb_inplace_lshift` (*C member*), 268
- `PyNumberMethods.nb_inplace_matrix_multiply` (*C member*), 268



<code>PyNumberMethods.nb_inplace_multiply</code> ( <i>C member</i> ), 268	<code>PyNumber_InPlaceRshift</code> ( <i>C function</i> ), 98
<code>PyNumberMethods.nb_inplace_or</code> ( <i>C member</i> ), 268	<code>PyNumber_InPlaceSubtract</code> ( <i>C function</i> ), 98
<code>PyNumberMethods.nb_inplace_power</code> ( <i>C member</i> ), 268	<code>PyNumber_InPlaceTrueDivide</code> ( <i>C function</i> ), 98
<code>PyNumberMethods.nb_inplace_remainder</code> ( <i>C member</i> ), 268	<code>PyNumber_InPlaceXor</code> ( <i>C function</i> ), 98
<code>PyNumberMethods.nb_inplace_rshift</code> ( <i>C member</i> ), 268	<code>PyNumber_Index</code> ( <i>C function</i> ), 99
<code>PyNumberMethods.nb_inplace_subtract</code> ( <i>C member</i> ), 268	<code>PyNumber_Invert</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_inplace_true_divide</code> ( <i>C member</i> ), 268	<code>PyNumber_Long</code> ( <i>C function</i> ), 99
<code>PyNumberMethods.nb_inplace_xor</code> ( <i>C member</i> ), 268	<code>PyNumber_Lshift</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_int</code> ( <i>C member</i> ), 268	<code>PyNumber_MatrixMultiply</code> ( <i>C function</i> ), 96
<code>PyNumberMethods.nb_invert</code> ( <i>C member</i> ), 267	<code>PyNumber_Multiply</code> ( <i>C function</i> ), 96
<code>PyNumberMethods.nb_lshift</code> ( <i>C member</i> ), 267	<code>PyNumber_Negative</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_matrix_multiply</code> ( <i>C member</i> ), 268	<code>PyNumber_Or</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_multiply</code> ( <i>C member</i> ), 267	<code>PyNumber_Positive</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_negative</code> ( <i>C member</i> ), 267	<code>PyNumber_Power</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_or</code> ( <i>C member</i> ), 268	<code>PyNumber_Remainder</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_positive</code> ( <i>C member</i> ), 267	<code>PyNumber_Rshift</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_power</code> ( <i>C member</i> ), 267	<code>PyNumber_Subtract</code> ( <i>C function</i> ), 96
<code>PyNumberMethods.nb_remainder</code> ( <i>C member</i> ), 267	<code>PyNumber_ToBase</code> ( <i>C function</i> ), 99
<code>PyNumberMethods.nb_reserved</code> ( <i>C member</i> ), 268	<code>PyNumber_TrueDivide</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_rshift</code> ( <i>C member</i> ), 268	<code>PyNumber_Xor</code> ( <i>C function</i> ), 97
<code>PyNumberMethods.nb_subtract</code> ( <i>C member</i> ), 267	<code>PyOS_AfterFork</code> ( <i>C function</i> ), 64
<code>PyNumberMethods.nb_true_divide</code> ( <i>C member</i> ), 268	<code>PyOS_AfterFork_Child</code> ( <i>C function</i> ), 64
<code>PyNumberMethods.nb_xor</code> ( <i>C member</i> ), 268	<code>PyOS_AfterFork_Parent</code> ( <i>C function</i> ), 63
<code>PyNumber_Absolute</code> ( <i>C function</i> ), 97	<code>PyOS_BeforeFork</code> ( <i>C function</i> ), 63
<code>PyNumber_Add</code> ( <i>C function</i> ), 96	<code>PyOS_CheckStack</code> ( <i>C function</i> ), 64
<code>PyNumber_And</code> ( <i>C function</i> ), 97	<code>PyOS_FSPath</code> ( <i>C function</i> ), 63
<code>PyNumber_AsSsize_t</code> ( <i>C function</i> ), 99	<code>PyOS_InputHook</code> ( <i>C var</i> ), 42
<code>PyNumber_Check</code> ( <i>C function</i> ), 96	<code>PyOS_ReadlineFunctionPointer</code> ( <i>C var</i> ), 42
<code>PyNumber_Divmod</code> ( <i>C function</i> ), 97	<code>PyOS_double_to_string</code> ( <i>C function</i> ), 82
<code>PyNumber_Float</code> ( <i>C function</i> ), 99	<code>PyOS_getsig</code> ( <i>C function</i> ), 64
<code>PyNumber_FloorDivide</code> ( <i>C function</i> ), 96	<code>PyOS_setsig</code> ( <i>C function</i> ), 64
<code>PyNumber_InPlaceAdd</code> ( <i>C function</i> ), 97	<code>PyOS_sighandler_t</code> ( <i>C type</i> ), 64
<code>PyNumber_InPlaceAnd</code> ( <i>C function</i> ), 98	<code>PyOS_snprintf</code> ( <i>C function</i> ), 81
<code>PyNumber_InPlaceFloorDivide</code> ( <i>C function</i> ), 98	<code>PyOS_stricmp</code> ( <i>C function</i> ), 83
<code>PyNumber_InPlaceLshift</code> ( <i>C function</i> ), 98	<code>PyOS_string_to_double</code> ( <i>C function</i> ), 82
<code>PyNumber_InPlaceMatrixMultiply</code> ( <i>C function</i> ), 98	<code>PyOS_strnicmp</code> ( <i>C function</i> ), 83
<code>PyNumber_InPlaceMultiply</code> ( <i>C function</i> ), 98	<code>PyOS_strtol</code> ( <i>C function</i> ), 82
<code>PyNumber_InPlaceOr</code> ( <i>C function</i> ), 99	<code>PyOS_strtoul</code> ( <i>C function</i> ), 81
<code>PyNumber_InPlacePower</code> ( <i>C function</i> ), 98	<code>PyOS_vsnprintf</code> ( <i>C function</i> ), 81
<code>PyNumber_InPlaceRemainder</code> ( <i>C function</i> ), 98	<code>PyObject</code> ( <i>C type</i> ), 234
	<code>PyObjectArenaAllocator</code> ( <i>C type</i> ), 231
	<code>PyObject_ASCII</code> ( <i>C function</i> ), 89
	<code>PyObject_AsCharBuffer</code> ( <i>C function</i> ), 110
	<code>PyObject_AsFileDescriptor</code> ( <i>C function</i> ), 156
	<code>PyObject_AsReadBuffer</code> ( <i>C function</i> ), 110
	<code>PyObject_AsWriteBuffer</code> ( <i>C function</i> ), 110
	<code>PyObject_Bytes</code> ( <i>C function</i> ), 90
	<code>PyObject_Call</code> ( <i>C function</i> ), 94
	<code>PyObject_CallFunction</code> ( <i>C function</i> ), 94
	<code>PyObject_CallFunctionObjArgs</code> ( <i>C function</i> ), 95
	<code>PyObject_CallMethod</code> ( <i>C function</i> ), 95
	<code>PyObject_CallMethodNoArgs</code> ( <i>C function</i> ), 95
	<code>PyObject_CallMethodObjArgs</code> ( <i>C function</i> ), 95
	<code>PyObject_CallMethodOneArg</code> ( <i>C function</i> ), 95
	<code>PyObject_CallNoArgs</code> ( <i>C function</i> ), 94
	<code>PyObject_CallObject</code> ( <i>C function</i> ), 94
	<code>PyObject_CallOneArg</code> ( <i>C function</i> ), 94

- PyObject\_Calloc (*C function*), 227
- PyObject\_CheckBuffer (*C function*), 109
- PyObject\_CheckReadBuffer (*C function*), 110
- PyObject\_ClearWeakRefs (*C function*), 168
- PyObject\_CopyData (*C function*), 109
- PyObject\_Del (*C function*), 233
- PyObject\_DelAttr (*C function*), 88
- PyObject\_DelAttrString (*C function*), 88
- PyObject\_DelItem (*C function*), 91
- PyObject\_Dir (*C function*), 91
- PyObject\_Format (*C function*), 89
- PyObject\_Free (*C function*), 227
- PyObject\_GC\_Del (*C function*), 276
- PyObject\_GC\_IsFinalized (*C function*), 276
- PyObject\_GC\_IsTracked (*C function*), 276
- PyObject\_GC\_New (*C macro*), 276
- PyObject\_GC\_NewVar (*C macro*), 276
- PyObject\_GC\_Resize (*C macro*), 276
- PyObject\_GC\_Track (*C function*), 276
- PyObject\_GC\_UnTrack (*C function*), 276
- PyObject\_GenericGetAttr (*C function*), 88
- PyObject\_GenericGetDict (*C function*), 88
- PyObject\_GenericSetAttr (*C function*), 88
- PyObject\_GenericSetDict (*C function*), 89
- PyObject\_GetAIter (*C function*), 91
- PyObject\_GetArenaAllocator (*C function*), 231
- PyObject\_GetAttr (*C function*), 88
- PyObject\_GetAttrString (*C function*), 88
- PyObject\_GetBuffer (*C function*), 109
- PyObject\_GetItem (*C function*), 91
- PyObject\_GetIter (*C function*), 91
- PyObject\_HEAD (*C macro*), 234
- PyObject\_HEAD\_INIT (*C macro*), 236
- PyObject\_HasAttr (*C function*), 87
- PyObject\_HasAttrString (*C function*), 87
- PyObject\_Hash (*C function*), 90
- PyObject\_HashNotImplemented (*C function*), 90
- PyObject\_IS\_GC (*C function*), 276
- PyObject\_Init (*C function*), 233
- PyObject\_InitVar (*C function*), 233
- PyObject\_IsInstance (*C function*), 90
- PyObject\_IsSubclass (*C function*), 90
- PyObject\_IsTrue (*C function*), 90
- PyObject\_Length (*C function*), 91
- PyObject\_LengthHint (*C function*), 91
- PyObject\_Malloc (*C function*), 227
- PyObject\_New (*C macro*), 233
- PyObject\_NewVar (*C macro*), 233
- PyObject\_Not (*C function*), 90
- PyObject\_Print (*C function*), 87
- PyObject\_Realloc (*C function*), 227
- PyObject\_Repr (*C function*), 89
- PyObject\_RichCompare (*C function*), 89
- PyObject\_RichCompareBool (*C function*), 89
- PyObject\_SetArenaAllocator (*C function*), 231
- PyObject\_SetAttr (*C function*), 88
- PyObject\_SetAttrString (*C function*), 88
- PyObject\_SetItem (*C function*), 91
- PyObject\_Size (*C function*), 91
- PyObject\_Str (*C function*), 89
- PyObject\_Type (*C function*), 90
- PyObject\_TypeCheck (*C function*), 90
- PyObject\_VAR\_HEAD (*C macro*), 234
- PyObject\_Vectorcall (*C function*), 95
- PyObject\_VectorcallDict (*C function*), 95
- PyObject\_VectorcallMethod (*C function*), 96
- PyObject.\_ob\_next (*C member*), 248
- PyObject.\_ob\_prev (*C member*), 248
- PyObject.ob\_refcnt (*C member*), 247
- PyObject.ob\_type (*C member*), 247
- PyPreConfig (*C type*), 204
- PyPreConfig\_InitIsolatedConfig (*C function*), 204
- PyPreConfig\_InitPythonConfig (*C function*), 204
- PyPreConfig allocator (*C member*), 204
- PyPreConfig.coerce\_c\_locale (*C member*), 204
- PyPreConfig.coerce\_c\_locale\_warn (*C member*), 205
- PyPreConfig.configure\_locale (*C member*), 204
- PyPreConfig.dev\_mode (*C member*), 205
- PyPreConfig.isolated (*C member*), 205
- PyPreConfig.legacy\_windows\_fs\_encoding (*C member*), 205
- PyPreConfig.parse\_argv (*C member*), 205
- PyPreConfig.use\_environment (*C member*), 205
- PyPreConfig.utf8\_mode (*C member*), 205
- PyProperty\_Type (*C var*), 165
- PyRun\_AnyFile (*C function*), 41
- PyRun\_AnyFileEx (*C function*), 41
- PyRun\_AnyFileExFlags (*C function*), 41
- PyRun\_AnyFileFlags (*C function*), 41
- PyRun\_File (*C function*), 43
- PyRun\_FileEx (*C function*), 43
- PyRun\_FileExFlags (*C function*), 43
- PyRun\_FileFlags (*C function*), 43
- PyRun\_InteractiveLoop (*C function*), 42
- PyRun\_InteractiveLoopFlags (*C function*), 42
- PyRun\_InteractiveOne (*C function*), 42
- PyRun\_InteractiveOneFlags (*C function*), 42
- PyRun\_SimpleFile (*C function*), 42
- PyRun\_SimpleFileEx (*C function*), 42
- PyRun\_SimpleFileExFlags (*C function*), 42
- PyRun\_SimpleString (*C function*), 42
- PyRun\_SimpleStringFlags (*C function*), 42
- PyRun\_String (*C function*), 43
- PyRun\_StringFlags (*C function*), 43
- PySendResult (*C type*), 103
- PySeqIter\_Check (*C function*), 164
- PySeqIter\_New (*C function*), 164

- PySeqIter\_Type (*C var*), 164
- PySequenceMethods (*C type*), 269
- PySequenceMethods.sq\_ass\_item (*C member*), 269
- PySequenceMethods.sq\_concat (*C member*), 269
- PySequenceMethods.sq\_contains (*C member*), 269
- PySequenceMethods.sq\_inplace\_concat (*C member*), 269
- PySequenceMethods.sq\_inplace\_repeat (*C member*), 269
- PySequenceMethods.sq\_item (*C member*), 269
- PySequenceMethods.sq\_length (*C member*), 269
- PySequenceMethods.sq\_repeat (*C member*), 269
- PySequence\_Check (*C function*), 99
- PySequence\_Concat (*C function*), 99
- PySequence\_Contains (*C function*), 100
- PySequence\_Count (*C function*), 100
- PySequence\_DelItem (*C function*), 100
- PySequence\_Delslice (*C function*), 100
- PySequence\_Fast (*C function*), 101
- PySequence\_Fast\_GET\_ITEM (*C function*), 101
- PySequence\_Fast\_GET\_SIZE (*C function*), 101
- PySequence\_Fast\_ITEMS (*C function*), 101
- PySequence\_GetItem (*C function*), 9, 100
- PySequence\_GetSlice (*C function*), 100
- PySequence\_ITEM (*C function*), 101
- PySequence\_InPlaceConcat (*C function*), 100
- PySequence\_InPlaceRepeat (*C function*), 100
- PySequence\_Index (*C function*), 100
- PySequence\_Length (*C function*), 99
- PySequence\_List (*C function*), 100
- PySequence\_Repeat (*C function*), 99
- PySequence\_SetItem (*C function*), 100
- PySequence\_SetSlice (*C function*), 100
- PySequence\_Size (*C function*), 99
- PySequence\_Tuple (*C function*), 100
- PySetObject (*C type*), 150
- PySet\_Add (*C function*), 151
- PySet\_Check (*C function*), 150
- PySet\_CheckExact (*C function*), 150
- PySet\_Clear (*C function*), 151
- PySet\_Contains (*C function*), 151
- PySet\_Discard (*C function*), 151
- PySet\_GET\_SIZE (*C function*), 151
- PySet\_New (*C function*), 151
- PySet\_Pop (*C function*), 151
- PySet\_Size (*C function*), 151
- PySet\_Type (*C var*), 150
- PySignal\_SetWakeUpFd (*C function*), 56
- PySlice\_AdjustIndices (*C function*), 166
- PySlice\_Check (*C function*), 165
- PySlice\_GetIndices (*C function*), 165
- PySlice\_GetIndicesEx (*C function*), 166
- PySlice\_New (*C function*), 165
- PySlice\_Type (*C var*), 165
- PySlice\_Unpack (*C function*), 166
- PyState\_AddModule (*C function*), 164
- PyState\_FindModule (*C function*), 164
- PyState\_RemoveModule (*C function*), 164
- PyStatus (*C type*), 203
- PyStatus\_Error (*C function*), 203
- PyStatus\_Exception (*C function*), 203
- PyStatus\_Exit (*C function*), 203
- PyStatus\_IsError (*C function*), 203
- PyStatus\_IsExit (*C function*), 203
- PyStatus\_NoMemory (*C function*), 203
- PyStatus\_Ok (*C function*), 203
- PyStatus.err\_msg (*C member*), 203
- PyStatus.exitcode (*C member*), 203
- PyStatus.func (*C member*), 203
- PyStructSequence\_Desc (*C type*), 144
- PyStructSequence\_Desc.doc (*C member*), 144
- PyStructSequence\_Desc.fields (*C member*), 145
- PyStructSequence\_Desc.n\_in\_sequence (*C member*), 145
- PyStructSequence\_Desc.name (*C member*), 144
- PyStructSequence\_Field (*C type*), 145
- PyStructSequence\_Field.doc (*C member*), 145
- PyStructSequence\_Field.name (*C member*), 145
- PyStructSequence\_GET\_ITEM (*C function*), 145
- PyStructSequence\_GetItem (*C function*), 145
- PyStructSequence\_InitType (*C function*), 144
- PyStructSequence\_InitType2 (*C function*), 144
- PyStructSequence\_New (*C function*), 145
- PyStructSequence\_NewType (*C function*), 144
- PyStructSequence\_SET\_ITEM (*C function*), 145
- PyStructSequence\_SetItem (*C function*), 145
- PyStructSequence\_UnnamedField (*C var*), 145
- PySys\_AddAuditHook (*C function*), 67
- PySys\_AddWarnOption (*C function*), 66
- PySys\_AddWarnOptionUnicode (*C function*), 66
- PySys\_AddXOption (*C function*), 67
- PySys\_Audit (*C function*), 67
- PySys\_FormatStderr (*C function*), 67
- PySys\_FormatStdout (*C function*), 66
- PySys\_GetObject (*C function*), 66
- PySys\_GetXOptions (*C function*), 67
- PySys\_ResetWarnOptions (*C function*), 66
- PySys\_SetArgv (*C function*), 182, 186
- PySys\_SetArgvEx (*C function*), 182, 185
- PySys\_SetObject (*C function*), 66
- PySys\_SetPath (*C function*), 66
- PySys\_WriteStderr (*C function*), 66
- PySys\_WriteStdout (*C function*), 66
- PyTZInfo\_Check (*C function*), 175
- PyTZInfo\_CheckExact (*C function*), 175

- PyThreadState (*C type*), 187, 189
- PyThreadState\_Clear (*C function*), 191
- PyThreadState\_Delete (*C function*), 191
- PyThreadState\_DeleteCurrent (*C function*), 191
- PyThreadState\_EnterTracing (*C function*), 192
- PyThreadState\_Get (*C function*), 189
- PyThreadState\_GetDict (*C function*), 193
- PyThreadState\_GetFrame (*C function*), 191
- PyThreadState\_GetID (*C function*), 191
- PyThreadState\_GetInterpreter (*C function*), 192
- PyThreadState\_LeaveTracing (*C function*), 192
- PyThreadState\_New (*C function*), 191
- PyThreadState\_Next (*C function*), 197
- PyThreadState\_SetAsyncExc (*C function*), 193
- PyThreadState\_Swap (*C function*), 189
- PyThreadState.interp (*C member*), 189
- PyThread\_ReInitTLS (*C function*), 199
- PyThread\_create\_key (*C function*), 199
- PyThread\_delete\_key (*C function*), 199
- PyThread\_delete\_key\_value (*C function*), 199
- PyThread\_get\_key\_value (*C function*), 199
- PyThread\_set\_key\_value (*C function*), 199
- PyThread\_tss\_alloc (*C function*), 198
- PyThread\_tss\_create (*C function*), 199
- PyThread\_tss\_delete (*C function*), 199
- PyThread\_tss\_free (*C function*), 198
- PyThread\_tss\_get (*C function*), 199
- PyThread\_tss\_is\_created (*C function*), 199
- PyThread\_tss\_set (*C function*), 199
- PyTimeZone\_FromOffset (*C function*), 176
- PyTimeZone\_FromOffsetAndName (*C function*), 176
- PyTime\_Check (*C function*), 175
- PyTime\_CheckExact (*C function*), 175
- PyTime\_FromTime (*C function*), 175
- PyTime\_FromTimeAndFold (*C function*), 176
- PyTraceMalloc\_Track (*C function*), 231
- PyTraceMalloc\_Untrack (*C function*), 231
- PyTrace\_CALL (*C var*), 196
- PyTrace\_C\_CALL (*C var*), 197
- PyTrace\_C\_EXCEPTION (*C var*), 197
- PyTrace\_C\_RETURN (*C var*), 197
- PyTrace\_EXCEPTION (*C var*), 196
- PyTrace\_LINE (*C var*), 196
- PyTrace\_OPCODE (*C var*), 197
- PyTrace\_RETURN (*C var*), 196
- PyTupleObject (*C type*), 143
- PyTuple\_Check (*C function*), 143
- PyTuple\_CheckExact (*C function*), 143
- PyTuple\_GET\_ITEM (*C function*), 143
- PyTuple\_GET\_SIZE (*C function*), 143
- PyTuple\_GetItem (*C function*), 143
- PyTuple\_GetSlice (*C function*), 144
- PyTuple\_New (*C function*), 143
- PyTuple\_Pack (*C function*), 143
- PyTuple\_SET\_ITEM (*C function*), 144
- PyTuple\_SetItem (*C function*), 8, 144
- PyTuple\_Size (*C function*), 143
- PyTuple\_Type (*C var*), 143
- PyTypeObject (*C type*), 111
- PyTypeObject.tp\_alloc (*C member*), 263
- PyTypeObject.tp\_as\_async (*C member*), 250
- PyTypeObject.tp\_as\_buffer (*C member*), 253
- PyTypeObject.tp\_as\_mapping (*C member*), 251
- PyTypeObject.tp\_as\_number (*C member*), 251
- PyTypeObject.tp\_as\_sequence (*C member*), 251
- PyTypeObject.tp\_base (*C member*), 260
- PyTypeObject.tp\_bases (*C member*), 264
- PyTypeObject.tp\_basicsize (*C member*), 248
- PyTypeObject.tp\_cache (*C member*), 264
- PyTypeObject.tp\_call (*C member*), 252
- PyTypeObject.tp\_clear (*C member*), 257
- PyTypeObject.tp\_dealloc (*C member*), 249
- PyTypeObject.tp\_del (*C member*), 265
- PyTypeObject.tp\_descr\_get (*C member*), 261
- PyTypeObject.tp\_descr\_set (*C member*), 261
- PyTypeObject.tp\_dict (*C member*), 261
- PyTypeObject.tp\_dictoffset (*C member*), 262
- PyTypeObject.tp\_doc (*C member*), 256
- PyTypeObject.tp\_finalize (*C member*), 265
- PyTypeObject.tp\_flags (*C member*), 253
- PyTypeObject.tp\_free (*C member*), 263
- PyTypeObject.tp\_getattr (*C member*), 250
- PyTypeObject.tp\_getattro (*C member*), 252
- PyTypeObject.tp\_getset (*C member*), 260
- PyTypeObject.tp\_hash (*C member*), 251
- PyTypeObject.tp\_init (*C member*), 262
- PyTypeObject.tp\_is\_gc (*C member*), 264
- PyTypeObject.tp\_ismember (*C member*), 248
- PyTypeObject.tp\_iter (*C member*), 260
- PyTypeObject.tp\_iternext (*C member*), 260
- PyTypeObject.tp\_members (*C member*), 260
- PyTypeObject.tp\_methods (*C member*), 260
- PyTypeObject.tp\_mro (*C member*), 264
- PyTypeObject.tp\_name (*C member*), 248
- PyTypeObject.tp\_new (*C member*), 263
- PyTypeObject.tp\_repr (*C member*), 251
- PyTypeObject.tp\_richcompare (*C member*), 258
- PyTypeObject.tp\_setattr (*C member*), 250
- PyTypeObject.tp\_setattro (*C member*), 252
- PyTypeObject.tp\_str (*C member*), 252
- PyTypeObject.tp\_subclasses (*C member*), 264
- PyTypeObject.tp\_traverse (*C member*), 256
- PyTypeObject.tp\_vectorcall (*C member*), 265
- PyTypeObject.tp\_vectorcall\_offset (*C member*), 250



PyTypeObject.tp_version_tag (C member), 265	PyUnicodeDecodeError_SetStart function), 58
PyTypeObject.tp_weaklist (C member), 264	PyUnicodeDecodeError_GetEncoding (C function), 58
PyTypeObject.tp_weaklistoffset (C member), 259	PyUnicodeDecodeError_GetEnd (C function), 58
PyType_Check (C function), 111	PyUnicodeDecodeError_GetObject (C function), 58
PyType_CheckExact (C function), 111	PyUnicodeDecodeError_GetReason (C function), 58
PyType_ClearCache (C function), 111	PyUnicodeDecodeError_GetStart (C function), 58
PyType_FromModuleAndSpec (C function), 113	PyUnicodeDecodeError_SetEnd (C function), 58
PyType_FromSpec (C function), 114	PyUnicodeDecodeError_SetReason (C function), 58
PyType_FromSpecWithBases (C function), 114	PyUnicodeDecodeError_SetStart (C function), 58
PyType_GenericAlloc (C function), 112	PyUnicodeObject (C type), 126
PyType_GenericNew (C function), 112	PyUnicodeTranslateError_GetEnd (C function), 58
PyType_GetFlags (C function), 112	PyUnicodeTranslateError_GetObject (C function), 58
PyType_GetModule (C function), 113	PyUnicodeTranslateError_GetReason (C function), 58
PyType_GetModuleByDef (C function), 113	PyUnicodeTranslateError_GetStart (C function), 58
PyType_GetModuleState (C function), 113	PyUnicodeTranslateError_SetEnd (C function), 58
PyType_GetName (C function), 112	PyUnicodeTranslateError_SetReason (C function), 58
PyType_GetQualName (C function), 112	PyUnicodeTranslateError_SetStart (C function), 58
PyType_GetSlot (C function), 112	PyUnicode_1BYTE_DATA (C function), 127
PyType_HasFeature (C function), 112	PyUnicode_1BYTE_KIND (C macro), 127
PyType_IS_GC (C function), 112	PyUnicode_2BYTE_DATA (C function), 127
PyType_IsSubtype (C function), 112	PyUnicode_2BYTE_KIND (C macro), 127
PyType_Modified (C function), 112	PyUnicode_4BYTE_DATA (C function), 127
PyType_Ready (C function), 112	PyUnicode_4BYTE_KIND (C macro), 127
PyType_Slot (C type), 114	PyUnicode_AS_DATA (C function), 128
PyType_Slot.PyType_Slot.pfunc (C member), 115	PyUnicode_AS_UNICODE (C function), 128
PyType_Slot.PyType_Slot.slot (C member), 114	PyUnicode_AsASCIIString (C function), 140
PyType_Spec (C type), 114	PyUnicode_AsCharmapString (C function), 140
PyType_Spec.PyType_Spec.basicsize (C member), 114	PyUnicode_AsEncodedString (C function), 137
PyType_Spec.PyType_Spec.flags (C member), 114	PyUnicode_AsLatin1String (C function), 140
PyType_Spec.PyType_Spec.itemsize (C member), 114	PyUnicode_AsMBCSString (C function), 141
PyType_Spec.PyType_Spec.name (C member), 114	PyUnicode_AsRawUnicodeEscapeString (C function), 139
PyType_Spec.PyType_Spec.slots (C member), 114	PyUnicode_AsUCS4 (C function), 132
PyType_Type (C var), 111	PyUnicode_AsUCS4Copy (C function), 132
PyUnicodeDecodeError_Create (C function), 58	PyUnicode_AsUTF8 (C function), 137
PyUnicodeDecodeError_GetEncoding (C function), 58	PyUnicode_AsUTF8AndSize (C function), 137
PyUnicodeDecodeError_GetEnd (C function), 58	PyUnicode_AsUTF8String (C function), 137
PyUnicodeDecodeError_GetObject (C function), 58	PyUnicode_AsUTF16String (C function), 139
PyUnicodeDecodeError_GetReason (C function), 58	PyUnicode_AsUTF32String (C function), 138
PyUnicodeDecodeError_GetStart (C function), 58	PyUnicode_AsUnicode (C function), 133
PyUnicodeDecodeError_SetEnd (C function), 58	PyUnicode_AsUnicodeAndSize (C function), 133
PyUnicodeDecodeError_SetReason (C function), 58	

- PyUnicode\_AsUnicodeEscapeString (C function), 139
- PyUnicode\_AsWideChar (C function), 136
- PyUnicode\_AsWideCharString (C function), 136
- PyUnicode\_Check (C function), 126
- PyUnicode\_CheckExact (C function), 126
- PyUnicode\_Compare (C function), 142
- PyUnicode\_CompareWithASCIIString (C function), 142
- PyUnicode\_Concat (C function), 141
- PyUnicode\_Contains (C function), 143
- PyUnicode\_CopyCharacters (C function), 132
- PyUnicode\_Count (C function), 142
- PyUnicode\_DATA (C function), 127
- PyUnicode\_Decode (C function), 137
- PyUnicode\_DecodeASCII (C function), 140
- PyUnicode\_DecodeCharmap (C function), 140
- PyUnicode\_DecodeFSDefault (C function), 135
- PyUnicode\_DecodeFSDefaultAndSize (C function), 135
- PyUnicode\_DecodeLatin1 (C function), 140
- PyUnicode\_DecodeLocale (C function), 134
- PyUnicode\_DecodeLocaleAndSize (C function), 134
- PyUnicode\_DecodeMBCS (C function), 141
- PyUnicode\_DecodeMBCSStateful (C function), 141
- PyUnicode\_DecodeRawUnicodeEscape (C function), 139
- PyUnicode\_DecodeUTF7 (C function), 139
- PyUnicode\_DecodeUTF7Stateful (C function), 139
- PyUnicode\_DecodeUTF8 (C function), 137
- PyUnicode\_DecodeUTF8Stateful (C function), 137
- PyUnicode\_DecodeUTF16 (C function), 138
- PyUnicode\_DecodeUTF16Stateful (C function), 139
- PyUnicode\_DecodeUTF32 (C function), 138
- PyUnicode\_DecodeUTF32Stateful (C function), 138
- PyUnicode\_DecodeUnicodeEscape (C function), 139
- PyUnicode\_EncodeCodePage (C function), 141
- PyUnicode\_EncodeFSDefault (C function), 135
- PyUnicode\_EncodeLocale (C function), 134
- PyUnicode\_FSConverter (C function), 134
- PyUnicode\_FSDecoder (C function), 135
- PyUnicode\_Fill (C function), 132
- PyUnicode\_Find (C function), 142
- PyUnicode\_FindChar (C function), 142
- PyUnicode\_Format (C function), 143
- PyUnicode\_FromEncodedObject (C function), 131
- PyUnicode\_FromFormat (C function), 130
- PyUnicode\_FromFormatV (C function), 131
- PyUnicode\_FromKindAndData (C function), 130
- PyUnicode\_FromObject (C function), 131
- PyUnicode\_FromString (C function), 130
- PyUnicode\_FromStringAndSize (C function), 130
- PyUnicode\_FromUnicode (C function), 133
- PyUnicode\_FromWideChar (C function), 136
- PyUnicode\_GET\_DATA\_SIZE (C function), 128
- PyUnicode\_GET\_LENGTH (C function), 127
- PyUnicode\_GET\_SIZE (C function), 128
- PyUnicode\_GetLength (C function), 132
- PyUnicode\_GetSize (C function), 133
- PyUnicode\_InternFromString (C function), 143
- PyUnicode\_InternInPlace (C function), 143
- PyUnicode\_IsIdentifier (C function), 128
- PyUnicode\_Join (C function), 142
- PyUnicode\_KIND (C function), 127
- PyUnicode\_MAX\_CHAR\_VALUE (C function), 127
- PyUnicode\_New (C function), 130
- PyUnicode\_READ (C function), 127
- PyUnicode\_READY (C function), 126
- PyUnicode\_READ\_CHAR (C function), 127
- PyUnicode\_ReadChar (C function), 132
- PyUnicode\_Replace (C function), 142
- PyUnicode\_RichCompare (C function), 142
- PyUnicode\_Split (C function), 141
- PyUnicode\_Splitlines (C function), 142
- PyUnicode\_Substring (C function), 132
- PyUnicode\_Tailmatch (C function), 142
- PyUnicode\_Translate (C function), 140
- PyUnicode\_Type (C var), 126
- PyUnicode\_WCHAR\_KIND (C macro), 127
- PyUnicode\_WRITE (C function), 127
- PyUnicode\_WriteChar (C function), 132
- PyVarObject (C type), 234
- PyVarObject\_HEAD\_INIT (C macro), 236
- PyVarObject.ob\_size (C member), 248
- PyVectorcall\_Call (C function), 93
- PyVectorcall\_Function (C function), 93
- PyVectorcall\_NARGS (C function), 93
- PyWeakref\_Check (C function), 168
- PyWeakref\_CheckProxy (C function), 168
- PyWeakref\_CheckRef (C function), 168
- PyWeakref\_GET\_OBJECT (C function), 168
- PyWeakref\_GetObject (C function), 168
- PyWeakref\_NewProxy (C function), 168
- PyWeakref\_NewRef (C function), 168
- PyWideStringList (C type), 202
- PyWideStringList\_Append (C function), 202
- PyWideStringList\_Insert (C function), 202
- PyWideStringList.items (C member), 202
- PyWideStringList.length (C member), 202
- PyWrapper\_New (C function), 165
- Py\_ABS (C macro), 4
- Py\_ALWAYS\_INLINE (C macro), 4
- Py\_AddPendingCall (C function), 195
- Py\_AtExit (C function), 68
- Py\_AuditHookFunction (C type), 68

- Py\_BEGIN\_ALLOW\_THREADS (*C macro*), 187, 190
- Py\_BLOCK\_THREADS (*C macro*), 190
- Py\_BuildValue (*C function*), 79
- Py\_BytesMain (*C function*), 41
- Py\_BytesWarningFlag (*C var*), 180
- Py\_CHARMASK (*C macro*), 5
- Py\_CLEAR (*C function*), 48
- Py\_CompileString (*C function*), 43, 44
- Py\_CompileStringExFlags (*C function*), 44
- Py\_CompileStringFlags (*C function*), 43
- Py\_CompileStringObject (*C function*), 43
- Py\_DEBUG (*C macro*), 13
- Py\_DECREF (*C function*), 7, 48
- Py\_DEPRECATED (*C macro*), 5
- Py\_DebugFlag (*C var*), 180
- Py\_DecRef (*C function*), 48
- Py\_DecodeLocale (*C function*), 64
- Py\_DontWriteBytecodeFlag (*C var*), 180
- Py\_END\_ALLOW\_THREADS (*C macro*), 187, 190
- Py\_EQ (*C macro*), 259
- Py\_Ellipsis (*C var*), 167
- Py\_EncodeLocale (*C function*), 65
- Py\_EndInterpreter (*C function*), 195
- Py\_EnterRecursiveCall (*C function*), 59
- Py\_Exit (*C function*), 68
- Py\_ExitStatusException (*C function*), 203
- Py\_False (*C var*), 118
- Py\_FatalError (*C function*), 68
- Py\_FatalError(), 185
- Py\_FdIsInteractive (*C function*), 63
- Py\_Finalize (*C function*), 182
- Py\_FinalizeEx (*C function*), 68, 182, 194, 195
- Py\_FrozenFlag (*C var*), 180
- Py\_GE (*C macro*), 259
- Py\_GETENV (*C macro*), 5
- Py\_GT (*C macro*), 259
- Py\_GenericAlias (*C function*), 177
- Py\_GenericAliasType (*C var*), 178
- Py\_GetArgcArgv (*C function*), 220
- Py\_GetBuildInfo (*C function*), 185
- Py\_GetCompiler (*C function*), 185
- Py\_GetCopyright (*C function*), 185
- Py\_GetExecPrefix (*C function*), 12, 183
- Py\_GetPath (*C function*), 12, 184
- Py\_GetPath(), 183, 184
- Py\_GetPlatform (*C function*), 185
- Py\_GetPrefix (*C function*), 12, 183
- Py\_GetProgramFullPath (*C function*), 12, 184
- Py\_GetProgramName (*C function*), 183
- Py\_GetPythonHome (*C function*), 186
- Py\_GetVersion (*C function*), 185
- Py\_HashRandomizationFlag (*C var*), 180
- Py\_INCREF (*C function*), 7, 47
- Py\_IS\_TYPE (*C function*), 235
- Py\_IgnoreEnvironmentFlag (*C var*), 180
- Py\_IncRef (*C function*), 48
- Py\_Initialize (*C function*), 12, 182, 194
- Py\_Initialize(), 183
- Py\_InitializeEx (*C function*), 182
- Py\_InitializeFromConfig (*C function*), 217
- Py\_InspectFlag (*C var*), 181
- Py\_InteractiveFlag (*C var*), 181
- Py\_Is (*C function*), 234
- Py\_IsFalse (*C function*), 235
- Py\_IsInitialized (*C function*), 12, 182
- Py\_IsNone (*C function*), 235
- Py\_IsTrue (*C function*), 235
- Py\_IsolatedFlag (*C var*), 181
- Py\_LE (*C macro*), 259
- Py\_LIMITED\_API (*C macro*), 15
- Py\_LT (*C macro*), 259
- Py\_LeaveRecursiveCall (*C function*), 59
- Py\_LegacyWindowsFSEncodingFlag (*C var*), 181
- Py\_LegacyWindowsStdioFlag (*C var*), 181
- Py\_MAX (*C macro*), 5
- Py\_MEMBER\_SIZE (*C macro*), 5
- Py\_MIN (*C macro*), 5
- Py\_Main (*C function*), 41
- Py\_NE (*C macro*), 259
- Py\_NO\_INLINE (*C macro*), 5
- Py\_NewInterpreter (*C function*), 194
- Py\_NewRef (*C function*), 47
- Py\_NoSiteFlag (*C var*), 181
- Py\_NoUserSiteDirectory (*C var*), 181
- Py\_None (*C var*), 115
- Py\_NotImplemented (*C var*), 87
- Py\_OpenCodeHookFunction (*C type*), 156
- Py\_OptimizeFlag (*C var*), 181
- Py\_PRINT\_RAW (*C macro*), 87, 157
- Py\_PreInitialize (*C function*), 206
- Py\_PreInitializeFromArgs (*C function*), 206
- Py\_PreInitializeFromBytesArgs (*C function*), 206
- Py\_QuietFlag (*C var*), 181
- Py\_REFCNT (*C function*), 235
- Py\_RETURN\_FALSE (*C macro*), 119
- Py\_RETURN\_NONE (*C macro*), 115
- Py\_RETURN\_NOTIMPLEMENTED (*C macro*), 87
- Py\_RETURN\_RICHCOMPARE (*C macro*), 259
- Py\_RETURN\_TRUE (*C macro*), 119
- Py\_ReprEnter (*C function*), 59
- Py\_ReprLeave (*C function*), 59
- Py\_RunMain (*C function*), 220
- Py\_SET\_REFCNT (*C function*), 235
- Py\_SET\_SIZE (*C function*), 235
- Py\_SET\_TYPE (*C function*), 235
- Py\_SIZE (*C function*), 235
- Py\_STRINGIFY (*C macro*), 5
- Py\_SetPath (*C function*), 184
- Py\_SetPath(), 184
- Py\_SetProgramName (*C function*), 12, 183
- Py\_SetProgramName(), 182, 184
- Py\_SetPythonHome (*C function*), 186
- Py\_SetStandardStreamEncoding (*C function*), 183

- Py\_TPFLAGS\_BASETYPE (*C macro*), 253
- Py\_TPFLAGS\_BASE\_EXC\_SUBCLASS (*C macro*), 255
- Py\_TPFLAGS\_BYTES\_SUBCLASS (*C macro*), 254
- Py\_TPFLAGS\_DEFAULT (*C macro*), 254
- Py\_TPFLAGS\_DICT\_SUBCLASS (*C macro*), 255
- Py\_TPFLAGS\_DISALLOW\_INSTANTIATION (*C macro*), 255
- Py\_TPFLAGS\_HAVE\_FINALIZE (*C macro*), 255
- Py\_TPFLAGS\_HAVE\_GC (*C macro*), 254
- Py\_TPFLAGS\_HAVE\_VECTORCALL (*C macro*), 255
- Py\_TPFLAGS\_HEAPTYPE (*C macro*), 253
- Py\_TPFLAGS\_IMMUTABLETYPE (*C macro*), 255
- Py\_TPFLAGS\_LIST\_SUBCLASS (*C macro*), 254
- Py\_TPFLAGS\_LONG\_SUBCLASS (*C macro*), 254
- Py\_TPFLAGS\_MAPPING (*C macro*), 255
- Py\_TPFLAGS\_METHOD\_DESCRIPTOR (*C macro*), 254
- Py\_TPFLAGS\_READY (*C macro*), 254
- Py\_TPFLAGS\_READYING (*C macro*), 254
- Py\_TPFLAGS\_SEQUENCE (*C macro*), 256
- Py\_TPFLAGS\_TUPLE\_SUBCLASS (*C macro*), 254
- Py\_TPFLAGS\_TYPE\_SUBCLASS (*C macro*), 255
- Py\_TPFLAGS\_UNICODE\_SUBCLASS (*C macro*), 254
- Py\_TYPE (*C function*), 235
- Py\_True (*C var*), 119
- Py\_UCS1 (*C type*), 126
- Py\_UCS2 (*C type*), 126
- Py\_UCS4 (*C type*), 126
- Py\_UNBLOCK\_THREADS (*C macro*), 191
- Py\_UNICODE (*C type*), 126
- Py\_UNICODE\_ISALNUM (*C function*), 129
- Py\_UNICODE\_ISALPHA (*C function*), 129
- Py\_UNICODE\_ISDECIMAL (*C function*), 128
- Py\_UNICODE\_ISDIGIT (*C function*), 129
- Py\_UNICODE\_ISLINEBREAK (*C function*), 128
- Py\_UNICODE\_ISLOWER (*C function*), 128
- Py\_UNICODE\_ISNUMERIC (*C function*), 129
- Py\_UNICODE\_ISPRINTABLE (*C function*), 129
- Py\_UNICODE\_ISSPACE (*C function*), 128
- Py\_UNICODE\_ISTITLE (*C function*), 128
- Py\_UNICODE\_ISUPPER (*C function*), 128
- Py\_UNICODE\_IS\_HIGH\_SURROGATE (*C macro*), 129
- Py\_UNICODE\_IS\_LOW\_SURROGATE (*C macro*), 129
- Py\_UNICODE\_IS\_SURROGATE (*C macro*), 129
- Py\_UNICODE\_JOIN\_SURROGATES (*C macro*), 129
- Py\_UNICODE\_TODECIMAL (*C function*), 129
- Py\_UNICODE\_TODIGIT (*C function*), 129
- Py\_UNICODE\_TOLOWER (*C function*), 129
- Py\_UNICODE\_TONUMERIC (*C function*), 129
- Py\_UNICODE\_TOTITLE (*C function*), 129
- Py\_UNICODE\_TOUPPER (*C function*), 129
- Py\_UNREACHABLE (*C macro*), 5
- Py\_UNUSED (*C macro*), 6
- Py\_UnbufferedStdioFlag (*C var*), 181
- Py\_VISIT (*C function*), 277
- Py\_VaBuildValue (*C function*), 81
- Py\_VerboseFlag (*C var*), 181
- Py\_Version (*C var*), 279
- Py\_XDECREF (*C function*), 12, 48
- Py\_XINCREf (*C function*), 47
- Py\_XNewRef (*C function*), 47
- Py\_buffer (*C type*), 104
- Py\_buffer.buf (*C member*), 104
- Py\_buffer.format (*C member*), 105
- Py\_buffer.internal (*C member*), 105
- Py\_buffer.itemsize (*C member*), 104
- Py\_buffer.len (*C member*), 104
- Py\_buffer.ndim (*C member*), 105
- Py\_buffer.obj (*C member*), 104
- Py\_buffer.readonly (*C member*), 104
- Py\_buffer.shape (*C member*), 105
- Py\_buffer.strides (*C member*), 105
- Py\_buffer.suboffsets (*C member*), 105
- Py\_complex (*C type*), 121
- Py\_eval\_input (*C var*), 44
- Py\_file\_input (*C var*), 44
- Py\_hash\_t (*C type*), 83
- Py\_mod\_create (*C macro*), 161
- Py\_mod\_exec (*C macro*), 161
- Py\_single\_input (*C var*), 44
- Py\_ssize\_t (*C type*), 10
- Py\_tracefunc (*C type*), 196
- Py\_tss\_NEEDS\_INIT (*C macro*), 198
- Py\_tss\_t (*C type*), 198
- Py\_uhash\_t (*C type*), 83
- Python 3000, 294
- Python Enhancement Proposals
  - PEP 1, 294
  - PEP 7, 3, 6
  - PEP 238, 45, 287
  - PEP 278, 297
  - PEP 302, 286, 290
  - PEP 343, 284
  - PEP 353, 10
  - PEP 362, 282, 293
  - PEP 383, 134
  - PEP 387, 15
  - PEP 393, 125, 133
  - PEP 411, 294
  - PEP 420, 286, 292, 294
  - PEP 432, 221
  - PEP 442, 265
  - PEP 443, 288
  - PEP 451, 161, 286
  - PEP 456, 83
  - PEP 483, 288
  - PEP 484, 282, 287, 288, 297
  - PEP 489, 161
  - PEP 492, 282284
  - PEP 498, 286
  - PEP 519, 293
  - PEP 523, 193

- PEP 525, 282
- PEP 526, 282, 297
- PEP 528, 181, 212
- PEP 529, 134, 181
- PEP 538, 219
- PEP 539, 198
- PEP 540, 219
- PEP 552, 209
- PEP 578, 67
- PEP 585, 288
- PEP 587, 201
- PEP 590, 92
- PEP 623, 126
- PEP 634, 256
- PEP 3116, 297
- PEP 3119, 90
- PEP 3121, 159
- PEP 3147, 70
- PEP 3151, 61
- PEP 3155, 294
- Pythonic, 294
- SIGINT (*C macro*), 56
- SIZE\_MAX (*C macro*), 117
- SystemError (*built-in exception*), 158
- ULONG\_MAX (*C macro*), 117
- USE\_STACKCHECK (*C macro*), 64
- Zen της Python, 297
- \_PyBytes\_Resize (*C function*), 124
- \_PyCFunctionFast (*C type*), 236
- \_PyCFunctionFastWithKeywords (*C type*), 236
- \_PyFrameEvalFunction (*C type*), 192
- \_PyInterpreterState\_GetEvalFrameFunc (*C function*), 192
- \_PyInterpreterState\_SetEvalFrameFunc (*C function*), 193
- \_PyObject\_GetDictPtr (*C function*), 89
- \_PyObject\_New (*C function*), 233
- \_PyObject\_NewVar (*C function*), 233
- \_PyTuple\_Resize (*C function*), 144
- \_Py\_InitializeMain (*C function*), 221
- \_Py\_NoneStruct (*C var*), 234
- \_Py\_c\_diff (*C function*), 121
- \_Py\_c\_neg (*C function*), 121
- \_Py\_c\_pow (*C function*), 121
- \_Py\_c\_prod (*C function*), 121
- \_Py\_c\_quot (*C function*), 121
- \_Py\_c\_sum (*C function*), 121
- \_\_PYENV\_LAUNCHER\_\_, 208, 214
- \_\_all\_\_ (*package variable*), 68
- \_\_dict\_\_ (*module attribute*), 157
- \_\_doc\_\_ (*module attribute*), 157
- \_\_file\_\_ (*module attribute*), 157, 158
- \_\_future\_\_, 287
- \_\_import\_\_
  - built-in function, 68
- \_\_loader\_\_ (*module attribute*), 157
- \_\_main\_\_
  - module, 12, 182, 194
- \_\_name\_\_ (*module attribute*), 157, 158
- \_\_package\_\_ (*module attribute*), 157
- \_\_slots\_\_, 295
- \_frozen (*C struct*), 71
- \_inittab (*C struct*), 71
- \_inittab.initfunc (*C member*), 71
- \_inittab.name (*C member*), 71
- \_thread
  - module, 189
- abort (*C function*), 68
- abs
  - built-in function, 97
- allocafunc (*C type*), 271
- annotation, 281
- annotation μεταβλητής, 297
- argv (*in module sys*), 185
- ascii
  - built-in function, 89
- awaitable, 283
- binaryfunc (*C type*), 273
- buffer interface
  - (see buffer protocol), 103
- buffer object
  - (see buffer protocol), 103
- buffer protocol, 103
- built-in function
  - \_\_import\_\_, 68
  - abs, 97
  - ascii, 89
  - bytes, 90
  - classmethod, 238
  - compile, 69
  - divmod, 97
  - float, 99
  - hash, 90, 251
  - int, 99
  - len, 91, 99, 101, 146, 149, 151
  - pow, 97, 98
  - repr, 89, 251
  - staticmethod, 238
  - tuple, 101, 147
  - type, 90
- builtins
  - module, 12, 182, 194
- bytearray
  - object, 124
- bytecode, 283
- bytes
  - built-in function, 90
  - object, 122
- bytes-like αντικείμενα, 283
- callable, 283
- callback, 284
- calloc (*C function*), 223
- classmethod
  - built-in function, 238
- cleanup functions, 68
- close (*in module os*), 195



- code object, 154
- compile
  - built-in function, 69
- complex number
  - object, 121
- context μεταβλητή, 284
- contiguous, 106, 284
- copyright (*in module sys*), 185
- coroutine, 284
- coroutine συνάρτηση, 284
- decorator, 285
- descrgetfunc (*C type*), 272
- descriptor, 285
- descrsetfunc (*C type*), 272
- destructor (*C type*), 272
- dictionary
  - object, 147
- divmod
  - built-in function, 97
- docstring, 285
- duck-typing, 285
- exc\_info (*in module sys*), 10
- executable (*in module sys*), 184
- exit (*C function*), 68
- f-string, 286
- file
  - object, 156
- finder, 286
- float
  - built-in function, 99
- floating point
  - object, 119
- free (*C function*), 223
- freefunc (*C type*), 272
- freeze utility, 71
- frozenset
  - object, 150
- function
  - object, 152
- generator, 287
- generator iterator, 287
- generator έκφραση, 287
- getattrfunc (*C type*), 272
- getattrofunc (*C type*), 272
- getbufferproc (*C type*), 272
- getiterfunc (*C type*), 272
- global interpreter lock, 187, 288
- hash
  - built-in function, 90, 251
- hash-based pyc, 288
- hashable, 288
- hashfunc (*C type*), 272
- immutable, 288
- incr\_item(), 11, 12
- initproc (*C type*), 272
- inquiry (*C type*), 277
- instancemethod
  - object, 153
- int
  - built-in function, 99
- integer
  - object, 115
- interpreted, 289
- interpreter lock, 187
- iterable, 289
- iterator, 289
- iternextfunc (*C type*), 272
- lambda, 290
- len
  - built-in function, 91, 99, 101, 146, 149, 151
- lenfunc (*C type*), 272
- list
  - object, 146
- list comprehension, 290
- loader, 290
- lock, interpreter, 187
- long integer
  - object, 115
- magic
  - μέθοδος, 291
- main(), 183, 185
- malloc (*C function*), 223
- mapping, 291
  - object, 147
- memoryview
  - object, 167
- meta path finder, 291
- method
  - object, 153
- module, 291
  - \_\_main\_\_, 12, 182, 194
  - \_thread, 189
  - builtins, 12, 182, 194
  - object, 157
  - search path, 12, 182, 184
  - signal, 56
  - sys, 12, 182, 194
- module επέκτασης, 286
- modules (*in module sys*), 68, 182
- mutable, 291
- named tuple, 292
- namespace, 292
- nested scope, 292
- newfunc (*C type*), 272
- numeric
  - object, 115
- object
  - Capsule, 169
  - None, 115
  - bytearray, 124
  - bytes, 122
  - code, 154
  - complex number, 121
  - dictionary, 147
  - file, 156

- floating point, 119
- frozenset, 150
- function, 152
- instancemethod, 153
- integer, 115
- list, 146
- long integer, 115
- mapping, 147
- memoryview, 167
- method, 153
- module, 157
- numeric, 115
- sequence, 122
- set, 150
- tuple, 143
- type, 7, 111
- objobjargproc (*C type*), 273
- objobjproc (*C type*), 273
- package variable
  - \_\_all\_\_, 68
- path
  - module search, 12, 182, 184
- path (*in module sys*), 12, 182, 184
- path based finder, 293
- path entry, 293
- path entry finder, 293
- path entry hook, 293
- path-like αντικείμενο, 293
- platform (*in module sys*), 185
- pow
  - built-in function, 97, 98
- provisional API, 294
- provisional πακέτο, 294
- realloc (*C function*), 223
- releasebufferproc (*C type*), 272
- repr
  - built-in function, 89, 251
- reprfunc (*C type*), 272
- richcmpfunc (*C type*), 272
- stderr
  - stdin stdout, 183
- search
  - path, module, 12, 182, 184
- sendfunc (*C type*), 273
- sequence
  - object, 122
- set
  - object, 150
- set comprehension, 295
- set\_all(), 9
- setattrfunc (*C type*), 272
- setattrofunc (*C type*), 272
- setswitchinterval (*in module sys*), 187
- signal
  - module, 56
- slice, 295
- special
  - μέθοδος, 296

- ssizeargfunc (*C type*), 273
- ssizeobjargproc (*C type*), 273
- staticmethod
  - built-in function, 238
- stderr (*in module sys*), 194
- stdin
  - stdout stderr, 183
- stdin (*in module sys*), 194
- stdout
  - stderr, stdin, 183
- stdout (*in module sys*), 194
- strerror (*C function*), 51
- string
  - PyObject\_Str (*C function*), 89
- strong reference, 296
- sum\_list(), 9
- sum\_sequence(), 10, 11
- sys
  - module, 12, 182, 194
- ternaryfunc (*C type*), 273
- traverseproc (*C type*), 277
- tuple
  - built-in function, 101, 147
  - object, 143
- type
  - built-in function, 90
  - object, 7, 111
- type alias, 296
- type hint, 297
- unaryfunc (*C type*), 272
- vectorcallfunc (*C type*), 92
- version (*in module sys*), 185
- virtual environment, 297
- virtual machine, 297
- visitproc (*C type*), 277

## A

- ακέραια διαίρεση, 286
- ακολουθία, 295
- αναγνωρισμένο όνομα, 294
- αντικείμενο, 292
- αντικείμενο αρχείου, 286
- αντικείμενο που μοιάζει με αρχείο, 286
- αρχείο κειμένου, 296
- ασύγχρονος generator, 282
- ασύγχρονος generator iterator, 282
- ασύγχρονος iterable, 282
- ασύγχρονος iterator, 282
- ασύγχρονος διαχειριστής context, 282
- αφηρημένη βασική κλάση, 281

## Γ

- γενική συνάρτηση, 288
- γενικός τύπος, 288

## Δ

- δανεική αναφορά, 283
- δήλωση, 296

διαδραστικός, [289](#)

διαχειριστής context, [284](#)

δυναμικό αρχείο, [283](#)

## E

ειδική μέθοδος, [296](#)

εισαγόμενο path, [289](#)

εισαγωγή, [289](#)

έκφραση, [286](#)

ελεγκτής στατικού τύπου, [296](#)

## K

καθολικές νέες γραμμές, [297](#)

κανονικό πακέτο, [295](#)

κατανόηση λεξικού, [285](#)

κλάση, [284](#)

κλάση νέου στυλ, [292](#)

κωδικοποίηση κειμένου, [296](#)

κωδικοποίηση συστήματος αρχείων και  
χειριστής σφαλμάτων, [286](#)

## Λ

λεξικό, [285](#)

λίστα, [290](#)

## M

μαγική μέθοδος, [291](#)

μέθοδος, [291](#)

magic, [291](#)

special, [296](#)

μετα-κλάση, [291](#)

μεταβλητή κλάσης, [284](#)

μεταβλητή περιβάλλοντος

PATH, [12](#)

PYTHONCOERCECLOCALE, [219](#)

PYTHONDEBUG, [180](#), [213](#)

PYTHONDEVMODE, [210](#)

PYTHONDONTWRITEBYTECODE, [180](#), [216](#)

PYTHONDUMPREFS, [210](#), [248](#)

PYTHONEXECUTABLE, [214](#)

PYTHONFAULTHANDLER, [210](#)

PYTHONHASHSEED, [180](#), [211](#)

PYTHONHOME, [12](#), [181](#), [186](#), [211](#)

PYTHONINSPECT, [181](#), [211](#)

PYTHONIOENCODING, [183](#), [215](#)

PYTHONLEGACYWINDOWSFSENCODING, [181](#),  
[205](#)

PYTHONLEGACYWINDOWSTDIO, [181](#), [212](#)

PYTHONMALLOC, [224](#), [227](#), [229](#), [231](#)

PYTHONMALLOCSTATS, [212](#), [224](#)

PYTHONNODEBUGRANGES, [209](#)

PYTHONNOUSERSITE, [181](#), [216](#)

PYTHONOPTIMIZE, [181](#), [213](#)

PYTHONPATH, [12](#), [181](#), [212](#)

PYTHONPLATLIBDIR, [212](#)

PYTHONPROFILEIMPORTTIME, [211](#)

PYTHONPYCACHEPREFIX, [214](#)

PYTHONSAFECPATH, [208](#)

PYTHONTRACEMALLOC, [215](#)

PYTHONUNBUFFERED, [181](#), [209](#)

PYTHONUTF8, [205](#), [219](#)

PYTHONVERBOSE, [182](#), [216](#)

PYTHONWARNINGS, [216](#)

\_\_PYENV\_\_LAUNCHER\_\_, [208](#), [214](#)

μιγαδικός αριθμός, [284](#)

μοναδικό dispatch, [295](#)

## O

όρισμα, [282](#)

όρισμα keyword, [290](#)

όρισμα θέσης, [294](#)

όψη λεξικού, [285](#)

## Π

πακέτο, [292](#)

πακέτο namespace, [292](#)

παράμετρος, [292](#)

πλήθος αναφοράς, [295](#)

## Σ

σειρά ανάλυσης μεθόδων, [291](#)

συλλογή απορριμάτων, [287](#)

συμβολοσειρά τριπλών εισαγωγικών, [296](#)

συνάρτηση, [287](#)

συνάρτηση annotation, [287](#)

συνάρτηση key, [290](#)

## T

τερματισμός λειτουργίας διερμηνέα, [289](#)

τεχνικές προδιαγραφές module, [291](#)

τμήμα, [294](#)

τοπική κωδικοποίηση, [291](#)

τύπος, [296](#)

## X

χαρακτηριστικό, [283](#)