
Python support for the Linux perf profiler

릴리스 3.14.0a2

Guido van Rossum and the Python development team

11월 23, 2024

Contents

1	How to enable <code>perf</code> profiling support	4
2	How to obtain the best results	4
3	How to work without frame pointers	5
	색인	6

author

Pablo Galindo

The `Linux perf profiler` is a very powerful tool that allows you to profile and obtain information about the performance of your application. `perf` also has a very vibrant ecosystem of tools that aid with the analysis of the data that it produces.

The main problem with using the `perf` profiler with Python applications is that `perf` only gets information about native symbols, that is, the names of functions and procedures written in C. This means that the names and file names of Python functions in your code will not appear in the output of `perf`.

Since Python 3.12, the interpreter can run in a special mode that allows Python functions to appear in the output of the `perf` profiler. When this mode is enabled, the interpreter will interpose a small piece of code compiled on the fly before the execution of every Python function and it will teach `perf` the relationship between this piece of code and the associated Python function using `perf map` files.

참고

Support for the `perf` profiler is currently only available for Linux on select architectures. Check the output of the `configure` build step or check the output of `python -m sysconfig | grep HAVE_PERF_TRAMPOLINE` to see if your system is supported.

For example, consider the following script:

```
def foo(n):
    result = 0
    for _ in range(n):
        result += 1
```

(다음 페이지에 계속)

If you don't see any output it means that your interpreter has not been compiled with frame pointers and therefore it may not be able to show Python functions in the output of `perf`.

3 How to work without frame pointers

If you are working with a Python interpreter that has been compiled without frame pointers, you can still use the `perf` profiler, but the overhead will be a bit higher because Python needs to generate unwinding information for every Python function call on the fly. Additionally, `perf` will take more time to process the data because it will need to use the DWARF debugging information to unwind the stack and this is a slow process.

To enable this mode, you can use the environment variable `PYTHON_PERF_JIT_SUPPORT` or the `-X perf_jit` option, which will enable the JIT mode for the `perf` profiler.

참고

Due to a bug in the `perf` tool, only `perf` versions higher than v6.8 will work with the JIT mode. The fix was also backported to the v6.7.2 version of the tool.

Note that when checking the version of the `perf` tool (which can be done by running `perf version`) you must take into account that some distros add some custom version numbers including a `-` character. This means that `perf 6.7-3` is not necessarily `perf 6.7.3`.

When using the `perf` JIT mode, you need an extra step before you can run `perf report`. You need to call the `perf inject` command to inject the JIT information into the `perf.data` file.:

```
$ perf record -F 9999 -g --call-graph dwarf -o perf.data python -Xperf_jit my_
→script.py
$ perf inject -i perf.data --jit --output perf.jit.data
$ perf report -g -i perf.jit.data
```

or using the environment variable:

```
$ PYTHON_PERF_JIT_SUPPORT=1 perf record -F 9999 -g --call-graph dwarf -o perf.data_
→python my_script.py
$ perf inject -i perf.data --jit --output perf.jit.data
$ perf report -g -i perf.jit.data
```

`perf inject --jit` command will read `perf.data`, automatically pick up the `perf` dump file that Python creates (in `/tmp/perf- $\$$ PID.dump`), and then create `perf.jit.data` which merges all the JIT information together. It should also create a lot of `jitted-XXXX-N.so` files in the current directory which are ELF images for all the JIT trampolines that were created by Python.

경고

Notice that when using `--call-graph dwarf` the `perf` tool will take snapshots of the stack of the process being profiled and save the information in the `perf.data` file. By default the size of the stack dump is 8192 bytes but the user can change the size by passing the size after comma like `--call-graph dwarf,4096`. The size of the stack dump is important because if the size is too small `perf` will not be able to unwind the stack and the output will be incomplete. On the other hand, if the size is too big, then `perf` won't be able to sample the process as frequently as it would like as the overhead will be higher.

색인

P

PYTHON_PERF_JIT_SUPPORT, 5
PYTHONPERFSUPPORT, 4

Y

환경 변수

PYTHON_PERF_JIT_SUPPORT, 5
PYTHONPERFSUPPORT, 4