

---

# **The Python/C API**

***Release 3.10.18***

**Guido van Rossum  
and the Python development team**

**julho 08, 2025**

**Python Software Foundation  
Email: [docs@python.org](mailto:docs@python.org)**



<b>1</b>	<b>Introdução</b>	<b>3</b>
1.1	Padrões de codificação	4
1.2	Arquivos de inclusão	4
1.3	Macros úteis	5
1.4	Objetos, tipos e contagens de referências	6
1.4.1	Contagens de referências	7
1.4.2	Tipos	10
1.5	Exceções	10
1.6	Incorporando Python	12
1.7	Compilações de depuração	13
<b>2</b>	<b>Estabilidade da API C</b>	<b>15</b>
2.1	Interface Binária de Aplicação Estável	15
2.1.1	Escopo e Desempenho da API Limitada	16
2.1.2	Limitações da API Limitada	16
2.2	Considerações da plataforma	17
2.3	Conteúdo da API Limitada	17
<b>3</b>	<b>A camada de nível muito alto</b>	<b>43</b>
<b>4</b>	<b>Contagem de Referências</b>	<b>49</b>
<b>5</b>	<b>Manipulando Exceções</b>	<b>51</b>
5.1	Impressão e limpeza	52
5.2	Lançando exceções	52
5.3	Emitindo advertências	55
5.4	Consultando o indicador de erro	56
5.5	Tratamento de sinal	57
5.6	Classes de exceção	58
5.7	Objeto Exceção	59
5.8	Objetos de exceção Unicode	59
5.9	Controle de recursão	61
5.10	Exceções Padrão	61
5.11	Categorias de aviso padrão	63
<b>6</b>	<b>Utilitários</b>	<b>65</b>
6.1	Utilitários do sistema operacional	65

6.2	System Functions . . . . .	68
6.3	Process Control . . . . .	70
6.4	Importando módulos . . . . .	70
6.5	Suporte a <i>marshalling</i> de dados . . . . .	74
6.6	Análise de argumentos e construção de valores . . . . .	75
6.6.1	Análise de argumentos . . . . .	75
6.6.2	Construindo valores . . . . .	81
6.7	Conversão e formação de strings . . . . .	83
6.8	Reflexão . . . . .	85
6.9	Registro de codec e funções de suporte . . . . .	86
6.9.1	API de pesquisa de codec . . . . .	86
6.9.2	API de registro de tratamentos de erros de decodificação Unicode . . . . .	87
<b>7</b>	<b>Camada de Objetos Abstratos</b>	<b>89</b>
7.1	Protocolo de objeto . . . . .	89
7.2	Protocolo de chamada . . . . .	93
7.2.1	O protocolo <i>tp_call</i> . . . . .	93
7.2.2	O protocolo <i>vectorcall</i> . . . . .	94
7.2.3	API de chamada de objetos . . . . .	95
7.2.4	API de suporte a chamadas . . . . .	98
7.3	Protocolo de número . . . . .	98
7.4	Protocolo de sequência . . . . .	101
7.5	Protocolo de mapeamento . . . . .	103
7.6	Protocolo Iterador . . . . .	104
7.7	Protocolo de Buffer . . . . .	105
7.7.1	Estrutura de Buffer . . . . .	106
7.7.2	Tipos de solicitação do buffer . . . . .	108
7.7.3	Vetores Complexos . . . . .	110
7.7.4	Funções relacionadas ao Buffer . . . . .	111
7.8	Protocolo de Buffer Antigo . . . . .	113
<b>8</b>	<b>Camada de Objetos Concretos</b>	<b>115</b>
8.1	Objetos Fundamentais . . . . .	115
8.1.1	Objetos tipo . . . . .	115
8.1.2	O Objeto <i>None</i> . . . . .	119
8.2	Objetos Numéricos . . . . .	119
8.2.1	Objetos Inteiros . . . . .	119
8.2.2	Objetos Booleanos . . . . .	122
8.2.3	Objetos de ponto flutuante . . . . .	123
8.2.4	Objetos números complexos . . . . .	124
8.3	Objetos Sequência . . . . .	125
8.3.1	Objetos bytes . . . . .	125
8.3.2	Objetos byte array . . . . .	127
8.3.3	Objetos Unicode e Codecs . . . . .	128
8.3.4	Objeto tupla . . . . .	148
8.3.5	Objetos sequência de estrutura . . . . .	149
8.3.6	Objeto List . . . . .	151
8.4	Coleções . . . . .	152
8.4.1	Objetos dicionários . . . . .	152
8.4.2	Objeto Set . . . . .	155
8.5	Objetos Function . . . . .	157
8.5.1	Objetos Function . . . . .	157
8.5.2	Objetos de Método de Instância . . . . .	158
8.5.3	Objetos método . . . . .	158

8.5.4	Objeto célula	159
8.5.5	Objetos código	160
8.6	Outros Objetos	160
8.6.1	Objetos arquivos	160
8.6.2	Objetos do Módulo	162
8.6.3	Objetos Iteradores	169
8.6.4	Objetos Descritores	170
8.6.5	Objetos Slice	170
8.6.6	Objeto Ellipsis	172
8.6.7	Objetos MemoryView	172
8.6.8	Objetos referência fraca	172
8.6.9	Capsules	173
8.6.10	Objetos Geradores	175
8.6.11	Objetos corrotina	176
8.6.12	Objetos de variáveis de contexto	176
8.6.13	Objetos DateTime	178
8.6.14	Objetos de indicação de tipos	181
<b>9</b>	<b>Inicialização, finalização e threads</b>	<b>183</b>
9.1	Antes da inicialização do Python	183
9.2	Variáveis de configuração global	184
9.3	Inicializando e encerrando o interpretador	186
9.4	Process-wide parameters	187
9.5	Estado de thread e trava global do interpretador	191
9.5.1	Releasing the GIL from extension code	191
9.5.2	Non-Python created threads	192
9.5.3	Cuidados com o uso de fork()	192
9.5.4	High-level API	193
9.5.5	Low-level API	195
9.6	Sub-interpreter support	198
9.6.1	Bugs and caveats	199
9.7	Notificações assíncronas	199
9.8	Profiling and Tracing	200
9.9	Advanced Debugger Support	201
9.10	Thread Local Storage Support	201
9.10.1	Thread Specific Storage (TSS) API	202
9.10.2	Thread Local Storage (TLS) API	203
<b>10</b>	<b>Configuração de Inicialização do Python</b>	<b>205</b>
10.1	Exemplo	205
10.2	PyWideStringList	206
10.3	PyStatus	207
10.4	PyPreConfig	208
10.5	Pré-inicializar Python com PyPreConfig	210
10.6	PyConfig	211
10.7	Initialization with PyConfig	220
10.8	Isolated Configuration	222
10.9	Configuração do Python	222
10.10	Python Path Configuration	222
10.11	Py_RunMain()	224
10.12	Py_GetArgcArgv()	224
10.13	Multi-Phase Initialization Private Provisional API	224
<b>11</b>	<b>Gerenciamento de Memória</b>	<b>227</b>

11.1	Visão Geral . . . . .	227
11.2	Allocator Domains . . . . .	228
11.3	Raw Memory Interface . . . . .	229
11.4	Interface da Memória . . . . .	229
11.5	Alocadores de objeto . . . . .	231
11.6	Alocadores de memória padrão . . . . .	232
11.7	Alocadores de memória . . . . .	232
11.8	Debug hooks on the Python memory allocators . . . . .	234
11.9	The pymalloc allocator . . . . .	235
11.9.1	Customize pymalloc Arena Allocator . . . . .	235
11.10	tracemalloc C API . . . . .	236
11.11	Exemplos . . . . .	236
<b>12</b>	<b>Suporte a implementação de Objetos</b>	<b>239</b>
12.1	Alocando objetos na heap . . . . .	239
12.2	Estruturas comuns de objetos . . . . .	240
12.2.1	Base object types and macros . . . . .	240
12.2.2	Implementing functions and methods . . . . .	242
12.2.3	Accessing attributes of extension types . . . . .	244
12.3	Objetos tipo . . . . .	246
12.3.1	Referências rápidas . . . . .	246
12.3.2	PyTypeObject Definition . . . . .	251
12.3.3	PyObject Slots . . . . .	252
12.3.4	PyVarObject Slots . . . . .	253
12.3.5	PyTypeObject Slots . . . . .	253
12.3.6	Static Types . . . . .	271
12.3.7	Tipos no heap . . . . .	272
12.4	Number Object Structures . . . . .	272
12.5	Mapping Object Structures . . . . .	274
12.6	Sequence Object Structures . . . . .	274
12.7	Buffer Object Structures . . . . .	275
12.8	Async Object Structures . . . . .	276
12.9	Slot Type typedefs . . . . .	277
12.10	Exemplos . . . . .	279
12.11	Suporte a Coleta Cíclica de Lixo . . . . .	281
12.11.1	Controlando o estado do coletor de lixo . . . . .	283
<b>13</b>	<b>API e Versionamento de ABI</b>	<b>285</b>
<b>A</b>	<b>Glossário</b>	<b>287</b>
<b>B</b>	<b>Sobre esses documentos</b>	<b>303</b>
B.1	Contribuidores da Documentação Python . . . . .	303
<b>C</b>	<b>História e Licença</b>	<b>305</b>
C.1	História do software . . . . .	305
C.2	Termos e condições para acessar ou usar Python . . . . .	306
C.2.1	ACORDO DE LICENCIAMENTO DA PSF PARA PYTHON 3.10.18 . . . . .	306
C.2.2	ACORDO DE LICENCIAMENTO DA BEOPEN.COM PARA PYTHON 2.0 . . . . .	307
C.2.3	CONTRATO DE LICENÇA DA CNRI PARA O PYTHON 1.6.1 . . . . .	308
C.2.4	ACORDO DE LICENÇA DA CWI PARA PYTHON 0.9.0 A 1.2 . . . . .	309
C.2.5	LICENÇA BSD DE ZERO CLÁUSULA PARA CÓDIGO NA DOCUMENTAÇÃO DO PYTHON 3.10.18 . . . . .	309
C.3	Licenças e Reconhecimentos para Software Incorporado . . . . .	310
C.3.1	Mersenne Twister . . . . .	310

C.3.2	Soquetes . . . . .	311
C.3.3	Serviços de soquete assíncrono . . . . .	311
C.3.4	Gerenciamento de cookies . . . . .	312
C.3.5	Rastreamento de execução . . . . .	312
C.3.6	Funções UUencode e UUdecode . . . . .	313
C.3.7	Chamadas de procedimento remoto XML . . . . .	313
C.3.8	test_epoll . . . . .	314
C.3.9	kqueue de seleção . . . . .	314
C.3.10	SipHash24 . . . . .	315
C.3.11	strtod e dtoa . . . . .	316
C.3.12	OpenSSL . . . . .	316
C.3.13	expat . . . . .	318
C.3.14	libffi . . . . .	319
C.3.15	zlib . . . . .	320
C.3.16	cfuhash . . . . .	320
C.3.17	libmpdec . . . . .	321
C.3.18	Conjunto de testes C14N do W3C . . . . .	321
C.3.19	Audioop . . . . .	322
<b>D</b>	<b>Direitos autorais</b>	<b>323</b>
	<b>Índice</b>	<b>325</b>





Este manual documenta a API usada por programadores C e C++ que desejam escrever módulos de extensões ou embutir Python. É um complemento para `extending-index`, que descreve os princípios gerais da escrita de extensões mas não documenta as funções da API em detalhes.



# CAPÍTULO 1

---

## Introdução

---

A Interface de Programação de Aplicações (API) para Python fornece aos programadores C e C++ acesso ao interpretador Python em uma variedade de níveis. A API pode ser usada igualmente em C++, mas, para abreviar, geralmente é chamada de API Python/C. Existem dois motivos fundamentalmente diferentes para usar a API Python/C. A primeira razão é escrever *módulos de extensão* para propósitos específicos; esses são módulos C que estendem o interpretador Python. Este é provavelmente o uso mais comum. O segundo motivo é usar Python como um componente em uma aplicação maior; esta técnica é geralmente referida como *incorporação* Python em uma aplicação.

Escrever um módulo de extensão é um processo relativamente bem compreendido, no qual uma abordagem de “livro de receitas” funciona bem. Existem várias ferramentas que automatizam o processo até certo ponto. Embora as pessoas tenham incorporado o Python em outras aplicações desde sua existência inicial, o processo de incorporação do Python é menos direto do que escrever uma extensão.

Muitas funções da API são úteis independentemente de você estar incorporando ou estendendo o Python; além disso, a maioria das aplicações que incorporam Python também precisará fornecer uma extensão customizada, portanto, é provavelmente uma boa ideia se familiarizar com a escrita de uma extensão antes de tentar incorporar Python em uma aplicação real.

## 1.1 Padrões de codificação

Se você estiver escrevendo código C para inclusão no CPython, **deve** seguir as diretrizes e padrões definidos na [PEP 7](#). Essas diretrizes se aplicam independentemente da versão do Python com a qual você está contribuindo. Seguir essas convenções não é necessário para seus próprios módulos de extensão de terceiros, a menos que você eventualmente espere contribuí-los para o Python.

## 1.2 Arquivos de inclusão

Todas as definições de função, tipo e macro necessárias para usar a API Python/C estão incluídas em seu código pela seguinte linha:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

Isso implica a inclusão dos seguintes cabeçalhos padrão: `<stdio.h>`, `<string.h>`, `<errno.h>`, `<limits.h>`, `<assert.h>` e `<stdlib.h>` (se disponível).

---

**Nota:** Uma vez que Python pode definir algumas definições de pré-processador que afetam os cabeçalhos padrão em alguns sistemas, você *deve* incluir `Python.h` antes de quaisquer cabeçalhos padrão serem incluídos.

É recomendável sempre definir `PY_SSIZE_T_CLEAN` antes de incluir `Python.h`. Veja [Análise de argumentos e construção de valores](#) para uma descrição desta macro.

---

Todos os nomes visíveis ao usuário definidos por `Python.h` (exceto aqueles definidos pelos cabeçalhos padrão incluídos) têm um dos prefixos `Py` ou `_Py`. Nomes começando com `_Py` são para uso interno pela implementação Python e não devem ser usados por escritores de extensão. Os nomes dos membros da estrutura não têm um prefixo reservado.

---

**Nota:** O código do usuário nunca deve definir nomes que começam com `Py` ou `_Py`. Isso confunde o leitor e coloca em risco a portabilidade do código do usuário para versões futuras do Python, que podem definir nomes adicionais começando com um desses prefixos.

---

Os arquivos de cabeçalho são normalmente instalados com Python. No Unix, eles estão localizados nos diretórios `prefix/include/pythonversion/` e `exec_prefix/include/pythonversion/`, onde `prefix` e `exec_prefix` são definidos pelos parâmetros correspondentes ao script **configure** e `version` do Python é `'%d.%d' % sys.version_info[:2]`. No Windows, os cabeçalhos são instalados em `prefix/include`, onde `prefix` é o diretório de instalação especificado para o instalador.

Para incluir os cabeçalhos, coloque os dois diretórios (se diferentes) no caminho de pesquisa do compilador para as inclusões. *Não* coloque os diretórios pais no caminho de busca e então use `#include <pythonX.Y/Python.h>`; isto irá quebrar em compilações multiplataforma, uma vez que os cabeçalhos independentes da plataforma em `prefix` incluem os cabeçalhos específicos da plataforma de `exec_prefix`.

Os usuários de C++ devem notar que embora a API seja definida inteiramente usando C, os arquivos de cabeçalho declaram apropriadamente os pontos de entrada como `extern "C"`. Como resultado, não há necessidade de fazer nada especial para usar a API do C++.

## 1.3 Macros úteis

Diversas macros úteis são definidas nos arquivos de cabeçalho do Python. Muitas são definidas mais próximas de onde são úteis (por exemplo, `Py_RETURN_NONE`). Outras de utilidade mais geral são definidas aqui. Esta não é necessariamente uma lista completa.

### **Py\_UNREACHABLE()**

Use isso quando você tiver um caminho de código que não pode ser alcançado por design. Por exemplo, na cláusula `default`: em uma instrução `switch` para a qual todos os valores possíveis são incluídos nas instruções `case`. Use isto em lugares onde você pode ficar tentado a colocar uma chamada `assert(0)` ou `abort()`.

No modo de lançamento, a macro ajuda o compilador a otimizar o código e evita um aviso sobre código inacessível. Por exemplo, a macro é implementada com `__builtin_unreachable()` no GCC em modo de lançamento.

Um uso para `Py_UNREACHABLE()` é seguir uma chamada de uma função que nunca retorna, mas que não é declarada com `_Py_NO_RETURN`.

Se um caminho de código for um código muito improvável, mas puder ser alcançado em casos excepcionais, esta macro não deve ser usada. Por exemplo, sob condição de pouca memória ou se uma chamada de sistema retornar um valor fora do intervalo esperado. Nesse caso, é melhor relatar o erro ao chamador. Se o erro não puder ser reportado ao chamador, `Py_FatalError()` pode ser usada.

Novo na versão 3.7.

### **Py\_ABS(x)**

Retorna o valor absoluto de `x`.

Novo na versão 3.3.

### **Py\_MIN(x, y)**

Retorna o valor mínimo entre `x` e `y`.

Novo na versão 3.3.

### **Py\_MAX(x, y)**

Retorna o valor máximo entre `x` e `y`.

Novo na versão 3.3.

### **Py\_STRINGIFY(x)**

Converte `x` para uma string C. Por exemplo, `Py_STRINGIFY(123)` retorna `"123"`.

Novo na versão 3.4.

### **Py\_MEMBER\_SIZE(type, member)**

Retorna o tamanho do `member` de uma estrutura (`type`) em bytes.

Novo na versão 3.6.

### **Py\_CHARMASK(c)**

O argumento deve ser um caractere ou um número inteiro no intervalo `[-128, 127]` ou `[0, 255]`. Esta macro retorna `c` convertido em um `unsigned char`.

### **Py\_GETENV(s)**

Como `getenv(s)`, mas retorna `NULL` se `-E` foi passada na linha de comando (isto é, se `Py_IgnoreEnvironmentFlag` estiver definida).

### **Py\_UNUSED(arg)**

Use isso para argumentos não usados em uma definição de função para silenciar avisos do compilador. Exemplo: `int func(int a, int Py_UNUSED(b)) { return a; }.`

Novo na versão 3.4.

**Py\_DEPRECATED** (*version*)

Use isso para declarações descontinuadas. A macro deve ser colocada antes do nome do símbolo.

Exemplo:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

Alterado na versão 3.8: Suporte a MSVC foi adicionado.

**PyDoc\_STRVAR** (*name*, *str*)

Cria uma variável com o nome *name* que pode ser usada em docstrings. Se o Python for compilado sem docstrings, o valor estará vazio.

Use `PyDoc_STRVAR` para docstrings para ter suporte à compilação do Python sem docstrings, conforme especificado em [PEP 7](#).

Exemplo:

```
PyDoc_STRVAR(pop_doc, "Remove and return the rightmost element.");

static PyMethodDef deque_methods[] = {
    // ...
    {"pop", (PyCFunction)deque_pop, METH_NOARGS, pop_doc},
    // ...
}
```

**PyDoc\_STR** (*str*)

Cria uma docstring para a string de entrada fornecida ou uma string vazia se docstrings estiverem desabilitadas.

Use `PyDoc_STR` ao especificar docstrings para ter suporte à compilação do Python sem docstrings, conforme especificado em [PEP 7](#).

Exemplo:

```
static PyMethodDef sqlite_row_methods[] = {
    {"keys", (PyCFunction)sqlite_row_keys, METH_NOARGS,
     PyDoc_STR("Returns the keys of the row.")},
    {NULL, NULL}
};
```

## 1.4 Objetos, tipos e contagens de referências

A maioria das funções da API Python/C tem um ou mais argumentos, bem como um valor de retorno do tipo `PyObject*`. Este tipo é um ponteiro para um tipo de dados opaco que representa um objeto Python arbitrário. Como todos os tipos de objeto Python são tratados da mesma maneira pela linguagem Python na maioria das situações (por exemplo, atribuições, regras de escopo e passagem de argumento), é adequado que eles sejam representados por um único tipo C. Quase todos os objetos Python vivem na pilha: você nunca declara uma variável automática ou estática do tipo `PyObject`, variáveis de apenas ponteiro do tipo `PyObject*` podem ser declaradas. A única exceção são os objetos de tipo; uma vez que estes nunca devem ser desalocados, eles são normalmente objetos estáticos `PyTypeObject`.

Todos os objetos Python (mesmo inteiros Python) têm um *tipo* e uma *contagem de referências*. O tipo de um objeto determina que tipo de objeto ele é (por exemplo, um número inteiro, uma lista ou uma função definida pelo usuário; existem muitos mais, conforme explicado em `types`). Para cada um dos tipos conhecidos, há uma macro para verificar se um objeto é desse tipo; por exemplo, `PyList_Check(a)` é verdadeiro se (e somente se) o objeto apontado por *a* for uma lista Python.

### 1.4.1 Contagens de referências

A contagem de referências é importante porque os computadores atuais têm um tamanho de memória finito (e frequentemente severamente limitado); ela conta quantos lugares diferentes existem que possuem uma *referência forte* a um objeto. Tal lugar pode ser outro objeto, ou uma variável C global (ou estática), ou uma variável local em alguma função C. Quando a última *referência forte* a um objeto é liberada (ou seja, sua contagem de referências se torna zero), o objeto é desalocado. Se ele contiver referências a outros objetos, essas referências são liberadas. Esses outros objetos podem ser desalocados por sua vez, se não houver mais referências a eles, e assim por diante. (Há um problema óbvio com objetos que referenciam uns aos outros aqui; por enquanto, a solução é “não faça isso”.)

Contagens de referências são sempre manipuladas explicitamente. A maneira normal é usar a macro `Py_INCREF()` para obter uma nova referência a um objeto (ou seja, incrementar sua contagem de referências em um), e `Py_DECREF()` para liberar essa referência (ou seja, decrementar a contagem de referências em um). A macro `Py_DECREF()` é consideravelmente mais complexa do que a `Py_INCREF()`, pois deve verificar se a contagem de referências se torna zero e, em seguida, fazer com que o desalocador do objeto seja chamado. O desalocador é um ponteiro para função contida na estrutura de tipo do objeto. O desalocador específico do tipo cuida da liberação de referências para outros objetos contidos no objeto se este for um tipo de objeto composto, como uma lista, bem como de executar qualquer finalização adicional necessária. Não há chance de a contagem de referências transbordar; pelo menos tantos bits são usados para armazenar a contagem de referência quantos forem os locais de memória distintos na memória virtual (presumindo `sizeof(Py_ssize_t) >= sizeof(void*)`). Portanto, o incremento da contagem de referências é uma operação simples.

Não é necessário manter uma *referência forte* (ou seja, incrementar a contagem de referências) para cada variável local que contém um ponteiro para um objeto. Em teoria, a contagem de referências do objeto aumenta em um quando a variável é feita para apontar para ele e diminui em um quando a variável sai do escopo. No entanto, esses dois se cancelam, portanto, no final, a contagem de referências não mudou. A única razão real para usar a contagem de referências é evitar que o objeto seja desalocado enquanto nossa variável estiver apontando para ele. Se sabemos que existe pelo menos uma outra referência ao objeto que vive pelo menos tanto quanto nossa variável, não há necessidade de tomar uma nova *referência forte* (ou seja, incrementar a contagem de referências) temporariamente. Uma situação importante em que isso ocorre é em objetos que são passados como argumentos para funções C em um módulo de extensão que são chamados de Python; o mecanismo de chamada garante manter uma referência a todos os argumentos durante a chamada.

No entanto, uma armadilha comum é extrair um objeto de uma lista e mantê-lo por um tempo, sem tomar uma nova referência. Alguma outra operação poderia remover o objeto da lista, liberando essa referência e possivelmente desalocando-o. O perigo real é que operações aparentemente inocentes podem invocar código Python arbitrário que poderia fazer isso; existe um caminho de código que permite que o controle flua de volta para o usuário a partir de um `Py_DECREF()`, então quase qualquer operação é potencialmente perigosa.

Uma abordagem segura é sempre usar as operações genéricas (funções cujo nome começa com `PyObject_`, `PyNumber_`, `PySequence_` ou `PyMapping_`). Essas operações sempre criam uma nova *referência forte* (ou seja, incrementam a contagem de referências) do objeto que retornam. Isso deixa o chamador com a responsabilidade de chamar `Py_DECREF()` quando terminar com o resultado; isso logo se torna uma segunda natureza.

#### Detalhes da contagem de referências

O comportamento da contagem de referências de funções na API C/Python é melhor explicado em termos de *propriedade de referências*. A propriedade pertence às referências, nunca aos objetos (os objetos não são possuídos: eles são sempre compartilhados). “Possuir uma referência” significa ser responsável por chamar `Py_DECREF()` nela quando a referência não for mais necessária. A propriedade também pode ser transferida, o que significa que o código que recebe a propriedade da referência torna-se responsável por eventualmente efetuar um liberando ela chamando `Py_DECREF()` ou `Py_XDECREF()` quando não é mais necessário – ou passando essa responsabilidade (geralmente para o responsável pela chamada). Quando uma função passa a propriedade de uma referência para seu chamador, diz-se que o chamador recebe uma *nova* referência. Quando nenhuma propriedade é transferida, diz-se que o chamador *toma emprestado* a referência. Nada precisa ser feito para uma *referência emprestada*.

Por outro lado, quando uma função de chamada passa uma referência a um objeto, há duas possibilidades: a função *rouba* uma referência ao objeto, ou não. *Roubar uma referência* significa que quando você passa uma referência para uma

função, essa função presume que agora ela possui essa referência e você não é mais responsável por ela.

Poucas funções roubam referências; as duas exceções notáveis são `PyList_SetItem()` e `PyTuple_SetItem()`, que roubam uma referência para o item (mas não para a tupla ou lista na qual o item é colocado!). Essas funções foram projetadas para roubar uma referência devido a um idioma comum para preencher uma tupla ou lista com objetos recém-criados; por exemplo, o código para criar a tupla `(1, 2, "three")` pode ser parecido com isto (esquecendo o tratamento de erros por enquanto; uma maneira melhor de codificar isso é mostrada abaixo):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Aqui, `PyLong_FromLong()` retorna uma nova referência que é imediatamente roubada por `PyTuple_SetItem()`. Quando você quiser continuar usando um objeto, embora a referência a ele seja roubada, use `Py_INCREF()` para obter outra referência antes de chamar a função de roubo de referência.

A propósito, `PyTuple_SetItem()` é a *única* maneira de definir itens de tupla; `PySequence_SetItem()` e `PyObject_SetItem()` se recusam a fazer isso, pois tuplas são um tipo de dados imutável. Você só deve usar `PyTuple_SetItem()` para tuplas que você mesmo está criando.

O código equivalente para preencher uma lista pode ser escrita usando `PyList_New()` e `PyList_SetItem()`.

No entanto, na prática, você raramente usará essas maneiras de criar e preencher uma tupla ou lista. Existe uma função genérica, `Py_BuildValue()`, que pode criar objetos mais comuns a partir de valores C, dirigidos por uma *string de formato*. Por exemplo, os dois blocos de código acima podem ser substituídos pelos seguintes (que também cuidam da verificação de erros):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

É muito mais comum usar `PyObject_SetItem()` e amigos com itens cujas referências você está apenas pegando emprestado, como argumentos que foram passados para a função que você está escrevendo. Nesse caso, o comportamento deles em relação às referências é muito mais são, já que você não precisa tomar uma nova referência só para poder doá-la (“mande-a ser roubada”). Por exemplo, esta função define todos os itens de uma lista (na verdade, qualquer sequência mutável) para um determinado item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;

    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {
            Py_DECREF(index);
            return -1;
        }
        Py_DECREF(index);
    }
}
```

(continua na próxima página)



(continuação da página anterior)

```

    }
    return 0;
}

```

A situação é ligeiramente diferente para os valores de retorno da função. Embora passar uma referência para a maioria das funções não altere suas responsabilidades de propriedade para aquela referência, muitas funções que retornam uma referência a um objeto fornecem a propriedade da referência. O motivo é simples: em muitos casos, o objeto retornado é criado instantaneamente e a referência que você obtém é a única referência ao objeto. Portanto, as funções genéricas que retornam referências a objetos, como `PyObject_GetItem()` e `PySequence_GetItem()`, sempre retornam uma nova referência (o chamador torna-se o dono da referência).

É importante perceber que se você possui uma referência retornada por uma função depende de qual função você chama apenas — *a plumagem* (o tipo do objeto passado como um argumento para a função) *não entra nela!* Assim, se você extrair um item de uma lista usando `PyList_GetItem()`, você não possui a referência — mas se obtiver o mesmo item da mesma lista usando `PySequence_GetItem()` (que leva exatamente os mesmos argumentos), você possui uma referência ao objeto retornado.

Aqui está um exemplo de como você poderia escrever uma função que calcula a soma dos itens em uma lista de inteiros; uma vez usando `PyList_GetItem()`, e uma vez usando `PySequence_GetItem()`.

```

long
sum_list(PyObject *list)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;

    n = PyList_Size(list);
    if (n < 0)
        return -1; /* Not a list */
    for (i = 0; i < n; i++) {
        item = PyList_GetItem(list, i); /* Can't fail */
        if (!PyLong_Check(item)) continue; /* Skip non-integers */
        value = PyLong_AsLong(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
    return total;
}

```

```

long
sum_sequence(PyObject *sequence)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;
    n = PySequence_Length(sequence);
    if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {

```

(continua na próxima página)

(continuação da página anterior)

```

        value = PyLong_AsLong(item);
        Py_DECREF(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
    else {
        Py_DECREF(item); /* Discard reference ownership */
    }
}
return total;
}

```

## 1.4.2 Tipos

Existem alguns outros tipos de dados que desempenham um papel significativo na API Python/C; a maioria são tipos C simples, como `int`, `long`, `double` e `char*`. Alguns tipos de estrutura são usados para descrever tabelas estáticas usadas para listar as funções exportadas por um módulo ou os atributos de dados de um novo tipo de objeto, e outro é usado para descrever o valor de um número complexo. Eles serão discutidos junto com as funções que os utilizam.

### type `Py_ssize_t`

*Part of the Stable ABI.* Um tipo integral assinado tal que `sizeof(Py_ssize_t) == sizeof(size_t)`. C99 não define tal coisa diretamente (`size_t` é um tipo integral não assinado). Veja **PEP 353** para mais detalhes. `PY_SSIZE_T_MAX` é o maior valor positivo do tipo `Py_ssize_t`.

## 1.5 Exceções

O programador Python só precisa lidar com exceções se o tratamento de erros específico for necessário; as exceções não tratadas são propagadas automaticamente para o chamador, depois para o chamador e assim por diante, até chegarem ao interpretador de nível superior, onde são relatadas ao usuário acompanhadas por um traceback (situação da pilha de execução).

Para programadores C, entretanto, a verificação de erros sempre deve ser explícita. Todas as funções na API Python/C podem levantar exceções, a menos que uma declaração explícita seja feita de outra forma na documentação de uma função. Em geral, quando uma função encontra um erro, ela define uma exceção, descarta todas as referências de objeto de sua propriedade e retorna um indicador de erro. Se não for documentado de outra forma, este indicador é `NULL` ou `-1`, dependendo do tipo de retorno da função. Algumas funções retornam um resultado booleano verdadeiro/falso, com falso indicando um erro. Muito poucas funções não retornam nenhum indicador de erro explícito ou têm um valor de retorno ambíguo e requerem teste explícito para erros com `PyErr_Occurred()`. Essas exceções são sempre documentadas explicitamente.

O estado de exceção é mantido no armazenamento por thread (isso é equivalente a usar o armazenamento global em uma aplicação sem thread). Uma thread pode estar em um de dois estados: ocorreu uma exceção ou não. A função `PyErr_Occurred()` pode ser usada para verificar isso: ela retorna uma referência emprestada ao objeto do tipo de exceção quando uma exceção ocorreu, e `NULL` caso contrário. Existem várias funções para definir o estado de exceção: `PyErr_SetString()` é a função mais comum (embora não a mais geral) para definir o estado de exceção, e `PyErr_Clear()` limpa o estado da exceção.

O estado de exceção completo consiste em três objetos (todos os quais podem ser `NULL`): o tipo de exceção, o valor de exceção correspondente e o traceback. Eles têm os mesmos significados que o resultado no Python de `sys.exc_info()`; no entanto, eles não são os mesmos: os objetos Python representam a última exceção sendo tratada por uma instrução

Python `try ... except`, enquanto o estado de exceção de nível C só existe enquanto uma exceção está sendo transmitido entre funções C até atingir o laço de repetição principal do interpretador de bytecode Python, que se encarrega de transferi-lo para `sys.exc_info()` e amigos.

Observe que a partir do Python 1.5, a maneira preferida e segura para thread para acessar o estado de exceção do código Python é chamar a função `sys.exc_info()`, que retorna o estado de exceção por thread para o código Python. Além disso, a semântica de ambas as maneiras de acessar o estado de exceção mudou, de modo que uma função que captura uma exceção salvará e restaurará o estado de exceção de seu segmento de modo a preservar o estado de exceção de seu chamador. Isso evita bugs comuns no código de tratamento de exceções causados por uma função aparentemente inocente sobrescrevendo a exceção sendo tratada; também reduz a extensão da vida útil frequentemente indesejada para objetos que são referenciados pelos quadros de pilha no traceback.

Como princípio geral, uma função que chama outra função para realizar alguma tarefa deve verificar se a função chamada levantou uma exceção e, em caso afirmativo, passar o estado da exceção para seu chamador. Ele deve descartar todas as referências de objeto que possui e retornar um indicador de erro, mas *não* deve definir outra exceção — que sobrescreveria a exceção que acabou de ser gerada e perderia informações importantes sobre a causa exata do erro.

Um exemplo simples de detecção de exceções e transmiti-las é mostrado no exemplo `sum_sequence()` acima. Acontece que este exemplo não precisa limpar nenhuma referência de propriedade quando detecta um erro. A função de exemplo a seguir mostra alguma limpeza de erro. Primeiro, para lembrar por que você gosta de Python, mostramos o código Python equivalente:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Aqui está o código C correspondente, em toda sua glória:

```
int
incr_item(PyObject *dict, PyObject *key)
{
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
    int rv = -1; /* Return value initialized to -1 (failure) */

    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;

        /* Clear the error and use zero: */
        PyErr_Clear();
        item = PyLong_FromLong(0L);
        if (item == NULL)
            goto error;
    }
    const_one = PyLong_FromLong(1L);
    if (const_one == NULL)
        goto error;

    incremented_item = PyNumber_Add(item, const_one);
    if (incremented_item == NULL)
        goto error;
```

(continua na próxima página)

(continuação da página anterior)

```

    if (PyObject_SetItem(dict, key, incremented_item) < 0)
        goto error;
    rv = 0; /* Success */
    /* Continue with cleanup code */

error:
    /* Cleanup code, shared by success and failure path */

    /* Use Py_XDECREF() to ignore NULL references */
    Py_XDECREF(item);
    Py_XDECREF(const_one);
    Py_XDECREF(incremented_item);

    return rv; /* -1 for error, 0 for success */
}

```

Este exemplo representa um uso endossado da instrução `goto` em C! Ele ilustra o uso de `PyErr_ExceptionMatches()` e `PyErr_Clear()` para lidar com exceções específicas, e o uso de `Py_XDECREF()` para descartar referências de propriedade que podem ser NULL (observe o 'X' no nome; `Py_DECREF()` traria quando confrontado com uma referência NULL). É importante que as variáveis usadas para manter as referências de propriedade sejam inicializadas com NULL para que isso funcione; da mesma forma, o valor de retorno proposto é inicializado para -1 (falha) e apenas definido para sucesso após a chamada final feita ser bem sucedida.

## 1.6 Incorporando Python

A única tarefa importante com a qual apenas os incorporadores (em oposição aos escritores de extensão) do interpretador Python precisam se preocupar é a inicialização e, possivelmente, a finalização do interpretador Python. A maior parte da funcionalidade do interpretador só pode ser usada após a inicialização do interpretador.

A função de inicialização básica é `Py_Initialize()`. Isso inicializa a tabela de módulos carregados e cria os módulos fundamentais `builtins`, `__main__` e `sys`. Ela também inicializa o caminho de pesquisa de módulos (`sys.path`).

`Py_Initialize()` não define a “lista de argumentos de script” (`sys.argv`). Se esta variável for necessária para o código Python que será executado posteriormente, ela deve ser definida explicitamente com uma chamada com `PySys_SetArgvEx(argc, argv, updatepath)` após a chamada de `Py_Initialize()`.

Na maioria dos sistemas (em particular, no Unix e no Windows, embora os detalhes sejam ligeiramente diferentes), `Py_Initialize()` calcula o caminho de pesquisa de módulos com base em sua melhor estimativa para a localização do executável do interpretador Python padrão, presumindo que a biblioteca Python é encontrada em um local fixo em relação ao executável do interpretador Python. Em particular, ele procura por um diretório chamado `lib/pythonX.Y` relativo ao diretório pai onde o executável chamado `python` é encontrado no caminho de pesquisa de comandos do shell (a variável de ambiente `PATH`).

Por exemplo, se o executável Python for encontrado em `/usr/local/bin/python`, ele presumirá que as bibliotecas estão em `/usr/local/lib/pythonX.Y`. (Na verdade, este caminho particular também é o local reserva, usado quando nenhum arquivo executável chamado `python` é encontrado ao longo de `PATH`.) O usuário pode substituir este comportamento definindo a variável de ambiente `PYTHONHOME`, ou insira diretórios adicionais na frente do caminho padrão definindo `PYTHONPATH`.

A aplicação de incorporação pode orientar a pesquisa chamando `Py_SetProgramName(file)` antes de chamar `Py_Initialize()`. Observe que `PYTHONHOME` ainda substitui isso e `PYTHONPATH` ainda é inserido na frente do caminho padrão. Uma aplicação que requer controle total deve fornecer sua própria implementação de `Py_GetPath()`, `Py_GetPrefix()`, `Py_GetExecPrefix()` e `Py_GetProgramFullPath()` (todas definidas em `Modules/getpath.c`).

Às vezes, é desejável “desinicializar” o Python. Por exemplo, a aplicação pode querer iniciar novamente (fazer outra chamada para `Py_Initialize()`) ou a aplicação simplesmente termina com o uso de Python e deseja liberar memória alocada pelo Python. Isso pode ser feito chamando `Py_FinalizeEx()`. A função `Py_IsInitialized()` retorna verdadeiro se o Python está atualmente no estado inicializado. Mais informações sobre essas funções são fornecidas em um capítulo posterior. Observe que `Py_FinalizeEx()` *não* libera toda a memória alocada pelo interpretador Python, por exemplo, a memória alocada por módulos de extensão atualmente não pode ser liberada.

## 1.7 Compilações de depuração

Python pode ser compilado com várias macros para permitir verificações extras do interpretador e módulos de extensão. Essas verificações tendem a adicionar uma grande quantidade de sobrecarga ao tempo de execução, portanto, não são habilitadas por padrão.

Uma lista completa dos vários tipos de compilações de depuração está no arquivo `Misc/SpecialBuilds.txt` na distribuição do código-fonte do Python. Estão disponíveis compilações que oferecem suporte ao rastreamento de contagens de referências, depuração do alocador de memória ou criação de perfil de baixo nível do laço do interpretador principal. Apenas as compilações usadas com mais frequência serão descritas no restante desta seção.

Compilar o interpretador com a macro `Py_DEBUG` definida produz o que geralmente se entende por uma compilação de depuração do Python. `Py_DEBUG` é habilitada na compilação Unix adicionando `--with-pydebug` ao comando `./configure`. Também está implícito na presença da macro não específica do Python `_DEBUG`. Quando `Py_DEBUG` está habilitado na compilação do Unix, a otimização do compilador é desabilitada.

Além da depuração de contagem de referências descrita abaixo, verificações extras são realizadas, consulte *Compilação de Depuração do Python*.

Definir `Py_TRACE_REFS` habilita o rastreamento de referência (veja a opção `--with-trace-refs` de `configure`). Quando definida, uma lista circular duplamente vinculada de objetos ativos é mantida adicionando dois campos extras a cada `PyObject`. As alocações totais também são rastreadas. Ao sair, todas as referências existentes são impressas. (No modo interativo, isso acontece após cada instrução executada pelo interpretador.)

Consulte `Misc/SpecialBuilds.txt` na distribuição do código-fonte Python para informações mais detalhadas.



---

## Estabilidade da API C

---

Python's C API is covered by the Backwards Compatibility Policy, [PEP 387](#). While the C API will change with every minor release (e.g. from 3.9 to 3.10), most changes will be source-compatible, typically by only adding new API. Changing existing API or removing API is only done after a deprecation period or to fix serious issues.

A Interface Binário de Aplicação (ABI) do CPython é compatível para frente e para trás através de uma versão menor (se elas forem compiladas da mesma maneira; veja [Considerações da plataforma](#) abaixo). Portanto, o código compilado para Python 3.10.0 funcionará em 3.10.8 e vice-versa, mas precisará ser compilado separadamente para 3.9.x e 3.10.x.

Names prefixed by an underscore, such as `_Py_InternalState`, are private API that can change without notice even in patch releases.

### 2.1 Interface Binária de Aplicação Estável

Python 3.2 introduced the *Limited API*, a subset of Python's C API. Extensions that only use the Limited API can be compiled once and work with multiple versions of Python. Contents of the Limited API are [listed below](#).

To enable this, Python provides a *Stable ABI*: a set of symbols that will remain compatible across Python 3.x versions. The Stable ABI contains symbols exposed in the Limited API, but also other ones – for example, functions necessary to support older versions of the Limited API.

(For simplicity, this document talks about *extensions*, but the Limited API and Stable ABI work the same way for all uses of the API – for example, embedding Python.)

#### **Py\_LIMITED\_API**

Defina essa macro antes de incluir `Python.h` para optar por usar apenas a API Limitada e selecionar a versão da API Limitada.

Define `Py_LIMITED_API` to the value of `PY_VERSION_HEX` corresponding to the lowest Python version your extension supports. The extension will work without recompilation with all Python 3 releases from the specified one onward, and can use Limited API introduced up to that version.

Em vez de usar diretamente a macro `PY_VERSION_HEX`, codifique uma versão menor mínima (por exemplo, `0x030A0000` para o Python 3.10) para garantir estabilidade ao compilar com versões futuras do Python.

Você também pode definir `Py_LIMITED_API` como 3. Isso funciona da mesma forma que `0x03020000` (Python 3.2, a versão que introduziu a API Limitada).

No Windows, as extensões que usam a ABI Estável devem ser vinculadas a `python3.dll` em vez de uma biblioteca específica de versão, como `python39.dll`.

Em algumas plataformas, o Python procurará e carregará arquivos de biblioteca compartilhada com o nome marcado como `abi3` (por exemplo, `meumódulo.abi3.so`). Ele não verifica se essas extensões estão em conformidade com uma ABI Estável. O usuário (ou suas ferramentas de empacotamento) precisa garantir que, por exemplo, as extensões construídas com a API Limitada 3.10+ não sejam instaladas em versões mais baixas do Python.

Todas as funções na ABI estável estão presentes como funções na biblioteca compartilhada do Python, não apenas como macros. Isso as torna utilizáveis em linguagens que não utilizam o pré-processador C.

### 2.1.1 Escopo e Desempenho da API Limitada

O objetivo da API Limitada é permitir tudo o que é possível com a API C completa, mas possivelmente com uma penalidade de desempenho.

Por exemplo, enquanto `PyList_GetItem()` está disponível, sua variante de macro “insegura” `PyList_GET_ITEM()` não está. A macro pode ser mais rápida porque pode depender de detalhes de implementação específicos da versão do objeto da lista.

Sem a definição de `Py_LIMITED_API`, algumas funções da API C são colocadas “inline” ou substituídas por macros. Definir `Py_LIMITED_API` desativa esse inline, permitindo estabilidade à medida que as estruturas de dados do Python são aprimoradas, mas possivelmente reduzindo o desempenho.

Ao deixar de fora a definição `Py_LIMITED_API`, é possível compilar uma extensão da API Limitada com uma ABI específica da versão. Isso pode melhorar o desempenho para essa versão do Python, mas limitará a compatibilidade. Compilar com `Py_LIMITED_API` vai produzir uma extensão que pode ser distribuída quando uma específica da versão não estiver disponível – por exemplo, para pré-lançamentos de uma próxima versão do Python.

### 2.1.2 Limitações da API Limitada

Note that compiling with `Py_LIMITED_API` is *not* a complete guarantee that code conforms to the Limited API or the Stable ABI. `Py_LIMITED_API` only covers definitions, but an API also includes other issues, such as expected semantics.

Uma questão que `Py_LIMITED_API` não protege é a chamada de uma função com argumentos inválidos em uma versão inferior do Python. Por exemplo, considere uma função que começa a aceitar `NULL` como argumento. No Python 3.9, `NULL` agora seleciona um comportamento padrão, mas no Python 3.8, o argumento será usado diretamente, causando uma referência `NULL` e uma falha. Um argumento similar funciona para campos de estruturas.

Outra questão é que alguns campos de estrutura não estão atualmente ocultos quando `Py_LIMITED_API` é definido, mesmo que eles façam parte da API Limitada.

Por esses motivos, recomendamos testar uma extensão com *todas* as versões menores do Python que ela oferece suporte e, preferencialmente, construir com a versão *mais baixa* dessas.

Também recomendamos revisar a documentação de todas as APIs utilizadas para verificar se ela faz parte explicitamente da API Limitada. Mesmo com a definição de `Py_LIMITED_API`, algumas declarações privadas são expostas por razões técnicas (ou até mesmo acidentalmente, como bugs).

Também observe que a API Limitada não é necessariamente estável: compilar com `Py_LIMITED_API` com Python 3.8 significa que a extensão será executada com Python 3.12, mas não necessariamente será *compilada* com Python 3.12. Em particular, partes da API Limitada podem ser descontinuadas e removidas, desde que a ABI Estável permaneça estável.



## 2.2 Considerações da plataforma

ABI stability depends not only on Python, but also on the compiler used, lower-level libraries and compiler options. For the purposes of the Stable ABI, these details define a “platform”. They usually depend on the OS type and processor architecture

É responsabilidade de cada distribuidor particular do Python garantir que todas as versões do Python em uma plataforma específica sejam construídas de forma a não quebrar a ABI estável. Isso é válido para as versões do Windows e macOS disponibilizadas pela `python.org` e por muitos distribuidores terceiros.

## 2.3 Conteúdo da API Limitada

Currently, the Limited API includes the following items:

- `PyAIter_Check()`
- `PyArg_Parse()`
- `PyArg_ParseTuple()`
- `PyArg_ParseTupleAndKeywords()`
- `PyArg_UnpackTuple()`
- `PyArg_VaParse()`
- `PyArg_VaParseTupleAndKeywords()`
- `PyArg_ValidateKeywordArguments()`
- `PyBaseObject_Type`
- `PyBool_FromLong()`
- `PyBool_Type`
- `PyByteArrayIter_Type`
- `PyByteArray_AsString()`
- `PyByteArray_Concat()`
- `PyByteArray_FromObject()`
- `PyByteArray_FromStringAndSize()`
- `PyByteArray_Resize()`
- `PyByteArray_Size()`
- `PyByteArray_Type`
- `PyBytesIter_Type`
- `PyBytes_AsString()`
- `PyBytes_AsStringAndSize()`
- `PyBytes_Concat()`
- `PyBytes_ConcatAndDel()`
- `PyBytes_DecodeEscape()`
- `PyBytes_FromFormat()`

- *PyBytes\_FromFormatV()*
- *PyBytes\_FromObject()*
- *PyBytes\_FromString()*
- *PyBytes\_FromStringAndSize()*
- *PyBytes\_Repr()*
- *PyBytes\_Size()*
- *PyBytes\_Type*
- *PyCFunction*
- *PyCFunctionWithKeywords*
- *PyCFunction\_Call()*
- *PyCFunction\_GetFlags()*
- *PyCFunction\_GetFunction()*
- *PyCFunction\_GetSelf()*
- *PyCFunction\_New()*
- *PyCFunction\_NewEx()*
- *PyCFunction\_Type*
- *PyCMethod\_New()*
- *PyCallIter\_New()*
- *PyCallIter\_Type*
- *PyCallable\_Check()*
- *PyCapsule\_Destructor*
- *PyCapsule\_GetContext()*
- *PyCapsule\_GetDestructor()*
- *PyCapsule\_GetName()*
- *PyCapsule\_GetPointer()*
- *PyCapsule\_Import()*
- *PyCapsule\_IsValid()*
- *PyCapsule\_New()*
- *PyCapsule\_SetContext()*
- *PyCapsule\_SetDestructor()*
- *PyCapsule\_SetName()*
- *PyCapsule\_SetPointer()*
- *PyCapsule\_Type*
- *PyClassMethodDescr\_Type*
- *PyCodec\_BackslashReplaceErrors()*
- *PyCodec\_Decode()*

- `PyCodec_Decoder()`
- `PyCodec_Encode()`
- `PyCodec_Encoder()`
- `PyCodec_IgnoreErrors()`
- `PyCodec_IncrementalDecoder()`
- `PyCodec_IncrementalEncoder()`
- `PyCodec_KnownEncoding()`
- `PyCodec_LookupError()`
- `PyCodec_NameReplaceErrors()`
- `PyCodec_Register()`
- `PyCodec_RegisterError()`
- `PyCodec_ReplaceErrors()`
- `PyCodec_StreamReader()`
- `PyCodec_StreamWriter()`
- `PyCodec_StrictErrors()`
- `PyCodec_Unregister()`
- `PyCodec_XMLCharRefReplaceErrors()`
- `PyComplex_FromDoubles()`
- `PyComplex_ImagAsDouble()`
- `PyComplex_RealAsDouble()`
- `PyComplex_Type`
- `PyDescr_NewClassMethod()`
- `PyDescr_NewGetSet()`
- `PyDescr_NewMember()`
- `PyDescr_NewMethod()`
- `PyDictItems_Type`
- `PyDictIterItem_Type`
- `PyDictIterKey_Type`
- `PyDictIterValue_Type`
- `PyDictKeys_Type`
- `PyDictProxy_New()`
- `PyDictProxy_Type`
- `PyDictRevIterItem_Type`
- `PyDictRevIterKey_Type`
- `PyDictRevIterValue_Type`
- `PyDictValues_Type`

- `PyDict_Clear()`
- `PyDict_Contains()`
- `PyDict_Copy()`
- `PyDict_DelItem()`
- `PyDict_DelItemString()`
- `PyDict_GetItem()`
- `PyDict_GetItemString()`
- `PyDict_GetItemWithError()`
- `PyDict_Items()`
- `PyDict_Keys()`
- `PyDict_Merge()`
- `PyDict_MergeFromSeq2()`
- `PyDict_New()`
- `PyDict_Next()`
- `PyDict_SetItem()`
- `PyDict_SetItemString()`
- `PyDict_Size()`
- `PyDict_Type`
- `PyDict_Update()`
- `PyDict_Values()`
- `PyEllipsis_Type`
- `PyEnum_Type`
- `PyErr_BadArgument()`
- `PyErr_BadInternalCall()`
- `PyErr_CheckSignals()`
- `PyErr_Clear()`
- `PyErr_Display()`
- `PyErr_ExceptionMatches()`
- `PyErr_Fetch()`
- `PyErr_Format()`
- `PyErr_FormatV()`
- `PyErr_GetExcInfo()`
- `PyErr_GivenExceptionMatches()`
- `PyErr_NewException()`
- `PyErr_NewExceptionWithDoc()`
- `PyErr_NoMemory()`

- `PyErr_NormalizeException()`
- `PyErr_Occurred()`
- `PyErr_Print()`
- `PyErr_PrintEx()`
- `PyErr_ProgramText()`
- `PyErr_ResourceWarning()`
- `PyErr_Restore()`
- `PyErr_SetExcFromWindowsErr()`
- `PyErr_SetExcFromWindowsErrWithFilename()`
- `PyErr_SetExcFromWindowsErrWithFilenameObject()`
- `PyErr_SetExcFromWindowsErrWithFilenameObjects()`
- `PyErr_SetExcInfo()`
- `PyErr_SetFromErrno()`
- `PyErr_SetFromErrnoWithFilename()`
- `PyErr_SetFromErrnoWithFilenameObject()`
- `PyErr_SetFromErrnoWithFilenameObjects()`
- `PyErr_SetFromWindowsErr()`
- `PyErr_SetFromWindowsErrWithFilename()`
- `PyErr_SetImportError()`
- `PyErr_SetImportErrorSubclass()`
- `PyErr_SetInterrupt()`
- `PyErr_SetInterruptEx()`
- `PyErr_SetNone()`
- `PyErr_SetObject()`
- `PyErr_SetString()`
- `PyErr_SyntaxLocation()`
- `PyErr_SyntaxLocationEx()`
- `PyErr_WarnEx()`
- `PyErr_WarnExplicit()`
- `PyErr_WarnFormat()`
- `PyErr_WriteUnraisable()`
- `PyEval_AcquireLock()`
- `PyEval_AcquireThread()`
- `PyEval_CallFunction()`
- `PyEval_CallMethod()`
- `PyEval_CallObjectWithKeywords()`

- `PyEval_EvalCode()`
- `PyEval_EvalCodeEx()`
- `PyEval_EvalFrame()`
- `PyEval_EvalFrameEx()`
- `PyEval_GetBuiltins()`
- `PyEval_GetFrame()`
- `PyEval_GetFuncDesc()`
- `PyEval_GetFuncName()`
- `PyEval_GetGlobals()`
- `PyEval_GetLocals()`
- `PyEval_InitThreads()`
- `PyEval_ReleaseLock()`
- `PyEval_ReleaseThread()`
- `PyEval_RestoreThread()`
- `PyEval_SaveThread()`
- `PyEval_ThreadsInitialized()`
- `PyExc_ArithmeticError`
- `PyExc_AssertionError`
- `PyExc_AttributeError`
- `PyExc_BaseException`
- `PyExc_BlockingIOError`
- `PyExc_BrokenPipeError`
- `PyExc_BufferError`
- `PyExc_BytesWarning`
- `PyExc_ChildProcessError`
- `PyExc_ConnectionAbortedError`
- `PyExc_ConnectionError`
- `PyExc_ConnectionRefusedError`
- `PyExc_ConnectionResetError`
- `PyExc_DeprecationWarning`
- `PyExc_EOFError`
- `PyExc_EncodingWarning`
- `PyExc_EnvironmentError`
- `PyExc_Exception`
- `PyExc_FileExistsError`
- `PyExc_FileNotFoundError`

- `PyExc_FloatingPointError`
- `PyExc_FutureWarning`
- `PyExc_GeneratorExit`
- `PyExc_IOError`
- `PyExc_ImportError`
- `PyExc_ImportWarning`
- `PyExc_IndentationError`
- `PyExc_IndexError`
- `PyExc_InterruptedError`
- `PyExc_IsADirectoryError`
- `PyExc_KeyError`
- `PyExc_KeyboardInterrupt`
- `PyExc_LookupError`
- `PyExc_MemoryError`
- `PyExc_ModuleNotFoundError`
- `PyExc_NameError`
- `PyExc_NotADirectoryError`
- `PyExc_NotImplementedError`
- `PyExc_OSError`
- `PyExc_OverflowError`
- `PyExc_PendingDeprecationWarning`
- `PyExc_PermissionError`
- `PyExc_ProcessLookupError`
- `PyExc_RecursionError`
- `PyExc_ReferenceError`
- `PyExc_ResourceWarning`
- `PyExc_RuntimeError`
- `PyExc_RuntimeWarning`
- `PyExc_StopAsyncIteration`
- `PyExc_StopIteration`
- `PyExc_SyntaxError`
- `PyExc_SyntaxWarning`
- `PyExc_SystemError`
- `PyExc_SystemExit`
- `PyExc_TabError`
- `PyExc_TimeoutError`

- `PyExc_TypeError`
- `PyExc_UnboundLocalError`
- `PyExc_UnicodeDecodeError`
- `PyExc_UnicodeEncodeError`
- `PyExc_UnicodeError`
- `PyExc_UnicodeTranslateError`
- `PyExc_UnicodeWarning`
- `PyExc_UserWarning`
- `PyExc_ValueError`
- `PyExc_Warning`
- `PyExc_WindowsError`
- `PyExc_ZeroDivisionError`
- `PyExceptionClass_Name()`
- `PyException_GetCause()`
- `PyException_GetContext()`
- `PyException_GetTraceback()`
- `PyException_SetCause()`
- `PyException_SetContext()`
- `PyException_SetTraceback()`
- `PyFile_FromFd()`
- `PyFile_GetLine()`
- `PyFile_WriteObject()`
- `PyFile_WriteString()`
- `PyFilter_Type`
- `PyFloat_AsDouble()`
- `PyFloat_FromDouble()`
- `PyFloat_FromString()`
- `PyFloat_GetInfo()`
- `PyFloat_GetMax()`
- `PyFloat_GetMin()`
- `PyFloat_Type`
- `PyFrameObject`
- `PyFrame_GetCode()`
- `PyFrame_GetLineNumber()`
- `PyFrozenSet_New()`
- `PyFrozenSet_Type`



- `PyGC_Collect()`
- `PyGC_Disable()`
- `PyGC_Enable()`
- `PyGC_IsEnabled()`
- `PyGILState_Ensure()`
- `PyGILState_GetThisThreadState()`
- `PyGILState_Release()`
- `PyGILState_STATE`
- `PyGetSetDef`
- `PyGetSetDescr_Type`
- `PyImport_AddModule()`
- `PyImport_AddModuleObject()`
- `PyImport_AppendInittab()`
- `PyImport_ExecCodeModule()`
- `PyImport_ExecCodeModuleEx()`
- `PyImport_ExecCodeModuleObject()`
- `PyImport_ExecCodeModuleWithPathnames()`
- `PyImport_GetImporter()`
- `PyImport_GetMagicNumber()`
- `PyImport_GetMagicTag()`
- `PyImport_GetModule()`
- `PyImport_GetModuleDict()`
- `PyImport_Import()`
- `PyImport_ImportFrozenModule()`
- `PyImport_ImportFrozenModuleObject()`
- `PyImport_ImportModule()`
- `PyImport_ImportModuleLevel()`
- `PyImport_ImportModuleLevelObject()`
- `PyImport_ImportModuleNoBlock()`
- `PyImport_ReloadModule()`
- `PyIndex_Check()`
- `PyInterpreterState`
- `PyInterpreterState_Clear()`
- `PyInterpreterState_Delete()`
- `PyInterpreterState_Get()`
- `PyInterpreterState_GetDict()`

- *PyInterpreterState\_GetID()*
- *PyInterpreterState\_New()*
- *PyIter\_Check()*
- *PyIter\_Next()*
- *PyIter\_Send()*
- *PyListIter\_Type*
- *PyListRevIter\_Type*
- *PyList\_Append()*
- *PyList\_AsTuple()*
- *PyList\_GetItem()*
- *PyList\_GetSlice()*
- *PyList\_Insert()*
- *PyList\_New()*
- *PyList\_Reverse()*
- *PyList\_SetItem()*
- *PyList\_SetSlice()*
- *PyList\_Size()*
- *PyList\_Sort()*
- *PyList\_Type*
- *PyLongObject*
- *PyLongRangeIter\_Type*
- *PyLong\_AsDouble()*
- *PyLong\_AsLong()*
- *PyLong\_AsLongAndOverflow()*
- *PyLong\_AsLongLong()*
- *PyLong\_AsLongLongAndOverflow()*
- *PyLong\_AsSize\_t()*
- *PyLong\_AsSsize\_t()*
- *PyLong\_AsUnsignedLong()*
- *PyLong\_AsUnsignedLongLong()*
- *PyLong\_AsUnsignedLongLongMask()*
- *PyLong\_AsUnsignedLongMask()*
- *PyLong\_AsVoidPtr()*
- *PyLong\_FromDouble()*
- *PyLong\_FromLong()*
- *PyLong\_FromLongLong()*

- `PyLong_FromSize_t()`
- `PyLong_FromSsize_t()`
- `PyLong_FromString()`
- `PyLong_FromUnsignedLong()`
- `PyLong_FromUnsignedLongLong()`
- `PyLong_FromVoidPtr()`
- `PyLong_GetInfo()`
- `PyLong_Type`
- `PyMap_Type`
- `PyMapping_Check()`
- `PyMapping_GetItemString()`
- `PyMapping_HasKey()`
- `PyMapping_HasKeyString()`
- `PyMapping_Items()`
- `PyMapping_Keys()`
- `PyMapping_Length()`
- `PyMapping_SetItemString()`
- `PyMapping_Size()`
- `PyMapping_Values()`
- `PyMem_Calloc()`
- `PyMem_Free()`
- `PyMem_Malloc()`
- `PyMem_Realloc()`
- `PyMemberDef`
- `PyMemberDescr_Type`
- `PyMemoryView_FromMemory()`
- `PyMemoryView_FromObject()`
- `PyMemoryView_GetContiguous()`
- `PyMemoryView_Type`
- `PyMethodDef`
- `PyMethodDescr_Type`
- `PyModuleDef`
- `PyModuleDef_Base`
- `PyModuleDef_Init()`
- `PyModuleDef_Type`
- `PyModule_AddFunctions()`

- `PyModule_AddIntConstant()`
- `PyModule_AddObject()`
- `PyModule_AddObjectRef()`
- `PyModule_AddStringConstant()`
- `PyModule_AddType()`
- `PyModule_Create2()`
- `PyModule_ExecDef()`
- `PyModule_FromDefAndSpec2()`
- `PyModule_GetDef()`
- `PyModule_GetDict()`
- `PyModule_GetFilename()`
- `PyModule_GetFilenameObject()`
- `PyModule_GetName()`
- `PyModule_GetNameObject()`
- `PyModule_GetState()`
- `PyModule_New()`
- `PyModule_NewObject()`
- `PyModule_SetDocString()`
- `PyModule_Type`
- `PyNumber_Absolute()`
- `PyNumber_Add()`
- `PyNumber_And()`
- `PyNumber_AsSsize_t()`
- `PyNumber_Check()`
- `PyNumber_Divmod()`
- `PyNumber_Float()`
- `PyNumber_FloorDivide()`
- `PyNumber_InPlaceAdd()`
- `PyNumber_InPlaceAnd()`
- `PyNumber_InPlaceFloorDivide()`
- `PyNumber_InPlaceLshift()`
- `PyNumber_InPlaceMatrixMultiply()`
- `PyNumber_InPlaceMultiply()`
- `PyNumber_InPlaceOr()`
- `PyNumber_InPlacePower()`
- `PyNumber_InPlaceRemainder()`

- `PyNumber_InPlaceRshift()`
- `PyNumber_InPlaceSubtract()`
- `PyNumber_InPlaceTrueDivide()`
- `PyNumber_InPlaceXor()`
- `PyNumber_Index()`
- `PyNumber_Invert()`
- `PyNumber_Long()`
- `PyNumber_Lshift()`
- `PyNumber_MatrixMultiply()`
- `PyNumber_Multiply()`
- `PyNumber_Negative()`
- `PyNumber_Or()`
- `PyNumber_Positive()`
- `PyNumber_Power()`
- `PyNumber_Remainder()`
- `PyNumber_Rshift()`
- `PyNumber_Subtract()`
- `PyNumber_ToBase()`
- `PyNumber_TrueDivide()`
- `PyNumber_Xor()`
- `PyOS_AfterFork()`
- `PyOS_AfterFork_Child()`
- `PyOS_AfterFork_Parent()`
- `PyOS_BeforeFork()`
- `PyOS_CheckStack()`
- `PyOS_FSPath()`
- `PyOS_InputHook`
- `PyOS_InterruptOccurred()`
- `PyOS_double_to_string()`
- `PyOS_getsig()`
- `PyOS_mystricmp()`
- `PyOS_mystrnicmp()`
- `PyOS_setsig()`
- `PyOS_sighandler_t`
- `PyOS_snprintf()`
- `PyOS_string_to_double()`

- `PyOS_strtol()`
- `PyOS_strtoul()`
- `PyOS_vsnprintf()`
- `PyObject`
- `PyObject.ob_refcnt`
- `PyObject.ob_type`
- `PyObject_ASCII()`
- `PyObject_AsCharBuffer()`
- `PyObject_AsFileDescriptor()`
- `PyObject_AsReadBuffer()`
- `PyObject_AsWriteBuffer()`
- `PyObject_Bytes()`
- `PyObject_Call()`
- `PyObject_CallFunction()`
- `PyObject_CallFunctionObjArgs()`
- `PyObject_CallMethod()`
- `PyObject_CallMethodObjArgs()`
- `PyObject_CallNoArgs()`
- `PyObject_CallObject()`
- `PyObject_Calloc()`
- `PyObject_CheckReadBuffer()`
- `PyObject_ClearWeakRefs()`
- `PyObject_DelItem()`
- `PyObject_DelItemString()`
- `PyObject_Dir()`
- `PyObject_Format()`
- `PyObject_Free()`
- `PyObject_GC_Del()`
- `PyObject_GC_IsFinalized()`
- `PyObject_GC_IsTracked()`
- `PyObject_GC_Track()`
- `PyObject_GC_UnTrack()`
- `PyObject_GenericGetAttr()`
- `PyObject_GenericGetDict()`
- `PyObject_GenericSetAttr()`
- `PyObject_GenericSetDict()`

- `PyObject_GetAIter()`
- `PyObject_GetAttr()`
- `PyObject_GetAttrString()`
- `PyObject_GetItem()`
- `PyObject_GetIter()`
- `PyObject_HasAttr()`
- `PyObject_HasAttrString()`
- `PyObject_Hash()`
- `PyObject_HashNotImplemented()`
- `PyObject_Init()`
- `PyObject_InitVar()`
- `PyObject_IsInstance()`
- `PyObject_IsSubclass()`
- `PyObject_IsTrue()`
- `PyObject_Length()`
- `PyObject_Malloc()`
- `PyObject_Not()`
- `PyObject_Realloc()`
- `PyObject_Repr()`
- `PyObject_RichCompare()`
- `PyObject_RichCompareBool()`
- `PyObject_SelfIter()`
- `PyObject_SetAttr()`
- `PyObject_SetAttrString()`
- `PyObject_SetItem()`
- `PyObject_Size()`
- `PyObject_Str()`
- `PyObject_Type()`
- `PyProperty_Type`
- `PyRangeIter_Type`
- `PyRange_Type`
- `PyReversed_Type`
- `PySeqIter_New()`
- `PySeqIter_Type`
- `PySequence_Check()`
- `PySequence_Concat()`

- `PySequence_Contains()`
- `PySequence_Count()`
- `PySequence_DelItem()`
- `PySequence_DelSlice()`
- `PySequence_Fast()`
- `PySequence_GetItem()`
- `PySequence_GetSlice()`
- `PySequence_In()`
- `PySequence_InPlaceConcat()`
- `PySequence_InPlaceRepeat()`
- `PySequence_Index()`
- `PySequence_Length()`
- `PySequence_List()`
- `PySequence_Repeat()`
- `PySequence_SetItem()`
- `PySequence_SetSlice()`
- `PySequence_Size()`
- `PySequence_Tuple()`
- `PySetIter_Type`
- `PySet_Add()`
- `PySet_Clear()`
- `PySet_Contains()`
- `PySet_Discard()`
- `PySet_New()`
- `PySet_Pop()`
- `PySet_Size()`
- `PySet_Type`
- `PySlice_AdjustIndices()`
- `PySlice_GetIndices()`
- `PySlice_GetIndicesEx()`
- `PySlice_New()`
- `PySlice_Type`
- `PySlice_Unpack()`
- `PyState_AddModule()`
- `PyState_FindModule()`
- `PyState_RemoveModule()`



- *PyStructSequence\_Desc*
- *PyStructSequence\_Field*
- *PyStructSequence\_GetItem()*
- *PyStructSequence\_New()*
- *PyStructSequence\_NewType()*
- *PyStructSequence\_SetItem()*
- *PySuper\_Type*
- *PySys\_AddWarnOption()*
- *PySys\_AddWarnOptionUnicode()*
- *PySys\_AddXOption()*
- *PySys\_FormatStderr()*
- *PySys\_FormatStdout()*
- *PySys\_GetObject()*
- *PySys\_GetXOptions()*
- *PySys\_HasWarnOptions()*
- *PySys\_ResetWarnOptions()*
- *PySys\_SetArgv()*
- *PySys\_SetArgvEx()*
- *PySys\_SetObject()*
- *PySys\_SetPath()*
- *PySys\_WriteStderr()*
- *PySys\_WriteStdout()*
- *PyThreadState*
- *PyThreadState\_Clear()*
- *PyThreadState\_Delete()*
- *PyThreadState\_Get()*
- *PyThreadState\_GetDict()*
- *PyThreadState\_GetFrame()*
- *PyThreadState\_GetID()*
- *PyThreadState\_GetInterpreter()*
- *PyThreadState\_New()*
- *PyThreadState\_SetAsyncExc()*
- *PyThreadState\_Swap()*
- *PyThread\_GetInfo()*
- *PyThread\_ReInitTLS()*
- *PyThread\_acquire\_lock()*

- `PyThread_acquire_lock_timed()`
- `PyThread_allocate_lock()`
- `PyThread_create_key()`
- `PyThread_delete_key()`
- `PyThread_delete_key_value()`
- `PyThread_exit_thread()`
- `PyThread_free_lock()`
- `PyThread_get_key_value()`
- `PyThread_get_stacksize()`
- `PyThread_get_thread_ident()`
- `PyThread_get_thread_native_id()`
- `PyThread_init_thread()`
- `PyThread_release_lock()`
- `PyThread_set_key_value()`
- `PyThread_set_stacksize()`
- `PyThread_start_new_thread()`
- `PyThread_tss_alloc()`
- `PyThread_tss_create()`
- `PyThread_tss_delete()`
- `PyThread_tss_free()`
- `PyThread_tss_get()`
- `PyThread_tss_is_created()`
- `PyThread_tss_set()`
- `PyTraceBack_Here()`
- `PyTraceBack_Print()`
- `PyTraceBack_Type`
- `PyTupleIter_Type`
- `PyTuple_GetItem()`
- `PyTuple_GetSlice()`
- `PyTuple_New()`
- `PyTuple_Pack()`
- `PyTuple_SetItem()`
- `PyTuple_Size()`
- `PyTuple_Type`
- `PyTypeObject`
- `PyType_ClearCache()`

- `PyType_FromModuleAndSpec()`
- `PyType_FromSpec()`
- `PyType_FromSpecWithBases()`
- `PyType_GenericAlloc()`
- `PyType_GenericNew()`
- `PyType_GetFlags()`
- `PyType_GetModule()`
- `PyType_GetModuleState()`
- `PyType_GetSlot()`
- `PyType_IsSubtype()`
- `PyType_Modified()`
- `PyType_Ready()`
- `PyType_Slot`
- `PyType_Spec`
- `PyType_Type`
- `PyUnicodeDecodeError_Create()`
- `PyUnicodeDecodeError_GetEncoding()`
- `PyUnicodeDecodeError_GetEnd()`
- `PyUnicodeDecodeError_GetObject()`
- `PyUnicodeDecodeError_GetReason()`
- `PyUnicodeDecodeError_GetStart()`
- `PyUnicodeDecodeError_SetEnd()`
- `PyUnicodeDecodeError_SetReason()`
- `PyUnicodeDecodeError_SetStart()`
- `PyUnicodeEncodeError_GetEncoding()`
- `PyUnicodeEncodeError_GetEnd()`
- `PyUnicodeEncodeError_GetObject()`
- `PyUnicodeEncodeError_GetReason()`
- `PyUnicodeEncodeError_GetStart()`
- `PyUnicodeEncodeError_SetEnd()`
- `PyUnicodeEncodeError_SetReason()`
- `PyUnicodeEncodeError_SetStart()`
- `PyUnicodeIter_Type`
- `PyUnicodeTranslateError_GetEnd()`
- `PyUnicodeTranslateError_GetObject()`
- `PyUnicodeTranslateError_GetReason()`

- `PyUnicodeTranslateError_GetStart()`
- `PyUnicodeTranslateError_SetEnd()`
- `PyUnicodeTranslateError_SetReason()`
- `PyUnicodeTranslateError_SetStart()`
- `PyUnicode_Append()`
- `PyUnicode_AppendAndDel()`
- `PyUnicode_AsASCIIString()`
- `PyUnicode_AsCharmapString()`
- `PyUnicode_AsDecodedObject()`
- `PyUnicode_AsDecodedUnicode()`
- `PyUnicode_AsEncodedObject()`
- `PyUnicode_AsEncodedString()`
- `PyUnicode_AsEncodedUnicode()`
- `PyUnicode_AsLatin1String()`
- `PyUnicode_AsMBCSString()`
- `PyUnicode_AsRawUnicodeEscapeString()`
- `PyUnicode_AsUCS4()`
- `PyUnicode_AsUCS4Copy()`
- `PyUnicode_AsUTF16String()`
- `PyUnicode_AsUTF32String()`
- `PyUnicode_AsUTF8AndSize()`
- `PyUnicode_AsUTF8String()`
- `PyUnicode_AsUnicodeEscapeString()`
- `PyUnicode_AsWideChar()`
- `PyUnicode_AsWideCharString()`
- `PyUnicode_BuildEncodingMap()`
- `PyUnicode_Compare()`
- `PyUnicode_CompareWithASCIIString()`
- `PyUnicode_Concat()`
- `PyUnicode_Contains()`
- `PyUnicode_Count()`
- `PyUnicode_Decode()`
- `PyUnicode_DecodeASCII()`
- `PyUnicode_DecodeCharmap()`
- `PyUnicode_DecodeCodePageStateful()`
- `PyUnicode_DecodeFSDefault()`

- `PyUnicode_DecodeFSDefaultAndSize()`
- `PyUnicode_DecodeLatin1()`
- `PyUnicode_DecodeLocale()`
- `PyUnicode_DecodeLocaleAndSize()`
- `PyUnicode_DecodeMBCS()`
- `PyUnicode_DecodeMBCSStateful()`
- `PyUnicode_DecodeRawUnicodeEscape()`
- `PyUnicode_DecodeUTF16()`
- `PyUnicode_DecodeUTF16Stateful()`
- `PyUnicode_DecodeUTF32()`
- `PyUnicode_DecodeUTF32Stateful()`
- `PyUnicode_DecodeUTF7()`
- `PyUnicode_DecodeUTF7Stateful()`
- `PyUnicode_DecodeUTF8()`
- `PyUnicode_DecodeUTF8Stateful()`
- `PyUnicode_DecodeUnicodeEscape()`
- `PyUnicode_EncodeCodePage()`
- `PyUnicode_EncodeFSDefault()`
- `PyUnicode_EncodeLocale()`
- `PyUnicode_FSConverter()`
- `PyUnicode_FSDecoder()`
- `PyUnicode_Find()`
- `PyUnicode_FindChar()`
- `PyUnicode_Format()`
- `PyUnicode_FromEncodedObject()`
- `PyUnicode_FromFormat()`
- `PyUnicode_FromFormatV()`
- `PyUnicode_FromObject()`
- `PyUnicode_FromOrdinal()`
- `PyUnicode_FromString()`
- `PyUnicode_FromStringAndSize()`
- `PyUnicode_FromWideChar()`
- `PyUnicode_GetDefaultEncoding()`
- `PyUnicode_GetLength()`
- `PyUnicode_GetSize()`
- `PyUnicode_InternFromString()`

- `PyUnicode_InternImmortal()`
- `PyUnicode_InternInPlace()`
- `PyUnicode_IsIdentifier()`
- `PyUnicode_Join()`
- `PyUnicode_Partition()`
- `PyUnicode_RPartition()`
- `PyUnicode_RSplit()`
- `PyUnicode_ReadChar()`
- `PyUnicode_Replace()`
- `PyUnicode_Resize()`
- `PyUnicode_RichCompare()`
- `PyUnicode_Split()`
- `PyUnicode_Splitlines()`
- `PyUnicode_Substring()`
- `PyUnicode_Tailmatch()`
- `PyUnicode_Translate()`
- `PyUnicode_Type`
- `PyUnicode_WriteChar()`
- `PyVarObject`
- `PyVarObject.ob_base`
- `PyVarObject.ob_size`
- `PyWeakReference`
- `PyWeakref_GetObject()`
- `PyWeakref_NewProxy()`
- `PyWeakref_NewRef()`
- `PyWrapperDescr_Type`
- `PyWrapper_New()`
- `PyZip_Type`
- `Py_AddPendingCall()`
- `Py_AtExit()`
- `Py_BEGIN_ALLOW_THREADS`
- `Py_BLOCK_THREADS`
- `Py_BuildValue()`
- `Py_BytesMain()`
- `Py_CompileString()`
- `Py_DecRef()`

- `Py_DecodeLocale()`
- `Py_END_ALLOW_THREADS`
- `Py_EncodeLocale()`
- `Py_EndInterpreter()`
- `Py_EnterRecursiveCall()`
- `Py_Exit()`
- `Py_FatalError()`
- `Py_FileSystemDefaultEncodeErrors`
- `Py_FileSystemDefaultEncoding`
- `Py_Finalize()`
- `Py_FinalizeEx()`
- `Py_GenericAlias()`
- `Py_GenericAliasType`
- `Py_GetBuildInfo()`
- `Py_GetCompiler()`
- `Py_GetCopyright()`
- `Py_GetExecPrefix()`
- `Py_GetPath()`
- `Py_GetPlatform()`
- `Py_GetPrefix()`
- `Py_GetProgramFullPath()`
- `Py_GetProgramName()`
- `Py_GetPythonHome()`
- `Py_GetRecursionLimit()`
- `Py_GetVersion()`
- `Py_HasFileSystemDefaultEncoding`
- `Py_IncRef()`
- `Py_Initialize()`
- `Py_InitializeEx()`
- `Py_Is()`
- `Py_IsFalse()`
- `Py_IsInitialized()`
- `Py_IsNone()`
- `Py_IsTrue()`
- `Py_LeaveRecursiveCall()`
- `Py_Main()`

- `Py_MakePendingCalls()`
- `Py_NewInterpreter()`
- `Py_NewRef()`
- `Py_ReprEnter()`
- `Py_ReprLeave()`
- `Py_SetPath()`
- `Py_SetProgramName()`
- `Py_SetPythonHome()`
- `Py_SetRecursionLimit()`
- `Py_UCS4`
- `Py_UNBLOCK_THREADS`
- `Py_UTF8Mode`
- `Py_VaBuildValue()`
- `Py_XNewRef()`
- `Py_intptr_t`
- `Py_ssize_t`
- `Py_uintptr_t`
- `allocfunc`
- `binaryfunc`
- `descrgetfunc`
- `descrsetfunc`
- `destructor`
- `getattrfunc`
- `getattrofunc`
- `getiterfunc`
- `getter`
- `hashfunc`
- `initproc`
- `inquiry`
- `iternextfunc`
- `lenfunc`
- `newfunc`
- `objobjargproc`
- `objobjproc`
- `reprfunc`
- `richcmpfunc`



- *setattrfunc*
- *setattrofunc*
- *setter*
- *ssizeargfunc*
- *ssizeobjargproc*
- *ssizessizeargfunc*
- *ssizessizeobjargproc*
- *symtable*
- *ternaryfunc*
- *traverseproc*
- *unaryfunc*
- *visitproc*



---

A camada de nível muito alto

---

As funções neste capítulo permitirão que você execute um código-fonte Python fornecido em um arquivo ou buffer, mas não permitirão que você interaja de forma mais detalhada com o interpretador.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are `Py_eval_input`, `Py_file_input`, and `Py_single_input`. These are described following the functions which accept them as parameters.

Note also that several of these functions take `FILE*` parameters. One particular issue which needs to be handled carefully is that the `FILE` structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that `FILE*` parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

int **Py\_Main** (int *argc*, wchar\_t \*\**argv*)

*Part of the Stable ABI.* The main program for the standard interpreter. This is made available for programs which embed Python. The *argc* and *argv* parameters should be prepared exactly as those which are passed to a C program's `main()` function (converted to `wchar_t` according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled `SystemExit` is raised, this function will not return 1, but exit the process, as long as `Py_InspectFlag` is not set.

int **Py\_BytesMain** (int *argc*, char \*\**argv*)

*Part of the Stable ABI since version 3.8.* Similar to `Py_Main()` but *argv* is an array of bytes strings.

Novo na versão 3.8.

int **PyRun\_AnyFile** (FILE \**fp*, const char \**filename*)

Esta é uma interface simplificada para `PyRun_AnyFileExFlags()` abaixo, deixando *closeit* definido como 0 e *flags* definido como NULL.

int **PyRun\_AnyFileFlags** (FILE \**fp*, const char \**filename*, *PyCompilerFlags* \**flags*)

Esta é uma interface simplificada para `PyRun_AnyFileExFlags()` abaixo, deixando o argumento *closeit* definido como 0.

int **PyRun\_AnyFileEx** (FILE \*fp, const char \*filename, int closeit)

Esta é uma interface simplificada para `PyRun_AnyFileExFlags()` abaixo, deixando o argumento *flags* definido como NULL.

int **PyRun\_AnyFileExFlags** (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

Se *fp* se referir a um arquivo associado a um dispositivo interativo (entrada de console ou terminal ou pseudo-terminal Unix), retorna o valor de `PyRun_InteractiveLoop()`, caso contrário, retorna o resultado de `PyRun_SimpleFile()`. *filename* é decodificado da codificação do sistema de arquivos (`sys.getfilesystemencoding()`). Se *filename* for NULL, esta função usa "???" como o nome do arquivo. Se *closeit* for verdadeiro, o arquivo será fechado antes de `PyRun_SimpleFileExFlags()` retornar.

int **PyRun\_SimpleString** (const char \*command)

Esta é uma interface simplificada para `PyRun_SimpleStringFlags()` abaixo, deixando o argumento `PyCompilerFlags*` definido como NULL.

int **PyRun\_SimpleStringFlags** (const char \*command, PyCompilerFlags \*flags)

Executa o código-fonte Python de *command* no módulo `__main__` de acordo com o argumento *flags*. Se `__main__` ainda não existir, ele será criado. Retorna 0 em caso de sucesso ou -1 se uma exceção foi gerada. Se houve um erro, não há como obter as informações da exceção. Para o significado de *flags*, veja abaixo.

Note that if an otherwise unhandled `SystemExit` is raised, this function will not return -1, but exit the process, as long as `Py_InspectFlag` is not set.

int **PyRun\_SimpleFile** (FILE \*fp, const char \*filename)

Esta é uma interface simplificada para `PyRun_SimpleFileExFlags()` abaixo, deixando *closeit* definido como 0 e *flags* definido como NULL.

int **PyRun\_SimpleFileEx** (FILE \*fp, const char \*filename, int closeit)

Esta é uma interface simplificada para `PyRun_SimpleFileExFlags()` abaixo, deixando o *flags* definido como NULL.

int **PyRun\_SimpleFileExFlags** (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

Semelhante a `PyRun_SimpleStringFlags()`, mas o código-fonte Python é lido de *fp* em vez de uma string na memória. *filename* deve ser o nome do arquivo, ele é decodificado a partir do *tratador de erros e codificação do sistema de arquivos*. Se *closeit* for true, o arquivo será fechado antes que `PyRun_SimpleFileExFlags()` retorne.

---

**Nota:** No Windows, *fp* deve ser aberto como modo binário (por exemplo, `fopen(filename, "rb")`). Caso contrário, o Python pode não manipular corretamente o arquivo de script com final de linha LF.

---

int **PyRun\_InteractiveOne** (FILE \*fp, const char \*filename)

Esta é uma interface simplificada para `PyRun_InteractiveOneFlags()` abaixo, deixando *flags* definido como NULL.

int **PyRun\_InteractiveOneFlags** (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Lê e executa uma única instrução de um arquivo associado a um dispositivo interativo de acordo com o argumento *flags*. O usuário será solicitado usando `sys.ps1` e `sys.ps2`. *filename* é decodificado a partir do *tratador de erros e codificação do sistema de arquivos*.

Retorna 0 quando a entrada foi executada com sucesso, -1 se houve uma exceção ou um código de erro do arquivo de inclusão `errcode.h` distribuído como parte do Python se houve um erro de análise. (Observe que `errcode.h` não é incluído por `Python.h`, então deve ser incluído especificamente se necessário.)

int **PyRun\_InteractiveLoop** (FILE \*fp, const char \*filename)

Esta é uma interface simplificada para `PyRun_InteractiveLoopFlags()` abaixo, deixando *flags* definido como NULL.

**int PyRun\_InteractiveLoopFlags** (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Lê e executa instruções de um arquivo associado a um dispositivo interativo até que o EOF seja atingido. O usuário será consultado usando `sys.ps1` e `sys.ps2`. *filename* é decodificado a partir do *tratador de erros e codificação do sistema de arquivos*. Retorna 0 no EOF ou um número negativo em caso de falha.

**int (\*PyOS\_InputHook)** (void)

*Part of the Stable ABI*. Pode ser definido para apontar para uma função com o protótipo `int func(void)`. A função será chamada quando o prompt do interpretador do Python estiver prestes a ficar ocioso e aguardar a entrada do usuário no terminal. O valor de retorno é ignorado. A substituição deste hook pode ser usada para integrar o prompt do interpretador com outros laços de eventos, como feito em `Modules/_tkinter.c` no código-fonte do Python.

**char (\*PyOS\_ReadlineFunctionPointer)** (FILE\*, FILE\*, const char\*)

Pode ser definido para apontar para uma função com o protótipo `char *func(FILE *stdin, FILE *stdout, char *prompt)`, substituindo a função padrão usada para ler uma única linha de entrada no prompt do interpretador. Espera-se que a função produza a string *prompt* se não for NULL e, em seguida, leia uma linha de entrada do arquivo de entrada padrão fornecido, retornando a string resultante. Por exemplo, o módulo `readline` define este gancho para fornecer recursos de edição de linha e preenchimento de tabulação.

O resultado deve ser uma string alocada por `PyMem_RawMalloc()` ou `PyMem_RawRealloc()`, ou NULL se ocorrer um erro.

Alterado na versão 3.4: O resultado deve ser alocado por `PyMem_RawMalloc()` ou `PyMem_RawRealloc()`, em vez de ser alocado por `PyMem_Malloc()` ou `PyMem_Realloc()`.

**PyObject \*PyRun\_String** (const char \*str, int start, PyObject \*globals, PyObject \*locals)

*Retorna valor: Nova referência.* Esta é uma interface simplificada para `PyRun_StringFlags()` abaixo, deixando *flags* definido como NULL.

**PyObject \*PyRun\_StringFlags** (const char \*str, int start, PyObject \*globals, PyObject \*locals, PyCompilerFlags \*flags)

*Retorna valor: Nova referência.* Executa o código-fonte Python de *str* no contexto especificado pelos objetos *globals* e *locals* com os sinalizadores do compilador especificados por *flags*. *globals* deve ser um dicionário; *locals* pode ser qualquer objeto que implemente o protocolo de mapeamento. O parâmetro *start* especifica o token de início que deve ser usado para analisar o código-fonte.

Retorna o resultado da execução do código como um objeto Python, ou NULL se uma exceção foi levantada.

**PyObject \*PyRun\_File** (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals)

*Retorna valor: Nova referência.* Esta é uma interface simplificada para `PyRun_FileExFlags()` abaixo, deixando *closeit* definido como 0 e *flags* definido como NULL.

**PyObject \*PyRun\_FileEx** (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit)

*Retorna valor: Nova referência.* Esta é uma interface simplificada para `PyRun_FileExFlags()` abaixo, deixando *flags* definido como NULL.

**PyObject \*PyRun\_FileFlags** (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, PyCompilerFlags \*flags)

*Retorna valor: Nova referência.* Esta é uma interface simplificada para `PyRun_FileExFlags()` abaixo, deixando *closeit* definido como 0.

**PyObject \*PyRun\_FileExFlags** (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit, PyCompilerFlags \*flags)

*Retorna valor: Nova referência.* Semelhante a `PyRun_StringFlags()`, mas o código-fonte Python é lido de *fp* em vez de uma string na memória. *filename* deve ser o nome do arquivo, ele é decodificado a partir do *tratador de erros e codificação do sistema de arquivos*. Se *closeit* for true, o arquivo será fechado antes que `PyRun_FileExFlags()` retorne.

**PyObject \*Py\_CompileString** (const char \*str, const char \*filename, int start)

*Retorna valor: Nova referência.* *Part of the Stable ABI*. Esta é uma interface simplificada para

*Py\_CompileStringFlags()* abaixo, deixando *flags* definido como `NULL`.

*PyObject* \***Py\_CompileStringFlags** (`const` char \**str*, `const` char \**filename*, int *start*, *PyCompilerFlags* \**flags*)

Retorna valor: Nova referência. Esta é uma interface simplificada para *Py\_CompileStringExFlags()* abaixo, com *optimize* definido como `-1`.

*PyObject* \***Py\_CompileStringObject** (`const` char \**str*, *PyObject* \**filename*, int *start*, *PyCompilerFlags* \**flags*, int *optimize*)

Retorna valor: Nova referência. Parse and compile the Python source code in *str*, returning the resulting code object. The start token is given by *start*; this can be used to constrain the code which can be compiled and should be `Py_eval_input`, `Py_file_input`, or `Py_single_input`. The filename specified by *filename* is used to construct the code object and may appear in tracebacks or `SyntaxError` exception messages. This returns `NULL` if the code cannot be parsed or compiled.

O inteiro *optimize* especifica o nível de otimização do compilador; um valor de `-1` seleciona o nível de otimização do interpretador dado pela opção `-O`. Níveis explícitos são `0` (nenhuma otimização; `__debug__` é verdadeiro), `1` (instruções `assert` são removidas, `__debug__` é falso) ou `2` (strings de documentação também são removidas).

Novo na versão 3.4.

*PyObject* \***Py\_CompileStringExFlags** (`const` char \**str*, `const` char \**filename*, int *start*, *PyCompilerFlags* \**flags*, int *optimize*)

Retorna valor: Nova referência. Como *Py\_CompileStringObject()*, mas *filename* é uma string de bytes decodificada a partir do *tratador de erros e codificação do sistema de arquivos*.

Novo na versão 3.2.

*PyObject* \***PyEval\_EvalCode** (*PyObject* \**co*, *PyObject* \**globals*, *PyObject* \**locals*)

Retorna valor: Nova referência. Part of the *Stable ABI*. Esta é uma interface simplificada para *PyEval\_EvalCodeEx()*, com apenas o objeto código e variáveis locais e globais. Os outros argumentos são definidos como `NULL`.

*PyObject* \***PyEval\_EvalCodeEx** (*PyObject* \**co*, *PyObject* \**globals*, *PyObject* \**locals*, *PyObject* \*`const` \**args*, int *argcount*, *PyObject* \*`const` \**kws*, int *kwcount*, *PyObject* \*`const` \**defs*, int *defcount*, *PyObject* \**kwdefs*, *PyObject* \**closure*)

Retorna valor: Nova referência. Part of the *Stable ABI*. Avalia um objeto código pré-compilado, dado um ambiente particular para sua avaliação. Este ambiente consiste em um dicionário de variáveis globais, um objeto mapeamento de variáveis locais, vetores de argumentos, nomeados e padrões, um dicionário de valores padrões para argumentos *somente-nomeados* e uma tupla de clausura de células.

## type PyFrameObject

Part of the *Limited API* (as an *opaque struct*). The C structure of the objects used to describe frame objects. The fields of this type are subject to change at any time.

*PyObject* \***PyEval\_EvalFrame** (*PyFrameObject* \**f*)

Retorna valor: Nova referência. Part of the *Stable ABI*. Avalia um quadro de execução. Esta é uma interface simplificada para *PyEval\_EvalFrameEx()*, para retrocompatibilidade.

*PyObject* \***PyEval\_EvalFrameEx** (*PyFrameObject* \**f*, int *throwflag*)

Retorna valor: Nova referência. Part of the *Stable ABI*. Esta é a função principal e sem retoques da interpretação Python. O objeto código associado ao quadro de execução *f* é executado, interpretando bytecode e executando chamadas conforme necessário. O parâmetro adicional *throwflag* pode ser ignorado na maioria das vezes - se verdadeiro, ele faz com que uma exceção seja levantada imediatamente; isso é usado para os métodos `throw()` de objetos geradores.

Alterado na versão 3.4: Essa função agora inclui uma asserção de depuração para ajudar a garantir que ela não descarte silenciosamente uma exceção ativa.

int **PyEval\_MergeCompilerFlags** (*PyCompilerFlags* \**cf*)

Esta função altera os sinalizadores do quadro de avaliação atual e retorna verdadeiro em caso de sucesso e falso em

caso de falha.

int **Py\_eval\_input**

O símbolo inicial da gramática Python para expressões isoladas; para uso com *Py\_CompileString()*.

int **Py\_file\_input**

O símbolo de início da gramática Python para sequências de instruções conforme lidas de um arquivo ou outra fonte; para uso com *Py\_CompileString()*. Este é o símbolo a ser usado ao compilar código-fonte Python arbitrariamente longo.

int **Py\_single\_input**

O símbolo de início da gramática Python para uma única declaração; para uso com *Py\_CompileString()*. Este é o símbolo usado para o laço do interpretador interativo.

**struct PyCompilerFlags**

Esta é a estrutura usada para manter os sinalizadores do compilador. Em casos onde o código está apenas sendo compilado, ele é passado como `int flags`, e em casos onde o código está sendo executado, ele é passado como `PyCompilerFlags *flags`. Neste caso, `from __future__ import` pode modificar *flags*.

Whenever `PyCompilerFlags *flags` is NULL, `cf_flags` is treated as equal to 0, and any modification due to `from __future__ import` is discarded.

int **cf\_flags**

Sinalizadores do compilador.

int **cf\_feature\_version**

*cf\_feature\_version* é a versão secundária do Python. Deve ser inicializada como `PY_MINOR_VERSION`.

The field is ignored by default, it is used if and only if `PyCF_ONLY_AST` flag is set in *cf\_flags*.

Alterado na versão 3.8: Adicionado campo *cf\_feature\_version*.

int **CO\_FUTURE\_DIVISION**

Este bit pode ser definido em *flags* para fazer com que o operador de divisão / seja interpretado como “divisão verdadeira” de acordo com a [PEP 238](#).





---

Contagem de Referências

---

As macros nesta seção são usadas para gerenciar contagens de referências de objetos Python.

void **Py\_INCREF** (*PyObject* \**o*)

Indicate taking a new *strong reference* to object *o*, indicating it is in use and should not be destroyed.

This function is usually used to convert a *borrowed reference* to a *strong reference* in-place. The *Py\_NewRef* () function can be used to create a new *strong reference*.

When done using the object, release it by calling *Py\_DECREF* () .

The object must not be NULL; if you aren't sure that it isn't NULL, use *Py\_X\_INCREF* () .

Do not expect this function to actually modify *o* in any way.

void **Py\_X\_INCREF** (*PyObject* \**o*)

Similar to *Py\_INCREF* () , but the object *o* can be NULL, in which case this has no effect.

See also *Py\_XNewRef* () .

*PyObject* \***Py\_NewRef** (*PyObject* \**o*)

*Part of the Stable ABI since version 3.10.* Create a new *strong reference* to an object: call *Py\_INCREF* () on *o* and return the object *o*.

When the *strong reference* is no longer needed, *Py\_DECREF* () should be called on it to release the reference.

The object *o* must not be NULL; use *Py\_XNewRef* () if *o* can be NULL.

Por exemplo:

```
Py_INCREF(obj);
self->attr = obj;
```

can be written as:

```
self->attr = Py_NewRef(obj);
```

See also *Py\_INCREF* () .

Novo na versão 3.10.

*PyObject* \***Py\_XNewRef** (*PyObject* \**o*)

Part of the *Stable ABI* since version 3.10. Similar to *Py\_NewRef()*, but the object *o* can be NULL.

If the object *o* is NULL, the function just returns NULL.

Novo na versão 3.10.

void **Py\_DECREF** (*PyObject* \**o*)

Release a *strong reference* to object *o*, indicating the reference is no longer used.

Once the last *strong reference* is released (i.e. the object's reference count reaches 0), the object's type's deallocation function (which must not be NULL) is invoked.

This function is usually used to delete a *strong reference* before exiting its scope.

The object must not be NULL; if you aren't sure that it isn't NULL, use *Py\_XDECREF()*.

Do not expect this function to actually modify *o* in any way.

**Aviso:** A função de desalocação pode fazer com que o código Python arbitrário seja invocado (por exemplo, quando uma instância de classe com um método `__del__()` é desalocada). Embora as exceções em tal código não sejam propagadas, o código executado tem acesso livre a todas as variáveis globais do Python. Isso significa que qualquer objeto que é alcançável de uma variável global deve estar em um estado consistente antes de *Py\_DECREF()* ser invocado. Por exemplo, o código para excluir um objeto de uma lista deve copiar uma referência ao objeto excluído em uma variável temporária, atualizar a estrutura de dados da lista e então chamar *Py\_DECREF()* para a variável temporária.

void **Py\_XDECREF** (*PyObject* \**o*)

Similar to *Py\_DECREF()*, but the object *o* can be NULL, in which case this has no effect. The same warning from *Py\_DECREF()* applies here as well.

void **Py\_CLEAR** (*PyObject* \**o*)

Release a *strong reference* for object *o*. The object may be NULL, in which case the macro has no effect; otherwise the effect is the same as for *Py\_DECREF()*, except that the argument is also set to NULL. The warning for *Py\_DECREF()* does not apply with respect to the object passed because the macro carefully uses a temporary variable and sets the argument to NULL before releasing the reference.

It is a good idea to use this macro whenever releasing a reference to an object that might be traversed during garbage collection.

void **Py\_IncRef** (*PyObject* \**o*)

Part of the *Stable ABI*. Indicate taking a new *strong reference* to object *o*. A function version of *Py\_XINCREF()*. It can be used for runtime dynamic embedding of Python.

void **Py\_DecRef** (*PyObject* \**o*)

Part of the *Stable ABI*. Release a *strong reference* to object *o*. A function version of *Py\_XDECREF()*. It can be used for runtime dynamic embedding of Python.

As seguintes funções ou macros são apenas para uso dentro do núcleo do interpretador: `_Py_Dealloc()`, `_Py_ForgetReference()`, `_Py_NewReference()`, bem como a variável global `_Py_RefTotal`.

---

## Manipulando Exceções

---

As funções descritas nesse capítulo permitem você tratar e gerar exceções em Python. É importante entender alguns princípios básicos no tratamento de exceção no Python. Funciona de forma parecida com a variável POSIX `errno`: existe um indicador global (por thread) do último erro ocorrido. A maioria das funções da API C não limpa isso com êxito, mas indica a causa do erro na falha. A maioria das funções da API retorna um indicador de erro, geralmente, `NULL` se eles devem retornar um ponteiro, ou `-1` se retornarem um inteiro (exceção: as funções `PyArg_*` retornam `1` para sucesso e `0` para falha).

Concretamente, o indicador de erro consiste em três ponteiros de objeto: o tipo da exceção, o valor da exceção e o objeto de traceback. Qualquer um desses ponteiros pode ser `NULL` se não definido (embora algumas combinações sejam proibidas, por exemplo, você não pode ter um retorno não `NULL` se o tipo de exceção for `NULL`).

Quando uma função deve falhar porque devido à falha de alguma função que ela chamou, ela geralmente não define o indicador de erro; a função que ela chamou já o definiu. Ela é responsável por manipular o erro e limpar a exceção ou retornar após limpar todos os recursos que possui (como referências a objetos ou alocações de memória); ela *não* deve continuar normalmente se não estiver preparada para lidar com o erro. Se estiver retornando devido a um erro, é importante indicar ao chamador que um erro foi definido. Se o erro não for manipulado ou propagado com cuidado, chamadas adicionais para a API Python/C podem não se comportar conforme o esperado e podem falhar de maneiras misteriosas.

---

**Nota:** O indicador de erro **not** é resultado de `sys.exc_info()`. O primeiro corresponde a uma exceção que ainda não foi capturada (e, portanto, ainda está se propagando), enquanto o segundo retorna uma exceção após ser capturada (e, portanto, parou de se propagar).

---

## 5.1 Impressão e limpeza

void **PyErr\_Clear** ()

*Part of the Stable ABI.* Limpe o indicador de erro. Se o indicador de erro não estiver definido, não haverá efeito.

void **PyErr\_PrintEx** (int *set\_sys\_last\_vars*)

*Part of the Stable ABI.* Print a standard traceback to `sys.stderr` and clear the error indicator. **Unless** the error is a `SystemExit`, in that case no traceback is printed and the Python process will exit with the error code specified by the `SystemExit` instance.

Chame esta função **apenas** quando o indicador de erro estiver definido. Caso contrário, causará um erro fatal!

If *set\_sys\_last\_vars* is nonzero, the variables `sys.last_type`, `sys.last_value` and `sys.last_traceback` will be set to the type, value and traceback of the printed exception, respectively.

void **PyErr\_Print** ()

*Part of the Stable ABI.* Apelido para `PyErr_PrintEx(1)`.

void **PyErr\_WriteUnraisable** (*PyObject* \**obj*)

*Part of the Stable ABI.* Chama `sys.unraisablehook()` usando a exceção atual e o argumento *obj*.

This utility function prints a warning message to `sys.stderr` when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an `__del__()` method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

Uma exceção deve ser definida ao chamar essa função.

## 5.2 Lançando exceções

Essas funções ajudam a definir o indicador de erro do thread. Por conveniência, algumas dessas funções sempre retornam um ponteiro `NULL` ao usar instrução com `return`.

void **PyErr\_SetString** (*PyObject* \**type*, const char \**message*)

*Part of the Stable ABI.* This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. `PyExc_RuntimeError`. You need not create a new *strong reference* to it (e.g. with `Py_INCREF()`). The second argument is an error message; it is decoded from 'utf-8'.

void **PyErr\_SetObject** (*PyObject* \**type*, *PyObject* \**value*)

*Part of the Stable ABI.* Essa função é semelhante à `PyErr_SetString()` mas permite especificar um objeto Python arbitrário para o valor da exceção.

*PyObject* \***PyErr\_Format** (*PyObject* \**exception*, const char \**format*, ...)

*Retorna valor:* Sempre `NULL`. *Part of the Stable ABI.* This function sets the error indicator and returns `NULL`. *exception* should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in `PyUnicode_FromFormat()`. *format* is an ASCII-encoded string.

*PyObject* \***PyErr\_FormatV** (*PyObject* \**exception*, const char \**format*, va\_list *vargs*)

*Retorna valor:* Sempre `NULL`. *Part of the Stable ABI since version 3.5.* Igual a `PyErr_Format()`, mas usando o argumento *va\_list* em vez de um número variável de argumentos.

Novo na versão 3.5.

void **PyErr\_SetNone** (*PyObject* \**type*)

*Part of the Stable ABI.* Isso é uma abreviação para `PyErr_SetObject(type, Py_None)`.

**int PyErr\_BadArgument ()**

Part of the [Stable ABI](#). This is a shorthand for `PyErr_SetString(PyExc_TypeError, message)`, where *message* indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

**PyObject \*PyErr\_NoMemory ()**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#). Essa é uma abreviação para `PyErr_SetNone(PyExc_MemoryError)`; que retorna NULL para que uma função de alocação de objeto possa escrever `return PyErr_NoMemory()`; quando ficar sem memória.

**PyObject \*PyErr\_SetFromErrno (PyObject \*type)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#). This is a convenience function to raise an exception when a C library function has returned an error and set the C variable `errno`. It constructs a tuple object whose first item is the integer `errno` value and whose second item is the corresponding error message (gotten from `strerror()`), and then calls `PyErr_SetObject(type, object)`. On Unix, when the `errno` value is `EINTR`, indicating an interrupted system call, this calls `PyErr_CheckSignals()`, and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write `return PyErr_SetFromErrno(type)`; when the system call returns an error.

**PyObject \*PyErr\_SetFromErrnoWithFilenameObject (PyObject \*type, PyObject \*filenameObject)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#). Similar to `PyErr_SetFromErrno()`, with the additional behavior that if *filenameObject* is not NULL, it is passed to the constructor of *type* as a third parameter. In the case of `OSError` exception, this is used to define the `filename` attribute of the exception instance.

**PyObject \*PyErr\_SetFromErrnoWithFilenameObjects (PyObject \*type, PyObject \*filenameObject, PyObject \*filenameObject2)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) since version 3.7. Similar to `PyErr_SetFromErrnoWithFilenameObject()`, but takes a second filename object, for raising errors when a function that takes two filenames fails.

Novo na versão 3.4.

**PyObject \*PyErr\_SetFromErrnoWithFilename (PyObject \*type, const char \*filename)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#). Similar to `PyErr_SetFromErrnoWithFilenameObject()`, but the filename is given as a C string. *filename* is decoded from the *filesystem encoding and error handler*.

**PyObject \*PyErr\_SetFromWindowsError (int ierr)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. This is a convenience function to raise `WindowsError`. If called with *ierr* of 0, the error code returned by a call to `GetLastError()` is used instead. It calls the Win32 function `FormatMessage()` to retrieve the Windows description of error code given by *ierr* or `GetLastError()`, then it constructs a tuple object whose first item is the *ierr* value and whose second item is the corresponding error message (gotten from `FormatMessage()`), and then calls `PyErr_SetObject(PyExc_WindowsError, object)`. This function always returns NULL.

Disponibilidade: Windows.

**PyObject \*PyErr\_SetExcFromWindowsError (PyObject \*type, int ierr)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. Similar to `PyErr_SetFromWindowsError()`, with an additional parameter specifying the exception type to be raised.

Disponibilidade: Windows.

**PyObject \*PyErr\_SetFromWindowsErrorWithFilename (int ierr, const char \*filename)**

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. Similar à `PyErr_SetFromWindowsErrorWithFilenameObject()`, mas o nome do arquivo é dados como uma String C. O nome do arquivo é decodificado a partir do sistema de arquivos (`os.fsdecode()`).

Disponibilidade: Windows.

*PyObject* \*PyErr\_SetExcFromWindowsErrWithFilenameObject (*PyObject* \*type, int ierr, *PyObject* \*filename)

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. Similar to `PyErr_SetFromWindowsErrWithFilenameObject()`, with an additional parameter specifying the exception type to be raised.

Disponibilidade: Windows.

*PyObject* \*PyErr\_SetExcFromWindowsErrWithFilenameObjects (*PyObject* \*type, int ierr, *PyObject* \*filename, *PyObject* \*filename2)

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. Similar à `PyErr_SetExcFromWindowsErrWithFilenameObject()`, mas aceita um segundo caminho do objeto.

Disponibilidade: Windows.

Novo na versão 3.4.

*PyObject* \*PyErr\_SetExcFromWindowsErrWithFilename (*PyObject* \*type, int ierr, const char \*filename)

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) on Windows since version 3.7. Similar à `PyErr_SetFromWindowsErrWithFilename()`, com um parâmetro adicional especificando o tipo de exceção a ser gerado.

Disponibilidade: Windows.

*PyObject* \*PyErr\_SetImportError (*PyObject* \*msg, *PyObject* \*name, *PyObject* \*path)

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) since version 3.7. This is a convenience function to raise `ImportError`. *msg* will be set as the exception's message string. *name* and *path*, both of which can be NULL, will be set as the `ImportError`'s respective name and path attributes.

Novo na versão 3.3.

*PyObject* \*PyErr\_SetImportErrorSubclass (*PyObject* \*exception, *PyObject* \*msg, *PyObject* \*name, *PyObject* \*path)

Retorna valor: Sempre NULL. Part of the [Stable ABI](#) since version 3.6. Muito parecido com `PyErr_SetImportError()` mas a função permite especificar uma subclasse de `ImportError` para levantar uma exceção.

Novo na versão 3.6.

void PyErr\_SyntaxLocationObject (*PyObject* \*filename, int lineno, int col\_offset)

Set file, line, and offset information for the current exception. If the current exception is not a `SyntaxError`, then it sets additional attributes, which make the exception printing subsystem think the exception is a `SyntaxError`.

Novo na versão 3.4.

void PyErr\_SyntaxLocationEx (const char \*filename, int lineno, int col\_offset)

Part of the [Stable ABI](#) since version 3.7. Like `PyErr_SyntaxLocationObject()`, but *filename* is a byte string decoded from the *filesystem encoding and error handler*.

Novo na versão 3.2.

void PyErr\_SyntaxLocation (const char \*filename, int lineno)

Part of the [Stable ABI](#). Like `PyErr_SyntaxLocationEx()`, but the *col\_offset* parameter is omitted.

void PyErr\_BadInternalCall ()

Part of the [Stable ABI](#). This is a shorthand for `PyErr_SetString(PyExc_SystemError, message)`, where *message* indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

## 5.3 Emitindo advertências

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python `warnings` module. They normally print a warning message to `sys.stderr`; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example, `Py_DECREF()` owned references and return an error value).

int **PyErr\_WarnEx** (*PyObject* \*category, const char \*message, *Py\_ssize\_t* stack\_level)

*Part of the Stable ABI.* Issue a warning message. The *category* argument is a warning category (see below) or NULL; the *message* argument is a UTF-8 encoded string. *stack\_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack\_level* of 1 is the function calling `PyErr_WarnEx()`, 2 is the function above that, and so forth.

Warning categories must be subclasses of `PyExc_Warning`; `PyExc_Warning` is a subclass of `PyExc_Exception`; the default warning category is `PyExc_RuntimeWarning`. The standard Python warning categories are available as global variables whose names are enumerated at *Categorias de aviso padrão*.

For information about warning control, see the documentation for the `warnings` module and the `-W` option in the command line documentation. There is no C API for warning control.

int **PyErr\_WarnExplicitObject** (*PyObject* \*category, *PyObject* \*message, *PyObject* \*filename, int lineno, *PyObject* \*module, *PyObject* \*registry)

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function `warnings.warn_explicit()`; see there for more information. The *module* and *registry* arguments may be set to NULL to get the default effect described there.

Novo na versão 3.4.

int **PyErr\_WarnExplicit** (*PyObject* \*category, const char \*message, const char \*filename, int lineno, const char \*module, *PyObject* \*registry)

*Part of the Stable ABI.* Similar to `PyErr_WarnExplicitObject()` except that *message* and *module* are UTF-8 encoded strings, and *filename* is decoded from the *filesystem encoding and error handler*.

int **PyErr\_WarnFormat** (*PyObject* \*category, *Py\_ssize\_t* stack\_level, const char \*format, ...)

*Part of the Stable ABI.* Function similar to `PyErr_WarnEx()`, but use `PyUnicode_FromFormat()` to format the warning message. *format* is an ASCII-encoded string.

Novo na versão 3.2.

int **PyErr\_ResourceWarning** (*PyObject* \*source, *Py\_ssize\_t* stack\_level, const char \*format, ...)

*Part of the Stable ABI since version 3.6.* Function similar to `PyErr_WarnFormat()`, but *category* is `ResourceWarning` and it passes *source* to `warnings.WarningMessage()`.

Novo na versão 3.6.



## 5.4 Consultando o indicador de erro

*PyObject* \*PyErr\_Occurred()

*Retorna valor:* Referência emprestada. *Part of the Stable ABI.* Test whether the error indicator is set. If set, return the exception *type* (the first argument to the last call to one of the PyErr\_Set\* functions or to PyErr\_Restore()). If not set, return NULL. You do not own a reference to the return value, so you do not need to Py\_DECREF() it.

The caller must hold the GIL.

---

**Nota:** Do not compare the return value to a specific exception; use PyErr\_ExceptionMatches() instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

---

int PyErr\_ExceptionMatches(PyObject \*exc)

*Part of the Stable ABI.* Equivalent to PyErr\_GivenExceptionMatches(PyErr\_Occurred(), exc). This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

int PyErr\_GivenExceptionMatches(PyObject \*given, PyObject \*exc)

*Part of the Stable ABI.* Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

void PyErr\_Fetch(PyObject \*\*ptype, PyObject \*\*pvalue, PyObject \*\*ptraceback)

*Part of the Stable ABI.* Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to NULL. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be NULL even when the type object is not.

---

**Nota:** Esta função, normalmente, é usada apenas pelo código que precisa capturar exceções ou pelo código que precisa salvar e restaurar temporariamente o indicador de erro. Por exemplo:

```
{
    PyObject *type, *value, *traceback;
    PyErr_Fetch(&type, &value, &traceback);

    /* ... code that might produce other errors ... */

    PyErr_Restore(type, value, traceback);
}
```

void PyErr\_Restore(PyObject \*type, PyObject \*value, PyObject \*traceback)

*Part of the Stable ABI.* Set the error indicator from the three objects. If the error indicator is already set, it is cleared first. If the objects are NULL, the error indicator is cleared. Do not pass a NULL type and non-NULL value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

---

**Nota:** This function is normally only used by code that needs to save and restore the error indicator temporarily. Use PyErr\_Fetch() to save the current error indicator.

---



void **PyErr\_NormalizeException** (*PyObject \*\*exc*, *PyObject \*\*val*, *PyObject \*\*tb*)

Part of the [Stable ABI](#). Under certain circumstances, the values returned by `PyErr_Fetch()` below can be “unnormalized”, meaning that `*exc` is a class object but `*val` is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

**Nota:** This function *does not* implicitly set the `__traceback__` attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
    PyException_SetTraceback(val, tb);
}
```

void **PyErr\_GetExcInfo** (*PyObject \*\*ptype*, *PyObject \*\*pvalue*, *PyObject \*\*ptraceback*)

Part of the [Stable ABI](#) since version 3.7. Retrieve the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be `NULL`. Does not modify the exception info state.

**Nota:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_SetExcInfo()` to restore or clear the exception state.

Novo na versão 3.3.

void **PyErr\_SetExcInfo** (*PyObject \*type*, *PyObject \*value*, *PyObject \*traceback*)

Part of the [Stable ABI](#) since version 3.7. Set the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass `NULL` for all three arguments. For general rules about the three arguments, see `PyErr_Restore()`.

**Nota:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use `PyErr_GetExcInfo()` to read the exception state.

Novo na versão 3.3.

## 5.5 Tratamento de sinal

int **PyErr\_CheckSignals** ()

Part of the [Stable ABI](#). Essa função interage com o manipulador de sinais do Python.

If the function is called from the main thread and under the main Python interpreter, it checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the `signal` module is supported, this can invoke a signal handler written in Python.

The function attempts to handle all pending signals, and then returns 0. However, if a Python signal handler raises an exception, the error indicator is set and the function returns -1 immediately (such that other pending signals may not have been handled yet: they will be on the next `PyErr_CheckSignals()` invocation).

If the function is called from a non-main thread, or under a non-main Python interpreter, it does nothing and returns 0.

This function can be called by long-running C code that wants to be interruptible by user requests (such as by pressing Ctrl-C).

---

**Nota:** The default Python signal handler for `SIGINT` raises the `KeyboardInterrupt` exception.

---

void **PyErr\_SetInterrupt** ()

Part of the [Stable ABI](#). Simulate the effect of a `SIGINT` signal arriving. This is equivalent to `PyErr_SetInterruptEx (SIGINT)`.

---

**Nota:** This function is async-signal-safe. It can be called without the [GIL](#) and from a C signal handler.

---

int **PyErr\_SetInterruptEx** (int *signum*)

Part of the [Stable ABI](#) since version 3.10. Simulate the effect of a signal arriving. The next time `PyErr_CheckSignals` () is called, the Python signal handler for the given signal number will be called.

This function can be called by C code that sets up its own signal handling and wants Python signal handlers to be invoked as expected when an interruption is requested (for example when the user presses Ctrl-C to interrupt an operation).

If the given signal isn't handled by Python (it was set to `signal.SIG_DFL` or `signal.SIG_IGN`), it will be ignored.

If *signum* is outside of the allowed range of signal numbers, `-1` is returned. Otherwise, `0` is returned. The error indicator is never changed by this function.

---

**Nota:** This function is async-signal-safe. It can be called without the [GIL](#) and from a C signal handler.

---

Novo na versão 3.10.

int **PySignal\_SetWakeupFd** (int *fd*)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. *fd* must be non-blocking. It returns the previous such file descriptor.

O valor `-1` desabilita o recurso; este é o estado inicial. Isso é equivalente à `signal.set_wakeup_fd()` em Python, mas sem nenhuma verificação de erro. *fd* deve ser um descritor de arquivo válido. A função só deve ser chamada a partir da thread principal.

Alterado na versão 3.5: No Windows, a função agora também suporta manipuladores de socket.

## 5.6 Classes de exceção

*PyObject* \***PyErr\_NewException** (const char \**name*, *PyObject* \**base*, *PyObject* \**dict*)

Retorna valor: Nova referência. Part of the [Stable ABI](#). This utility function creates and returns a new exception class. The *name* argument must be the name of the new exception, a C string of the form `module.classname`. The *base* and *dict* arguments are normally `NULL`. This creates a class object derived from `Exception` (accessible in C as `PyExc_Exception`).

The `__module__` attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

*PyObject* \*PyErr\_NewExceptionWithDoc (const char \*name, const char \*doc, PyObject \*base, PyObject \*dict)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Same as `PyErr_NewException()`, except that the new exception class can easily be given a docstring: If *doc* is non-NULL, it will be used as the docstring for the exception class.

Novo na versão 3.2.

## 5.7 Objeto Exceção

*PyObject* \*PyException\_GetTraceback (PyObject \*ex)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Return the traceback associated with the exception as a new reference, as accessible from Python through `__traceback__`. If there is no traceback associated, this returns NULL.

int PyException\_SetTraceback (PyObject \*ex, PyObject \*tb)

Part of the [Stable ABI](#). Defina o retorno traceback (situação da pilha de execução) associado à exceção como *tb*. Use `Py_None` para limpá-lo.

*PyObject* \*PyException\_GetContext (PyObject \*ex)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Return the context (another exception instance during whose handling *ex* was raised) associated with the exception as a new reference, as accessible from Python through `__context__`. If there is no context associated, this returns NULL.

void PyException\_SetContext (PyObject \*ex, PyObject \*ctx)

Part of the [Stable ABI](#). Set the context associated with the exception to *ctx*. Use NULL to clear it. There is no type check to make sure that *ctx* is an exception instance. This steals a reference to *ctx*.

*PyObject* \*PyException\_GetCause (PyObject \*ex)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Return the cause (either an exception instance, or None, set by `raise ... from ...`) associated with the exception as a new reference, as accessible from Python through `__cause__`.

void PyException\_SetCause (PyObject \*ex, PyObject \*cause)

Part of the [Stable ABI](#). Set the cause associated with the exception to *cause*. Use NULL to clear it. There is no type check to make sure that *cause* is either an exception instance or None. This steals a reference to *cause*.

`__suppress_context__` para essa função é definido True, implicitamente.

## 5.8 Objetos de exceção Unicode

As seguintes funções são usadas para criar e modificar exceções Unicode de C.

*PyObject* \*PyUnicodeDecodeError\_Create (const char \*encoding, const char \*object, Py\_ssize\_t length, Py\_ssize\_t start, Py\_ssize\_t end, const char \*reason)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Create a `UnicodeDecodeError` object with the attributes *encoding*, *object*, *length*, *start*, *end* and *reason*. *encoding* and *reason* are UTF-8 encoded strings.

*PyObject* \*PyUnicodeEncodeError\_Create (const char \*encoding, const Py\_UNICODE \*object, Py\_ssize\_t length, Py\_ssize\_t start, Py\_ssize\_t end, const char \*reason)

Retorna valor: Nova referência. Create a `UnicodeEncodeError` object with the attributes *encoding*, *object*, *length*, *start*, *end* and *reason*. *encoding* and *reason* are UTF-8 encoded strings.

Obsoleto desde a versão 3.3: 3.11

`Py_UNICODE` is deprecated since Python 3.3. Please migrate to `PyObject_CallFunction (PyExc_UnicodeEncodeError, "sOnns", ...)`.

*PyObject \*PyUnicodeTranslateError\_Create (const Py\_UNICODE \*object, Py\_ssize\_t length, Py\_ssize\_t start, Py\_ssize\_t end, const char \*reason)*

*Retorna valor:* Nova referência. Create a `UnicodeTranslateError` object with the attributes *object*, *length*, *start*, *end* and *reason*. *reason* is a UTF-8 encoded string.

Obsoleto desde a versão 3.3: 3.11

`Py_UNICODE` is deprecated since Python 3.3. Please migrate to `PyObject_CallFunction (PyExc_UnicodeTranslateError, "sOnns", ...)`.

*PyObject \*PyUnicodeDecodeError\_GetEncoding (PyObject \*exc)*

*PyObject \*PyUnicodeEncodeError\_GetEncoding (PyObject \*exc)*

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Retorna o atributo *\*encoding\** dado no objeto da exceção.

*PyObject \*PyUnicodeDecodeError\_GetObject (PyObject \*exc)*

*PyObject \*PyUnicodeEncodeError\_GetObject (PyObject \*exc)*

*PyObject \*PyUnicodeTranslateError\_GetObject (PyObject \*exc)*

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Retorna o atributo *object* dado no objeto da exceção.

`int PyUnicodeDecodeError_GetStart (PyObject *exc, Py_ssize_t *start)`

`int PyUnicodeEncodeError_GetStart (PyObject *exc, Py_ssize_t *start)`

`int PyUnicodeTranslateError_GetStart (PyObject *exc, Py_ssize_t *start)`

Part of the [Stable ABI](#). Obtém o atributo *start* do objeto da exceção coloca-o em *\*start*. *start* não deve ser `NULL`. Retorna 0 se não der erro, -1 caso dê erro.

`int PyUnicodeDecodeError_SetStart (PyObject *exc, Py_ssize_t start)`

`int PyUnicodeEncodeError_SetStart (PyObject *exc, Py_ssize_t start)`

`int PyUnicodeTranslateError_SetStart (PyObject *exc, Py_ssize_t start)`

Part of the [Stable ABI](#). Define o atributo *start* dado no objeto de exceção *start*. Em caso de sucesso, retorna 0, em caso de falha, retorna -1.

`int PyUnicodeDecodeError_GetEnd (PyObject *exc, Py_ssize_t *end)`

`int PyUnicodeEncodeError_GetEnd (PyObject *exc, Py_ssize_t *end)`

`int PyUnicodeTranslateError_GetEnd (PyObject *exc, Py_ssize_t *end)`

Part of the [Stable ABI](#). Obtenha o atributo *end* dado no objeto de exceção e coloque *\*end*. O *end* não deve ser `NULL`. Em caso de sucesso, retorna 0, em caso de falha, retorna -1.

`int PyUnicodeDecodeError_SetEnd (PyObject *exc, Py_ssize_t end)`

`int PyUnicodeEncodeError_SetEnd (PyObject *exc, Py_ssize_t end)`

`int PyUnicodeTranslateError_SetEnd (PyObject *exc, Py_ssize_t end)`

Part of the [Stable ABI](#). Set the *end* attribute of the given exception object to *end*. Return 0 on success, -1 on failure.

*PyObject \*PyUnicodeDecodeError\_GetReason (PyObject \*exc)*

*PyObject \*PyUnicodeEncodeError\_GetReason (PyObject \*exc)*

*PyObject \*PyUnicodeTranslateError\_GetReason (PyObject \*exc)*

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Retorna o atributo *reason* dado no objeto da exceção.

`int PyUnicodeDecodeError_SetReason (PyObject *exc, const char *reason)`

`int PyUnicodeEncodeError_SetReason (PyObject *exc, const char *reason)`

`int PyUnicodeTranslateError_SetReason (PyObject *exc, const char *reason)`

Part of the [Stable ABI](#). Set the *reason* attribute of the given exception object to *reason*. Return 0 on success, -1 on failure.

## 5.9 Controle de recursão

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically). They are also not needed for *tp\_call* implementations because the *call protocol* takes care of recursion handling.

int **Py\_EnterRecursiveCall** (const char \*where)

*Part of the Stable ABI since version 3.9.* Marca um ponto em que a chamada recursiva em nível C está prestes a ser executada.

If `USE_STACKCHECK` is defined, this function checks if the OS stack overflowed using `PyOS_CheckStack()`. In this is the case, it sets a `MemoryError` and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a `RecursionError` is set and a nonzero value is returned. Otherwise, zero is returned.

*where* should be a UTF-8 encoded string such as " in instance check" to be concatenated to the `RecursionError` message caused by the recursion depth limit.

Alterado na versão 3.9: This function is now also available in the limited API.

void **Py\_LeaveRecursiveCall** (void)

*Part of the Stable ABI since version 3.9.* Ends a `Py_EnterRecursiveCall()`. Must be called once for each successful invocation of `Py_EnterRecursiveCall()`.

Alterado na versão 3.9: This function is now also available in the limited API.

Properly implementing *tp\_repr* for container types requires special recursion handling. In addition to protecting the stack, *tp\_repr* also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to `reprlib.recursive_repr()`.

int **Py\_ReprEnter** (PyObject \*object)

*Part of the Stable ABI.* Chamado no início da implementação *tp\_repr* para detectar ciclos.

If the object has already been processed, the function returns a positive integer. In that case the *tp\_repr* implementation should return a string object indicating a cycle. As examples, `dict` objects return `{...}` and `list` objects return `[...]`.

A função retornará um inteiro negativo se o limite da recursão for atingido. Nesse caso a implementação *tp\_repr* deverá, normalmente, retornar `NULL`.

Caso contrário, a função retorna zero e a implementação *tp\_repr* poderá continuar normalmente.

void **Py\_ReprLeave** (PyObject \*object)

*Part of the Stable ABI.* Termina a `Py_ReprEnter()`. Deve ser chamado uma vez para cada chamada de `Py_ReprEnter()` que retorna zero.

## 5.10 Exceções Padrão

All standard Python exceptions are available as global variables whose names are `PyExc_` followed by the Python exception name. These have the type `PyObject*`; they are all class objects. For completeness, here are all the variables:

Nome C	Nome Python	Notas
<code>PyExc_BaseException</code>	<code>BaseException</code>	<sup>1</sup>
<code>PyExc_Exception</code>	<code>Exception</code>	<sup>1</sup>
<code>PyExc_ArithmeticError</code>	<code>ArithmeticError</code>	<sup>1</sup>

continua na próxima página

Tabela 1 – continuação da página anterior

Nome C	Nome Python	Notas
PyExc_AssertionError	AssertionError	
PyExc_AttributeError	AttributeError	
PyExc_BlockingIOError	BlockingIOError	
PyExc_BrokenPipeError	BrokenPipeError	
PyExc_BufferError	BufferError	
PyExc_ChildProcessError	ChildProcessError	
PyExc_ConnectionAbortedError	ConnectionAbortedError	
PyExc_ConnectionError	ConnectionError	
PyExc_ConnectionRefusedError	ConnectionRefusedError	
PyExc_ConnectionResetError	ConnectionResetError	
PyExc_EOFError	EOFError	
PyExc_FileExistsError	FileExistsError	
PyExc_FileNotFoundError	FileNotFoundError	
PyExc_FloatingPointError	FloatingPointError	
PyExc_GeneratorExit	GeneratorExit	
PyExc_ImportError	ImportError	
PyExc_IndentationError	IndentationError	
PyExc_IndexError	IndexError	
PyExc_InterruptedError	InterruptedError	
PyExc_IsADirectoryError	IsADirectoryError	
PyExc_KeyError	KeyError	
PyExc_KeyboardInterrupt	KeyboardInterrupt	
PyExc_LookupError	LookupError	<sup>1</sup>
PyExc_MemoryError	MemoryError	
PyExc_ModuleNotFoundError	ModuleNotFoundError	
PyExc_NameError	NameError	
PyExc_NotADirectoryError	NotADirectoryError	
PyExc_NotImplementedError	NotImplementedError	
PyExc_OSError	OSError	<sup>1</sup>
PyExc_OverflowError	OverflowError	
PyExc_PermissionError	PermissionError	
PyExc_ProcessLookupError	ProcessLookupError	
PyExc_RecursionError	RecursionError	
PyExc_ReferenceError	ReferenceError	
PyExc_RuntimeError	RuntimeError	
PyExc_StopAsyncIteration	StopAsyncIteration	
PyExc_StopIteration	StopIteration	
PyExc_SyntaxError	SyntaxError	
PyExc_SystemError	SystemError	
PyExc_SystemExit	SystemExit	
PyExc_TabError	TabError	
PyExc_TimeoutError	TimeoutError	
PyExc_TypeError	TypeError	
PyExc_UnboundLocalError	UnboundLocalError	
PyExc_UnicodeDecodeError	UnicodeDecodeError	
PyExc_UnicodeEncodeError	UnicodeEncodeError	
PyExc_UnicodeError	UnicodeError	
PyExc_UnicodeTranslateError	UnicodeTranslateError	
PyExc_ValueError	ValueError	

continua na próxima página

Tabela 1 – continuação da página anterior

Nome C	Nome Python	Notas
PyExc_ZeroDivisionError	ZeroDivisionError	

Novo na versão 3.3: PyExc\_BlockingIOError, PyExc\_BrokenPipeError, PyExc\_ChildProcessError, PyExc\_ConnectionError, PyExc\_ConnectionAbortedError, PyExc\_ConnectionRefusedError, PyExc\_ConnectionResetError, PyExc\_FileExistsError, PyExc\_FileNotFoundError, PyExc\_InterruptedError, PyExc\_IsADirectoryError, PyExc\_NotADirectoryError, PyExc\_PermissionError, PyExc\_ProcessLookupError e PyExc\_TimeoutError foram introduzidos seguindo a [PEP 3151](#).

Novo na versão 3.5: PyExc\_StopAsyncIteration e PyExc\_RecursionError.

Novo na versão 3.6: PyExc\_ModuleNotFoundError.

Esses são os aliases de compatibilidade para PyExc\_OSError:

Nome C	Notas
PyExc_EnvironmentError	
PyExc_IOError	
PyExc_WindowsError	<sup>2</sup>

Alterado na versão 3.3: Esses aliases costumavam ser tipos de exceção separados.

Notas:

## 5.11 Categorias de aviso padrão

All standard Python warning categories are available as global variables whose names are `PyExc_` followed by the Python exception name. These have the type `PyObject*`; they are all class objects. For completeness, here are all the variables:

Nome C	Nome Python	Notas
PyExc_Warning	Warning	<sup>3</sup>
PyExc_BytesWarning	BytesWarning	
PyExc_DeprecationWarning	DeprecationWarning	
PyExc_FutureWarning	FutureWarning	
PyExc_ImportWarning	ImportWarning	
PyExc_PendingDeprecationWarning	PendingDeprecationWarning	
PyExc_ResourceWarning	ResourceWarning	
PyExc_RuntimeWarning	RuntimeWarning	
PyExc_SyntaxWarning	SyntaxWarning	
PyExc_UnicodeWarning	UnicodeWarning	
PyExc_UserWarning	UserWarning	

Novo na versão 3.2: PyExc\_ResourceWarning.

Notas:

<sup>1</sup> Esta é uma classe base para outras exceções padrão.

<sup>2</sup> Define apenas no Windows; proteja o código que usa isso testando se a macro do pré-processador `MS_WINDOWS` está definida.

<sup>3</sup> Esta é uma classe base para outras categorias de aviso padrão.





As funções neste capítulo executam várias tarefas de utilidade pública, desde ajudar o código C a ser mais portátil em plataformas, usando módulos Python de C, como também, a análise de argumentos de função e a construção de valores Python a partir de valores C.

## 6.1 Utilitários do sistema operacional

*PyObject* \*PyOS\_FSPath (*PyObject* \*path)

*Retorna valor:* Nova referência. *Part of the Stable ABI since version 3.6.* Retorna a representação do sistema de arquivos para *path*. Se o objeto for um objeto `str` ou `bytes`, então uma nova *referência forte* é retornada. Se o objeto implementa a interface `os.PathLike`, então `__fspath__()` é retornado desde que seja um objeto `str` ou `bytes`. Caso contrário, `TypeError` é levantada e `NULL` é retornado.

Novo na versão 3.6.

int Py\_FdIsInteractive (FILE \*fp, const char \*filename)

Return true (nonzero) if the standard I/O file *fp* with name *filename* is deemed interactive. This is the case for files for which `isatty(fileno(fp))` is true. If the global flag `Py_InteractiveFlag` is true, this function also returns true if the *filename* pointer is `NULL` or if the name is equal to one of the strings '`<stdin>`' or '`???`'.

void PyOS\_BeforeFork ()

*Part of the Stable ABI on platforms with fork() since version 3.7.* Função para preparar algum estado interno antes de ser feito um `fork` do processo. Isso deve ser chamado antes de chamar `fork()` ou qualquer função semelhante que clone o processo atual. Disponível apenas em sistemas onde `fork()` é definido.

**Aviso:** A chamada C `fork()` só deve ser feita a partir da *thread* “main” (do *interpretador* “main”). O mesmo vale para `PyOS_BeforeFork()`.

Novo na versão 3.7.

void **PyOS\_AfterFork\_Parent** ()

*Part of the [Stable ABI](#) on platforms with `fork()` since version 3.7.* Função para atualizar algum estado interno depois de ser feito um `fork` do processo. Isso deve ser chamado a partir do processo pai depois de chamar `fork()` ou qualquer função semelhante que clone o processo atual, independentemente da clonagem do processo ter sido bem-sucedida ou não. Disponível apenas em sistemas onde `fork()` é definido.

**Aviso:** A chamada C `fork()` só deve ser feita a partir da *thread* “`main`” (do *interpretador* “`main`”). O mesmo vale para `PyOS_AfterFork_Parent()`.

Novo na versão 3.7.

void **PyOS\_AfterFork\_Child** ()

*Part of the [Stable ABI](#) on platforms with `fork()` since version 3.7.* Função para atualizar o estado interno do interpretador depois de ser feito um `fork` do processo. Isso deve ser chamado a partir do processo filho depois de chamar `fork()` ou qualquer função semelhante que clone o processo atual, se houver alguma chance do processo ter uma chamada de retorno para o interpretador Python. Disponível apenas em sistemas onde `fork()` é definido.

**Aviso:** A chamada C `fork()` só deve ser feita a partir da *thread* “`main`” (do *interpretador* “`main`”). O mesmo vale para `PyOS_AfterFork_Child()`.

Novo na versão 3.7.

**Ver também:**

`os.register_at_fork()` permite registrar funções personalizadas do Python para serem chamadas por `PyOS_BeforeFork()`, `PyOS_AfterFork_Parent()` e `PyOS_AfterFork_Child()`.

void **PyOS\_AfterFork** ()

*Part of the [Stable ABI](#) on platforms with `fork()`.* Função para atualizar algum estado interno após ser feito um `fork` de processo; isso deve ser chamado no novo processo se o interpretador do Python continuar a ser usado. Se um novo executável é carregado no novo processo, esta função não precisa ser chamada.

Obsoleto desde a versão 3.7: Esta função foi sucedida por `PyOS_AfterFork_Child()`.

int **PyOS\_CheckStack** ()

*Part of the [Stable ABI](#) on platforms with `USE_STACKCHECK` since version 3.7.* Retorna verdadeiro quando o interpretador ficar sem espaço de pilha. Esta é uma verificação confiável, mas só está disponível quando `USE_STACKCHECK` está definido (atualmente no Windows usando o compilador Microsoft Visual C++). `USE_STACKCHECK` será definido automaticamente; você nunca deve mudar a definição em seu próprio código.

`PyOS_sighandler_t` **PyOS\_getsig** (int *i*)

*Part of the [Stable ABI](#).* Return the current signal handler for signal *i*. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly! `PyOS_sighandler_t` is a typedef alias for `void (*)int`.

`PyOS_sighandler_t` **PyOS\_setsig** (int *i*, `PyOS_sighandler_t` *h*)

*Part of the [Stable ABI](#).* Set the signal handler for signal *i* to be *h*; return the old signal handler. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly! `PyOS_sighandler_t` is a typedef alias for `void (*)int`.

`wchar_t *`**Py\_DecodeLocale** (const char \**arg*, `size_t` \**size*)

*Part of the [Stable ABI](#) since version 3.7.*

**Aviso:** Esta função não deve ser chamada diretamente: use a API *PyConfig* com a função *PyConfig\_SetBytesString()* que garante que *Python* esteja pré-inicializado.

Esta função não deve ser chamada antes de *Python* estar pré-inicializado e para que a localidade *LC\_CTYPE* seja configurada corretamente: consulte a função *Py\_PreInitialize()*.

Decodifica uma string de bytes do *tratador de erros e codificação do sistema de arquivos*. Se o tratador de erros for o tratador de errors surrogateescape, bytes não decodificáveis são decodificados como caracteres no intervalo U+DC80..U+DCFF; e se uma string de bytes puder ser decodificada como um caractere substituto, os bytes são escapados usando o tratador de erros surrogateescape em vez de decodificá-los.

Retorna um ponteiro para uma string de caracteres largos recém-alocada, usa *PyMem\_RawFree()* para liberar a memória. Se o tamanho não for NULL, escreve o número de caracteres largos excluindo o caractere nulo em *\*size*.

Retorna NULL em erro de decodificação ou erro de alocação de memória. Se *size* não for NULL, *\*size* é definido como *(size\_t)-1* em erro de memória ou definido como *(size\_t)-2* em erro de decodificação.

*tratador de erros e codificação do sistema de arquivos* são selecionados por *PyConfig\_Read()*: veja os membros *filesystem\_encoding* e *filesystem\_errors* de *PyConfig*.

Erros de decodificação nunca devem acontecer, a menos que haja um bug na biblioteca C.

Use a função *Py\_EncodeLocale()* para codificar a string de caracteres de volta para uma string de bytes.

#### Ver também:

As funções *PyUnicode\_DecodeFSDefaultAndSize()* e *PyUnicode\_DecodeLocaleAndSize()*.

Novo na versão 3.5.

Alterado na versão 3.7: A função agora usa a codificação UTF-8 no Modo UTF-8 do Python.

Alterado na versão 3.8: The function now uses the UTF-8 encoding on Windows if *Py\_LegacyWindowsFSEncodingFlag* is zero;

char **\*Py\_EncodeLocale** (const wchar\_t \*text, size\_t \*error\_pos)

Part of the Stable ABI since version 3.7. Encode a wide character string to the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Return a pointer to a newly allocated byte string, use *PyMem\_Free()* to free the memory. Return NULL on encoding error or memory allocation error.

If error\_pos is not NULL, \*error\_pos is set to (size\_t)-1 on success, or set to the index of the invalid character on encoding error.

*tratador de erros e codificação do sistema de arquivos* são selecionados por *PyConfig\_Read()*: veja os membros *filesystem\_encoding* e *filesystem\_errors* de *PyConfig*.

Use the *Py\_DecodeLocale()* function to decode the bytes string back to a wide character string.

**Aviso:** Esta função não deve ser chamada antes de *Python* estar pré-inicializado e para que a localidade *LC\_CTYPE* seja configurada corretamente: consulte a função *Py\_PreInitialize()*.

#### Ver também:

The *PyUnicode\_EncodeFSDefault()* and *PyUnicode\_EncodeLocale()* functions.

Novo na versão 3.5.

Alterado na versão 3.7: A função agora usa a codificação UTF-8 no Modo UTF-8 do Python.

Alterado na versão 3.8: The function now uses the UTF-8 encoding on Windows if `Py_LegacyWindowsFSEncodingFlag` is zero.

## 6.2 System Functions

These are utility functions that make functionality from the `sys` module accessible to C code. They all work with the current interpreter thread's `sys` module's dict, which is contained in the internal thread state structure.

*PyObject* **PySys\_GetObject** (`const char *name`)

*Retorna valor: Referência emprestada. Part of the Stable ABI.* Return the object `name` from the `sys` module or NULL if it does not exist, without setting an exception.

int **PySys\_SetObject** (`const char *name`, *PyObject* \*v)

*Part of the Stable ABI.* Set `name` in the `sys` module to `v` unless `v` is NULL, in which case `name` is deleted from the `sys` module. Returns 0 on success, -1 on error.

void **PySys\_ResetWarnOptions** ()

*Part of the Stable ABI.* Reset `sys.warnoptions` to an empty list. This function may be called prior to `Py_Initialize()`.

void **PySys\_AddWarnOption** (`const wchar_t *s`)

*Part of the Stable ABI.* Append `s` to `sys.warnoptions`. This function must be called prior to `Py_Initialize()` in order to affect the warnings filter list.

void **PySys\_AddWarnOptionUnicode** (*PyObject* \*unicode)

*Part of the Stable ABI.* Append `unicode` to `sys.warnoptions`.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of `warnings` in `Py_Initialize()` to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

void **PySys\_SetPath** (`const wchar_t *path`)

*Part of the Stable ABI.* Set `sys.path` to a list object of paths found in `path` which should be a list of paths separated with the platform's search path delimiter (`:` on Unix, `;` on Windows).

void **PySys\_WriteStdout** (`const char *format`, ...)

*Part of the Stable ABI.* Write the output string described by `format` to `sys.stdout`. No exceptions are raised, even if truncation occurs (see below).

`format` should limit the total size of the formatted output string to 1000 bytes or less – after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted “%s” formats should occur; these should be limited using “%.<N>s” where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for “%f”, which can print hundreds of digits for very large numbers.

If a problem occurs, or `sys.stdout` is unset, the formatted message is written to the real (C level) `stdout`.

void **PySys\_WriteStderr** (`const char *format`, ...)

*Part of the Stable ABI.* As `PySys_WriteStdout()`, but write to `sys.stderr` or `stderr` instead.

void **PySys\_FormatStdout** (`const char *format`, ...)

*Part of the Stable ABI.* Function similar to `PySys_WriteStdout()` but format the message using `PyUnicode_FromFormatV()` and don't truncate the message to an arbitrary length.

Novo na versão 3.2.

void **PySys\_FormatStderr** (`const char *format`, ...)

*Part of the Stable ABI.* As `PySys_FormatStdout()`, but write to `sys.stderr` or `stderr` instead.

Novo na versão 3.2.

void **PySys\_AddXOption** (**const** wchar\_t \*s)

Part of the [Stable ABI](#) since version 3.7. Parse *s* as a set of -X options and add them to the current options mapping as returned by [PySys\\_GetXOptions\(\)](#). This function may be called prior to [Py\\_Initialize\(\)](#).

Novo na versão 3.2.

*PyObject* \***PySys\_GetXOptions** ()

Retorna valor: Referência emprestada. Part of the [Stable ABI](#) since version 3.7. Return the current dictionary of -X options, similarly to `sys._xoptions`. On error, NULL is returned and an exception is set.

Novo na versão 3.2.

int **PySys\_Audit** (**const** char \*event, **const** char \*format, ...)

Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure.

If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from N, the same format characters as used in [Py\\_BuildValue\(\)](#) are available. If the built value is not a tuple, it will be added into a single-element tuple. (The N format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

Note that # format characters should always be treated as *Py\_ssize\_t*, regardless of whether `PY_SSIZE_T_CLEAN` was defined.

`sys.audit()` performs the same function from Python code.

Novo na versão 3.8.

Alterado na versão 3.8.2: Require *Py\_ssize\_t* for # format characters. Previously, an unavoidable deprecation warning was raised.

int **PySys\_AddAuditHook** (Py\_AuditHookFunction *hook*, void \**userData*)

Append the callable *hook* to the list of active auditing hooks. Return zero on success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

O ponteiro *userData* é passado para a função de gancho. Como as funções de gancho podem ser chamadas de diferentes tempos de execução, esse ponteiro não deve se referir diretamente ao estado do Python.

This function is safe to call before [Py\\_Initialize\(\)](#). When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from `Exception` (other errors will not be silenced).

The hook function is of type `int (*)const char *event, PyObject *args, void *userData`, where *args* is guaranteed to be a *PyTupleObject*. The hook function is always called with the GIL held by the Python interpreter that raised the event.

See [PEP 578](#) for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

If the interpreter is initialized, this function raises a auditing event `sys.addaudithook` with no arguments. If any existing hooks raise an exception derived from `Exception`, the new hook will not be added and the exception is cleared. As a result, callers cannot assume that their hook has been added unless they control all existing hooks.

Novo na versão 3.8.

## 6.3 Process Control

void **Py\_FatalError** (const char \*message)

*Part of the Stable ABI.* Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function `abort()` is called which will attempt to produce a core file.

The `Py_FatalError()` function is replaced with a macro which logs automatically the name of the current function, unless the `Py_LIMITED_API` macro is defined.

Alterado na versão 3.9: Log the function name automatically.

void **Py\_Exit** (int status)

*Part of the Stable ABI.* Exit the current process. This calls `Py_FinalizeEx()` and then calls the standard C library function `exit(status)`. If `Py_FinalizeEx()` indicates an error, the exit status is set to 120.

Alterado na versão 3.6: Errors from finalization no longer ignored.

int **Py\_AtExit** (void (\*func))

*Part of the Stable ABI.* Register a cleanup function to be called by `Py_FinalizeEx()`. The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful, `Py_AtExit()` returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

## 6.4 Importando módulos

*PyObject* \***PyImport\_ImportModule** (const char \*name)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Esta é uma interface simplificada para `PyImport_ImportModuleEx()` abaixo, deixando os argumentos *globals* e *locals* definidos como NULL e *level* definido como 0. Quando o argumento *name* contém um caractere de ponto (quando especifica um submódulo de um pacote), o argumento *fromlist* é definido para a lista `['*']` de modo que o valor de retorno é o módulo nomeado em vez do pacote de nível superior que o contém como faria caso contrário, seja o caso. (Infelizmente, isso tem um efeito colateral adicional quando *name* de fato especifica um subpacote em vez de um submódulo: os submódulos especificados na variável `__all__` do pacote são carregados.) Retorna uma nova referência ao módulo importado, ou NULL com uma exceção definida em caso de falha. Uma importação com falha de um módulo não deixa o módulo em `sys.modules`.

Esta função sempre usa importações absolutas.

*PyObject* \***PyImport\_ImportModuleNoBlock** (const char \*name)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Esta função é um alias descontinuado de `PyImport_ImportModule()`.

Alterado na versão 3.3: Essa função falhava em alguns casos, quando a trava de importação era mantida por outra thread. No Python 3.3, no entanto, o esquema de trava mudou passando a ser de travas por módulo na maior parte, dessa forma, o comportamento especial dessa função não é mais necessário.

*PyObject* \***PyImport\_ImportModuleEx** (const char \*name, *PyObject* \*globals, *PyObject* \*locals, *PyObject* \*fromlist)

*Retorna valor:* Nova referência. Importa um módulo. Isso é melhor descrito referindo-se à função embutida do Python `__import__()`.

O valor de retorno é uma nova referência ao módulo importado ou pacote de nível superior, ou NULL com uma exceção definida em caso de falha. Como para `__import__()`, o valor de retorno quando um submódulo de um pacote é solicitado é normalmente o pacote de nível superior, a menos que um *fromlist* não vazio seja fornecido.

As importações com falhas removem objetos incompletos do módulo, como em `PyImport_ImportModule()`.

**`PyObject*PyImport_ImportModuleLevelObject`** (`PyObject*name`, `PyObject*globals`, `PyObject*locals`, `PyObject*fromlist`, `int level`)

*Retorna valor:* Nova referência. *Part of the Stable ABI since version 3.7.* Importa um módulo. Isso é melhor descrito referindo-se à função embutida do Python `__import__()`, já que a função padrão `__import__()` chama essa função diretamente.

O valor de retorno é uma nova referência ao módulo importado ou pacote de nível superior, ou `NULL` com uma exceção definida em caso de falha. Como para `__import__()`, o valor de retorno quando um submódulo de um pacote é solicitado é normalmente o pacote de nível superior, a menos que um *fromlist* não vazio seja fornecido.

Novo na versão 3.3.

**`PyObject*PyImport_ImportModuleLevel`** (`const char*name`, `PyObject*globals`, `PyObject*locals`, `PyObject*fromlist`, `int level`)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Semelhante para `PyImport_ImportModuleLevelObject()`, mas o nome é uma string codificada em UTF-8 de um objeto Unicode.

Alterado na versão 3.3: Valores negativos para *level* não são mais aceitos.

**`PyObject*PyImport_Import`** (`PyObject*name`)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Essa é uma interface de alto nível que chama a atual “função auxiliar de importação” (com um *level* explícito de 0, significando importação absoluta). Invoca a função `__import__()` a partir de `__builtins__` da global atual. Isso significa que a importação é feita usando quaisquer extras de importação instalados no ambiente atual.

Esta função sempre usa importações absolutas.

**`PyObject*PyImport_ReloadModule`** (`PyObject*m`)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Recarrega um módulo. Retorna uma nova referência para o módulo recarregado, ou `NULL` com uma exceção definida em caso de falha (o módulo ainda existe neste caso).

**`PyObject*PyImport_AddModuleObject`** (`PyObject*name`)

*Retorna valor:* Referência emprestada. *Part of the Stable ABI since version 3.7.* Retorna o objeto módulo correspondente a um nome de módulo. O argumento *name* pode ter a forma `package.module`. Primeiro verifica o dicionário de módulos se houver algum, caso contrário, cria um novo e insere-o no dicionário de módulos. Retorna `NULL` com uma exceção definida em caso de falha.

---

**Nota:** Esta função não carrega ou importa o módulo; se o módulo não foi carregado, você receberá um objeto de módulo vazio. Use `PyImport_ImportModule()` ou uma de suas variações para importar um módulo. Estruturas de pacotes implícitos por um nome pontilhado para a *name* não são criados se não estiverem presentes.

---

Novo na versão 3.3.

**`PyObject*PyImport_AddModule`** (`const char*name`)

*Retorna valor:* Referência emprestada. *Part of the Stable ABI.* Semelhante para `PyImport_AddModuleObject()`, mas o nome é uma string codificada em UTF-8 em vez de um objeto Unicode.

**`PyObject*PyImport_ExecCodeModule`** (`const char*name`, `PyObject*co`)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Dado um nome de módulo (possivelmente na forma `package.module`) e um objeto código lido de um arquivo de bytecode Python ou obtido da função embutida `compile()`, carrega o módulo. Retorna uma nova referência ao objeto do módulo, ou `NULL` com uma exceção definida se ocorrer um erro. *name* é removido de `sys.modules` em casos de erro, mesmo se *name* já estivesse em `sys.modules` na entrada para `PyImport_ExecCodeModule()`. Deixar módulos incompletamente



inicializados em `sys.modules` é perigoso, pois as importações de tais módulos não têm como saber se o objeto módulo é um estado desconhecido (e provavelmente danificado em relação às intenções do autor do módulo).

O `__spec__` e o `__loader__` do módulo serão definidos, se não estiverem, com os valores apropriados. O carregador do `spec` será definido para o `__loader__` do módulo (se definido) e para uma instância da classe `SourceFileLoader` em caso contrário.

O atributo `__file__` do módulo será definido para o `co_filename` do objeto código. Se aplicável, `__cached__` também será definido.

Esta função recarregará o módulo se este já tiver sido importado. Veja `PyImport_ReloadModule()` para forma desejada de recarregar um módulo.

Se `name` apontar para um nome pontilhado no formato de `package.module`, quaisquer estruturas de pacote ainda não criadas ainda não serão criadas.

Veja também `PyImport_ExecCodeModuleEx()` e `PyImport_ExecCodeModuleWithPathnames()`.

*PyObject* \***PyImport\_ExecCodeModuleEx**(const char \*name, PyObject \*co, const char \*pathname)

Retorna valor: Nova referência. Part of the Stable ABI. Como `PyImport_ExecCodeModule()`, mas o atributo `__file__` do objeto módulo é definido como `pathname` se não for NULL.

Veja também `PyImport_ExecCodeModuleWithPathnames()`.

*PyObject* \***PyImport\_ExecCodeModuleObject**(PyObject \*name, PyObject \*co, PyObject \*pathname, PyObject \*cpathname)

Retorna valor: Nova referência. Part of the Stable ABI since version 3.7. Como `PyImport_ExecCodeModuleEx()`, mas o atributo `__cached__` do objeto módulo é definido como `cpathname` se não for NULL. Das três funções, esta é a preferida para usar.

Novo na versão 3.3.

*PyObject* \***PyImport\_ExecCodeModuleWithPathnames**(const char \*name, PyObject \*co, const char \*pathname, const char \*cpathname)

Retorna valor: Nova referência. Part of the Stable ABI. Como `PyImport_ExecCodeModuleObject()`, mas `name`, `pathname` e `cpathname` são strings codificadas em UTF-8. Também são feitas tentativas para descobrir qual valor para `pathname` deve ser de `cpathname` se o primeiro estiver definido como NULL.

Novo na versão 3.2.

Alterado na versão 3.3: Usa `imp.source_from_cache()` no cálculo do caminho de origem se apenas o caminho do bytecode for fornecido.

long **PyImport\_GetMagicNumber**()

Part of the Stable ABI. Retorna o número mágico para arquivos de bytecode Python (também conhecido como arquivo `.pyc`). O número mágico deve estar presente nos primeiros quatro bytes do arquivo bytecode, na ordem de bytes little-endian. Retorna `-1` em caso de erro.

Alterado na versão 3.3: Retorna o valor de `-1` no caso de falha.

const char \***PyImport\_GetMagicTag**()

Part of the Stable ABI. Retorna a string de tag mágica para nomes de arquivo de bytecode Python no formato de **PEP 3147**. Tenha em mente que o valor em `sys.implementation.cache_tag` é autoritativo e deve ser usado no lugar desta função.

Novo na versão 3.2.

*PyObject* \***PyImport\_GetModuleDict**()

Retorna valor: Referência emprestada. Part of the Stable ABI. Retorna o dicionário usado para a administração do módulo (também conhecido como `sys.modules`). Observe que esta é uma variável por interpretador.

*PyObject* \***PyImport\_GetModule**(PyObject \*name)

Retorna valor: Nova referência. Part of the Stable ABI since version 3.8. Retorna o módulo já importado com o



nome fornecido. Se o módulo ainda não foi importado, retorna NULL, mas não define um erro. Retorna NULL e define um erro se a pesquisa falhar.

Novo na versão 3.7.

*PyObject* \*PyImport\_GetImporter(*PyObject* \*path)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um objeto localizador para o item *path* de `sys.path/pkg.__path__`, possivelmente obtendo-o do dicionário `sys.path_importer_cache`. Se ainda não foi armazenado em cache, atravessa `sys.path_hooks` até que um gancho seja encontrado que possa lidar com o item de caminho. Retorna None se nenhum gancho puder; isso diz ao nosso chamador que o *localizador baseado no caminho* não conseguiu encontrar um localizador para este item de caminho. Armazena o resultado em `sys.path_importer_cache`. Retorna uma nova referência ao objeto localizador.

int PyImport\_ImportFrozenModuleObject(*PyObject* \*name)

*Part of the Stable ABI since version 3.7*. Carrega um módulo congelado chamado *name*. Retorna 1 para sucesso, 0 se o módulo não for encontrado e -1 com uma exceção definida se a inicialização falhar. Para acessar o módulo importado em um carregamento bem-sucedido, use `PyImport_ImportModule()`. (Observe o nome incorreto — esta função recarregaria o módulo se ele já tivesse sido importado.)

Novo na versão 3.3.

Alterado na versão 3.4: O atributo `__file__` não está mais definido no módulo.

int PyImport\_ImportFrozenModule(const char \*name)

*Part of the Stable ABI*. Semelhante a `PyImport_ImportFrozenModuleObject()`, mas o nome é uma string codificada em UTF-8 em vez de um objeto Unicode.

struct \_frozen

Esta é a definição do tipo de estrutura para descritores de módulo congelados, conforme gerado pelo utilitário **freeze** (veja `Tools/freeze/` na distribuição fonte do Python). Sua definição, encontrada em `Include/import.h`, é:

```
struct _frozen {
    const char *name;
    const unsigned char *code;
    int size;
};
```

const struct \_frozen \*PyImport\_FrozenModules

Este ponteiro é inicializado para apontar para um vetor de registros de `_frozen`, terminado por um cujos membros são todos NULL ou zero. Quando um módulo congelado é importado, ele é pesquisado nesta tabela. O código de terceiros pode fazer truques com isso para fornecer uma coleção criada dinamicamente de módulos congelados.

int PyImport\_AppendInittab(const char \*name, *PyObject* \*(\*initfunc)) void

*Part of the Stable ABI*. Adiciona um único módulo à tabela existente de módulos embutidos. Este é um invólucro prático em torno de `PyImport_ExtendInittab()`, retornando -1 se a tabela não puder ser estendida. O novo módulo pode ser importado pelo nome *name* e usa a função *initfunc* como a função de inicialização chamada na primeira tentativa de importação. Deve ser chamado antes de `Py_Initialize()`.

struct \_inittab

Estrutura que descreve uma única entrada na lista de módulos embutidos. Cada uma dessas estruturas fornece o nome e a função de inicialização para um módulo embutido ao interpretador. O nome é uma string codificada em ASCII. Os programas que embutem Python podem usar um vetor dessas estruturas em conjunto com `PyImport_ExtendInittab()` para fornecer módulos embutidos adicionais. A estrutura é definida em `Include/import.h` como:

```
struct _inittab {
    const char *name;           /* ASCII encoded string */
```

(continua na próxima página)

```
PyObject* (*initfunc)(void);
};
```

int **PyImport\_ExtendInittab** (struct *\_inittab* \*newtab)

Adiciona uma coleção de módulos à tabela de módulos embutidos. O vetor *newtab* deve terminar com uma entrada sentinela que contém NULL para o campo *name*; a falha em fornecer o valor sentinela pode resultar em uma falha de memória. Retorna 0 em caso de sucesso ou -1 se memória insuficiente puder ser alocada para estender a tabela interna. Em caso de falha, nenhum módulo é adicionado à tabela interna. Deve ser chamado antes de *Py\_Initialize()*.

Se Python é inicializado várias vezes, *PyImport\_AppendInittab()* ou *PyImport\_ExtendInittab()* devem ser chamados antes de cada inicialização do Python.

## 6.5 Suporte a *marshalling* de dados

Essas rotinas permitem que o código C trabalhe com objetos serializados usando o mesmo formato de dados que o módulo *marshal*. Existem funções para gravar dados no formato de serialização e funções adicionais que podem ser usadas para ler os dados novamente. Os arquivos usados para armazenar dados empacotados devem ser abertos no modo binário.

Os valores numéricos são armazenados primeiro com o byte menos significativo.

O módulo possui suporte a duas versões do formato de dados: a versão 0 é a versão histórica, a versão 1 compartilha strings internas no arquivo e após a desserialização. A versão 2 usa um formato binário para números de ponto flutuante. *PY\_MARSHAL\_VERSION* indica o formato do arquivo atual (atualmente 2).

void **PyMarshal\_WriteLongToFile** (long *value*, FILE \**file*, int *version*)

Aplica *marshalling* em um inteiro long, *value*, para *file*. Isso escreverá apenas os 32 bits menos significativos de *value*; independentemente do tamanho do tipo nativo long. *version* indica o formato do arquivo.

Esta função pode falhar, caso em que define o indicador de erro. Use *PyErr\_Occurred()* para verificar isso.

void **PyMarshal\_WriteObjectToFile** (PyObject \**value*, FILE \**file*, int *version*)

Aplica *marshalling* em um objeto Python, *value*, para *file*. *version* indica o formato do arquivo.

Esta função pode falhar, caso em que define o indicador de erro. Use *PyErr\_Occurred()* para verificar isso.

PyObject \***PyMarshal\_WriteObjectToString** (PyObject \**value*, int *version*)

Retorna valor: Nova referência. Retorna um objeto de bytes que contém a representação pós-*marshalling* de *value*. *version* indica o formato do arquivo.

As seguintes funções permitem que os valores pós-*marshalling* sejam lidos novamente.

long **PyMarshal\_ReadLongFromFile** (FILE \**file*)

Retorna um long C do fluxo de dados em um FILE\* aberto para leitura. Somente um valor de 32 bits pode ser lido usando essa função, independentemente do tamanho nativo de long.

Em caso de erro, define a exceção apropriada (EOFError) e retorna -1.

int **PyMarshal\_ReadShortFromFile** (FILE \**file*)

Retorna um short C do fluxo de dados em um FILE\* aberto para leitura. Somente um valor de 16 bits pode ser lido usando essa função, independentemente do tamanho nativo de short.

Em caso de erro, define a exceção apropriada (EOFError) e retorna -1.

PyObject \***PyMarshal\_ReadObjectFromFile** (FILE \**file*)

Retorna valor: Nova referência. Retorna um objeto Python do fluxo de dados em um FILE\* aberto para leitura.

Em caso de erro, define a exceção apropriada (EOFError, ValueError ou TypeError) e retorna NULL.

*PyObject* \*PyMarshal\_ReadLastObjectFromFile (FILE \*file)

*Retorna valor:* Nova referência. Retorna um objeto Python do fluxo de dados em um FILE\* aberto para leitura. Diferentemente de *PyMarshal\_ReadObjectFromFile()*, essa função presume que nenhum objeto adicional será lido do arquivo, permitindo que ela carregue agressivamente os dados do arquivo na memória, para que a desserialização possa operar a partir de dados na memória em vez de ler um byte por vez do arquivo. Use essas variantes apenas se tiver certeza de que não estará lendo mais nada do arquivo.

Em caso de erro, define a exceção apropriada (EOFError, ValueError ou TypeError) e retorna NULL.

*PyObject* \*PyMarshal\_ReadObjectFromString (const char \*data, Py\_ssize\_t len)

*Retorna valor:* Nova referência. Retorna um objeto Python do fluxo de dados em um buffer de bytes contendo len bytes apontados por data.

Em caso de erro, define a exceção apropriada (EOFError, ValueError ou TypeError) e retorna NULL.

## 6.6 Análise de argumentos e construção de valores

Essas funções são úteis ao criar funções e métodos das suas extensões. Informações adicionais e exemplos estão disponíveis em *extending-index*.

As três primeiras funções descritas, *PyArg\_ParseTuple()*, *PyArg\_ParseTupleAndKeywords()*, e *PyArg\_Parse()*, todas usam a *string de formatação* que informam à função sobre os argumentos esperados. As strings de formato usam a mesma sintaxe para cada uma dessas funções.

### 6.6.1 Análise de argumentos

Uma string de formato consiste em zero ou mais “unidades de formato”. Uma unidade de formato descreve um objeto Python; geralmente é um único caractere ou uma sequência entre parênteses de unidades de formato. Com algumas poucas exceções, uma unidade de formato que não é uma sequência entre parênteses normalmente corresponde a um único argumento de endereço para essas funções. Na descrição a seguir, a forma citada é a unidade de formato; a entrada em parênteses ( ) é o tipo de objeto Python que corresponde à unidade de formato; e a entrada em colchetes [ ] é o tipo da variável(s) C cujo endereço deve ser passado.

#### Strings e buffers

Esses formatos permitem acessar um objeto como um pedaço contíguo de memória. Você não precisa fornecer armazenamento bruto para a área de unicode ou bytes retornada.

Salvo indicação em contrário, os buffers não são terminados em NUL.

Existem três maneiras pelas quais strings e buffers podem ser convertidos em C:

- Formatos como *y\** e *s\** estão dentro de uma estrutura *Py\_buffer*. Isso bloqueia o buffer subjacente para que o chamador possa posteriormente usar o buffer, mesmo dentro de um bloco *Py\_BEGIN\_ALLOW\_THREADS* sem que haja o risco de que dados mutáveis sejam redimensionados ou destruídos. Dessa forma, **você precisa chamar *PyBuffer\_Release()*** depois de ter concluído o processamento de dados (ou em qualquer caso de interrupção precoce).
- Os formatos *es*, *es#*, *et* e *et#* alocam o buffer resultante. **Você precisa chamar *PyMem\_Free()*** depois de ter concluído o processamento de dados (ou em qualquer caso de interrupção precoce).
- Outros formatos usam um *str* ou um *objeto bytes ou similar* somente leitura, como *bytes*, e fornecem um ponteiro *const char \** para seu buffer. Nesse caso, o buffer é “emprestado”: ele é gerenciado pelo objeto Python correspondente e compartilha o tempo de vida desse objeto. Você mesmo não precisará liberar nenhuma memória.

Para garantir que o buffer subjacente possa ser emprestado com segurança, o campo `PyBufferProcs.bf_releasebuffer` do objeto deve ser `NULL`. Isso não permite objetos mutáveis comuns, como `bytearray`, mas também alguns objetos somente leitura, como `memoryview` ou `bytes`.

Além desse requisito `bf_releasebuffer`, não há nenhuma verificação para saber se o objeto de entrada é imutável (por exemplo, se ele atenderia a uma solicitação de um buffer gravável ou se outro thread pode alterar os dados).

---

**Nota:** Para todas as variantes de formatos `#` (`s#`, `y#`, etc.), a macro `PY_SSIZE_T_CLEAN` deve ser definida antes de incluir `Python.h`. No Python 3.9 e mais antigo, o tipo do argumento de comprimento é `Py_ssize_t` se a macro `PY_SSIZE_T_CLEAN` é definida, ou `int` caso contrário.

---

**s (str) [const char \*]** Converte um objeto Unicode para um ponteiro em C para uma string. Um ponteiro para uma string existente é armazenado na variável do ponteiro do caractere cujo o endereço que você está passando. A string em C é terminada em `NULO`. A string no Python não deve conter pontos de código nulo embutidos; se isso acontecer, uma exceção `ValueError` é levantada. Objetos Unicode são convertidos para strings em C usando a codificação `'utf-8'`. Se essa conversão falhar, uma exceção `UnicodeError` é levantada.

---

**Nota:** Esse formato não aceita *objetos bytes ou similares*. Se você quer aceitar caminhos de sistema de arquivos e convertê-los para strings de caracteres em C, é preferível que use o formato `O&` com `PyUnicode_FSConverter()` como *conversor*.

---

Alterado na versão 3.5: Anteriormente, a exceção `TypeError` era levantada quando pontos de código nulo embutidos em string Python eram encontrados.

**s\* (str ou objeto bytes ou similar) [Py\_buffer]** Esse formato aceita tanto objetos Unicode quanto objetos bytes ou similares. Preenche uma estrutura `Py_buffer` fornecida pelo chamador. Nesse caso, a string em C resultante pode conter bytes `NUL` embutidos. Objetos Unicode são convertidos para strings em C usando codificação `'utf-8'`.

**s# (str, objeto bytes ou similar somente leitura) [const char \*, Py\_ssize\_t]** Como `s*`, exceto que não fornece um *buffer emprestado*. O resultado é armazenado em duas variáveis em C, a primeira é um ponteiro para uma string em C, a segunda é o tamanho. A string pode conter bytes nulos embutidos. Objetos Unicode são convertidos para strings em C usando codificação `'utf-8'`.

**z (str ou None) [const char \*]** Como `s`, mas o objeto Python também pode ser `None`, nesse caso o ponteiro C é definido como `NULL`.

**z\* (str, objeto bytes ou similar ou None) [Py\_buffer]** Como `s*`, mas o objeto Python também pode ser `None`, nesse caso o membro `buf` da estrutura `Py_buffer` é definido como `NULL`.

**z# (str, objeto bytes ou similar somente leitura ou None) [const char \*, Py\_ssize\_t]** Como `s#`, mas o objeto Python também pode ser `None`, nesse caso o ponteiro C é definido como `NULL`.

**y (objeto bytes ou similar somente leitura) [const char \*]** Este formato converte um objeto bytes ou similar para um ponteiro C para uma string de caracteres *emprestada*; não aceita objetos Unicode. O buffer de bytes não pode conter bytes nulos embutidos; se isso ocorrer uma exceção `ValueError` será levantada.

Alterado na versão 3.5: Anteriormente, a exceção `TypeError` era levantada quando pontos de código nulo embutidos em string Python eram encontrados no buffer de bytes.

**y\* (objeto bytes ou similar) [Py\_buffer]** Esta variante em `s*` não aceita objetos unicode, apenas objetos bytes ou similares. Esta é a maneira recomendada para aceitar dados binários.

**y# (objeto bytes ou similar somente leitura) [const char \*, Py\_ssize\_t]** Esta variação de `s#` não aceita objetos Unicode, apenas objetos bytes ou similares.

**S (bytes) [PyBytesObject \*]** Exige que o objeto Python seja um objeto `bytes`, sem tentar nenhuma conversão. Levanta `TypeError` se o objeto não for um objeto `byte`. A variável C pode ser declarada como `PyObject*`.

**Y (bytearray) [PyByteArrayObject \*]** Exige que o objeto Python seja um objeto `bytearray`, sem aceitar qualquer conversão. Levanta `TypeError` se o objeto não é um objeto `bytearray`. A variável C apenas pode ser declarada como `PyObject*`.

**u (str) [const Py\_UNICODE \*]** Converte um objeto Python Unicode para um ponteiro C para um buffer de caracteres Unicode terminado em NUL. Você deve passar o endereço de uma variável ponteiro `Py_UNICODE`, que será preenchida com um ponteiro para um buffer Unicode existente. Por favor, note que o comprimento de um caractere `Py_UNICODE` depende das opções de compilação (está entre 16 ou 32 bits). A string Python não deve conter pontos de código nulos incorporados, se isso ocorrer uma exceção `ValueError` será levantada.

Alterado na versão 3.5: Anteriormente, a exceção `TypeError` era levantada quando pontos de código nulo embutidos em string Python eram encontrados.

Deprecated since version 3.3, will be removed in version 3.12: Parte do estilo antigo `Py_UNICODE` API; por favor migre o uso para `PyUnicode_AsWideCharString()`.

**u# (str) [const Py\_UNICODE \*, Py\_ssize\_t]** Esta variante de `u` armazena em duas variáveis C, a primeira um ponteiro para um buffer Unicode de dados, a segunda para seu comprimento. Esta variante permite ponteiros para nulos.

Deprecated since version 3.3, will be removed in version 3.12: Parte do estilo antigo `Py_UNICODE` API; por favor migre o uso para `PyUnicode_AsWideCharString()`.

**Z (str ou None) [const Py\_UNICODE \*]** Como `u`, mas o objeto Python também pode ser `None`, nesse caso o ponteiro `Py_UNICODE` é definido como `NULL`.

Deprecated since version 3.3, will be removed in version 3.12: Parte do estilo antigo `Py_UNICODE` API; por favor migre o uso para `PyUnicode_AsWideCharString()`.

**Z# (str ou None) [const Py\_UNICODE \*, Py\_ssize\_t]** Como `u#`, mas o objeto Python também pode ser `None`, nesse caso o ponteiro `Py_UNICODE` é definido como `NULL`.

Deprecated since version 3.3, will be removed in version 3.12: Parte do estilo antigo `Py_UNICODE` API; por favor migre o uso para `PyUnicode_AsWideCharString()`.

**U (str) [PyObject \*]** Exige que o objeto python seja um objeto Unicode, sem tentar alguma conversão. Levanta `TypeError` se o objeto não for um objeto Unicode. A variável C deve ser declarada como `PyObject*`.

**w\* (objeto bytes ou similar de leitura e escrita) [Py\_buffer]** Este formato aceita qualquer objeto que implemente a interface do buffer de leitura e escrita. Ele preenche uma estrutura `Py_buffer` fornecida pelo chamador. O buffer pode conter bytes nulos incorporados. O chamador deve chamar `PyBuffer_Release()` quando isso for feito com o buffer.

**es (str) [const char \*encoding, char \*\*buffer]** Esta variante em `s` é utilizada para codificação do Unicode em um buffer de caracteres. Ele só funciona para dados codificados sem NUL bytes incorporados.

Este formato exige dois argumentos. O primeiro é usado apenas como entrada e deve ser a `const char*` que aponta para o nome de uma codificação como uma string terminada em NUL ou `NULL`, nesse caso a codificação `'utf-8'` é usada. Uma exceção é levantada se a codificação nomeada não for conhecida pelo Python. O segundo argumento deve ser um `char**`; o valor do ponteiro a que ele faz referência será definido como um buffer com o conteúdo do texto do argumento. O texto será codificado na codificação especificada pelo primeiro argumento.

`PyArg_ParseTuple()` alocará um buffer do tamanho necessário, copiará os dados codificados nesse buffer e ajustará `*buffer` para referenciar o armazenamento recém-alocado. O chamador é responsável por chamar `PyMem_Free()` para liberar o buffer alocado após o uso.

**et (str, bytes ou bytearray) [const char \*encoding, char \*\*buffer]** O mesmo que `es`, exceto que os objetos strings de bytes são passados sem os recodificar. Em vez disso, a implementação presume que o objeto string de bytes usa a codificação passada como parâmetro.

**es# (str) [const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length]** Essa variante em `s#` é usada para codificar Unicode em um buffer de caracteres. Diferente do formato `es`, essa variante permite a entrada de dados que contêm caracteres NUL.

Exige três argumentos. O primeiro é usado apenas como entrada e deve ser a `const char*` que aponta para o nome de uma codificação como uma string terminada em NUL ou NULL, nesse caso a codificação `'utf-8'` é usada. Uma exceção será gerada se a codificação nomeada não for conhecida pelo Python. O segundo argumento deve ser um `char**`; o valor do ponteiro a que ele faz referência será definido como um buffer com o conteúdo do texto do argumento. O texto será codificado na codificação especificada pelo primeiro argumento. O terceiro argumento deve ser um ponteiro para um número inteiro; o número inteiro referenciado será definido como o número de bytes no buffer de saída.

Há dois modos de operação:

Se `*buffer` apontar um ponteiro NULL, a função irá alocar um buffer do tamanho necessário, copiar os dados codificados para dentro desse buffer e configurar `*buffer` para referenciar o novo armazenamento alocado. O chamador é responsável por chamar `PyMem_Free()` para liberar o buffer alocado após o uso.

Se `*buffer` apontar para um ponteiro que não seja NULL (um buffer já alocado), `PyArg_ParseTuple()` irá usar essa localização como buffer e interpretar o valor inicial de `*buffer_length` como sendo o tamanho do buffer. Depois ela vai copiar os dados codificados para dentro do buffer e terminá-lo com NUL. Se o buffer não for suficientemente grande, um `ValueError` será definido.

Em ambos os casos, o `*buffer_length` é definido como o comprimento dos dados codificados sem o byte NUL à direita.

**et# (str, bytes ou bytearray) [const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length]** O mesmo que `es#`, exceto que os objetos strings de bytes são passados sem que sejam recodificados. Em vez disso, a implementação presume que o objeto string de bytes usa a codificação passada como parâmetro.

## Números

**b (int) [unsigned char]** Converte um inteiro Python não negativo em um inteiro pequeno sem sinal (unsigned tiny int), armazenado em um `unsigned char` do C.

**B (int) [unsigned char]** Converte um inteiro Python para um inteiro pequeno (tiny int) sem verificação de estouro, armazenado em um `unsigned char` do C.

**h (int) [short int]** Converte um inteiro Python para um `short int` do C.

**H (int) [unsigned short int]** Converte um inteiro Python para um `unsigned short int` do C, sem verificação de estouro.

**i (int) [int]** Converte um inteiro Python para um `int` simples do C.

**I (int) [unsigned int]** Converte um inteiro Python para um `unsigned int` do C, sem verificação de estouro.

**l (int) [long int]** Converte um inteiro Python para um `long int` do C.

**k (int) [unsigned long]** Converte um inteiro Python para um `unsigned long` do C sem verificação de estouro.

**L (int) [longo longo]** Converte um inteiro Python para um `long long` do C.

**K (int) [unsigned long long]** Converte um inteiro Python para um `unsigned long long` do C sem verificação de estouro.

**n (int) [Py\_ssize\_t]** Converte um inteiro Python para um `Py_ssize_t` do C.

**c (bytes ou bytearray de comprimento 1) [char]** Converte um byte Python, representado com um objeto `byte` ou `bytearray` de comprimento 1, para um `char` do C.

Alterado na versão 3.3: Permite objetos `bytearray`.



**C (str de comprimento 1) [int]** Converte um caractere Python, representado como uma `str` objeto de comprimento 1, para um `int` do C

**f` (float) [float]** Converte um número de ponto flutuante Python para um `float` do C.

**d (float) [double]** Converte um número de ponto flutuante Python para um `double` do C.

**D (complex) [Py\_complex]** Converte um número complexo Python para uma estrutura C `Py_complex`

## Outros objetos

**O (objeto) [PyObject\*]** Armazena um objeto Python (sem qualquer conversão) em um ponteiro de objeto C. O programa C então recebe o objeto real que foi passado. Uma nova *referência forte* ao objeto não é criado (isto é sua contagem de referências não é aumentada). O ponteiro armazenado não é `NULL`.

**O! (objeto) [PyObject\*, PyObject\*]** Armazena um objeto Python em um ponteiro de objeto C. Isso é similar a `O`, mas usa dois argumentos C: o primeiro é o endereço de um objeto do tipo Python, o segundo é um endereço da variável C (de tipo `PyObject*`) no qual o ponteiro do objeto está armazenado. Se o objeto Python não tiver o tipo necessário, `TypeError` é levantada.

**O& (objeto) [converter, anything]** Converte um objeto Python em uma variável C através de uma função `converter`. Isso leva dois argumentos: o primeiro é a função, o segundo é o endereço da variável C (de tipo arbitrário), convertendo para `void*`. A função `converter` por sua vez, é chamada da seguinte maneira:

```
status = converter(object, address);
```

onde `object` é o objeto Python a ser convertido e `address` é o argumento `void*` que foi passado para a função `PyArg_Parse*`. O `status` retornado deve ser 1 para uma conversão bem-sucedida e 0 se a conversão falhar. Quando a conversão falha, a função `converter` deve levantar uma exceção e deixar o conteúdo de `address` inalterado.

Se o `converter` retornar `Py_CLEANUP_SUPPORTED`, ele poderá ser chamado uma segunda vez se a análise do argumento eventualmente falhar, dando ao conversor a chance de liberar qualquer memória que já havia alocado. Nesta segunda chamada, o parâmetro `object` será `NULL`; `address` terá o mesmo valor que na chamada original.

Alterado na versão 3.1: 109 `Py_CLEANUP_SUPPORTED` foi adicionado.

**p (bool) [int]** Testa o valor transmitido para a verdade (um booleano `p` predicado) e converte o resultado em seu valor inteiro C verdadeiro/falso equivalente. Define o `int` como 1 se a expressão for verdadeira e 0 se for falsa. Isso aceita qualquer valor válido do Python. Veja `truth` para obter mais informações sobre como o Python testa valores para a verdade.

Novo na versão 3.3.

**(items) (tuple) [matching-items]** O objeto deve ser uma sequência Python cujo comprimento seja o número de unidades de formato em `items`. Os argumentos C devem corresponder às unidades de formato individuais em `items`. As unidades de formato para sequências podem ser aninhadas.

É possível passar inteiros “long” (inteiros em que o valor excede a constante da plataforma `LONG_MAX`) contudo nenhuma checagem de intervalo é propriamente feita — os bits mais significativos são silenciosamente truncados quando o campo de recebimento é muito pequeno para receber o valor (na verdade, a semântica é herdada de downcasts no C — seu raio de ação pode variar).

Alguns outros caracteres possuem significados na string de formatação. Isso pode não ocorrer dentro de parênteses aninhados. Eles são:

- | Indica que os argumentos restantes na lista de argumentos do Python são opcionais. As variáveis C correspondentes a argumentos opcionais devem ser inicializadas para seus valores padrão — quando um argumento opcional não é especificado, `PyArg_ParseTuple()` não toca no conteúdo da(s) variável(eis) C correspondente(s).

\$ `PyArg_ParseTupleAndKeywords()` apenas: Indica que os argumentos restantes na lista de argumentos do Python são somente-nomeados. Atualmente, todos os argumentos somente-nomeados devem ser também argumentos opcionais, então | deve sempre ser especificado antes de \$ na string de formatação.

Novo na versão 3.3.

- : A lista de unidades de formatação acaba aqui; a string após os dois pontos é usada como o nome da função nas mensagens de erro (o “valor associado” da exceção que `PyArg_ParseTuple()` levanta).
- ; A lista de unidades de formatação acaba aqui; a string após o ponto e vírgula é usada como a mensagem de erro *ao invés* da mensagem de erro padrão. : e ; se excluem mutuamente.

Note que quaisquer referências a objeto Python que são fornecidas ao chamador são referências *emprestadas*; não libera-as (isto é, não decremente a contagem de referências delas)!

Argumentos adicionais passados para essas funções devem ser endereços de variáveis cujo tipo é determinado pela string de formatação; estes são usados para armazenar valores vindos da tupla de entrada. Existem alguns casos, como descrito na lista de unidades de formatação acima, onde esses parâmetros são usados como valores de entrada; eles devem concordar com o que é especificado para a unidade de formatação correspondente nesse caso.

Para a conversão funcionar, o objeto *arg* deve corresponder ao formato e o formato deve estar completo. Em caso de sucesso, as funções `PyArg_Parse*` retornam verdadeiro, caso contrário retornam falso e levantam uma exceção apropriada. Quando as funções `PyArg_Parse*` falham devido a uma falha de conversão em uma das unidades de formatação, as variáveis nos endereços correspondentes àquela unidade e às unidades de formatação seguintes são deixadas intocadas.

## Funções da API

int `PyArg_ParseTuple` (*PyObject* \*args, const char \*format, ...)

*Part of the Stable ABI.* Analisa os parâmetros de uma função que recebe apenas parâmetros posicionais em variáveis locais. Retorna verdadeiro em caso de sucesso; em caso de falha, retorna falso e levanta a exceção apropriada.

int `PyArg_VaParse` (*PyObject* \*args, const char \*format, va\_list vargs)

*Part of the Stable ABI.* Idêntico a `PyArg_ParseTuple()`, exceto que aceita uma *va\_list* ao invés de um número variável de argumentos.

int `PyArg_ParseTupleAndKeywords` (*PyObject* \*args, *PyObject* \*kw, const char \*format, char \*keywords[], ...)

*Part of the Stable ABI.* Analisa os parâmetros de uma função que recebe ambos parâmetros posicionais e de palavra reservada em variáveis locais. O argumento *keywords* é um vetor terminado por NULL de nomes de parâmetros de palavra reservada. Nomes vazios denotam *positional-only parameters*. Retorna verdadeiro em caso de sucesso; em caso de falha, retorna falso e levanta a exceção apropriada.

Alterado na versão 3.6: Adicionado suporte para *positional-only parameters*.

int `PyArg_VaParseTupleAndKeywords` (*PyObject* \*args, *PyObject* \*kw, const char \*format, char \*keywords[], va\_list vargs)

*Part of the Stable ABI.* Idêntico a `PyArg_ParseTupleAndKeywords()`, exceto que aceita uma *va\_list* ao invés de um número variável de argumentos.

int `PyArg_ValidateKeywordArguments` (*PyObject*\*)

*Part of the Stable ABI.* Garante que as chaves no dicionário de argumento de palavras reservadas são strings. Isso só é necessário se `PyArg_ParseTupleAndKeywords()` não é usado, já que o último já faz essa checagem.

Novo na versão 3.2.

int `PyArg_Parse` (*PyObject* \*args, const char \*format, ...)

*Part of the Stable ABI.* Função usada para desconstruir as listas de argumento de funções “old-style” — estas são funções que usam o método de análise de parâmetro `METH_OLDARGS`, que foi removido no Python 3. Isso não é recomendado para uso de análise de parâmetro em código novo, e a maior parte do código no interpretador padrão



foi modificada para não usar mais isso para esse propósito. Ela continua um modo conveniente de decompor outras tuplas, contudo, e pode continuar a ser usada para esse propósito.

int **PyArg\_UnpackTuple** (*PyObject* \*args, const char \*name, *Py\_ssize\_t* min, *Py\_ssize\_t* max, ...)

*Part of the Stable ABI.* A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as *METH\_VARARGS* in function or method tables. The tuple containing the actual parameters should be passed as *args*; it must actually be a tuple. The length of the tuple must be at least *min* and no more than *max*; *min* and *max* may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a *PyObject*\* variable; these will be filled in with the values from *args*; they will contain *borrowed references*. The variables which correspond to optional parameters not given by *args* will not be filled in; these should be initialized by the caller. This function returns true on success and false if *args* is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

Este é um exemplo do uso dessa função, tirado das fontes do módulo auxiliar para referências fracas `_weakref`:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

A chamada à `PyArg_UnpackTuple()` neste exemplo é inteiramente equivalente à chamada para `PyArg_ParseTuple()`:

```
PyArg_ParseTuple(args, "O|O:ref", &object, &callback)
```

## 6.6.2 Construindo valores

*PyObject*\* **Py\_BuildValue** (const char \*format, ...)

*Retorna valor: Nova referência. Part of the Stable ABI.* Cria um novo valor baseado em uma string de formatação similar àquelas aceitas pela família de funções `PyArg_Parse*` e uma sequência de valores. Retorna o valor ou NULL em caso de erro; uma exceção será levantada se NULL for retornado.

`Py_BuildValue()` não constrói sempre uma tupla. Ela constrói uma tupla apenas se a sua string de formatação contém duas ou mais unidades de formatação. Se a string de formatação estiver vazia, ela retorna None; se ela contém exatamente uma unidade de formatação, ela retorna qualquer que seja o objeto que for descrito pela unidade de formatação. Para forçar ela a retornar uma tupla de tamanho 0 ou um, use parênteses na string de formatação.

Quando buffers de memória são passados como parâmetros para fornecer dados para construir objetos, como nos formatos `s` e `s#`, os dados necessários são copiados. Buffers fornecidos pelo chamador nunca são referenciados pelos objetos criados por `Py_BuildValue()`. Em outras palavras, se o seu código invoca `malloc()` e passa a memória alocada para `Py_BuildValue()`, seu código é responsável por chamar `free()` para aquela memória uma vez que `Py_BuildValue()` tiver retornado.

Na descrição a seguir, a forma entre aspas é a unidade de formatação; a entrada em parênteses (arredondado) é o tipo do objeto Python que a unidade de formatação irá retornar; e a entrada em colchetes [quadrado] é o tipo do(s) valor(es) C a ser(em) passado(s).

Os caracteres de espaço, tab, dois pontos e vírgula são ignorados em strings de formatação (mas não dentro de unidades de formatação como `s#`). Isso pode ser usado para tornar strings de formatação longas um pouco mais legíveis.

**s (str ou None) [const char \*]** Converte uma string C terminada em NULL em um objeto Python `str` usando codificação `'utf-8'`. Se o ponteiro da string C é NULL, None é usado.

**s# (str ou None) [const char \*, Py\_ssize\_t]** Converte uma string C e seu comprimento em um objeto Python `str` usando a codificação `'utf-8'`. Se o ponteiro da string C é NULL, o comprimento é ignorado e None é retornado.

**y (bytes) [const char \*]** Isso converte uma string C para um objeto Python `bytes`. Se o ponteiro da string C é NULL, None é retornado.

**y# (bytes) [const char \*, Py\_ssize\_t]** Isso converte uma string C e seu comprimento para um objeto Python. Se o ponteiro da string C é NULL, None é retornado.

**z (str ou None) [const char \*]** O mesmo de `s`.

**z# (str ou None) [const char \*, Py\_ssize\_t]** O mesmo de `s#`.

**u (str) [const wchar\_t \*]** Convert a null-terminated `wchar_t` buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is NULL, None is returned.

**u# (str) [const wchar\_t \*, Py\_ssize\_t]** Converte um buffer de dados Unicode (UTF-17 ou UCS-4) e seu comprimento em um objeto Python Unicode. Se o ponteiro do buffer Unicode é NULL, o comprimento é ignorado e None é retornado.

**U (str ou None) [const char \*]** O mesmo de `s`.

**U# (str ou None) [const char \*, Py\_ssize\_t]** O mesmo de `s#`.

**i (int) [int]** Converte um simples `int` do C em um objeto inteiro do Python.

**b (int) [char]** Converte um simples `char` do C em um objeto inteiro do Python.

**h (int) [short int]** Converte um simples `short int` do C em um objeto inteiro do Python.

**l (int) [long int]** Converte um `long int` do C em um objeto inteiro do Python.

**B (int) [unsigned char]** Converte um `unsigned char` do C em um objeto inteiro do Python.

**H (int) [unsigned short int]** Converte um `unsigned short int` do C em um objeto inteiro do Python.

**I (int) [unsigned int]** Converte um `unsigned int` do C em um objeto inteiro do Python.

**k (int) [unsigned long]** Converte um `unsigned long` do C em um objeto inteiro do Python.

**L (int) [longo longo]** Converte um `long long` do C em um objeto inteiro do Python.

**K (int) [unsigned long long]** Converte um `unsigned long long` do C em um objeto inteiro do Python.

**n (int) [Py\_ssize\_t]** Converte um `Py_ssize_t` do C em um objeto inteiro do Python.

**c (bytes de comprimento 1) [char]** Converte um `int` representando um byte do C em um objeto `bytes` de comprimento 1 do Python.

**C (str de comprimento 1) [int]** Converte um `int` representando um caractere do C em um objeto `str` de comprimento 1 do Python.

**d (float) [double]** Converte um `double` do C em um número ponto flutuante do Python.

**f` (float) [float]** Converte um `float` do C em um número ponto flutuante do Python.

**D (complex) [Py\_complex \*]** Converte uma estrutura `Py_complex` do C em um número complexo do Python.

**O (objeto) [PyObject\*]** Passa um objeto Python intocado, mas cria uma nova *referência forte* a ele (isto é, sua contagem de referências é incrementada por um). Se o objeto passado é um ponteiro NULL, presume-se que isso foi causado porque a chamada que produziu o argumento encontrou um erro e definiu uma exceção. Portanto, `Py_BuildValue()` irá retornar NULL mas não irá levantar uma exceção. Se nenhuma exceção foi levantada ainda, `SystemError` é definida.

**S (objeto) [PyObject\*]** O mesmo que O.

**N (objeto) [PyObject\*]** O mesmo que O, exceto que não cria uma nova *referência forte*. Útil quando o objeto é criado por uma chamada a um construtor de objeto na lista de argumento.

**O& (objeto) [converter, anything]** Converte *anything* para um objeto Python através de uma função *converter*. A função é chamada com *anything* (que deve ser compatível com o `void*`) como argumento e deve retornar um “novo” objeto Python, ou NULL se um erro ocorreu.

**(items) (tuple) [matching-items]** Converte uma sequência de valores C para uma tupla Python com o mesmo número de itens.

**[items] (list) [matching-items]** Converte uma sequência de valores C para uma lista Python com o mesmo número de itens.

**{items} (dict) [matching-items]** Converte uma sequência de valores C para um dicionário Python. Cada par de valores consecutivos do C adiciona um item ao dicionário, servindo como chave e valor, respectivamente.

Se existir um erro na string de formatação, a exceção `SystemError` é definida e NULL é retornado.

*PyObject\** **Py\_VaBuildValue** (`const` char \**format*, va\_list *vargs*)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Idêntico a `Py_BuildValue()`, exceto que aceita uma *va\_list* ao invés de um número variável de argumentos.

## 6.7 Conversão e formação de strings

Funções para conversão de números e saída formatada de strings.

int **PyOS\_snprintf** (char \**str*, size\_t *size*, `const` char \**format*, ...)

Part of the [Stable ABI](#). Saída não superior a *size* bytes para *str* de acordo com a string de formato *format* e os argumentos extras. Veja a página man do Unix `snprintf(3)`.

int **PyOS\_vsnprintf** (char \**str*, size\_t *size*, `const` char \**format*, va\_list *va*)

Part of the [Stable ABI](#). Saída não superior a *size* bytes para *str* de acordo com o string de formato *format* e a variável argumento de lista *va*. Página man do Unix `vsnprintf(3)`.

`PyOS_snprintf()` e `PyOS_vsnprintf()` envolvem as funções `snprintf()` e `vsnprintf()` da biblioteca Standard C. Seu objetivo é garantir um comportamento consistente em casos extremos, o que as funções do Standard C não garantem.

Os invólucros garantem que `str[size-1]` seja sempre `'\0'` no retorno. Eles nunca escrevem mais do que *size* bytes (incluindo o `'\0'` ao final) em *str*. Ambas as funções exigem que `str != NULL`, `size > 0`, `format != NULL` e `size < INT_MAX`. Note que isso significa que não há equivalente ao `n = snprintf(NULL, 0, ...)` do C99 que determinaria o tamanho de buffer necessário.

O valor de retorno (*rv*) para essas funções deve ser interpretado da seguinte forma:

- Quando `0 <= rv < size`, a conversão de saída foi bem-sucedida e os caracteres de *rv* foram escritos em *str* (excluindo o `'\0'` byte em `str[rv]`).
- Quando `rv >= size`, a conversão de saída foi truncada e um buffer com `rv + 1` bytes teria sido necessário para ter sucesso. `str[size-1]` é `'\0'` neste caso.

- Quando `rv < 0`, “aconteceu algo de errado.” `str[size-1]` é `'\0'` neste caso também, mas o resto de `str` é indefinido. A causa exata do erro depende da plataforma subjacente.

As funções a seguir fornecem strings independentes de localidade para conversões de números.

`double PyOS_string_to_double(const char *s, char **endptr, PyObject *overflow_exception)`

*Part of the Stable ABI.* Converte uma string `s` em `double`, levantando uma exceção Python em caso de falha. O conjunto de strings aceitas corresponde ao conjunto de strings aceito pelo construtor `float()` do Python, exceto que `s` não deve ter espaços em branco à esquerda ou à direita. A conversão é independente da localidade atual.

Se `endptr` for `NULL`, converte a string inteira. Levanta `ValueError` e retorna `-1.0` se a string não for uma representação válida de um número de ponto flutuante.

Se `endptr` não for `NULL`, converte o máximo possível da string e define `*endptr` para apontar para o primeiro caractere não convertido. Se nenhum segmento inicial da string for a representação válida de um número de ponto flutuante, define `*endptr` para apontar para o início da string, levanta `ValueError` e retorna `-1.0`.

Se `s` representa um valor que é muito grande para armazenar em um ponto flutuante (por exemplo, `"1e500"` é uma string assim em muitas plataformas), então se `overflow_exception` for `NULL` retorna `Py_HUGE_VAL` (com um sinal apropriado) e não define nenhuma exceção. Caso contrário, `overflow_exception` deve apontar para um objeto de exceção Python; levanta essa exceção e retorna `-1.0`. Em ambos os casos, define `*endptr` para apontar para o primeiro caractere após o valor convertido.

Se qualquer outro erro ocorrer durante a conversão (por exemplo, um erro de falta de memória), define a exceção Python apropriada e retorna `-1.0`.

Novo na versão 3.1.

`char *PyOS_double_to_string(double val, char format_code, int precision, int flags, int *ptype)`

*Part of the Stable ABI.* Converte um `val` `double` para uma string usando `format_code`, `precision` e `flags` fornecidos.

`format_code` deve ser um entre `'e'`, `'E'`, `'f'`, `'F'`, `'g'`, `'G'` ou `'r'`. Para `'r'`, a precisão `precision` fornecida deve ser 0 e é ignorada. O código de formato `'r'` especifica o formato padrão de `repr()`.

`flags` pode ser zero ou mais de valores `Py_DTSTF_SIGN`, `Py_DTSTF_ADD_DOT_0` ou `Py_DTSTF_ALT`, alternados por operador lógico OU:

- `Py_DTSTF_SIGN` significa sempre preceder a string retornada com um caractere de sinal, mesmo se `val` não for negativo.
- `Py_DTSTF_ADD_DOT_0` significa garantir que a string retornada não se pareça com um inteiro.
- `Py_DTSTF_ALT` significa aplicar regras de formatação “alternativas”. Veja a documentação para o especificador `'#'` de `PyOS_snprintf()` para detalhes.

Se `type` não for `NULL`, então o valor para o qual ele aponta será definido como um dos `Py_DTST_FFINITE`, `Py_DTST_INFINITE` ou `Py_DTST_NAN`, significando que `val` é um número finito, um número infinito ou não um número, respectivamente.

O valor de retorno é um ponteiro para `buffer` com a string convertida ou `NULL` se a conversão falhou. O chamador é responsável por liberar a string retornada chamando `PyMem_Free()`.

Novo na versão 3.1.

`int PyOS_stricmp(const char *s1, const char *s2)`

Comparação de strings sem diferença entre maiúsculas e minúsculas. A função funciona quase de forma idêntica a `strcmp()` exceto que ignora o caso.

`int PyOS_strnicmp(const char *s1, const char *s2, Py_ssize_t size)`

Comparação de strings sem diferença entre maiúsculas e minúsculas. A função funciona quase de forma idêntica a `strncmp()` exceto que ignora o caso.

## 6.8 Reflexão

*PyObject* \***PyEval\_GetBuiltins** (void)

Retorna valor: *Referência emprestada. Part of the Stable ABI.* Retorna um dicionário dos componentes embutidos no quadro de execução atual ou o interpretador do estado da thread, se nenhum quadro estiver em execução no momento.

*PyObject* \***PyEval\_GetLocals** (void)

Retorna valor: *Referência emprestada. Part of the Stable ABI.* Retorna um dicionário das variáveis locais no quadro de execução atual ou NULL se nenhum quadro estiver sendo executado no momento.

*PyObject* \***PyEval\_GetGlobals** (void)

Retorna valor: *Referência emprestada. Part of the Stable ABI.* Retorna um dicionário das variáveis globais no quadro de execução atual ou NULL se nenhum quadro estiver sendo executado no momento.

*PyFrameObject* \***PyEval\_GetFrame** (void)

Retorna valor: *Referência emprestada. Part of the Stable ABI.* Retorna o quadro do estado atual da thread, que é NULL se nenhum quadro estiver em execução no momento.

Veja também *PyThreadState\_GetFrame()*.

*PyFrameObject* \***PyFrame\_GetBack** (*PyFrameObject* \*frame)

Obtém o *frame* próximo ao quadro externo.

Retorna uma *referência forte* ou NULL se *frame* não tiver quadro externo.

*frame* não deve ser NULL.

Novo na versão 3.9.

*PyCodeObject* \***PyFrame\_GetCode** (*PyFrameObject* \*frame)

*Part of the Stable ABI since version 3.10.* Obtém o código de *frame*.

Retorna uma *referência forte*.

*frame* não deve ser NULL. O resultado (código do quadro) não pode ser NULL.

Novo na versão 3.9.

int **PyFrame\_GetLineNumber** (*PyFrameObject* \*frame)

*Part of the Stable ABI since version 3.10.* Retorna o número da linha do *frame* atualmente em execução.

*frame* não deve ser NULL.

const char \***PyEval\_GetFuncName** (*PyObject* \*func)

*Part of the Stable ABI.* Retorna o nome de *func* se for uma função, classe ou objeto de instância, senão o nome do tipo da *func*.

const char \***PyEval\_GetFuncDesc** (*PyObject* \*func)

*Part of the Stable ABI.* Retorna uma sequência de caracteres de descrição, dependendo do tipo de *func*. Os valores de retorno incluem “()” para funções e métodos, “ constructor”, “ instance” e “ object”.. Concatenado com o resultado de *PyEval\_GetFuncName()*, o resultado será uma descrição de *func*.

## 6.9 Registro de codec e funções de suporte

int **PyCodec\_Register** (*PyObject* \*search\_function)

*Part of the Stable ABI.* Registra uma nova função de busca de codec.

Como efeito colateral, tenta carregar o pacote `encodings`, se isso ainda não tiver sido feito, com o propósito de garantir que ele sempre seja o primeiro na lista de funções de busca.

int **PyCodec\_Unregister** (*PyObject* \*search\_function)

*Part of the Stable ABI since version 3.10.* Cancela o registro de uma função de busca de codec e limpa o cache de registro. Se a função de busca não está registrada, não faz nada. Retorna 0 no sucesso. Levanta uma exceção e retorna -1 em caso de erro.

Novo na versão 3.10.

int **PyCodec\_KnownEncoding** (const char \*encoding)

*Part of the Stable ABI.* Retorna 1 ou 0 dependendo se há um codec registrado para a dada codificação *encoding*. Essa função sempre é bem-sucedida.

*PyObject* \***PyCodec\_Encode** (*PyObject* \*object, const char \*encoding, const char \*errors)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* API de codificação baseada em codec genérico.

*object* é passado através da função de codificação encontrada para a codificação fornecida por meio de *encoding*, usando o método de tratamento de erros definido por *errors*. *errors* pode ser NULL para usar o método padrão definido para o codec. Levanta um `LookupError` se nenhum codificador puder ser encontrado.

*PyObject* \***PyCodec\_Decompile** (*PyObject* \*object, const char \*encoding, const char \*errors)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* API de decodificação baseada em decodificador genérico.

*object* é passado através da função de decodificação encontrada para a codificação fornecida por meio de *encoding*, usando o método de tratamento de erros definido por *errors*. *errors* pode ser NULL para usar o método padrão definido para o codec. Levanta um `LookupError` se nenhum codificador puder ser encontrado.

### 6.9.1 API de pesquisa de codec

Nas funções a seguir, a string *encoding* é pesquisada com todos os caracteres sendo convertidos para minúsculo, o que faz com que as codificações pesquisadas por esse mecanismo não façam distinção entre maiúsculas e minúsculas. Se nenhum codec for encontrado, um `KeyError` é definido e NULL é retornado.

*PyObject* \***PyCodec\_Encoder** (const char \*encoding)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Obtém uma função de codificação para o *encoding* dado.

*PyObject* \***PyCodec\_Decoder** (const char \*encoding)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Obtém uma função de decodificação para o *encoding* dado.

*PyObject* \***PyCodec\_IncrementalEncoder** (const char \*encoding, const char \*errors)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Obtém um objeto `IncrementalEncoder` para o *encoding* dado.

*PyObject* \***PyCodec\_IncrementalDecoder** (const char \*encoding, const char \*errors)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Obtém um objeto `IncrementalDecoder` para o *encoding* dado.

*PyObject* \***PyCodec\_StreamReader** (const char \*encoding, *PyObject* \*stream, const char \*errors)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Obtém uma função de fábrica `StreamReader` para o *encoding* dado.



*PyObject* \*PyCodec\_StreamWriter (const char \*encoding, *PyObject* \*stream, const char \*errors)

Retorna valor: Nova referência. *Part of the Stable ABI*. Obtém uma função de fábrica StreamWriter para o encoding dado.

## 6.9.2 API de registro de tratamentos de erros de decodificação Unicode

int PyCodec\_RegisterError (const char \*name, *PyObject* \*error)

*Part of the Stable ABI*. Registra a função de retorno de chamada de tratamento de erro para o nome fornecido. Esta chamada de função é invocada por um codificador quando encontra caracteres/bytes indecodificáveis e nome é especificado como o parâmetro de erro na chamada da função de codificação/decodificação.

O retorno de chamada obtém um único argumento, uma instância de UnicodeEncodeError, UnicodeDecodeError ou UnicodeTranslateError que contém informações sobre a sequência problemática de caracteres ou bytes e seu deslocamento na string original (consulte *Objetos de exceção Unicode* para funções que extraem essa informação). A função de retorno de chamada deve levantar a exceção dada, ou retornar uma tupla de dois itens contendo a substituição para a sequência problemática, e um inteiro fornecendo o deslocamento na string original na qual a codificação/decodificação deve ser retomada.

Retorna 0 em caso de sucesso, -1 em caso de erro.

*PyObject* \*PyCodec\_LookupError (const char \*name)

Retorna valor: Nova referência. *Part of the Stable ABI*. Pesquisa a função de retorno de chamada de tratamento de erros registrada em name. Como um caso especial, NULL pode ser passado; nesse caso, o erro no tratamento de retorno de chamada para “strict” será retornado.

*PyObject* \*PyCodec\_StrictErrors (*PyObject* \*exc)

Retorna valor: Sempre NULL. *Part of the Stable ABI*. Levanta exc como uma exceção.

*PyObject* \*PyCodec\_IgnoreErrors (*PyObject* \*exc)

Retorna valor: Nova referência. *Part of the Stable ABI*. Ignora o erro de unicode, ignorando a entrada que causou o erro.

*PyObject* \*PyCodec\_ReplaceErrors (*PyObject* \*exc)

Retorna valor: Nova referência. *Part of the Stable ABI*. Substitui o erro de unicode por ? ou U+FFFD.

*PyObject* \*PyCodec\_XMLCharRefReplaceErrors (*PyObject* \*exc)

Retorna valor: Nova referência. *Part of the Stable ABI*. Substitui o erro de unicode por caracteres da referência XML.

*PyObject* \*PyCodec\_BackslashReplaceErrors (*PyObject* \*exc)

Retorna valor: Nova referência. *Part of the Stable ABI*. Substitui o erro de unicode com escapes de barra invertida (\x, \u e \U).

*PyObject* \*PyCodec\_NameReplaceErrors (*PyObject* \*exc)

Retorna valor: Nova referência. *Part of the Stable ABI since version 3.7*. Substitui os erros de codificação unicode com escapes \N{...}.

Novo na versão 3.5.





---

Camada de Objetos Abstratos

---

As funções neste capítulo interagem com objetos Python independentemente do seu tipo, ou com classes amplas de tipos de objetos (por exemplo, todos os tipos numéricos ou todos os tipos de sequência). Quando usadas em tipos de objetos para os quais não se aplicam, elas irão levantar uma exceção Python.

Não é possível usar essas funções em objetos que não foram inicializados corretamente, como um objeto de lista criado por `PyList_New()`, mas cujos itens ainda não foram definidos para algum valor diferente de `NULL`.

## 7.1 Protocolo de objeto

### *PyObject* \*Py\_NotImplemented

O singleton `NotImplemented`, usado para sinalizar que uma operação não foi implementada para a combinação de tipo fornecida.

### Py\_RETURN\_NOTIMPLEMENTED

Properly handle returning *Py\_NotImplemented* from within a C function (that is, create a new *strong reference* to `NotImplemented` and return it).

### int PyObject\_Print (PyObject \*o, FILE \*fp, int flags)

Print an object *o*, on file *fp*. Returns `-1` on error. The flags argument is used to enable certain printing options. The only option currently supported is `Py_PRINT_RAW`; if given, the `str()` of the object is written instead of the `repr()`.

### int PyObject\_HasAttr (PyObject \*o, PyObject \*attr\_name)

Part of the *Stable ABI*. Returns 1 if *o* has the attribute *attr\_name*, and 0 otherwise. This is equivalent to the Python expression `hasattr(o, attr_name)`. This function always succeeds.

Note that exceptions which occur while calling `__getattr__()` and `__getattribute__()` methods will get suppressed. To get error reporting use *PyObject\_GetAttr()* instead.

### int PyObject\_HasAttrString (PyObject \*o, const char \*attr\_name)

Part of the *Stable ABI*. Returns 1 if *o* has the attribute *attr\_name*, and 0 otherwise. This is equivalent to the Python expression `hasattr(o, attr_name)`. This function always succeeds.

Note that exceptions which occur while calling `__getattr__()` and `__getattribute__()` methods and creating a temporary string object will get suppressed. To get error reporting use `PyObject_GetAttrString()` instead.

*PyObject \****PyObject\_GetAttr** (*PyObject \*o*, *PyObject \*attr\_name*)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression `o.attr_name`.

*PyObject \****PyObject\_GetAttrString** (*PyObject \*o*, *const char \*attr\_name*)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression `o.attr_name`.

*PyObject \****PyObject\_GenericGetAttr** (*PyObject \*o*, *PyObject \*name*)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Generic attribute getter function that is meant to be put into a type object's `tp_getattro` slot. It looks for a descriptor in the dictionary of classes in the object's MRO as well as an attribute in the object's `__dict__` (if present). As outlined in descriptors, data descriptors take preference over instance attributes, while non-data descriptors don't. Otherwise, an `AttributeError` is raised.

int **PyObject\_SetAttr** (*PyObject \*o*, *PyObject \*attr\_name*, *PyObject \*v*)

Part of the [Stable ABI](#). Set the value of the attribute named *attr\_name*, for object *o*, to the value *v*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o.attr_name = v`.

If *v* is NULL, the attribute is deleted. This behaviour is deprecated in favour of using `PyObject_DelAttr()`, but there are currently no plans to remove it.

int **PyObject\_SetAttrString** (*PyObject \*o*, *const char \*attr\_name*, *PyObject \*v*)

Part of the [Stable ABI](#). Set the value of the attribute named *attr\_name*, for object *o*, to the value *v*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o.attr_name = v`.

If *v* is NULL, the attribute is deleted, but this feature is deprecated in favour of using `PyObject_DelAttrString()`.

int **PyObject\_GenericSetAttr** (*PyObject \*o*, *PyObject \*name*, *PyObject \*value*)

Part of the [Stable ABI](#). Generic attribute setter and deleter function that is meant to be put into a type object's `tp_setattro` slot. It looks for a data descriptor in the dictionary of classes in the object's MRO, and if found it takes preference over setting or deleting the attribute in the instance dictionary. Otherwise, the attribute is set or deleted in the object's `__dict__` (if present). On success, `0` is returned, otherwise an `AttributeError` is raised and `-1` is returned.

int **PyObject\_DelAttr** (*PyObject \*o*, *PyObject \*attr\_name*)

Delete attribute named *attr\_name*, for object *o*. Returns `-1` on failure. This is the equivalent of the Python statement `del o.attr_name`.

int **PyObject\_DelAttrString** (*PyObject \*o*, *const char \*attr\_name*)

Delete attribute named *attr\_name*, for object *o*. Returns `-1` on failure. This is the equivalent of the Python statement `del o.attr_name`.

*PyObject \****PyObject\_GenericGetDict** (*PyObject \*o*, *void \*context*)

*Retorna valor:* Nova referência. Part of the [Stable ABI since version 3.10](#). A generic implementation for the getter of a `__dict__` descriptor. It creates the dictionary if necessary.

Novo na versão 3.3.

int **PyObject\_GenericSetDict** (*PyObject \*o*, *PyObject \*value*, *void \*context*)

Part of the [Stable ABI since version 3.7](#). A generic implementation for the setter of a `__dict__` descriptor. This implementation does not allow the dictionary to be deleted.

Novo na versão 3.3.

**PyObject\***`PyObject_RichCompare` (*PyObject* \*o1, *PyObject* \*o2, int opid)

*Retorna valor: Nova referência. Part of the Stable ABI.* Compare the values of *o1* and *o2* using the operation specified by *opid*, which must be one of `Py_LT`, `Py_LE`, `Py_EQ`, `Py_NE`, `Py_GT`, or `Py_GE`, corresponding to `<`, `<=`, `==`, `!=`, `>`, or `>=` respectively. This is the equivalent of the Python expression `o1 op o2`, where `op` is the operator corresponding to *opid*. Returns the value of the comparison on success, or `NULL` on failure.

int **PyObject\_RichCompareBool** (*PyObject* \*o1, *PyObject* \*o2, int opid)

*Part of the Stable ABI.* Compare the values of *o1* and *o2* using the operation specified by *opid*, which must be one of `Py_LT`, `Py_LE`, `Py_EQ`, `Py_NE`, `Py_GT`, or `Py_GE`, corresponding to `<`, `<=`, `==`, `!=`, `>`, or `>=` respectively. Returns `-1` on error, `0` if the result is false, `1` otherwise. This is the equivalent of the Python expression `o1 op o2`, where `op` is the operator corresponding to *opid*.

---

**Nota:** If *o1* and *o2* are the same object, `PyObject_RichCompareBool()` will always return `1` for `Py_EQ` and `0` for `Py_NE`.

---

**PyObject\***`PyObject_Format` (*PyObject* \*obj, *PyObject* \*format\_spec)

*Part of the Stable ABI.* Format *obj* using *format\_spec*. This is equivalent to the Python expression `format(obj, format_spec)`.

*format\_spec* may be `NULL`. In this case the call is equivalent to `format(obj)`. Returns the formatted string on success, `NULL` on failure.

**PyObject\***`PyObject_Repr` (*PyObject* \*o)

*Retorna valor: Nova referência. Part of the Stable ABI.* Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `repr(o)`. Called by the `repr()` built-in function.

Alterado na versão 3.4: Essa função agora inclui uma asserção de depuração para ajudar a garantir que ela não descarte silenciosamente uma exceção ativa.

**PyObject\***`PyObject_ASCII` (*PyObject* \*o)

*Retorna valor: Nova referência. Part of the Stable ABI.* As `PyObject_Repr()`, compute a string representation of object *o*, but escape the non-ASCII characters in the string returned by `PyObject_Repr()` with `\x`, `\u` or `\U` escapes. This generates a string similar to that returned by `PyObject_Repr()` in Python 2. Called by the `ascii()` built-in function.

**PyObject\***`PyObject_Str` (*PyObject* \*o)

*Retorna valor: Nova referência. Part of the Stable ABI.* Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `str(o)`. Called by the `str()` built-in function and, therefore, by the `print()` function.

Alterado na versão 3.4: Essa função agora inclui uma asserção de depuração para ajudar a garantir que ela não descarte silenciosamente uma exceção ativa.

**PyObject\***`PyObject_Bytes` (*PyObject* \*o)

*Retorna valor: Nova referência. Part of the Stable ABI.* Compute a bytes representation of object *o*. `NULL` is returned on failure and a bytes object on success. This is equivalent to the Python expression `bytes(o)`, when *o* is not an integer. Unlike `bytes(o)`, a `TypeError` is raised when *o* is an integer instead of a zero-initialized bytes object.

int **PyObject\_IsSubclass** (*PyObject* \*derived, *PyObject* \*cls)

*Part of the Stable ABI.* Return `1` if the class *derived* is identical to or derived from the class *cls*, otherwise return `0`. In case of an error, return `-1`.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be `1` when at least one of the checks returns `1`, otherwise it will be `0`.

If *cls* has a `__subclasscheck__()` method, it will be called to determine the subclass status as described in [PEP 3119](#). Otherwise, *derived* is a subclass of *cls* if it is a direct or indirect subclass, i.e. contained in *cls*.`__mro__`.

Normally only class objects, i.e. instances of `type` or a derived class, are considered classes. However, objects can override this by having a `__bases__` attribute (which must be a tuple of base classes).

**int PyObject\_IsInstance** (*PyObject* \*inst, *PyObject* \*cls)

*Part of the Stable ABI.* Return 1 if *inst* is an instance of the class *cls* or a subclass of *cls*, or 0 if not. On error, returns -1 and sets an exception.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a `__instancecheck__()` method, it will be called to determine the subclass status as described in [PEP 3119](#). Otherwise, *inst* is an instance of *cls* if its class is a subclass of *cls*.

An instance *inst* can override what is considered its class by having a `__class__` attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a `__bases__` attribute (which must be a tuple of base classes).

**Py\_hash\_t PyObject\_Hash** (*PyObject* \*o)

*Part of the Stable ABI.* Compute and return the hash value of an object *o*. On failure, return -1. This is the equivalent of the Python expression `hash(o)`.

Alterado na versão 3.2: The return type is now `Py_hash_t`. This is a signed integer the same size as `Py_ssize_t`.

**Py\_hash\_t PyObject\_HashNotImplemented** (*PyObject* \*o)

*Part of the Stable ABI.* Set a `TypeError` indicating that `type(o)` is not *hashable* and return -1. This function receives special treatment when stored in a `tp_hash` slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

**int PyObject\_IsTrue** (*PyObject* \*o)

*Part of the Stable ABI.* Returns 1 if the object *o* is considered to be true, and 0 otherwise. This is equivalent to the Python expression `not not o`. On failure, return -1.

**int PyObject\_Not** (*PyObject* \*o)

*Part of the Stable ABI.* Returns 0 if the object *o* is considered to be true, and 1 otherwise. This is equivalent to the Python expression `not o`. On failure, return -1.

**PyObject\* PyObject\_Type** (*PyObject* \*o)

*Retorna valor: Nova referência. Part of the Stable ABI.* When *o* is non-NULL, returns a type object corresponding to the object type of object *o*. On failure, raises `SystemError` and returns NULL. This is equivalent to the Python expression `type(o)`. This function creates a new *strong reference* to the return value. There's really no reason to use this function instead of the `Py_TYPE()` function, which returns a pointer of type `PyTypeObject*`, except when a new *strong reference* is needed.

**int PyObject\_TypeCheck** (*PyObject* \*o, *PyTypeObject* \*type)

Return non-zero if the object *o* is of type *type* or a subtype of *type*, and 0 otherwise. Both parameters must be non-NULL.

**Py\_ssize\_t PyObject\_Size** (*PyObject* \*o)

**Py\_ssize\_t PyObject\_Length** (*PyObject* \*o)

*Part of the Stable ABI.* Return the length of object *o*. If the object *o* provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression `len(o)`.

**Py\_ssize\_t PyObject\_LengthHint** (*PyObject* \*o, *Py\_ssize\_t* defaultvalue)

Return an estimated length for the object *o*. First try to return its actual length, then an estimate using

`__length_hint__()`, and finally return the default value. On error return `-1`. This is the equivalent to the Python expression `operator.length_hint(o, defaultvalue)`.

Novo na versão 3.4.

*PyObject* \***PyObject\_GetItem**(PyObject \*o, PyObject \*key)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Return element of *o* corresponding to the object *key* or `NULL` on failure. This is the equivalent of the Python expression `o[key]`.

int **PyObject\_SetItem**(PyObject \*o, PyObject \*key, PyObject \*v)

*Part of the Stable ABI.* Map the object *key* to the value *v*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o[key] = v`. This function *does not* steal a reference to *v*.

int **PyObject\_DelItem**(PyObject \*o, PyObject \*key)

*Part of the Stable ABI.* Remove the mapping for the object *key* from the object *o*. Return `-1` on failure. This is equivalent to the Python statement `del o[key]`.

*PyObject* \***PyObject\_Dir**(PyObject \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* This is equivalent to the Python expression `dir(o)`, returning a (possibly empty) list of strings appropriate for the object argument, or `NULL` if there was an error. If the argument is `NULL`, this is like the Python `dir()`, returning the names of the current locals; in this case, if no execution frame is active then `NULL` is returned but `PyErr_Occurred()` will return false.

*PyObject* \***PyObject\_GetIter**(PyObject \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* This is equivalent to the Python expression `iter(o)`. It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises `TypeError` and returns `NULL` if the object cannot be iterated.

*PyObject* \***PyObject\_GetAIter**(PyObject \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI since version 3.10.* This is the equivalent to the Python expression `aiter(o)`. Takes an `AsyncIterable` object and returns an `AsyncIterator` for it. This is typically a new iterator but if the argument is an `AsyncIterator`, this returns itself. Raises `TypeError` and returns `NULL` if the object cannot be iterated.

Novo na versão 3.10.

## 7.2 Protocolo de chamada

O CPython permite dois protocolos de chamada: `tp_call` e `vectorcall`.

### 7.2.1 O protocolo `tp_call`

Instâncias de classe que definem `tp_call` são chamáveis. A assinatura do slot é:

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

Uma chamada é feita usando uma tupla para os argumentos posicionais e um dicionário para os argumentos nomeados, similar a `callable(*args, **kwargs)` no Python. *args* não pode ser nulo (utilize uma tupla vazia se não houver argumentos), mas *kwargs* pode ser `NULL` se não houver argumentos nomeados.

Esta convenção não é somente usada por `tp_call`: `tp_new` e `tp_init` também passam argumento dessa forma.

Para chamar um objeto, use `PyObject_Call()` ou outra *call API*.

## 7.2.2 O protocolo vectorcall

Novo na versão 3.9.

O protocolo vectorcall foi introduzido pela **PEP 590** como um protocolo adicional para tornar invocações mais eficientes.

Como regra de bolso, CPython vai preferir o vectorcall para invocações internas se o chamável suportar. Entretanto, isso não é uma regra rígida. Ademais, algumas extensões de terceiros usam diretamente `tp_call` (em vez de utilizar `PyObject_Call()`). Portanto, uma classe que suporta vectorcall precisa também implementar `tp_call`. Além disso, o chamável precisa se comportar da mesma forma independente de qual protocolo é utilizado. A forma recomendada de alcançar isso é definindo `tp_call` para `PyVectorcall_Call()`. Vale a pena repetir:

**Aviso:** Uma classe que suporte vectorcall também **precisa** implementar `tp_call` com a mesma semântica.

Uma classe não deve implementar vectorcall se for mais lento que `tp_call`. Por exemplo, se o chamador precisa converter os argumentos para uma tupla `args` e um dicionário `kwargs` de qualquer forma, então não é necessário implementar vectorcall.

Classes podem implementar o protocolo de chamada de vetor ativando a flag `Py_TPFLAGS_HAVE_VECTORCALL` e configurando `tp_vectorcall_offset` para o offset dentro da estrutura do objeto onde uma `vectorcallfunc` aparece. Este é um ponteiro para uma função com a seguinte assinatura:

```
typedef PyObject *(*vectorcallfunc)(PyObject *callable, PyObject *const *args, size_t nargsf,
                                   PyObject *kwnames)
```

- `callable` é o objeto sendo chamado.
- `args` é um array C formado pelos argumentos posicionais seguidos de valores dos argumentos nomeados. Este pode ser `NULL` se não existirem argumentos.
- `nargsf` é o número de argumentos posicionais somado á possível `PY_VECTORCALL_ARGUMENTS_OFFSET` flag. To get the actual number of positional arguments from `nargsf`, use `PyVectorcall_NARGS()`.
- `kwnames` é uma tupla contendo os nomes dos argumentos nomeados; em outras palavras, as chaves do dicionário `kwargs`. Estes nomes devem ser strings (instâncias de `str` ou uma subclasse) e eles devem ser únicos. Se não existem argumentos nomeados, então `kwnames` deve então ser `NULL`.

### `PY_VECTORCALL_ARGUMENTS_OFFSET`

Se esse sinalizador é definido em um argumento `nargsf` do vectorcall, deve ser permitido ao chamado temporariamente mudar `args[-1]`. Em outras palavras, `args` aponta para o argumento 1 (não 0) no vetor alocado. O chamado deve restaurar o valor de `args[-1]` antes de retornar.

Para `PyObject_VectorcallMethod()`, este sinalizador significa que `args[0]` pode ser alterado.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use `PY_VECTORCALL_ARGUMENTS_OFFSET`. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended `self` argument) very efficiently.

Para invocar um objeto que implementa vectorcall, utilize a função `call API` como qualquer outra invocável. `PyObject_Vectorcall()` será normalmente mais eficiente.

**Nota:** No CPython 3.8, a API vectorcall e funções relacionadas estavam disponíveis provisoriamente sob nomes com um sublinhado inicial: `_PyObject_Vectorcall`, `_Py_TPFLAGS_HAVE_VECTORCALL`, `_PyObject_VectorcallMethod`, `_PyVectorcall_Function`, `_PyObject_CallOneArg`, `_PyObject_CallMethodNoArgs`, `_PyObject_CallMethodOneArg`. Além disso, `PyObject_VectorcallDict` estava disponível como `_PyObject_FastCallDict`. Os nomes antigos ainda estão definidos como apelidos para os novos nomes sem o sublinhado.

## Controle de recursão

Quando utilizando *tp\_call*, invocadores não precisam se preocupar sobre *recursão*: CPython usa *Py\_EnterRecursiveCall()* e *Py\_LeaveRecursiveCall()* para chamadas utilizando *tp\_call*.

Por questão de eficiência, este não é o caso de chamadas utilizando o *vectorcall*: o que chama deve utilizar *Py\_EnterRecursiveCall* e *Py\_LeaveRecursiveCall* se necessário.

## API de suporte à chamada de vetores

*Py\_ssize\_t* **PyVectorcall\_NARGS** (*size\_t nargsf*)

Dado um argumento de chamada de vetor *nargsf*, retorna o número real de argumentos. Atualmente equivalente a:

```
(Py_ssize_t)(nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET)
```

Entretanto, a função *PyVectorcall\_NARGS* deve ser usada para permitir para futuras extensões.

Novo na versão 3.8.

*vectorcallfunc* **PyVectorcall\_Function** (*PyObject \*op*)

Se *op* não suporta o protocolo de chamada de vetor (seja porque o tipo ou a instância específica não suportam), retorne *NULL*. Se não, retorne o ponteiro da função chamada de vetor armazenado em *op*. Esta função nunca levanta uma exceção.

É mais útil checar se *op* suporta ou não chamada de vetor, o que pode ser feito checando *PyVectorcall\_Function(op) != NULL*.

Novo na versão 3.8.

*PyObject \****PyVectorcall\_Call** (*PyObject \*callable, PyObject \*tuple, PyObject \*dict*)

Chama o *vectorcallfunc* de *callable* com argumentos posicionais e nomeados dados em uma tupla e dicionário, respectivamente.

This is a specialized function, intended to be put in the *tp\_call* slot or be used in an implementation of *tp\_call*. It does not check the *Py\_TPFLAGS\_HAVE\_VECTORCALL* flag and it does not fall back to *tp\_call*.

Novo na versão 3.8.

## 7.2.3 API de chamada de objetos

Várias funções estão disponíveis para chamar um objeto Python. Cada uma converte seus argumentos para uma convenção suportada pelo objeto chamado – seja *tp\_call* ou chamada de vetor. Para fazer o mínimo possível de conversões, escolha um que melhor se adapte ao formato de dados que você tem disponível.

A tabela a seguir resume as funções disponíveis; por favor, veja a documentação individual para detalhes.



Função	chamável	args	kwargs
<code>PyObject_Call()</code>	<code>PyObject *</code>	tupla	dict/NULL
<code>PyObject_CallNoArgs()</code>	<code>PyObject *</code>	—	—
<code>PyObject_CallOneArg()</code>	<code>PyObject *</code>	1 objeto	—
<code>PyObject_CallObject()</code>	<code>PyObject *</code>	tupla/NULL	—
<code>PyObject_CallFunction()</code>	<code>PyObject *</code>	format	—
<code>PyObject_CallMethod()</code>	<code>obj + char *</code>	format	—
<code>PyObject_CallFunctionObjArgs()</code>	<code>PyObject *</code>	variádica	—
<code>PyObject_CallMethodObjArgs()</code>	<code>obj + nome</code>	variádica	—
<code>PyObject_CallMethodNoArgs()</code>	<code>obj + nome</code>	—	—
<code>PyObject_CallMethodOneArg()</code>	<code>obj + nome</code>	1 objeto	—
<code>PyObject_Vectorcall()</code>	<code>PyObject *</code>	vectorcall	vectorcall
<code>PyObject_VectorcallDict()</code>	<code>PyObject *</code>	vectorcall	dict/NULL
<code>PyObject_VectorcallMethod()</code>	<code>arg + nome</code>	vectorcall	vectorcall

*PyObject \****PyObject\_Call** (*PyObject \**callable, *PyObject \**args, *PyObject \**kwargs)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama um objeto Python chamável de *callable*, com argumentos dados pela tupla *args*, e argumentos nomeados dados pelo dicionário *kwargs*.

*args* não deve ser *NULL*; use uma tupla vazia se não precisar de argumentos. Se nenhum argumento nomeado é necessário, *kwargs* pode ser *NULL*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Esse é o equivalente da expressão Python: `callable(*args, **kwargs)`.

*PyObject \****PyObject\_CallNoArgs** (*PyObject \**callable)

*Part of the Stable ABI since version 3.10*. Chama um objeto Python chamável de *callable* sem nenhum argumento. É o jeito mais eficiente de chamar um objeto Python sem nenhum argumento.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

*PyObject \****PyObject\_CallOneArg** (*PyObject \**callable, *PyObject \**arg)

Chama um objeto Python chamável de *callable* com exatamente 1 argumento posicional *arg* e nenhum argumento nomeado.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

*PyObject \****PyObject\_CallObject** (*PyObject \**callable, *PyObject \**args)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama um objeto Python chamável de *callable* com argumentos dados pela tupla *args*. Se nenhum argumento é necessário, *args* pode ser *NULL*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Este é o equivalente da expressão Python: `callable(*args)`.

*PyObject \****PyObject\_CallFunction** (*PyObject \**callable, **const** char \*format, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama um objeto Python chamável de *callable*, com um número variável de argumentos C. Os argumentos C são descritos usando uma string de estilo no formato `Py_BuildValue()`. O formato pode ser *NULL*, indicando que nenhum argumento foi provido.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Este é o equivalente da expressão Python: `callable(*args)`.

Note que se você apenas passa argumentos *PyObject \**, `PyObject_CallFunctionObjArgs()` é uma alternativa mais rápida.



Alterado na versão 3.4: O tipo de *format* foi mudado de `char *`.

*PyObject* \***PyObject\_CallMethod** (*PyObject* \*obj, const char \*name, const char \*format, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama o método chamado *name* do objeto *obj* com um número variável de argumentos C. Os argumentos C são descritos com uma string de formato *Py\_BuildValue()* que deve produzir uma tupla.

O formato pode ser *NULL*, indicado que nenhum argumento foi provido.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Este é o equivalente da expressão Python: `obj.name(arg1, arg2, ...)`.

Note que se você apenas passa argumentos *PyObject\**, *PyObject\_CallMethodObjArgs()* é uma alternativa mais rápida.

Alterado na versão 3.4: Os tipos de *name* e *format* foram mudados de `char *`.

*PyObject* \***PyObject\_CallFunctionObjArgs** (*PyObject* \*callable, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama um objeto Python chamável de *callable*, com um número variável de argumentos *PyObject\**. Os argumentos são providos como um número variável de parâmetros seguidos por um *NULL*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Este é o equivalente da expressão Python: `callable(arg1, arg2, ...)`.

*PyObject* \***PyObject\_CallMethodObjArgs** (*PyObject* \*obj, *PyObject* \*name, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Chama um método do objeto Python *obj*, onde o nome do método é dado como um objeto string Python em *name*. É chamado com um número variável de argumentos *PyObject\**. Os argumentos são providos como um número variável de parâmetros seguidos por um *NULL*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

*PyObject* \***PyObject\_CallMethodNoArgs** (*PyObject* \*obj, *PyObject* \*name)

Chama um método do objeto Python *obj* sem argumentos, onde o nome do método é fornecido como um objeto string do Python em *name*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

*PyObject* \***PyObject\_CallMethodOneArg** (*PyObject* \*obj, *PyObject* \*name, *PyObject* \*arg)

Chama um método do objeto Python *obj* com um argumento posicional *arg*, onde o nome do método é fornecido como um objeto string do Python em *name*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

*PyObject* \***PyObject\_Vectorcall** (*PyObject* \*callable, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwnames)

Chama um objeto Python chamável *callable*. Os argumentos são os mesmos de *vectorcallfunc*. Se *callable* tiver suporte a *vectorcall*, isso chamará diretamente a função *vectorcall* armazenada em *callable*.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

*PyObject* \***PyObject\_VectorcallDict** (*PyObject* \*callable, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwdict)

Chama *callable* com argumentos posicionais passados exatamente como no protocolo *vectorcall*, mas com argumentos nomeados passados como um dicionário *kwdict*. O array *args* contém apenas os argumentos posicionais.

Independentemente de qual protocolo é usado internamente, uma conversão de argumentos precisa ser feita. Portanto, esta função só deve ser usada se o chamador já tiver um dicionário pronto para usar para os argumentos nomeados, mas não uma tupla para os argumentos posicionais.

Novo na versão 3.9.

*PyObject* \***PyObject\_VectorcallMethod** (*PyObject* \*name, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwnames)

Call a method using the vectorcall calling convention. The name of the method is given as a Python string *name*. The object whose method is called is *args*[0], and the *args* array starting at *args*[1] represents the arguments of the call. There must be at least one positional argument. *nargsf* is the number of positional arguments including *args*[0], plus `PY_VECTORCALL_ARGUMENTS_OFFSET` if the value of *args*[0] may temporarily be changed. Keyword arguments can be passed just like in *PyObject\_Vectorcall*().

If the object has the `Py_TPFLAGS_METHOD_DESCRIPTOR` feature, this will call the unbound method object with the full *args* vector as arguments.

Retorna o resultado da chamada em sucesso, ou levanta uma exceção e retorna *NULL* em caso de falha.

Novo na versão 3.9.

## 7.2.4 API de suporte a chamadas

int **PyCallable\_Check** (*PyObject* \*o)

*Part of the Stable ABI.* Determine se o objeto *o* é chamável. Devolva 1 se o objeto é chamável e 0 caso contrário. Esta função sempre tem êxito.

## 7.3 Protocolo de número

int **PyNumber\_Check** (*PyObject* \*o)

*Part of the Stable ABI.* Retorna 1 se o objeto *o* fornece protocolos numéricos; caso contrário, retorna falso. Esta função sempre tem sucesso.

Alterado na versão 3.8: Retorna 1 se *o* for um número inteiro de índice.

*PyObject* \***PyNumber\_Add** (*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna o resultado da adição de *o1* e *o2*, ou *NULL* em caso de falha. Este é o equivalente da expressão Python `o1 + o2`.

*PyObject* \***PyNumber\_Subtract** (*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna o resultado da subtração de *o2* por *o1*, ou *NULL* em caso de falha. Este é o equivalente da expressão Python `o1 - o2`.

*PyObject* \***PyNumber\_Multiply** (*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna o resultado da multiplicação de *o1* e *o2*, ou *NULL* em caso de falha. Este é o equivalente da expressão Python `o1 * o2`.

*PyObject* \***PyNumber\_MatrixMultiply** (*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor: Nova referência. Part of the Stable ABI since version 3.7.* Retorna o resultado da multiplicação da matriz em *o1* e *o2*, ou *NULL* em caso de falha. Este é o equivalente da expressão Python `o1 @ o2`.

Novo na versão 3.5.

*PyObject* \***PyNumber\_FloorDivide** (*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor: Nova referência. Part of the Stable ABI.* Return the floor of *o1* divided by *o2*, or *NULL* on failure. This is the equivalent of the Python expression `o1 // o2`.

*PyObject* \*PyNumber\_TrueDivide(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or NULL on failure. The return value is “approximate” because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. This is the equivalent of the Python expression *o1* / *o2*.

*PyObject* \*PyNumber\_Remainder(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the remainder of dividing *o1* by *o2*, or NULL on failure. This is the equivalent of the Python expression *o1* % *o2*.

*PyObject* \*PyNumber\_Divmod(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* See the built-in function `divmod()`. Returns NULL on failure. This is the equivalent of the Python expression `divmod(o1, o2)`.

*PyObject* \*PyNumber\_Power(*PyObject* \*o1, *PyObject* \*o2, *PyObject* \*o3)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* See the built-in function `pow()`. Returns NULL on failure. This is the equivalent of the Python expression `pow(o1, o2, o3)`, where *o3* is optional. If *o3* is to be ignored, pass `Py_None` in its place (passing NULL for *o3* would cause an illegal memory access).

*PyObject* \*PyNumber\_Negative(*PyObject* \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the negation of *o* on success, or NULL on failure. This is the equivalent of the Python expression `-o`.

*PyObject* \*PyNumber\_Positive(*PyObject* \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns *o* on success, or NULL on failure. This is the equivalent of the Python expression `+o`.

*PyObject* \*PyNumber\_Absolute(*PyObject* \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the absolute value of *o*, or NULL on failure. This is the equivalent of the Python expression `abs(o)`.

*PyObject* \*PyNumber\_Invert(*PyObject* \*o)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the bitwise negation of *o* on success, or NULL on failure. This is the equivalent of the Python expression `~o`.

*PyObject* \*PyNumber\_Lshift(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the result of left shifting *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 << o2`.

*PyObject* \*PyNumber\_Rshift(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the result of right shifting *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 >> o2`.

*PyObject* \*PyNumber\_And(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the “bitwise and” of *o1* and *o2* on success and NULL on failure. This is the equivalent of the Python expression `o1 & o2`.

*PyObject* \*PyNumber\_Xor(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the “bitwise exclusive or” of *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 ^ o2`.

*PyObject* \*PyNumber\_Or(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the “bitwise or” of *o1* and *o2* on success, or NULL on failure. This is the equivalent of the Python expression `o1 | o2`.

*PyObject* \*PyNumber\_InPlaceAdd(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the result of adding *o1* and *o2*, or NULL on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 += o2`.

*PyObject* \*PyNumber\_InPlaceSubtract(*PyObject* \*o1, *PyObject* \*o2)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the result of subtracting *o2* from *o1*, or NULL on

failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 -= o2`.

***PyObject \*PyNumber\_InPlaceMultiply (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the result of multiplying *o1* and *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 *= o2`.

***PyObject \*PyNumber\_InPlaceMatrixMultiply (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) since version 3.7. Returns the result of matrix multiplication on *o1* and *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 @= o2`.

Novo na versão 3.5.

***PyObject \*PyNumber\_InPlaceFloorDivide (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the mathematical floor of dividing *o1* by *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 //= o2`.

***PyObject \*PyNumber\_InPlaceTrueDivide (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or `NULL` on failure. The return value is “approximate” because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 /= o2`.

***PyObject \*PyNumber\_InPlaceRemainder (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the remainder of dividing *o1* by *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 %= o2`.

***PyObject \*PyNumber\_InPlacePower (PyObject \*o1, PyObject \*o2, PyObject \*o3)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). See the built-in function `pow()`. Returns `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 **= o2` when *o3* is `Py_None`, or an in-place variant of `pow(o1, o2, o3)` otherwise. If *o3* is to be ignored, pass `Py_None` in its place (passing `NULL` for *o3* would cause an illegal memory access).

***PyObject \*PyNumber\_InPlaceLshift (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the result of left shifting *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 <= o2`.

***PyObject \*PyNumber\_InPlaceRshift (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the result of right shifting *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 >= o2`.

***PyObject \*PyNumber\_InPlaceAnd (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the “bitwise and” of *o1* and *o2* on success and `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 &= o2`.

***PyObject \*PyNumber\_InPlaceXor (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the “bitwise exclusive or” of *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 ^= o2`.

***PyObject \*PyNumber\_InPlaceOr (PyObject \*o1, PyObject \*o2)***

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Returns the “bitwise or” of *o1* and *o2* on success, or `NULL`

on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 |= o2`.

*PyObject* \***PyNumber\_Long** (*PyObject* \**o*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the *o* converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression `int(o)`.

*PyObject* \***PyNumber\_Float** (*PyObject* \**o*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the *o* converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression `float(o)`.

*PyObject* \***PyNumber\_Index** (*PyObject* \**o*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the *o* converted to a Python int on success or NULL with a `TypeError` exception raised on failure.

Alterado na versão 3.10: O resultado sempre tem o tipo exato `int`. Anteriormente, o resultado poderia ter sido uma instância de uma subclasse de `int`.

*PyObject* \***PyNumber\_ToBase** (*PyObject* \**n*, int *base*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Returns the integer *n* converted to base *base* as a string. The *base* argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of `'0b'`, `'0o'`, or `'0x'`, respectively. If *n* is not a Python int, it is converted with `PyNumber_Index()` first.

*Py\_ssize\_t* **PyNumber\_AsSsize\_t** (*PyObject* \**o*, *PyObject* \**exc*)

*Part of the Stable ABI.* Returns *o* converted to a *Py\_ssize\_t* value if *o* can be interpreted as an integer. If the call fails, an exception is raised and `-1` is returned.

If *o* can be converted to a Python int but the attempt to convert to a *Py\_ssize\_t* value would raise an `OverflowError`, then the *exc* argument is the type of exception that will be raised (usually `IndexError` or `OverflowError`). If *exc* is NULL, then the exception is cleared and the value is clipped to `PY_SSIZE_T_MIN` for a negative integer or `PY_SSIZE_T_MAX` for a positive integer.

int **PyIndex\_Check** (*PyObject* \**o*)

*Part of the Stable ABI since version 3.8.* Returns 1 if *o* is an index integer (has the `nb_index` slot of the `tp_as_number` structure filled in), and 0 otherwise. This function always succeeds.

## 7.4 Protocolo de sequência

int **PySequence\_Check** (*PyObject* \**o*)

*Part of the Stable ABI.* Return 1 if the object provides the sequence protocol, and 0 otherwise. Note that it returns 1 for Python classes with a `__getitem__()` method, unless they are `dict` subclasses, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

*Py\_ssize\_t* **PySequence\_Size** (*PyObject* \**o*)

*Py\_ssize\_t* **PySequence\_Length** (*PyObject* \**o*)

*Part of the Stable ABI.* Retorna o número de objetos na sequência *o* em caso de sucesso, ou `-1` em caso de falha. Equivale à expressão Python `len(o)`.

*PyObject* \***PySequence\_Concat** (*PyObject* \**o1*, *PyObject* \**o2*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Retorna a concatenação de *o1* e *o2* em caso de sucesso, e NULL em caso de falha. Equivale à expressão Python `o1 + o2`.

*PyObject* \***PySequence\_Repeat** (*PyObject* \**o*, *Py\_ssize\_t* *count*)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Retorna o resultado da repetição do objeto sequência *o* *count* vezes ou NULL em caso de falha. Equivale à expressão Python `o * count`.



*PyObject* \*PySequence\_InPlaceConcat (*PyObject* \*o1, *PyObject* \*o2)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna a concatenação de *o1* e *o2* em caso de sucesso, e NULL em caso de falha. A operação é feita *localmente* se *o1* permitir. Equivale à expressão Python `o1 += o2`.

*PyObject* \*PySequence\_InPlaceRepeat (*PyObject* \*o, *Py\_ssize\_t* count)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna o resultado da repetição do objeto sequência *o* *count* vezes ou NULL em caso de falha. A operação é feita *localmente* se *o* permitir. Equivale à expressão Python `o *= count`.

*PyObject* \*PySequence\_GetItem (*PyObject* \*o, *Py\_ssize\_t* i)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna o elemento *i* de *o* ou NULL em caso de falha. Equivale à expressão Python `o[i]`.

*PyObject* \*PySequence\_GetSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna a fatia do objeto sequência *o* entre *i1* e *i2*, ou NULL em caso de falha. Equivale à expressão Python `o[i1:i2]`.

int PySequence\_SetItem (*PyObject* \*o, *Py\_ssize\_t* i, *PyObject* \*v)

*Part of the Stable ABI*. Atribui o objeto *v* ao elemento *i* de *o*. Levanta uma exceção e retorna -1 em caso de falha; retorna 0 em caso de sucesso. Esta função *não* rouba uma referência a *v*. Equivale à instrução Python `o[i]=v`.

Se *v* for NULL, o elemento será removido, mas este recurso foi descontinuado em favor do uso de `PySequence_DelItem()`.

int PySequence\_DelItem (*PyObject* \*o, *Py\_ssize\_t* i)

*Part of the Stable ABI*. Exclui o elemento *i* do objeto *o*. Retorna -1 em caso de falha. Equivale à instrução Python `del o[i]`.

int PySequence\_SetSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2, *PyObject* \*v)

*Part of the Stable ABI*. Atribui o objeto sequência *v* à fatia no objeto sequência *o* de *i1* a *i2*. Equivale à instrução Python `o[i1:i2] = v`.

int PySequence\_DelSlice (*PyObject* \*o, *Py\_ssize\_t* i1, *Py\_ssize\_t* i2)

*Part of the Stable ABI*. Exclui a fatia no objeto sequência *o* de *i1* a *i2*. Retorna -1 em caso de falha. Equivale à instrução Python `del o[i1:i2]`.

*Py\_ssize\_t* PySequence\_Count (*PyObject* \*o, *PyObject* \*value)

*Part of the Stable ABI*. Retorna a quantidade de ocorrências de *value* em *o*, isto é, retorna a quantidade de chaves onde `o[key] == value`. Em caso de falha, retorna -1. Equivale à expressão Python `o.count(value)`.

int PySequence\_Contains (*PyObject* \*o, *PyObject* \*value)

*Part of the Stable ABI*. Determina se *o* contém *value*. Se um item em *o* for igual a *value*, retorna 1, senão, retorna 0. Em caso de erro, retorna -1. Equivale à expressão Python `value in o`.

*Py\_ssize\_t* PySequence\_Index (*PyObject* \*o, *PyObject* \*value)

*Part of the Stable ABI*. Retorna o primeiro índice *i* tal que `o[i] == value`. Em caso de erro, retorna -1. Equivale à expressão Python `o.index(value)`.

*PyObject* \*PySequence\_List (*PyObject* \*o)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um objeto lista com o mesmo conteúdo da sequência ou iterável *o*, ou NULL em caso de falha. Garante-se que a lista retornada será nova. Equivale à expressão Python `list(o)`.

*PyObject* \*PySequence\_Tuple (*PyObject* \*o)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna o objeto tupla com o mesmo conteúdo da sequência ou iterável *o*, ou NULL em caso de falha. Se *o* for uma tupla, retorna uma nova referência. Senão, uma tupla será construída com o conteúdo apropriado. Equivale à expressão Python `tuple(o)`.

*PyObject* \*PySequence\_Fast (*PyObject* \*o, **const** char \*m)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna a sequência ou iterável *o* como um objeto usável

por outras funções da família `PySequence_Fast*`. Se o objeto não for uma sequência ou iterável, levanta `TypeError` com *m* sendo o texto da mensagem. Retorna `NULL` em caso de falha.

As funções `PySequence_Fast*` têm esse nome porque presumem que *o* é um `PyTupleObject` ou um `PyListObject` e porque acessam os campos de dados de *o* diretamente.

Como detalhe de implementação de CPython, se *o* já for uma sequência ou lista, ele será retornado.

*Py\_ssize\_t* **PySequence\_Fast\_GET\_SIZE** (*PyObject* \**o*)

Retorna o comprimento de *o*, presumindo que *o* foi retornado por `PySequence_Fast()` e que *o* não seja `NULL`. O tamanho também pode ser obtido ao chamar `PySequence_Size()` em *o*, mas `PySequence_Fast_GET_SIZE()` é mais rápida, ao supor que *o* é uma lista ou tupla.

*PyObject* \***PySequence\_Fast\_GET\_ITEM** (*PyObject* \**o*, *Py\_ssize\_t* *i*)

Retorna valor: Referência emprestada. Retorna o elemento *i* de *o*, presumindo que *o* foi retornado por `PySequence_Fast()`, que *o* seja `NULL`, e que *i* esteja nos limites.

*PyObject* \*\***PySequence\_Fast\_ITEMS** (*PyObject* \**o*)

Retorna o vetor subjacente de ponteiros `PyObject`. Presume que *o* foi retornado por `PySequence_Fast()` e que *o* não seja `NULL`.

Note que, se uma lista for redimensionada, a realocação poderá reposicionar o vetor de itens. Portanto, só use o ponteiro de vetor subjacente em contextos onde a sequência não mudará.

*PyObject* \***PySequence\_ITEM** (*PyObject* \**o*, *Py\_ssize\_t* *i*)

Retorna valor: Nova referência. Retorna o elemento *i* de *o*, ou `NULL` em caso de falha. É uma forma mais rápida de `PySequence_GetItem()`, mas sem verificar se `PySequence_Check()` em *o* é verdadeiro e sem ajustar índices negativos.

## 7.5 Protocolo de mapeamento

Veja também `PyObject_GetItem()`, `PyObject_SetItem()` e `PyObject_DelItem()`.

int **PyMapping\_Check** (*PyObject* \**o*)

Part of the Stable ABI. Retorna 1 se o objeto fornece protocolo de mapeamento ou suporta fatiamento e 0 caso contrário. Note que ele retorna 1 para classes Python com um método `__getitem__()` visto que geralmente é impossível determinar a que tipo de chaves a classe tem suporte. Esta função sempre tem sucesso.

*Py\_ssize\_t* **PyMapping\_Size** (*PyObject* \**o*)

*Py\_ssize\_t* **PyMapping\_Length** (*PyObject* \**o*)

Part of the Stable ABI. Retorna o número de chaves no objeto *o* em caso de sucesso e `-1` em caso de falha. Isso é equivalente à expressão Python `len(o)`.

*PyObject* \***PyMapping\_GetItemString** (*PyObject* \**o*, const char \**key*)

Retorna valor: Nova referência. Part of the Stable ABI. Retorna o elemento de *o* correspondente à string *key* ou `NULL` em caso de falha. Este é o equivalente da expressão Python `o[key]`. Veja também `PyObject_GetItem()`.

int **PyMapping\_SetItemString** (*PyObject* \**o*, const char \**key*, *PyObject* \**v*)

Part of the Stable ABI. Mapeia a string *key* para o valor *v* no objeto *o*. Retorna `-1` em caso de falha. Este é o equivalente da instrução Python `o[key] = v`. Veja também `PyObject_SetItem()`. Esta função não rouba uma referência a *v*.

int **PyMapping\_DelItem** (*PyObject* \**o*, *PyObject* \**key*)

Remove o mapeamento para o objeto *key* do objeto *o*. Retorna `-1` em caso de falha. Isso é equivalente à instrução Python `del o[key]`. Este é um alias de `PyObject_DelItem()`.

int **PyMapping\_DelItemString** (*PyObject* \**o*, const char \**key*)

Remove o mapeamento para a string *key* do objeto *o*. Retorna `-1` em caso de falha. Isso é equivalente à instrução Python `del o[key]`.

int **PyMapping\_HasKey** (*PyObject* \**o*, *PyObject* \**key*)

*Part of the Stable ABI*. Retorna `1` se o objeto de mapeamento tiver a chave *key* e `0` caso contrário. Isso é equivalente à expressão Python `key in o`. Esta função sempre tem sucesso.

Observe que as exceções que ocorrem ao chamar o método `__getitem__()` serão suprimidas. Para obter relatórios de erros, use `PyObject_GetItem()`.

int **PyMapping\_HasKeyString** (*PyObject* \**o*, const char \**key*)

*Part of the Stable ABI*. Retorna `1` se o objeto de mapeamento tiver a chave *key* e `0` caso contrário. Isso é equivalente à expressão Python `key in o`. Esta função sempre tem sucesso.

Observe que as exceções que ocorrem ao chamar o método `__getitem__()` e criar um objeto string temporário serão suprimidas. Para obter relatórios de erros, use `PyMapping_GetItemString()`.

*PyObject* \***PyMapping\_Keys** (*PyObject* \**o*)

*Retorna valor: Nova referência. Part of the Stable ABI*. Em caso de sucesso, retorna uma lista das chaves no objeto *o*. Em caso de falha, retorna `NULL`.

Alterado na versão 3.7: Anteriormente, a função retornava uma lista ou tupla.

*PyObject* \***PyMapping\_Values** (*PyObject* \**o*)

*Retorna valor: Nova referência. Part of the Stable ABI*. Em caso de sucesso, retorna uma lista dos valores no objeto *o*. Em caso de falha, retorna `NULL`.

Alterado na versão 3.7: Anteriormente, a função retornava uma lista ou tupla.

*PyObject* \***PyMapping\_Items** (*PyObject* \**o*)

*Retorna valor: Nova referência. Part of the Stable ABI*. Em caso de sucesso, retorna uma lista dos itens no objeto *o*, onde cada item é uma tupla contendo um par de valores-chave. Em caso de falha, retorna `NULL`.

Alterado na versão 3.7: Anteriormente, a função retornava uma lista ou tupla.

## 7.6 Protocolo Iterador

Existem duas funções específicas para trabalhar com iteradores.

int **PyIter\_Check** (*PyObject* \**o*)

*Part of the Stable ABI since version 3.8*. Retorna valor diferente de zero se o objeto *o* puder ser passado com segurança para `PyIter_Next()`, e `0` caso contrário. Esta função sempre é bem-sucedida.

int **PyAsyncIter\_Check** (*PyObject* \**o*)

*Part of the Stable ABI since version 3.10*. Retorna valor diferente de zero se o objeto *o* fornecer o protocolo `AsyncIterator` e `0` caso contrário. Esta função sempre é bem-sucedida.

Novo na versão 3.10.

*PyObject* \***PyIter\_Next** (*PyObject* \**o*)

*Retorna valor: Nova referência. Part of the Stable ABI*. Retorna o próximo valor do iterador *o*. O objeto deve ser um iterador de acordo com `PyIter_Check()` (cabe ao chamador verificar isso). Se não houver valores restantes, retorna `NULL` sem nenhuma exceção definida. Se ocorrer um erro ao recuperar o item, retorna `NULL` e passa a exceção.

Para escrever um laço que itere sobre um iterador, o código C deve ser algo como isto:



```

PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while ((item = PyIter_Next(iterator))) {
    /* do something with item */
    ...
    /* release reference when done */
    Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
}
else {
    /* continue doing useful work */
}

```

**type PySendResult**

O valor de enum usado para representar diferentes resultados de `PyIter_Send()`.

Novo na versão 3.10.

*PySendResult* **PyIter\_Send** (*PyObject* \*iter, *PyObject* \*arg, *PyObject* \*\*presult)

*Part of the Stable ABI since version 3.10.* Envia o valor *arg* para o iterador *iter*. Retorna:

- `PYGEN_RETURN` se o iterador retornar. O valor de retorno é retornado via *presult*.
- `PYGEN_NEXT` se o iterador render. O valor produzido é retornado via *presult*.
- `PYGEN_ERROR` se o iterador tiver levantado uma exceção. *presult* é definido como `NULL`.

Novo na versão 3.10.

## 7.7 Protocolo de Buffer

Certos objetos disponíveis no Python envolvem o acesso a um vetor ou *buffer* de memória subjacente. Esses objetos incluem as `bytes` e `bytearray` embutidas, e alguns tipos de extensão como `array.array`. As bibliotecas de terceiros podem definir seus próprios tipos para fins especiais, como processamento de imagem ou análise numérica.

Embora cada um desses tipos tenha sua própria semântica, eles compartilham a característica comum de serem suportados por um *buffer* de memória possivelmente grande. É desejável, em algumas situações, acessar esse *buffer* diretamente e sem cópia intermediária.

Python fornece essa facilidade no nível C sob a forma de *protocolo de buffer*. Este protocolo tem dois lados:

- do lado do produtor, um tipo pode exportar uma “interface de *buffer*” que permite que objetos desse tipo exponham informações sobre o *buffer* subjacente. Esta interface é descrita na seção *Buffer Object Structures*;
- do lado do consumidor, vários meios estão disponíveis para obter o ponteiro para os dados subjacentes de um objeto (por exemplo, um parâmetro de método).

Objetos simples como `bytes` e `bytearray` expõem seu *buffer* subjacente em uma forma orientada a *byte*. Outras formas são possíveis; por exemplo, os elementos expostos por uma `array.array` podem ser valores de vários *bytes*.

Um exemplo de consumidor da interface de buffer é o método `write()` de objetos arquivo: qualquer objeto que pode exportar uma série de bytes através da interface de buffer pode ser gravado em um arquivo. Enquanto `write()` só precisa de acesso somente leitura aos conteúdos internos do objeto passado, outros métodos, tais como `readinto()` precisam de acesso de gravação ao conteúdo de seu argumento. A interface de buffer permite aos objetos permitir ou rejeitar seletivamente a exportação de buffers de leitura e escrita e de somente leitura.

Existem duas maneiras para um consumidor da interface de buffer adquirir um buffer em um objeto alvo:

- chamada de `PyObject_GetBuffer()` com os parâmetros certos;
- chamada de `PyArg_ParseTuple()` (ou um dos seus irmãos) com um dos *códigos de formatação* `y*`, `w*` ou `s*`.

Em ambos os casos, `PyBuffer_Release()` deve ser chamado quando o buffer não é mais necessário. A falta de tal pode levar a várias questões, tais como vazamentos de recursos.

## 7.7.1 Estrutura de Buffer

As estruturas de buffer (ou simplesmente “buffers”) são úteis como uma maneira de expor os dados binários de outro objeto para o programador Python. Eles também podem ser usados como um mecanismo de cópia silenciosa. Usando sua capacidade de fazer referência a um bloco de memória, é possível expor facilmente qualquer dado ao programador Python. A memória pode ser uma matriz grande e constante em uma extensão C, pode ser um bloco bruto de memória para manipulação antes de passar para uma biblioteca do sistema operacional, ou pode ser usado para transmitir dados estruturados no formato nativo e formato de memória.

Ao contrário da maioria dos tipos de dados expostos pelo interpretador Python, os buffers não são ponteiros `PyObject` mas sim estruturas C simples. Isso permite que eles sejam criados e copiados de forma muito simples. Quando um invólucro genérico em torno de um buffer é necessário, um objeto `memoryview` pode ser criado.

Para obter instruções curtas sobre como escrever um objeto exportador, consulte *Buffer Object Structures*. Para obter um buffer, veja `PyObject_GetBuffer()`.

**type `Py_buffer`**

`void *buf`

Um ponteiro para o início da estrutura lógica descrita pelos campos do buffer. Este pode ser qualquer local dentro do bloco de memória física subjacente do exportador. Por exemplo, com negativo `strides` o valor pode apontar para o final do bloco de memória.

Para vetores *contíguos*, o valor aponta para o início do bloco de memória.

`PyObject *obj`

Uma nova referência ao objeto sendo exporta. A referência pertence ao consumidor e é automaticamente liberada (por exemplo, a contagem de referências é decrementada) e é atribuída para NULL por `PyBuffer_Release()`. O campo é equivalente ao valor de retorno de qualquer função do padrão C-API.

Como um caso especial, para buffers *temporários* que são encapsulados por `PyMemoryView_FromBuffer()` ou `PyBuffer_FillInfo()` esse campo é NULL. Em geral, objetos exportadores NÃO DEVEM usar esse esquema.

`Py_ssize_t len`

`product(shape) * itemsize`. Para matrizes contínuas, este é o comprimento do bloco de memória subjacente. Para matrizes não contínuas, é o comprimento que a estrutura lógica teria se fosse copiado para uma representação contígua.

Acessando `((char *)buf)[0]` up to `((char *)buf)[len-1]` só é válido se o buffer tiver sido obtido por uma solicitação que garanta a contiguidade. Na maioria dos casos, esse pedido será

*PyBUF\_SIMPLE* ou *PyBUF\_WRITABLE*.

**int readonly**

Um indicador de se o buffer é somente leitura. Este campo é controlado pelo sinalizador *PyBUF\_WRITABLE*.

*Py\_ssize\_t* **itemsize**

O tamanho do item em bytes de um único elemento. O mesmo que o valor de `struct.calcsize()` chamado em valores não NULL de *format*.

Exceção importante: Se um consumidor requisita um buffer sem sinalizador *PyBUF\_FORMAT*, *format* será definido como NULL, mas *itemsize* ainda terá seu valor para o formato original.

Se *shape* está presente, a igualdade `product(shape) * itemsize == len` ainda é válida e o usuário pode usar *itemsize* para navegar o buffer.

Se *shape* é NULL como resultado de uma *PyBUF\_SIMPLE* ou uma requisição *PyBUF\_WRITABLE*, o consumidor deve ignorar *itemsize* e presumir `itemsize == 1`.

**const char \*format**

Uma string terminada por NUL no estilo de sintaxe de módulo `struct` descrevendo os conteúdos de um único item. Se isso é NULL, "B" (unsigned bytes) é assumido.

Este campo é controlado pelo sinalizador *PyBUF\_FORMAT*.

**int ndim**

O número de dimensões que a memória representa como um vetor n-dimensional. Se é 0, *buf* aponta para um único item representando um escalar. Neste caso, *shape*, *strides* e *suboffsets* DEVEM ser NULL.

A macro `PyBUF_MAX_NDIM` limita o número máximo de dimensões a 64. Os exportadores DEVEM respeitar esse limite, os consumidores de buffers multidimensionais DEVEM ser capazes de lidar com dimensões `PyBUF_MAX_NDIM`.

*Py\_ssize\_t* \***shape**

Uma matriz de *Py\_ssize\_t* do comprimento *ndim* indicando a forma da memória como uma matriz n-dimensional. Observe que a forma `shape[0] * ... * shape[ndim-1] * itemsize` DEVE ser igual a *len*.

Os valores da forma são restritos a `shape[n] >= 0`. The case `shape[n] == 0` requer atenção especial. Veja *complex arrays* para mais informações.

A forma de acesso a matriz é de somente leitura para o usuário.

*Py\_ssize\_t* \***strides**

Um vetor de *Py\_ssize\_t* de comprimento *ndim* dando o número de bytes para saltar para obter um novo elemento em cada dimensão.

Os valores de Stride podem ser qualquer número inteiro. Para arrays regulares, os passos são geralmente positivos, mas um consumidor DEVE ser capaz de lidar com o caso `strides[n] <= 0`. Veja *complex arrays* para mais informações.

A matriz de passos é de somente leitura para o consumidor.

*Py\_ssize\_t* \***suboffsets**

Uma matriz de *Py\_ssize\_t* de comprimento *ndim*. Se `suboffsets[n] >= 0`, os valores armazenados ao longo da n-ésima dimensão são ponteiros e o valor suboffset determina quantos bytes para adicionar a cada ponteiro após desreferenciar. Um valor de suboffset que é negativo indica que não deve ocorrer desreferenciação (caminhando em um bloco de memória contíguo).

Se todos os subconjuntos forem negativos (ou seja, não é necessário fazer referência), então este campo deve ser NULL (o valor padrão).

Esse tipo de representação de matriz é usado pela Python Imaging Library (PIL). Veja *complex arrays* para obter mais informações sobre como acessar elementos dessa matriz.

A matriz de subconjuntos é somente leitura para o consumidor.

void **\*internal**

Isso é para uso interno pelo objeto exportador. Por exemplo, isso pode ser re-moldado como um número inteiro pelo exportador e usado para armazenar bandeiras sobre se os conjuntos de forma, passos e suboffsets devem ou não ser liberados quando o buffer é liberado. O consumidor NÃO DEVE alterar esse valor.

## 7.7.2 Tipos de solicitação do buffer

Os buffers geralmente são obtidos enviando uma solicitação de buffer para um objeto exportador via `PyObject_GetBuffer()`. Uma vez que a complexidade da estrutura lógica da memória pode variar drasticamente, o consumidor usa o argumento *flags* para especificar o tipo de buffer exato que pode manipular.

Todos *Py\_buffer* são inequivocamente definidos pelo tipo de solicitação.

### campos independentes do pedido

Os seguintes campos não são influenciados por *flags* e devem sempre ser preenchidos com os valores corretos: *obj*, *buf*, *len*, *itemsize*, *ndim*.

### apenas em formato

#### **PyBUF\_WRITABLE**

Controla o campo *readonly*. Se configurado, o exportador DEVE fornecer um buffer gravável ou então reportar falha. Caso contrário, o exportador pode fornecer um buffer de somente leitura ou gravável, mas a escolha DEVE ser consistente para todos os consumidores.

#### **PyBUF\_FORMAT**

Controla o campo *format*. Se configurado, este campo DEVE ser preenchido corretamente. Caso contrário, este campo DEVE ser NULL.

*PyBUF\_WRITABLE* pode ser |'d para qualquer um dos sinalizadores na próxima seção. Uma vez que *PyBUF\_WRITABLE* é definido como 0, *PyBUF\_WRITABLE* pode ser usado como uma bandeira autônoma para solicitar um buffer simples gravável.

*PyBUF\_FORMAT* pode ser |'d para qualquer um dos sinalizadores, exceto *PyBUF\_SIMPLE*. O último já implica o formato B (bytes não assinados).

### forma, avanços, suboffsets

As bandeiras que controlam a estrutura lógica da memória estão listadas em ordem decrescente de complexidade. Observe que cada bandeira contém todos os bits das bandeiras abaixo.

Solicitação	Forma	Avanços	subconjuntos
<b>PyBUF_INDIRECT</b>	sim	sim	se necessário
<b>PyBUF_STRIDES</b>	sim	sim	NULL
<b>PyBUF_ND</b>	sim	NULL	NULL
<b>PyBUF_SIMPLE</b>	NULL	NULL	NULL

### requisições contíguas

*contiguity* do C ou Fortran podem ser explicitamente solicitadas, com ou sem informação de avanço. Sem informação de avanço, o buffer deve ser C-contíguo.

Solicitação	Forma	Avanços	subconjuntos	contig
<b>PyBUF_C_CONTIGUOUS</b>	sim	sim	NULL	C
<b>PyBUF_F_CONTIGUOUS</b>	sim	sim	NULL	F
<b>PyBUF_ANY_CONTIGUOUS</b>	sim	sim	NULL	C ou F
<i>PyBUF_ND</i>	sim	NULL	NULL	C

### requisições compostas

Todas as requisições possíveis foram completamente definidas por alguma combinação dos sinalizadores na seção anterior. Por conveniência, o protocolo do buffer fornece combinações frequentemente utilizadas como sinalizadores únicos.

Na seguinte tabela *U* significa contiguidade indefinida. O consumidor deve chamar *PyBuffer\_IsContiguous()* para determinar a contiguidade.

Solicitação	Forma	Avanços	subconjuntos	contig	readonly	format
<code>PyBUF_FULL</code>	sim	sim	se necessário	U	0	sim
<code>PyBUF_FULL_RO</code>	sim	sim	se necessário	U	1 ou 0	sim
<code>PyBUF_RECORDS</code>	sim	sim	NULL	U	0	sim
<code>PyBUF_RECORDS_RO</code>	sim	sim	NULL	U	1 ou 0	sim
<code>PyBUF_STRIDED</code>	sim	sim	NULL	U	0	NULL
<code>PyBUF_STRIDED_RO</code>	sim	sim	NULL	U	1 ou 0	NULL
<code>PyBUF_CONTIG</code>	sim	NULL	NULL	C	0	NULL
<code>PyBUF_CONTIG_RO</code>	sim	NULL	NULL	C	1 ou 0	NULL

## 7.7.3 Vetores Complexos

### Estilo NumPy: forma e avanços

A estrutura lógica de vetores do estilo NumPy é definida por *itemsize*, *ndim*, *shape* e *strides*.

Se *ndim* == 0, a localização da memória apontada para *buf* é interpretada como um escalar de tamanho *itemsize*. Nesse caso, ambos *shape* e *strides* são NULL.

Se *strides* é NULL, o vetor é interpretado como um vetor C n-dimensional padrão. Caso contrário, o consumidor deve acessar um vetor n-dimensional como a seguir:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

Como notado acima, *buf* pode apontar para qualquer localização dentro do bloco de memória em si. Um exportador pode verificar a validade de um buffer com essa função:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
    the bounds of the allocated memory:
        char *mem: start of the physical memory block
        memlen: length of the physical memory block
        offset: (char *)buf - mem
    """
    if offset % itemsize:
        return False
    if offset < 0 or offset+itemsize > memlen:
        return False
    if any(v % itemsize for v in strides):
        return False
```

(continua na próxima página)

(continuação da página anterior)

```

if ndim <= 0:
    return ndim == 0 and not shape and not strides
if 0 in shape:
    return True

imin = sum(strides[j]*(shape[j]-1) for j in range(ndim)
            if strides[j] <= 0)
imax = sum(strides[j]*(shape[j]-1) for j in range(ndim)
            if strides[j] > 0)

return 0 <= offset+imin and offset+imax+itemsizesize <= memlen

```

### Estilo-PIL: forma, avanços e suboffsets

Além dos itens normais, uma matriz em estilo PIL pode conter ponteiros que devem ser seguidos para se obter o próximo elemento em uma dimensão. Por exemplo, a matriz tridimensional em C `char v[2][2][3]` também pode ser vista como um vetor de 2 ponteiros para duas matrizes bidimensionais: `char (*v[2])[2][3]`. Na representação por suboffsets, esses dois ponteiros podem ser embutidos no início de *buf*, apontando para duas matrizes `char x[2][3]` que podem estar localizadas em qualquer lugar na memória.

Esta é uma função que retorna um ponteiro para o elemento em uma matriz N-D apontada por um índice N-dimensional onde existem ambos passos e subconjuntos não-NULL:

```

void *get_item_pointer(int ndim, void *buf, Py_ssize_t *strides,
                      Py_ssize_t *suboffsets, Py_ssize_t *indices) {
    char *pointer = (char*)buf;
    int i;
    for (i = 0; i < ndim; i++) {
        pointer += strides[i] * indices[i];
        if (suboffsets[i] >= 0) {
            pointer = *((char**)pointer) + suboffsets[i];
        }
    }
    return (void*)pointer;
}

```

## 7.7.4 Funções relacionadas ao Buffer

int **PyObject\_CheckBuffer** (PyObject \*obj)

Retorna 1 se *obj* oferece suporte à interface de buffer, se não, 0. Quando 1 é retornado, isso não garante que *PyObject\_GetBuffer()* será bem sucedida. Esta função é sempre bem sucedida.

int **PyObject\_GetBuffer** (PyObject \*exporter, Py\_buffer \*view, int flags)

Envia uma requisição para o *exporter* para preencher *view* como especificado por *flags*. Se o exportador não consegue prover um buffer do mesmo tipo, ele DEVE levantar `PyExc_BufferError`, definir *view->obj* para NULL e retornar -1.

Em caso de sucesso, preenche *view*, define *view->obj* para uma nova referência para *exporter* e retorna 0. No caso de provedores de buffer encadeados que redirecionam requisições para um único objeto, *view->obj* DEVE se referir a este objeto em vez de *exporter* (Veja *Buffer Object Structures*).

Chamadas bem sucedidas para *PyObject\_GetBuffer()* devem ser emparelhadas a chamadas para *PyBuffer\_Release()*, similar para *malloc()* e *free()*. Assim, após o consumidor terminar com o

buffer, `PyBuffer_Release()` deve ser chamado exatamente uma vez.

void **PyBuffer\_Release** (*Py\_buffer* \*view)

Libera o buffer de *view* e libera o *strong reference* (por exemplo, decrementa o contador de referências) para o objeto de suporte da *view*, `view->obj`. Esta função DEVE ser chamada quando o buffer não estiver mais sendo usado, ou o vazamento de referências pode acontecer.

É um erro chamar essa função em um buffer que não foi obtido via `PyObject_GetBuffer()`.

*Py\_ssize\_t* **PyBuffer\_SizeFromFormat** (**const** char \*format)

Retorna o implícito *itemsize* de *format*. Se houver erro, levanta uma exceção e retorna -1.

Novo na versão 3.9.

int **PyBuffer\_IsContiguous** (*Py\_buffer* \*view, char order)

Retorna 1 se a memória definida pela *view* é *contígua* no estilo C (*order* é 'C') ou no estilo Fortran (*order* é 'F') ou qualquer outra (*order* é 'A'). Retorna 0 caso contrário. Essa função é sempre bem sucedida.

void \***PyBuffer\_GetPointer** (*Py\_buffer* \*view, *Py\_ssize\_t* \*indices)

Recebe a área de memória apontada pelos *indices* dentro da *view* dada. *indices* deve apontar para um array de `view->ndim` índices.

int **PyBuffer\_FromContiguous** (*Py\_buffer* \*view, void \*buf, *Py\_ssize\_t* len, char fort)

Copia *len* bytes contíguos de *buf* para *view*. *fort* pode ser 'C' ou 'F' (para ordenação estilo C ou estilo Fortran). Retorna 0 em caso de sucesso e -1 em caso de erro.

int **PyBuffer\_ToContiguous** (void \*buf, *Py\_buffer* \*src, *Py\_ssize\_t* len, char order)

Copia *len* bytes de *src* para sua representação contígua em *buf*. *order* pode ser 'C' ou 'F' ou 'A' (para ordenação estilo C, Fortran ou qualquer uma). O retorno é 0 em caso de sucesso e -1 em caso de falha.

Esta função falha se *len* != *src->len*.

void **PyBuffer\_FillContiguousStrides** (int ndims, *Py\_ssize\_t* \*shape, *Py\_ssize\_t* \*strides, int itemsize, char order)

Preenche o array *strides* com byte-strides de um array *contíguo* (estilo C se *order* é 'C' ou estilo Fortran se *order* for 'F') da forma dada com o número dado de bytes por elemento.

int **PyBuffer\_FillInfo** (*Py\_buffer* \*view, *PyObject* \*exporter, void \*buf, *Py\_ssize\_t* len, int readonly, int flags)

Manipula requisições de buffer para um exportador que quer expor *buf* de tamanho *len* com capacidade de escrita definida de acordo com *readonly*. *buf* é interpretada como uma sequência de bytes sem sinal.

O argumento *flags* indica o tipo de requisição. Esta função sempre preenche *view* como especificado por *flags*, a não ser que *buf* seja designado como somente leitura e `PyBUF_WRITABLE` esteja definido em *flags*.

Em caso de sucesso, define `view->obj` para uma nova referência para *exporter* e retorna 0. Caso contrário, levanta `PyExc_BufferError`, define `view->obj` para NULL e retorna -1;

Se esta função é usada como parte de um *getbufferproc*, *exporter* DEVE ser definida para o objeto de exportação e *flags* deve ser passado sem modificações. Caso contrário, *exporter* DEVE ser NULL.



## 7.8 Protocolo de Buffer Antigo

Obsoleto desde a versão 3.0.

Essas funções faziam parte da API do “protocolo de buffer antigo” no Python 2. No Python 3, esse protocolo não existe mais, mas as funções ainda estão expostas para facilitar a portabilidade do código 2.x. Eles atuam como um wrapper de compatibilidade em torno do *novο protocolo de buffer*, mas não oferecem controle sobre a vida útil dos recursos adquiridos quando um buffer é exportado.

Portanto, é recomendável que você chame `PyObject_GetBuffer()` (ou os *códigos de formatação* `y*` ou `w*` com o família de funções de `PyArg_ParseTuple()`) para obter uma visão de buffer sobre um objeto e `PyBuffer_Release()` quando a visão de buffer puder ser liberada.

int **PyObject\_AsCharBuffer** (*PyObject* \*obj, const char \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

*Part of the Stable ABI.* Retorna um ponteiro para um local de memória somente leitura utilizável como entrada baseada em caracteres. O argumento *obj* deve ter suporte a interface do buffer de caracteres de segmento único. Em caso de sucesso, retorna 0, define *buffer* com o local da memória e *buffer\_len* com o comprimento do buffer. Retorna -1 e define a `TypeError` em caso de erro.

int **PyObject\_AsReadBuffer** (*PyObject* \*obj, const void \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

*Part of the Stable ABI.* Retorna um ponteiro para um local de memória somente leitura que contém dados arbitrários. O argumento *obj* deve ter suporte a interface de buffer legível de segmento único. Em caso de sucesso, retorna 0, define *buffer* com o local da memória e *buffer\_len* com o comprimento do buffer. Retorna -1 e define a `TypeError` em caso de erro.

int **PyObject\_CheckReadBuffer** (*PyObject* \*o)

*Part of the Stable ABI.* Retorna 1 se *o* tiver suporte a interface de buffer legível de segmento único. Caso contrário, retorna 0. Esta função sempre tem sucesso.

Observe que esta função tenta obter e liberar um buffer, e as exceções que ocorrem ao chamar as funções correspondentes serão suprimidas. Para obter o relatório de erros, use `PyObject_GetBuffer()` em vez disso.

int **PyObject\_AsWriteBuffer** (*PyObject* \*obj, void \*\*buffer, *Py\_ssize\_t* \*buffer\_len)

*Part of the Stable ABI.* Retorna um ponteiro para um local de memória gravável. O argumento *obj* deve ter suporte a interface de buffer de caracteres de segmento único. Em caso de sucesso, retorna 0, define *buffer* com o local da memória e *buffer\_len* com o comprimento do buffer. Retorna -1 e define a `TypeError` em caso de erro.



---

## Camada de Objetos Concretos

---

As funções neste capítulo são específicas para certos tipos de objetos Python. Passar para eles um objeto do tipo errado não é uma boa ideia; se você receber um objeto de um programa Python e não tiver certeza de que ele tem o tipo certo, primeiro execute uma verificação de tipo; por exemplo, para verificar se um objeto é um dicionário, use `PyDict_Check()`. O capítulo está estruturado como a “árvore genealógica” dos tipos de objetos Python.

**Aviso:** Enquanto as funções descritas neste capítulo verificam cuidadosamente o tipo de objetos passados, muitos deles não verificam a passagem de `NULL` em vez de um objeto válido. Permitir a passagem de `NULL` pode causar violações ao acesso à memória e encerramento imediato do interpretador.

### 8.1 Objetos Fundamentais

Esta seção descreve os objetos de tipo Python e o objeto singleton `None`.

#### 8.1.1 Objetos tipo

##### **type** `PyTypeObject`

*Part of the Limited API (as an opaque struct).* A estrutura C dos objetos usados para descrever tipos embutidos.

##### *PyTypeObject* **PyType\_Type**

*Part of the Stable ABI.* Este é o objeto de tipo para objetos tipo; é o mesmo objeto que `type` na camada Python.

##### **int** `PyType_Check` (*PyObject* \**o*)

Retorna valor diferente de zero se o objeto *o* for um objeto tipo, incluindo instâncias de tipos derivados do objeto tipo padrão. Retorna 0 em todos os outros casos. Esta função sempre tem sucesso.

##### **int** `PyType_CheckExact` (*PyObject* \**o*)

Retorna valor diferente de zero se o objeto *o* for um objeto tipo, mas não um subtipo do objeto tipo padrão. Retorna 0 em todos os outros casos. Esta função sempre tem sucesso.

unsigned int **PyType\_ClearCache** ()

*Part of the Stable ABI.* Limpa o cache de pesquisa interno. Retorna a marcação de versão atual.

unsigned long **PyType\_GetFlags** (*PyTypeObject \*type*)

*Part of the Stable ABI.* Return the *tp\_flags* member of *type*. This function is primarily meant for use with `Py_LIMITED_API`; the individual flag bits are guaranteed to be stable across Python releases, but access to *tp\_flags* itself is not part of the limited API.

Novo na versão 3.2.

Alterado na versão 3.4: O tipo de retorno é agora um `unsigned long` em vez de um `long`.

void **PyType\_Modified** (*PyTypeObject \*type*)

*Part of the Stable ABI.* Invalida o cache de pesquisa interna para o tipo e todos os seus subtipos. Esta função deve ser chamada após qualquer modificação manual dos atributos ou classes bases do tipo.

int **PyType\_HasFeature** (*PyTypeObject \*o*, int *feature*)

Retorna valor diferente de zero se o objeto tipo *o* define o recurso *feature*. Os recursos de tipo são denotados por sinalizadores de bit único.

int **PyType\_IS\_GC** (*PyTypeObject \*o*)

Retorna verdadeiro se o objeto tipo incluir suporte para o detector de ciclo; isso testa o sinalizador de tipo `Py_TPFLAGS_HAVE_GC`.

int **PyType\_IsSubtype** (*PyTypeObject \*a*, *PyTypeObject \*b*)

*Part of the Stable ABI.* Retorna verdadeiro se *a* for um subtipo de *b*.

Esta função só verifica pelos subtipos, o que significa que `__subclasscheck__()` não é chamado em *b*. Chame `PyObject_IsSubclass()` para fazer a mesma verificação que `issubclass()` faria.

*PyObject \****PyType\_GenericAlloc** (*PyTypeObject \*type*, *Py\_ssize\_t nitems*)

Retorna valor: Nova referência. *Part of the Stable ABI.* Manipulador genérico para o slot `tp_alloc` de um objeto tipo. Use o mecanismo de alocação de memória padrão do Python para alocar uma nova instância e inicializar todo o seu conteúdo para `NULL`.

*PyObject \****PyType\_GenericNew** (*PyTypeObject \*type*, *PyObject \*args*, *PyObject \*kwargs*)

Retorna valor: Nova referência. *Part of the Stable ABI.* Manipulador genérico para o slot `tp_new` de um objeto tipo. Cria uma nova instância usando o slot `tp_alloc` do tipo.

int **PyType\_Ready** (*PyTypeObject \*type*)

*Part of the Stable ABI.* Finaliza um objeto tipo. Isso deve ser chamado em todos os objetos tipo para finalizar sua inicialização. Esta função é responsável por adicionar slots herdados da classe base de um tipo. Retorna 0 em caso de sucesso, ou retorna -1 e define uma exceção em caso de erro.

---

**Nota:** If some of the base classes implements the GC protocol and the provided type does not include the `Py_TPFLAGS_HAVE_GC` in its flags, then the GC protocol will be automatically implemented from its parents. On the contrary, if the type being created does include `Py_TPFLAGS_HAVE_GC` in its flags then it **must** implement the GC protocol itself by at least implementing the `tp_traverse` handle.

---

void **\*PyType\_GetSlot** (*PyTypeObject \*type*, int *slot*)

*Part of the Stable ABI since version 3.4.* Retorna o ponteiro de função armazenado no slot fornecido. Se o resultado for `NULL`, isso indica que o slot é `NULL` ou que a função foi chamada com parâmetros inválidos. Os chamadores normalmente lançarão o ponteiro do resultado no tipo de função apropriado.

Veja `PyType_Slot.slot` por possíveis valores do argumento *slot*.

Novo na versão 3.4.

Alterado na versão 3.10: `PyType_GetSlot()` can now accept all types. Previously, it was limited to *heap types*.

*PyObject* \*PyType\_GetModule (PyTypeObject \*type)

Part of the [Stable ABI](#) since version 3.10. Retorna o objeto de módulo associado ao tipo fornecido quando o tipo foi criado usando `PyType_FromModuleAndSpec()`.

Se nenhum módulo estiver associado com o tipo fornecido, define `TypeError` e retorna `NULL`.

This function is usually used to get the module in which a method is defined. Note that in such a method, `PyType_GetModule(Py_TYPE(self))` may not return the intended result. `Py_TYPE(self)` may be a subclass of the intended class, and subclasses are not necessarily defined in the same module as their superclass. See [PyCMethod](#) to get the class that defines the method.

Novo na versão 3.9.

void \*PyType\_GetModuleState (PyTypeObject \*type)

Part of the [Stable ABI](#) since version 3.10. Return the state of the module object associated with the given type. This is a shortcut for calling `PyModule_GetState()` on the result of `PyType_GetModule()`.

Se nenhum módulo estiver associado com o tipo fornecido, define `TypeError` e retorna `NULL`.

If the *type* has an associated module but its state is `NULL`, returns `NULL` without setting an exception.

Novo na versão 3.9.

## Creating Heap-Allocated Types

The following functions and structs are used to create *heap types*.

*PyObject* \*PyType\_FromModuleAndSpec (PyObject \*module, PyType\_Spec \*spec, PyObject \*bases)

Retorna valor: Nova referência. Part of the [Stable ABI](#) since version 3.10. Creates and returns a *heap type* from the *spec* (`Py_TPFLAGS_HEAPTYPE`).

The *bases* argument can be used to specify base classes; it can either be only one class or a tuple of classes. If *bases* is `NULL`, the `Py_tp_bases` slot is used instead. If that also is `NULL`, the `Py_tp_base` slot is used instead. If that also is `NULL`, the new type derives from `object`.

The *module* argument can be used to record the module in which the new class is defined. It must be a module object or `NULL`. If not `NULL`, the module is associated with the new type and can later be retrieved with `PyType_GetModule()`. The associated module is not inherited by subclasses; it must be specified for each class individually.

This function calls `PyType_Ready()` on the new type.

Novo na versão 3.9.

Alterado na versão 3.10: The function now accepts a single class as the *bases* argument and `NULL` as the `tp_doc` slot.

*PyObject* \*PyType\_FromSpecWithBases (PyType\_Spec \*spec, PyObject \*bases)

Retorna valor: Nova referência. Part of the [Stable ABI](#) since version 3.3. Equivalent to `PyType_FromModuleAndSpec(NULL, spec, bases)`.

Novo na versão 3.3.

*PyObject* \*PyType\_FromSpec (PyType\_Spec \*spec)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Equivalent to `PyType_FromSpecWithBases(spec, NULL)`.

type PyType\_Spec

Part of the [Stable ABI](#) (including all members). Structure defining a type's behavior.

const char \*PyType\_Spec.name

Name of the type, used to set `PyTypeObject.tp_name`.

`int PyType_Spec.basicsize`

`int PyType_Spec.itemsize`

Size of the instance in bytes, used to set `PyTypeObject.tp_basicsize` and `PyTypeObject.tp_itemsize`.

`int PyType_Spec.flags`

Type flags, used to set `PyTypeObject.tp_flags`.

If the `Py_TPFLAGS_HEAPTYPE` flag is not set, `PyType_FromSpecWithBases()` sets it automatically.

`PyType_Slot *PyType_Spec.slots`

Array of `PyType_Slot` structures. Terminated by the special slot value `{0, NULL}`.

**type `PyType_Slot`**

Part of the [Stable ABI](#) (including all members). Structure defining optional functionality of a type, containing a slot ID and a value pointer.

`int PyType_Slot.slot`

A slot ID.

Slot IDs are named like the field names of the structures `PyTypeObject`, `PyNumberMethods`, `PySequenceMethods`, `PyMappingMethods` and `PyAsyncMethods` with an added `Py_` prefix. For example, use:

- `Py_tp_dealloc` to set `PyTypeObject.tp_dealloc`
- `Py_nb_add` to set `PyNumberMethods.nb_add`
- `Py_sq_length` to set `PySequenceMethods.sq_length`

The following fields cannot be set at all using `PyType_Spec` and `PyType_Slot`:

- `tp_dict`
- `tp_mro`
- `tp_cache`
- `tp_subclasses`
- `tp_weaklist`
- `tp_vectorcall`
- `tp_weaklistoffset` (see `PyMemberDef`)
- `tp_dictoffset` (see `PyMemberDef`)
- `tp_vectorcall_offset` (see `PyMemberDef`)

The following fields cannot be set using `PyType_Spec` and `PyType_Slot` under the limited API:

- `bf_getbuffer`
- `bf_releasebuffer`

Setting `Py_tp_bases` or `Py_tp_base` may be problematic on some platforms. To avoid issues, use the `bases` argument of `PyType_FromSpecWithBases()` instead.

Alterado na versão 3.9: Slots in `PyBufferProcs` may be set in the unlimited API.

`void *PyType_Slot.pfunc`

The desired value of the slot. In most cases, this is a pointer to a function.

Slots other than `Py_tp_doc` may not be NULL.

### 8.1.2 O Objeto None

Observe que o `PyTypeObject` para `None` não está diretamente exposto pela API Python/C. Como `None` é um singleton, é suficiente testar a identidade do objeto (usando `==` em C). Não há nenhuma função `PyNone_Check()` pela mesma razão.

*PyObject* \***Py\_None**

O objeto Python `None`, denota falta de valor. Este objeto não tem métodos. O mesmo precisa ser tratado como qualquer outro objeto com relação à contagem de referência.

**Py\_RETURN\_NONE**

Manipular devidamente o retorno `Py_None` de dentro de uma função C (ou seja, incrementar a contagem de referência de `None` e devolvê-la.)

## 8.2 Objetos Numéricos

### 8.2.1 Objetos Inteiros

Todos os inteiros são implementados como objetos inteiros “longos” de tamanho arbitrário.

Em caso de erro, a maioria das APIs `PyLong_As*` retorna (tipo de retorno) `-1` que não pode ser distinguido de um número. Use `PyErr_Occurred()` para desambiguar.

**type PyLongObject**

Part of the [Limited ABI](#) (as an opaque struct). Este subtipo de `PyObject` representa um objeto inteiro Python.

*PyTypeObject* **PyLong\_Type**

Part of the [Stable ABI](#). Esta instância de `PyTypeObject` representa o tipo inteiro Python. Este é o mesmo objeto que `int` na camada Python.

int **PyLong\_Check** (*PyObject* \*p)

Retorna true se seu argumento é um `PyLongObject` ou um subtipo de `PyLongObject`. Esta função sempre tem sucesso.

int **PyLong\_CheckExact** (*PyObject* \*p)

Retorna true se seu argumento é um `PyLongObject`, mas não um subtipo de `PyLongObject`. Esta função sempre tem sucesso.

*PyObject* \***PyLong\_FromLong** (long v)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Retorna um novo objeto `PyLongObject` de `v` ou NULL em caso de falha.

A implementação atual mantém um vetor de objetos inteiros para todos os inteiros entre `-5` e `256`. Quando você cria um `int` nesse intervalo, você na verdade apenas obtém uma referência ao objeto existente.

*PyObject* \***PyLong\_FromUnsignedLong** (unsigned long v)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Retorna um novo objeto `PyLongObject` de um unsigned long C ou NULL em caso de falha.

*PyObject* \***PyLong\_FromSsize\_t** (*Py\_ssize\_t* v)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Retorna um novo objeto `PyLongObject` de um `Py_ssize_t` C ou NULL em caso de falha.

*PyObject* \***PyLong\_FromSize\_t** (size\_t v)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto *PyLongObject* de um size\_t C ou NULL em caso de falha.

*PyObject* \***PyLong\_FromLongLong** (long long v)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto *PyLongObject* de um long long C ou NULL em caso de falha.

*PyObject* \***PyLong\_FromUnsignedLongLong** (unsigned long long v)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto *PyLongObject* de um unsigned long long C ou NULL em caso de falha.

*PyObject* \***PyLong\_FromDouble** (double v)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto *PyLongObject* da parte inteira de v ou NULL em caso de falha.

*PyObject* \***PyLong\_FromString** (const char \*str, char \*\*pend, int base)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo *PyLongObject* com base no valor da string em str, que é interpretado de acordo com a raiz em base. Se pend não for NULL, \*pend apontará para o primeiro caractere em str que segue a representação do número. Se base for 0, str é interpretado usando a definição de integers; neste caso, zeros à esquerda em um número decimal diferente de zero aumenta um ValueError. Se base não for 0, deve estar entre 2 e 36, inclusive. Espaços iniciais e sublinhados simples após um especificador de base e entre dígitos são ignorados. Se não houver dígitos, ValueError será levantada.

#### Ver também:

Python methods `int.to_bytes()` and `int.from_bytes()` to convert a *PyLongObject* to/from an array of bytes in base 256. You can call those from C using *PyObject\_CallMethod()*.

*PyObject* \***PyLong\_FromUnicodeObject** (*PyObject* \*u, int base)

Retorna valor: Nova referência. Converte uma sequência de dígitos Unicode na string u para um valor inteiro Python.

Novo na versão 3.3.

*PyObject* \***PyLong\_FromVoidPtr** (void \*p)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um inteiro Python a partir do ponteiro p. O valor do ponteiro pode ser recuperado do valor resultante usando *PyLong\_AsVoidPtr()*.

long **PyLong\_AsLong** (*PyObject* \*obj)

*Part of the Stable ABI*. Return a C long representation of obj. If obj is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Raise `OverflowError` if the value of obj is out of range for a long.

Retorna -1 no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

Alterado na versão 3.10: This function will no longer use `__int__()`.

long **PyLong\_AsLongAndOverflow** (*PyObject* \*obj, int \*overflow)

*Part of the Stable ABI*. Return a C long representation of obj. If obj is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Se o valor de obj for maior que `LONG_MAX` ou menor que `LONG_MIN`, define \*overflow para 1 ou -1, respectivamente, e retorna -1; caso contrário, define \*overflow para 0. Se qualquer outra exceção ocorrer, define \*overflow para 0 e retorne -1 como de costume.

Retorna -1 no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

Alterado na versão 3.8: Usa `__index__()`, se disponível.



Alterado na versão 3.10: This function will no longer use `__int__()`.

`long long PyLong_AsLongLong (PyObject *obj)`

*Part of the Stable ABI.* Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Raise `OverflowError` if the value of *obj* is out of range for a long long.

Retorna -1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

Alterado na versão 3.10: This function will no longer use `__int__()`.

`long long PyLong_AsLongLongAndOverflow (PyObject *obj, int *overflow)`

*Part of the Stable ABI.* Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Se o valor de *obj* for maior que `LLONG_MAX` ou menor que `LLONG_MIN`, define *\*overflow* para 1 ou -1, respectivamente, e retorna -1; caso contrário, define *\*overflow* para 0. Se qualquer outra exceção ocorrer, define *\*overflow* para 0 e retorne -1 como de costume.

Retorna -1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

Novo na versão 3.2.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

Alterado na versão 3.10: This function will no longer use `__int__()`.

`Py_ssize_t PyLong_AsSsize_t (PyObject *pylong)`

*Part of the Stable ABI.* Retorna uma representação de `Py_ssize_t` C de *pylong*. *pylong* deve ser uma instância de *PyLongObject*.

Levanta `OverflowError` se o valor de *pylong* estiver fora do intervalo de um `Py_ssize_t`.

Retorna -1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

`unsigned long PyLong_AsUnsignedLong (PyObject *pylong)`

*Part of the Stable ABI.* Return a C unsigned long representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for a unsigned long.

Retorna (unsigned long)-1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

`size_t PyLong_AsSize_t (PyObject *pylong)`

*Part of the Stable ABI.* Retorna uma representação de `size_t` C de *pylong*. *pylong* deve ser uma instância de *PyLongObject*.

Levanta `OverflowError` se o valor de *pylong* estiver fora do intervalo de um `size_t`.

Retorna (size)-1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

`unsigned long long PyLong_AsUnsignedLongLong (PyObject *pylong)`

*Part of the Stable ABI.* Return a C unsigned long long representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for an unsigned long long.

Retorna (unsigned long long)-1 no caso de erro. Use `PyErr_Occurred()` para desambiguar.

Alterado na versão 3.1: Um *pylong* negativo agora levanta `OverflowError`, não `TypeError`.

unsigned long **PyLong\_AsUnsignedLongMask** (*PyObject* \*obj)

*Part of the Stable ABI.* Return a C unsigned long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long, return the reduction of that value modulo `ULONG_MAX + 1`.

Retorna (unsigned long)-1 no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

Alterado na versão 3.10: This function will no longer use `__int__()`.

unsigned long long **PyLong\_AsUnsignedLongLongMask** (*PyObject* \*obj)

*Part of the Stable ABI.* Return a C unsigned long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long long, return the reduction of that value modulo `ULLONG_MAX + 1`.

Retorna (unsigned long long)-1 no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

Alterado na versão 3.10: This function will no longer use `__int__()`.

double **PyLong\_AsDouble** (*PyObject* \*pylong)

*Part of the Stable ABI.* Return a C double representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise *OverflowError* if the value of *pylong* is out of range for a double.

Retorna -1.0 no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

void \***PyLong\_AsVoidPtr** (*PyObject* \*pylong)

*Part of the Stable ABI.* Convert a Python integer *pylong* to a C void pointer. If *pylong* cannot be converted, an *OverflowError* will be raised. This is only assured to produce a usable void pointer for values created with *PyLong\_FromVoidPtr()*.

Retorna NULL no caso de erro. Use *PyErr\_Occurred()* para desambiguar.

## 8.2.2 Objetos Booleanos

Booleano em Python é implementado como uma subclasse de inteiros. Existem apenas dois tipos de booleanos `Py_False` e `Py_True`. Como tal, as funções normais de criação e exclusão não se aplicam a booleanos. No entanto, as seguintes macros estão disponíveis.

int **PyBool\_Check** (*PyObject* \*o)

Retorna verdadeiro se *o* for do tipo `PyBool_Type`. Esta função sempre tem sucesso.

*PyObject* \***Py\_False**

O objeto Python `False`. Este objeto não possui métodos. Ele precisa ser tratado como qualquer outro objeto em relação às contagens de referência.

*PyObject* \***Py\_True**

O objeto Python `True`. Este objeto não possui métodos. Ele precisa ser tratado como qualquer outro objeto em relação às contagens de referência.

**Py\_RETURN\_FALSE**

Retornar `Py_False` de uma função, incrementando adequadamente sua contagem de referência.

**Py\_RETURN\_TRUE**

Retorna `Py_True` de uma função, incrementando adequadamente sua contagem de referência.

*PyObject* \***PyBool\_FromLong** (long *v*)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna uma nova referência para `Py_True` ou `Py_False` dependendo do valor de verdade de *v*.

## 8.2.3 Objetos de ponto flutuante

**type PyFloatObject**

Este subtipo de *PyObject* representa um objeto de ponto flutuante do Python.

*PyTypeObject* **PyFloat\_Type**

*Part of the Stable ABI*. Esta instância do *PyTypeObject* representa o tipo de ponto flutuante do Python. Este é o mesmo objeto `float` na camada do Python.

int **PyFloat\_Check** (*PyObject* \**p*)

Retorna true se seu argumento é um *PyFloatObject* ou um subtipo de *PyFloatObject*. Esta função sempre tem sucesso.

int **PyFloat\_CheckExact** (*PyObject* \**p*)

Retorna true se seu argumento é um *PyFloatObject*, mas um subtipo de *PyFloatObject*. Esta função sempre tem sucesso.

*PyObject* \***PyFloat\_FromString** (*PyObject* \**str*)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um objeto *PyFloatObject* baseado em uma string de valor “str” ou NULL em falha.

*PyObject* \***PyFloat\_FromDouble** (double *v*)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um objeto *PyFloatObject* de *v* ou NULL em falha.

double **PyFloat\_AsDouble** (*PyObject* \**pyfloat*)

*Part of the Stable ABI*. Return a C double representation of the contents of *pyfloat*. If *pyfloat* is not a Python floating point object but has a `__float__()` method, this method will first be called to convert *pyfloat* into a float. If `__float__()` is not defined then it falls back to `__index__()`. This method returns `-1.0` upon failure, so one should call *PyErr\_Occurred()* to check for errors.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

double **PyFloat\_AS\_DOUBLE** (*PyObject* \**pyfloat*)

Retorna uma representação C double do conteúdo de *pyfloat*, mas sem verificação de erro.

*PyObject* \***PyFloat\_GetInfo** (void)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna uma instância de structseq que contém informações sobre a precisão, os valores mínimo e máximo de um ponto flutuante. É um invólucro fino em torno do arquivo de cabeçalho `float.h`.

double **PyFloat\_GetMax** ()

*Part of the Stable ABI*. Retorna o ponto flutuante finito máximo representável *DBL\_MAX* como double do C.

double **PyFloat\_GetMin** ()

*Part of the Stable ABI*. Retorna o ponto flutuante positivo mínimo normalizado *DBL\_MIN* como double do C.

## 8.2.4 Objetos números complexos

Os objetos números complexos do Python são implementados como dois tipos distintos quando visualizados na API C: um é o objeto Python exposto aos programas Python e o outro é uma estrutura C que representa o valor real do número complexo. A API fornece funções para trabalhar com ambos.

### Números complexos como estruturas C.

Observe que as funções que aceitam essas estruturas como parâmetros e as retornam como resultados o fazem *por valor* em vez de desreferenciá-las por meio de ponteiros. Isso é consistente em toda a API.

#### type `Py_complex`

A estrutura C que corresponde à parte do valor de um objeto de número complexo Python. A maioria das funções para lidar com objetos de números complexos usa estruturas desse tipo como valores de entrada ou saída, conforme apropriado. É definido como:

```
typedef struct {  
    double real;  
    double imag;  
} Py_complex;
```

*Py\_complex* `_Py_c_sum` (*Py\_complex* left, *Py\_complex* right)

Retorna a soma de dois números complexos, utilizando a representação C *Py\_complex*.

*Py\_complex* `_Py_c_diff` (*Py\_complex* left, *Py\_complex* right)

Retorna a diferença entre dois números complexos, utilizando a representação C *Py\_complex*.

*Py\_complex* `_Py_c_neg` (*Py\_complex* num)

Retorna a negação do número complexo *num*, utilizando a representação C *Py\_complex*.

*Py\_complex* `_Py_c_prod` (*Py\_complex* left, *Py\_complex* right)

Retorna o produto de dois números complexos, utilizando a representação C *Py\_complex*.

*Py\_complex* `_Py_c_quot` (*Py\_complex* dividend, *Py\_complex* divisor)

Retorna o quociente de dois números complexos, utilizando a representação C *Py\_complex*.

Se *divisor* é nulo, este método retorna zero e define `errno` para `EDOM`.

*Py\_complex* `_Py_c_pow` (*Py\_complex* num, *Py\_complex* exp)

Retorna a exponenciação de *num* por *exp*, utilizando a representação C *Py\_complex*.

Se *num* for nulo e *exp* não for um número real positivo, este método retorna zero e define `errno` para `EDOM`.

### Números complexos como objetos Python

#### type `PyComplexObject`

Este subtipo de *PyObject* representa um objeto Python de número complexo.

#### *PyTypeObject* `PyComplex_Type`

Part of the *Stable ABI*. Esta instância de *PyTypeObject* representa o tipo de número complexo Python. É o mesmo objeto que `complex` na camada Python.

int `PyComplex_Check` (*PyObject* \*p)

Retorna true se seu argumento é um *PyComplexObject* ou um subtipo de *PyComplexObject*. Esta função sempre tem sucesso.

**int PyComplex\_CheckExact** (*PyObject* \**p*)

Retorna true se seu argumento é um *PyComplexObject*, mas não um subtipo de *PyComplexObject*. Esta função sempre tem sucesso.

*PyObject* \***PyComplex\_FromCComplex** (*Py\_complex* *v*)

Retorna valor: Nova referência. Cria um novo objeto de número complexo Python a partir de um valor C *Py\_complex*.

*PyObject* \***PyComplex\_FromDoubles** (double *real*, double *imag*)

Retorna valor: Nova referência. Part of the Stable ABI. Retorna um novo objeto *PyComplexObject* de *real* e *imag*.

double **PyComplex\_RealAsDouble** (*PyObject* \**op*)

Part of the Stable ABI. Retorna a parte real de *op* como um double C.

double **PyComplex\_ImagAsDouble** (*PyObject* \**op*)

Part of the Stable ABI. Retorna a parte imaginária de *op* como um double C.

*Py\_complex* **PyComplex\_AsCComplex** (*PyObject* \**op*)

Retorna o valor *Py\_complex* do número complexo *op*.

Se *op* não é um objeto de número complexo Python, mas tem um método `__complex__()`, este método será primeiro chamado para converter *op* em um objeto de número complexo Python. Se `__complex__()` não for definido, então ele recorre a `__float__()`. Se `__float__()` não estiver definido, então ele volta para `__index__()`. Em caso de falha, este método retorna `-1.0` como um valor real.

Alterado na versão 3.8: Usa `__index__()`, se disponível.

## 8.3 Objetos Sequência

Operações genéricas em objetos de sequência foram discutidas no capítulo anterior; Esta seção lida com os tipos específicos de objetos sequência que são intrínsecos à linguagem Python.

### 8.3.1 Objetos bytes

Estas funções levantam `TypeError` quando se espera um parâmetro bytes e são chamados com um parâmetro que não é bytes.

**type PyBytesObject**

Esta é uma instância de *PyObject* representando o objeto bytes do Python.

*PyTypeObject* **PyBytes\_Type**

Part of the Stable ABI. Esta instância de *PyTypeObject* representa o tipo de bytes Python; é o mesmo objeto que bytes na camada de Python.

**int PyBytes\_Check** (*PyObject* \**o*)

Retorna verdadeiro se o objeto *o* for um objeto bytes ou se for uma instância de um subtipo do tipo bytes. Esta função sempre tem sucesso.

**int PyBytes\_CheckExact** (*PyObject* \**o*)

Retorna verdadeiro se o objeto *o* for um objeto bytes, mas não uma instância de um subtipo do tipo bytes. Esta função sempre tem sucesso.

*PyObject* \***PyBytes\_FromString** (const char \**v*)

Retorna valor: Nova referência. Part of the Stable ABI. Retorna um novo objeto de bytes com uma cópia da string *v* como valor em caso de sucesso e NULL em caso de falha. O parâmetro *v* não deve ser NULL e isso não será verificado.

*PyObject* \*PyBytes\_FromStringAndSize (const char \*v, Py\_ssize\_t len)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto de bytes com uma cópia da string *v* como valor e comprimento *len* em caso de sucesso e NULL em caso de falha. Se *v* for NULL, o conteúdo do objeto bytes não será inicializado.

*PyObject* \*PyBytes\_FromFormat (const char \*format, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Leva uma string tipo `printf()` do C *format* e um número variável de argumentos, calcula o tamanho do objeto bytes do Python resultante e retorna um objeto bytes com os valores formatados nela. Os argumentos da variável devem ser tipos C e devem corresponder exatamente aos caracteres de formato na string *format*. Os seguintes formatos de caracteres são permitidos:

Caracteres Formatados	Tipo	Comentário
%%	<i>n/d</i>	O caractere literal %.
%c	int	Um único byte, representado como um C int.
%d	int	Equivalente a <code>printf("%d").</code> <sup>1</sup>
%u	unsigned int	Equivalente a <code>printf("%u").</code> <sup>1</sup>
%ld	long	Equivalente a <code>printf("%ld").</code> <sup>1</sup>
%lu	unsigned long	Equivalente a <code>printf("%lu").</code> <sup>1</sup>
%zd	<i>Py_ssize_t</i>	Equivalente a <code>printf("%zd").</code> <sup>1</sup>
%zu	<i>size_t</i>	Equivalente a <code>printf("%zu").</code> <sup>1</sup>
%i	int	Equivalente a <code>printf("%i").</code> <sup>1</sup>
%x	int	Equivalente a <code>printf("%x").</code> <sup>1</sup>
%s	const char*	Uma matriz de caracteres C com terminação nula.
%p	const void*	A representação hexadecimal de um ponteiro C. Principalmente equivalente a <code>printf("%p")</code> exceto que é garantido que comece com o literal 0x independentemente do que o <code>printf</code> da plataforma ceda.

Um caractere de formato não reconhecido faz com que todo o resto da string de formato seja copiado como é para o objeto resultante e todos os argumentos extras sejam descartados.

*PyObject* \*PyBytes\_FromFormatV (const char \*format, va\_list vars)

Retorna valor: Nova referência. *Part of the Stable ABI*. Idêntico a `PyBytes_FromFormat()` exceto que é preciso exatamente dois argumentos.

*PyObject* \*PyBytes\_FromObject (PyObject \*o)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna a representação de bytes do objeto *o* que implementa o protocolo de buffer.

*Py\_ssize\_t* PyBytes\_Size (PyObject \*o)

*Part of the Stable ABI*. Retorna o comprimento dos bytes em objeto bytes *o*.

*Py\_ssize\_t* PyBytes\_GET\_SIZE (PyObject \*o)

Forma macro de `PyBytes_Size()`, mas sem verificação de erro.

char \*PyBytes\_AsString (PyObject \*o)

*Part of the Stable ABI*. Retorna um ponteiro para o conteúdo de *o*. O ponteiro se refere ao buffer interno de *o*, que consiste em `len(o) + 1` bytes. O último byte no buffer é sempre nulo, independentemente de haver outros bytes nulos. Os dados não devem ser modificados de forma alguma, a menos que o objeto tenha sido criado usando `PyBytes_FromStringAndSize(NULL, size)`. Não deve ser desalocado. Se *o* não é um objeto de bytes, `PyBytes_AsString()` retorna NULL e levanta `TypeError`.

char \*PyBytes\_AS\_STRING (PyObject \*string)

Forma de macro de `PyBytes_AsString()`, mas sem verificação de erro.

<sup>1</sup> Para especificadores de número inteiro (d, u, ld, lu, zd, zu, i, x): o sinalizador de conversão 0 tem efeito mesmo quando uma precisão é fornecida.

int **PyBytes\_AsStringAndSize** (*PyObject* \*obj, char \*\*buffer, *Py\_ssize\_t* \*length)

*Part of the Stable ABI.* Retorna os conteúdos terminados nulos do objeto *obj* através das variáveis de saída *buffer* e *length*.

Se *length* for NULL, o objeto bytes não poderá conter bytes nulos incorporados; se isso acontecer, a função retornará -1 e a `ValueError` será levantado.

O buffer refere-se a um buffer interno de *obj*, que inclui um byte nulo adicional no final (não contado em *length*). Os dados não devem ser modificados de forma alguma, a menos que o objeto tenha sido criado apenas usando `PyBytes_FromStringAndSize(NULL, size)`. Não deve ser desalinhado. Se *obj* não é um objeto bytes, `PyBytes_AsStringAndSize()` retorna -1 e levanta `TypeError`.

Alterado na versão 3.5: Anteriormente `TypeError` era levantado quando os bytes nulos incorporados eram encontrados no objeto bytes.

void **PyBytes\_Concat** (*PyObject* \*\*bytes, *PyObject* \*newpart)

*Part of the Stable ABI.* Cria um novo objeto de bytes em *\*bytes* contendo o conteúdo de *newpart* anexado a *bytes*; o chamador será o proprietário da nova referência. A referência ao valor antigo de *bytes* será roubada. Se o novo objeto não puder ser criado, a antiga referência a *bytes* ainda será descartada e o valor de *\*bytes* será definido como NULL; a exceção apropriada será definida.

void **PyBytes\_ConcatAndDel** (*PyObject* \*\*bytes, *PyObject* \*newpart)

*Part of the Stable ABI.* “Crie um novo objeto bytes em *\*bytes* contendo o conteúdo de *newpart* anexado a *bytes*. Esta versão libera a *strong reference* (referência forte) para *newpart* (ou seja, decrementa a contagem de referências a ele).”

int **\_PyBytes\_Resize** (*PyObject* \*\*bytes, *Py\_ssize\_t* newsize)

Uma maneira de redimensionar um objeto de bytes, mesmo que seja “imutável”. Use isso apenas para construir um novo objeto de bytes; não use isso se os bytes já puderem ser conhecidos em outras partes do código. É um erro invocar essa função se o refcount no objeto de bytes de entrada não for um. Passe o endereço de um objeto de bytes existente como um lvalue (pode ser gravado) e o novo tamanho desejado. Em caso de sucesso, *\*bytes* mantém o objeto de bytes redimensionados e 0 é retornado; o endereço em *\*bytes* pode diferir do seu valor de entrada. Se a realocação falhar, o objeto de bytes originais em *\*bytes* é desalocado, *\*bytes* é definido como NULL, `MemoryError` é definido e -1 é retornado.

## 8.3.2 Objetos byte array

**type** `PyByteArrayObject`

Esse subtipo de *PyObject* representa um objeto Python bytearray.

*PyTypeObject* `PyByteArray_Type`

*Part of the Stable ABI.* Essa instância de *PyTypeObject* representa um tipo Python bytearray; é o mesmo objeto que o bytearray na camada Python.

### Macros para verificação de tipo

int **PyByteArray\_Check** (*PyObject* \*o)

Retorna verdadeiro se o objeto *o* for um objeto bytearray ou se for uma instância de um subtipo do tipo bytearray. Esta função sempre tem sucesso.

int **PyByteArray\_CheckExact** (*PyObject* \*o)

Retorna verdadeiro se o objeto *o* for um objeto bytearray, mas não uma instância de um subtipo do tipo bytearray. Esta função sempre tem sucesso.



## Funções diretas da API

*PyObject* \***PyByteArray\_FromObject** (*PyObject* \*o)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto bytearray, o, que implementa o protocolo de buffer.

*PyObject* \***PyByteArray\_FromStringAndSize** (const char \*string, *Py\_ssize\_t* len)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um novo objeto bytearray a partir de string e seu comprimento, len. Em caso de falha, NULL é retornado.

*PyObject* \***PyByteArray\_Concat** (*PyObject* \*a, *PyObject* \*b)

Retorna valor: Nova referência. *Part of the Stable ABI*. Concatena os bytearrays a e b e retorna um novo bytearray com o resultado.

*Py\_ssize\_t* **PyByteArray\_Size** (*PyObject* \*bytearray)

*Part of the Stable ABI*. Retorna o tamanho de bytearray após verificar se há um ponteiro NULL.

char \***PyByteArray\_AsString** (*PyObject* \*bytearray)

*Part of the Stable ABI*. Retorna o conteúdo de bytearray como uma matriz de caracteres após verificar um ponteiro NULL. O array retornado sempre tem um byte nulo extra acrescentado.

int **PyByteArray\_Resize** (*PyObject* \*bytearray, *Py\_ssize\_t* len)

*Part of the Stable ABI*. Redimensiona o buffer interno de bytearray para o tamanho len.

## Macros

Estas macros trocam segurança por velocidade e não verificam os ponteiros.

char \***PyByteArray\_AS\_STRING** (*PyObject* \*bytearray)

Versão macro de *PyByteArray\_AsString()*.

*Py\_ssize\_t* **PyByteArray\_GET\_SIZE** (*PyObject* \*bytearray)

Versão macro de *PyByteArray\_Size()*.

## 8.3.3 Objetos Unicode e Codecs

### Objetos Unicode

Desde a implementação da **PEP 393** no Python 3.3, os objetos Unicode usam internamente uma variedade de representações para permitir o processamento de toda a gama de caracteres Unicode, mantendo a eficiência de memória. Há casos especiais para strings em que todos os pontos de código estão abaixo de 128, 256 ou 65536; caso contrário, os pontos de código devem estar abaixo de 1114112 (que é a gama completa de caracteres Unicode).

*Py\_UNICODE\** and UTF-8 representations are created on demand and cached in the Unicode object. The *Py\_UNICODE\** representation is deprecated and inefficient.

Due to the transition between the old APIs and the new APIs, Unicode objects can internally be in two states depending on how they were created:

- “canonical” Unicode objects are all objects created by a non-deprecated Unicode API. They use the most efficient representation allowed by the implementation.
- “legacy” Unicode objects have been created through one of the deprecated APIs (typically *PyUnicode\_FromUnicode()*) and only bear the *Py\_UNICODE\** representation; you will have to call *PyUnicode\_READY()* on them before calling any other API.



---

**Nota:** The “legacy” Unicode object will be removed in Python 3.12 with deprecated APIs. All Unicode objects will be “canonical” since then. See [PEP 623](#) for more information.

---

## Tipo Unicode

Estes são os tipos básicos de objetos Unicode usados para a implementação Unicode em Python:

**type** `Py_UCS4`

**type** `Py_UCS2`

**type** `Py_UCS1`

*Part of the Stable ABI.* Esses tipos são definições de tipo para tipos inteiros sem sinal, amplos o suficiente para conter caracteres de 32 bits, 16 bits e 8 bits, respectivamente. Ao lidar com caracteres Unicode simples, use `Py_UCS4`.

Novo na versão 3.3.

**type** `Py_UNICODE`

This is a typedef of `wchar_t`, which is a 16-bit type or 32-bit type depending on the platform.

Alterado na versão 3.3: Em versões anteriores, esse era um tipo de 16 bits ou de 32 bits, dependendo se você selecionava uma versão Unicode “estreita” ou “ampla” do Python no momento da construção.

**type** `PyASCIIObject`

**type** `PyCompactUnicodeObject`

**type** `PyUnicodeObject`

Esses subtipos de `PyObject` representam um objeto Unicode do Python. Em quase todos os casos, eles não devem ser usados diretamente, pois todas as funções da API que lidam com objetos Unicode recebem e retornam ponteiros `PyObject`.

Novo na versão 3.3.

*PyTypeObject* **PyUnicode\_Type**

*Part of the Stable ABI.* This instance of `PyTypeObject` represents the Python Unicode type. It is exposed to Python code as `str`.

The following APIs are really C macros and can be used to do fast checks and to access internal read-only data of Unicode objects:

**int** `PyUnicode_Check` (`PyObject *o`)

Return true if the object `o` is a Unicode object or an instance of a Unicode subtype. This function always succeeds.

**int** `PyUnicode_CheckExact` (`PyObject *o`)

Return true if the object `o` is a Unicode object, but not an instance of a subtype. This function always succeeds.

**int** `PyUnicode_READY` (`PyObject *o`)

Ensure the string object `o` is in the “canonical” representation. This is required before using any of the access macros described below.

Returns 0 on success and -1 with an exception set on failure, which in particular happens if memory allocation fails.

Novo na versão 3.3.

Deprecated since version 3.10, will be removed in version 3.12: This API will be removed with `PyUnicode_FromUnicode()`.

*Py\_ssize\_t* **PyUnicode\_GET\_LENGTH** (*PyObject* \**o*)

Return the length of the Unicode string, in code points. *o* has to be a Unicode object in the “canonical” representation (not checked).

Novo na versão 3.3.

*Py\_UCS1* \***PyUnicode\_1BYTE\_DATA** (*PyObject* \**o*)

*Py\_UCS2* \***PyUnicode\_2BYTE\_DATA** (*PyObject* \**o*)

*Py\_UCS4* \***PyUnicode\_4BYTE\_DATA** (*PyObject* \**o*)

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use *PyUnicode\_KIND()* to select the right macro. Make sure *PyUnicode\_READY()* has been called before accessing this.

Novo na versão 3.3.

**PyUnicode\_WCHAR\_KIND**

**PyUnicode\_1BYTE\_KIND**

**PyUnicode\_2BYTE\_KIND**

**PyUnicode\_4BYTE\_KIND**

Valores de retorno da macro *PyUnicode\_KIND()*.

Novo na versão 3.3.

Deprecated since version 3.10, will be removed in version 3.12: *PyUnicode\_WCHAR\_KIND* is deprecated.

unsigned int **PyUnicode\_KIND** (*PyObject* \**o*)

Return one of the *PyUnicode* kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. *o* has to be a Unicode object in the “canonical” representation (not checked).

Novo na versão 3.3.

void \***PyUnicode\_DATA** (*PyObject* \**o*)

Return a void pointer to the raw Unicode buffer. *o* has to be a Unicode object in the “canonical” representation (not checked).

Novo na versão 3.3.

void **PyUnicode\_WRITE** (int *kind*, void \**data*, *Py\_ssize\_t* *index*, *Py\_UCS4* *value*)

Write into a canonical representation *data* (as obtained with *PyUnicode\_DATA()*). This macro does not do any sanity checks and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other macro calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

Novo na versão 3.3.

*Py\_UCS4* **PyUnicode\_READ** (int *kind*, void \**data*, *Py\_ssize\_t* *index*)

Lê um ponto de código de uma representação canônica *data* (conforme obtido com *PyUnicode\_DATA()*). Nenhuma verificação ou chamada pronta é realizada.

Novo na versão 3.3.

*Py\_UCS4* **PyUnicode\_READ\_CHAR** (*PyObject* \**o*, *Py\_ssize\_t* *index*)

Read a character from a Unicode object *o*, which must be in the “canonical” representation. This is less efficient than *PyUnicode\_READ()* if you do multiple consecutive reads.

Novo na versão 3.3.

**PyUnicode\_MAX\_CHAR\_VALUE** (*o*)

Return the maximum code point that is suitable for creating another string based on *o*, which must be in the “canonical” representation. This is always an approximation but more efficient than iterating over the string.

Novo na versão 3.3.

*Py\_ssize\_t* **PyUnicode\_GET\_SIZE** (*PyObject* \**o*)

Return the size of the deprecated *Py\_UNICODE* representation, in code units (this includes surrogate pairs as 2 units). *o* has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

*Py\_ssize\_t* **PyUnicode\_GET\_DATA\_SIZE** (*PyObject* \**o*)

Return the size of the deprecated *Py\_UNICODE* representation in bytes. *o* has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

*Py\_UNICODE* \***PyUnicode\_AS\_UNICODE** (*PyObject* \**o*)

**const** char \***PyUnicode\_AS\_DATA** (*PyObject* \**o*)

Return a pointer to a *Py\_UNICODE* representation of the object. The returned buffer is always terminated with an extra null code point. It may also contain embedded null code points, which would cause the string to be truncated when used in most C functions. The AS\_DATA form casts the pointer to **const** char\*. The *o* argument has to be a Unicode object (not checked).

Alterado na versão 3.3: This macro is now inefficient – because in many cases the *Py\_UNICODE* representation does not exist and needs to be created – and can fail (return NULL with an exception set). Try to port the code to use the new *PyUnicode\_nBYTE\_DATA()* macros or use *PyUnicode\_WRITE()* or *PyUnicode\_READ()*.

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using the *PyUnicode\_nBYTE\_DATA()* family of macros.

int **PyUnicode\_IsIdentifier** (*PyObject* \**o*)

*Part of the Stable ABI.* Retorna 1 se a string é um identificador válido conforme a definição da linguagem, seção identifiers. Do contrário, retorna 0.

Alterado na versão 3.9: A função não chama mais *Py\_FatalError()* se a string não estiver pronta.

## Propriedade de caracteres Unicode

O Unicode fornece muitas propriedades de caracteres diferentes. As mais frequentemente necessárias estão disponíveis por meio destas macros, que são mapeadas para funções C, dependendo da configuração do Python.

int **Py\_UNICODE\_ISSPACE** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere de espaço em branco.

int **Py\_UNICODE\_ISLOWER** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere minúsculo.

int **Py\_UNICODE\_ISUPPER** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere maiúsculo.

int **Py\_UNICODE\_ISTITLE** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere em TitleCase.

int **Py\_UNICODE\_ISLINEBREAK** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere de quebra de linha.

int **Py\_UNICODE\_ISDECIMAL** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere decimal.

int **Py\_UNICODE\_ISDIGIT** (*Py\_UCS4* *ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere de dígito.

int **Py\_UNICODE\_ISNUMERIC** (*Py\_UCS4 ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere numérico.

int **Py\_UNICODE\_ISALPHA** (*Py\_UCS4 ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere alfabético.

int **Py\_UNICODE\_ISALNUM** (*Py\_UCS4 ch*)

Retorna 1 ou 0 dependendo se *ch* é um caractere alfanumérico.

int **Py\_UNICODE\_ISPRINTABLE** (*Py\_UCS4 ch*)

Return 1 or 0 depending on whether *ch* is a printable character. Nonprintable characters are those characters defined in the Unicode character database as “Other” or “Separator”, excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when `repr()` is invoked on a string. It has no bearing on the handling of strings written to `sys.stdout` or `sys.stderr`.)

These APIs can be used for fast direct character conversions:

*Py\_UCS4* **Py\_UNICODE\_TOLOWER** (*Py\_UCS4 ch*)

Return the character *ch* converted to lower case.

Obsoleto desde a versão 3.3: This function uses simple case mappings.

*Py\_UCS4* **Py\_UNICODE\_TOUPPER** (*Py\_UCS4 ch*)

Return the character *ch* converted to upper case.

Obsoleto desde a versão 3.3: This function uses simple case mappings.

*Py\_UCS4* **Py\_UNICODE\_TOTITLE** (*Py\_UCS4 ch*)

Return the character *ch* converted to title case.

Obsoleto desde a versão 3.3: This function uses simple case mappings.

int **Py\_UNICODE\_TODECIMAL** (*Py\_UCS4 ch*)

Return the character *ch* converted to a decimal positive integer. Return `-1` if this is not possible. This macro does not raise exceptions.

int **Py\_UNICODE\_TODIGIT** (*Py\_UCS4 ch*)

Return the character *ch* converted to a single digit integer. Return `-1` if this is not possible. This macro does not raise exceptions.

double **Py\_UNICODE\_TONUMERIC** (*Py\_UCS4 ch*)

Return the character *ch* converted to a double. Return `-1.0` if this is not possible. This macro does not raise exceptions.

These APIs can be used to work with surrogates:

**Py\_UNICODE\_IS\_SURROGATE** (*ch*)

Check if *ch* is a surrogate (`0xD800 <= ch <= 0xDFFF`).

**Py\_UNICODE\_IS\_HIGH\_SURROGATE** (*ch*)

Check if *ch* is a high surrogate (`0xD800 <= ch <= 0xDBFF`).

**Py\_UNICODE\_IS\_LOW\_SURROGATE** (*ch*)

Check if *ch* is a low surrogate (`0xDC00 <= ch <= 0xDFFF`).

**Py\_UNICODE\_JOIN\_SURROGATES** (*high, low*)

Join two surrogate characters and return a single *Py\_UCS4* value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair.

## Creating and accessing Unicode strings

To create Unicode objects and access their basic sequence properties, use these APIs:

*PyObject* \***PyUnicode\_New** (*Py\_ssize\_t* size, *Py\_UCS4* maxchar)

*Retorna valor:* Nova referência. Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable.

Novo na versão 3.3.

*PyObject* \***PyUnicode\_FromKindAndData** (int kind, const void \*buffer, *Py\_ssize\_t* size)

*Retorna valor:* Nova referência. Cria um novo objeto Unicode com o tipo *type* fornecido (os valores possíveis são *PyUnicode\_1BYTE\_KIND* etc., conforme retornado por *PyUnicode\_KIND()*). O *buffer* deve apontar para um array de unidades com *size* de 1, 2 ou 4 bytes por caractere, conforme fornecido pelo tipo.

Novo na versão 3.3.

*PyObject* \***PyUnicode\_FromStringAndSize** (const char \*u, *Py\_ssize\_t* size)

*Retorna valor:* Nova referência. *Part of the Stable ABI*. Create a Unicode object from the char buffer *u*. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. If the buffer is not NULL, the return value might be a shared object, i.e. modification of the data is not allowed.

If *u* is NULL, this function behaves like *PyUnicode\_FromUnicode()* with the buffer set to NULL. This usage is deprecated in favor of *PyUnicode\_New()*, and will be removed in Python 3.12.

*PyObject* \***PyUnicode\_FromString** (const char \*u)

*Retorna valor:* Nova referência. *Part of the Stable ABI*. Create a Unicode object from a UTF-8 encoded null-terminated char buffer *u*.

*PyObject* \***PyUnicode\_FromFormat** (const char \*format, ...)

*Retorna valor:* Nova referência. *Part of the Stable ABI*. Take a C *printf()*-style *format* string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the *format* ASCII-encoded string. The following format characters are allowed:

Caracteres Formatados	Tipo	Comentário
<code>%%</code>	<i>n/d</i>	O caractere literal %.
<code>%c</code>	<code>int</code>	A single character, represented as a C int.
<code>%d</code>	<code>int</code>	Equivalente a <code>printf("%d").</code> <sup>1</sup>
<code>%u</code>	<code>unsigned int</code>	Equivalente a <code>printf("%u").</code> <sup>1</sup>
<code>%ld</code>	<code>long</code>	Equivalente a <code>printf("%ld").</code> <sup>1</sup>
<code>%li</code>	<code>long</code>	Equivalent to <code>printf("%li").</code> <sup>1</sup>
<code>%lu</code>	<code>unsigned long</code>	Equivalente a <code>printf("%lu").</code> <sup>1</sup>
<code>%lld</code>	<code>long long</code>	Equivalent to <code>printf("%lld").</code> <sup>1</sup>
<code>%lli</code>	<code>long long</code>	Equivalent to <code>printf("%lli").</code> <sup>1</sup>
<code>%llu</code>	<code>unsigned long long</code>	Equivalent to <code>printf("%llu").</code> <sup>1</sup>
<code>%zd</code>	<code>Py_ssize_t</code>	Equivalente a <code>printf("%zd").</code> <sup>1</sup>
<code>%zi</code>	<code>Py_ssize_t</code>	Equivalent to <code>printf("%zi").</code> <sup>1</sup>
<code>%zu</code>	<code>size_t</code>	Equivalente a <code>printf("%zu").</code> <sup>1</sup>
<code>%i</code>	<code>int</code>	Equivalente a <code>printf("%i").</code> <sup>1</sup>
<code>%x</code>	<code>int</code>	Equivalente a <code>printf("%x").</code> <sup>1</sup>
<code>%s</code>	<code>const char*</code>	Uma matriz de caracteres C com terminação nula.
<code>%p</code>	<code>const void*</code>	A representação hexadecimal de um ponteiro C. Principalmente equivalente a <code>printf("%p")</code> exceto que é garantido que comece com o literal 0x independentemente do que o <code>printf</code> da plataforma ceda.
<code>%A</code>	<code>PyObject*</code>	The result of calling <code>ascii()</code> .
<code>%U</code>	<code>PyObject*</code>	A Unicode object.
<code>%V</code>	<code>PyObject*</code> , <code>const char*</code>	A Unicode object (which may be NULL) and a null-terminated C character array as a second parameter (which will be used, if the first parameter is NULL).
<code>%S</code>	<code>PyObject*</code>	The result of calling <code>PyObject_Str()</code> .
<code>%R</code>	<code>PyObject*</code>	The result of calling <code>PyObject_Repr()</code> .

An unrecognized format character causes all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

**Nota:** The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes for `%s` and `%V` (if the `PyObject*` argument is NULL), and a number of characters for `%A`, `%U`, `%S`, `%R` and `%V` (if the `PyObject*` argument is not NULL).

Alterado na versão 3.2: Suporte adicionado para `%lld` e `%llu`.

Alterado na versão 3.3: Support for `%li`, `%lli` and `%zi` added.

Alterado na versão 3.4: Support width and precision formatter for `%s`, `%A`, `%U`, `%V`, `%S`, `%R` added.

*PyObject\** **PyUnicode\_FromFormatV**(`const char *format`, `va_list vargs`)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Identical to `PyUnicode_FromFormat()` except that it takes exactly two arguments.

*PyObject\** **PyUnicode\_FromEncodedObject**(*PyObject\** `obj`, `const char *encoding`, `const char *errors`)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Decode an encoded object `obj` to a Unicode object.

<sup>1</sup> For integer specifiers (d, u, ld, li, lu, lld, lli, llu, zd, zi, zu, i, x): the 0-conversion flag has effect even when a precision is given.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be NULL to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a `TypeError` to be set.

The API returns NULL if there was an error. The caller is responsible for decref'ing the returned objects.

*Py\_ssize\_t* **PyUnicode\_GetLength** (*PyObject* \*unicode)

*Part of the Stable ABI since version 3.7.* Return the length of the Unicode object, in code points.

Novo na versão 3.3.

*Py\_ssize\_t* **PyUnicode\_CopyCharacters** (*PyObject* \*to, *Py\_ssize\_t* to\_start, *PyObject* \*from, *Py\_ssize\_t* from\_start, *Py\_ssize\_t* how\_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to `memcpy()` if possible. Returns -1 and sets an exception on error, otherwise returns the number of copied characters.

Novo na versão 3.3.

*Py\_ssize\_t* **PyUnicode\_Fill** (*PyObject* \*unicode, *Py\_ssize\_t* start, *Py\_ssize\_t* length, *Py\_UCS4* fill\_char)

Fill a string with a character: write *fill\_char* into `unicode[start:start+length]`.

Fail if *fill\_char* is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return -1 and raise an exception on error.

Novo na versão 3.3.

int **PyUnicode\_WriteChar** (*PyObject* \*unicode, *Py\_ssize\_t* index, *Py\_UCS4* character)

*Part of the Stable ABI since version 3.7.* Write a character to a string. The string must have been created through `PyUnicode_New()`. Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that its reference count is one).

Novo na versão 3.3.

*Py\_UCS4* **PyUnicode\_ReadChar** (*PyObject* \*unicode, *Py\_ssize\_t* index)

*Part of the Stable ABI since version 3.7.* Read a character from a string. This function checks that *unicode* is a Unicode object and the index is not out of bounds, in contrast to the macro version `PyUnicode_READ_CHAR()`.

Novo na versão 3.3.

*PyObject* \***PyUnicode\_Substring** (*PyObject* \*str, *Py\_ssize\_t* start, *Py\_ssize\_t* end)

*Retorna valor: Nova referência. Part of the Stable ABI since version 3.7.* Return a substring of *str*, from character index *start* (included) to character index *end* (excluded). Negative indices are not supported.

Novo na versão 3.3.

*Py\_UCS4* \***PyUnicode\_AsUCS4** (*PyObject* \*u, *Py\_UCS4* \*buffer, *Py\_ssize\_t* buflen, int copy\_null)

*Part of the Stable ABI since version 3.7.* Copy the string *u* into a UCS4 buffer, including a null character, if *copy\_null* is set. Returns NULL and sets an exception on error (in particular, a `SystemError` if *buflen* is smaller than the length of *u*). *buffer* is returned on success.

Novo na versão 3.3.

*Py\_UCS4* \***PyUnicode\_AsUCS4Copy** (*PyObject* \*u)

*Part of the Stable ABI since version 3.7.* Copy the string *u* into a new UCS4 buffer that is allocated using `PyMem_Malloc()`. If this fails, NULL is returned with a `MemoryError` set. The returned buffer always has an extra null code point appended.

Novo na versão 3.3.



## Deprecated Py\_UNICODE APIs

Deprecated since version 3.3, will be removed in version 3.12.

These API functions are deprecated with the implementation of **PEP 393**. Extension modules can continue using them, as they will not be removed in Python 3.x, but need to be aware that their use can now cause performance and memory hits.

*PyObject* \***PyUnicode\_FromUnicode** (const *Py\_UNICODE* \**u*, *Py\_ssize\_t* *size*)

*Retorna valor: Nova referência.* Create a Unicode object from the *Py\_UNICODE* buffer *u* of the given size. *u* may be NULL which causes the contents to be undefined. It is the user's responsibility to fill in the needed data. The buffer is copied into the new object.

If the buffer is not NULL, the return value might be a shared object. Therefore, modification of the resulting Unicode object is only allowed when *u* is NULL.

If the buffer is NULL, *PyUnicode\_READY()* must be called once the string content has been filled before using any of the access macros such as *PyUnicode\_KIND()*.

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_FromKindAndData()*, *PyUnicode\_FromWideChar()*, or *PyUnicode\_New()*.

*Py\_UNICODE* \***PyUnicode\_AsUnicode** (*PyObject* \**unicode*)

Return a read-only pointer to the Unicode object's internal *Py\_UNICODE* buffer, or NULL on error. This will create the *Py\_UNICODE*\* representation of the object if it is not yet available. The buffer is always terminated with an extra null code point. Note that the resulting *Py\_UNICODE* string may also contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_AsUCS4()*, *PyUnicode\_AsWideChar()*, *PyUnicode\_ReadChar()* or similar new APIs.

*PyObject* \***PyUnicode\_TransformDecimalToASCII** (*Py\_UNICODE* \**s*, *Py\_ssize\_t* *size*)

*Retorna valor: Nova referência.* Create a Unicode object by replacing all decimal digits in *Py\_UNICODE* buffer of the given *size* by ASCII digits 0–9 according to their decimal value. Return NULL if an exception occurs.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style *Py\_UNICODE* API; please migrate to using *Py\_UNICODE\_TODECIMAL()*.

*Py\_UNICODE* \***PyUnicode\_AsUnicodeAndSize** (*PyObject* \**unicode*, *Py\_ssize\_t* \**size*)

Like *PyUnicode\_AsUnicode()*, but also saves the *Py\_UNICODE()* array length (excluding the extra null terminator) in *size*. Note that the resulting *Py\_UNICODE*\* string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Novo na versão 3.3.

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_AsUCS4()*, *PyUnicode\_AsWideChar()*, *PyUnicode\_ReadChar()* or similar new APIs.

*Py\_ssize\_t* **PyUnicode\_GetSize** (*PyObject* \**unicode*)

*Part of the Stable ABI.* Return the size of the deprecated *Py\_UNICODE* representation, in code units (this includes surrogate pairs as 2 units).

Deprecated since version 3.3, will be removed in version 3.12: Part of the old-style Unicode API, please migrate to using *PyUnicode\_GET\_LENGTH()*.

*PyObject* \***PyUnicode\_FromObject** (*PyObject* \**obj*)

*Retorna valor: Nova referência.* *Part of the Stable ABI.* Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If *obj* is already a true Unicode object (not a subtype), return the reference with incremented refcount.



Objects other than Unicode or its subtypes will cause a `TypeError`.

## Locale Encoding

The current locale encoding can be used to decode text from the operating system.

***PyObject*** \*PyUnicode\_DecodeLocaleAndSize (const char \*str, Py\_ssize\_t len, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) since version 3.7. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" ([PEP 383](#)). The decoder uses "strict" error handler if *errors* is NULL. *str* must end with a null character but cannot contain embedded null characters.

Use `PyUnicode_DecodeFSDefaultAndSize()` to decode a string from `Py_FileSystemDefaultEncoding` (the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

### Ver também:

The `Py_DecodeLocale()` function.

Novo na versão 3.3.

Alterado na versão 3.7: The function now also uses the current locale encoding for the `surrogateescape` error handler, except on Android. Previously, `Py_DecodeLocale()` was used for the `surrogateescape`, and the current locale encoding was used for `strict`.

***PyObject*** \*PyUnicode\_DecodeLocale (const char \*str, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) since version 3.7. Similar to `PyUnicode_DecodeLocaleAndSize()`, but compute the string length using `strlen()`.

Novo na versão 3.3.

***PyObject*** \*PyUnicode\_EncodeLocale (*PyObject* \*unicode, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) since version 3.7. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" ([PEP 383](#)). The encoder uses "strict" error handler if *errors* is NULL. Return a bytes object. *unicode* cannot contain embedded null characters.

Use `PyUnicode_EncodeFSDefault()` to encode a string to `Py_FileSystemDefaultEncoding` (the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

### Ver também:

The `Py_EncodeLocale()` function.

Novo na versão 3.3.

Alterado na versão 3.7: The function now also uses the current locale encoding for the `surrogateescape` error handler, except on Android. Previously, `Py_EncodeLocale()` was used for the `surrogateescape`, and the current locale encoding was used for `strict`.

## File System Encoding

To encode and decode file names and other environment strings, `Py_FileSystemDefaultEncoding` should be used as the encoding, and `Py_FileSystemDefaultEncodeErrors` should be used as the error handler ([PEP 383](#) and [PEP 529](#)). To encode file names to bytes during argument parsing, the "O&" converter should be used, passing `PyUnicode_FSConverter()` as the conversion function:

int **PyUnicode\_FSConverter** (*PyObject* \*obj, void \*result)

*Part of the [Stable ABI](#). ParseTuple converter: encode str objects – obtained directly or through the `os.PathLike` interface – to bytes using `PyUnicode_EncodeFSDefault()`; bytes objects are output as-is. *result* must be a *PyBytesObject*\* which must be released when it is no longer used.*

Novo na versão 3.1.

Alterado na versão 3.6: Aceita um *objeto caminho ou similar*.

To decode file names to str during argument parsing, the "O&" converter should be used, passing `PyUnicode_FSDecoder()` as the conversion function:

int **PyUnicode\_FSDecoder** (*PyObject* \*obj, void \*result)

*Part of the [Stable ABI](#). ParseTuple converter: decode bytes objects – obtained either directly or indirectly through the `os.PathLike` interface – to str using `PyUnicode_DecodeFSDefaultAndSize()`; str objects are output as-is. *result* must be a *PyUnicodeObject*\* which must be released when it is no longer used.*

Novo na versão 3.2.

Alterado na versão 3.6: Aceita um *objeto caminho ou similar*.

*PyObject* \***PyUnicode\_DecodeFSDefaultAndSize** (const char \*s, *Py\_ssize\_t* size)

*Retorna valor: Nova referência. Part of the [Stable ABI](#). Decode a string from the *filesystem encoding and error handler*.*

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

`Py_FileSystemDefaultEncoding` is initialized at startup from the locale encoding and cannot be modified later. If you need to decode a string from the current locale encoding, use `PyUnicode_DecodeLocaleAndSize()`.

### Ver também:

The `Py_DecodeLocale()` function.

Alterado na versão 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

*PyObject* \***PyUnicode\_DecodeFSDefault** (const char \*s)

*Retorna valor: Nova referência. Part of the [Stable ABI](#). Decode a null-terminated string from the *filesystem encoding and error handler*.*

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

Use `PyUnicode_DecodeFSDefaultAndSize()` if you know the string length.

Alterado na versão 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

*PyObject* \***PyUnicode\_EncodeFSDefault** (*PyObject* \*unicode)

*Retorna valor: Nova referência. Part of the [Stable ABI](#). Encode a Unicode object to `Py_FileSystemDefaultEncoding` with the `Py_FileSystemDefaultEncodeErrors` error handler, and return bytes. Note that the resulting bytes object may contain null bytes.*

If `Py_FileSystemDefaultEncoding` is not set, fall back to the locale encoding.

`Py_FileSystemDefaultEncoding` is initialized at startup from the locale encoding and cannot be modified later. If you need to encode a string to the current locale encoding, use `PyUnicode_EncodeLocale()`.

**Ver também:**

The `Py_EncodeLocale()` function.

Novo na versão 3.2.

Alterado na versão 3.6: Use `Py_FileSystemDefaultEncodeErrors` error handler.

**wchar\_t Support**

`wchar_t` support for platforms which support it:

*PyObject* \***PyUnicode\_FromWideChar** (const `wchar_t` \*w, *Py\_ssize\_t* size)

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Create a Unicode object from the `wchar_t` buffer `w` of the given *size*. Passing `-1` as the *size* indicates that the function must itself compute the length, using `wcslen`. Return `NULL` on failure.

*Py\_ssize\_t* **PyUnicode\_AsWideChar** (*PyObject* \*unicode, `wchar_t` \*w, *Py\_ssize\_t* size)

*Part of the Stable ABI.* Copy the Unicode object contents into the `wchar_t` buffer `w`. At most *size* `wchar_t` characters are copied (excluding a possibly trailing null termination character). Return the number of `wchar_t` characters copied or `-1` in case of an error. Note that the resulting `wchar_t`\* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the `wchar_t`\* string is null-terminated in case this is required by the application. Also, note that the `wchar_t`\* string might contain null characters, which would cause the string to be truncated when used with most C functions.

`wchar_t` \***PyUnicode\_AsWideCharString** (*PyObject* \*unicode, *Py\_ssize\_t* \*size)

*Part of the Stable ABI since version 3.7.* Convert the Unicode object to a wide character string. The output string always ends with a null character. If *size* is not `NULL`, write the number of wide characters (excluding the trailing null termination character) into \**size*. Note that the resulting `wchar_t` string might contain null characters, which would cause the string to be truncated when used with most C functions. If *size* is `NULL` and the `wchar_t`\* string contains null characters a `ValueError` is raised.

Returns a buffer allocated by `PyMem_Alloc()` (use `PyMem_Free()` to free it) on success. On error, returns `NULL` and \**size* is undefined. Raises a `MemoryError` if memory allocation is failed.

Novo na versão 3.2.

Alterado na versão 3.7: Raises a `ValueError` if *size* is `NULL` and the `wchar_t`\* string contains null characters.

**Built-in Codecs**

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in `str()` string object constructor.

Setting encoding to `NULL` causes the default encoding to be used which is UTF-8. The file system calls should use `PyUnicode_FSConverter()` for encoding file names. This uses the variable `Py_FileSystemDefaultEncoding` internally. This variable should be treated as read-only: on some systems, it will be a pointer to a static string, on others, it will change at run-time (such as when the application invokes `setlocale`).

Error handling is set by errors which may also be set to `NULL` meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is “strict” (`ValueError` is raised).

The codecs all use a similar interface. Only deviations from the following generic ones are documented for simplicity.

## Generic Codecs

These are the generic codec APIs:

*PyObject* \***PyUnicode\_Decode**(**const** char \*s, *Py\_ssize\_t* size, **const** char \*encoding, **const** char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding *size* bytes of the encoded string *s*. *encoding* and *errors* have the same meaning as the parameters of the same name in the `str()` built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_AsEncodedString**(*PyObject* \*unicode, **const** char \*encoding, **const** char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object and return the result as Python bytes object. *encoding* and *errors* have the same meaning as the parameters of the same name in the `Unicode encode()` method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_Encode**(**const** *Py\_UNICODE* \*s, *Py\_ssize\_t* size, **const** char \*encoding, **const** char \*errors)

*Retorna valor:* Nova referência. Encode the *Py\_UNICODE* buffer *s* of the given *size* and return a Python bytes object. *encoding* and *errors* have the same meaning as the parameters of the same name in the `Unicode encode()` method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style *Py\_UNICODE* API; please migrate to using `PyUnicode_AsEncodedString()`.

## UTF-8 Codecs

These are the UTF-8 codec APIs:

*PyObject* \***PyUnicode\_DecodeUTF8**(**const** char \*s, *Py\_ssize\_t* size, **const** char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *s*. Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_DecodeUTF8Stateful**(**const** char \*s, *Py\_ssize\_t* size, **const** char \*errors, *Py\_ssize\_t* \*consumed)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). If *consumed* is NULL, behave like `PyUnicode_DecodeUTF8()`. If *consumed* is not NULL, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \***PyUnicode\_AsUTF8String**(*PyObject* \*unicode)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.

**const** char \***PyUnicode\_AsUTF8AndSize**(*PyObject* \*unicode, *Py\_ssize\_t* \*size)

Part of the [Stable ABI](#) since version 3.10. Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in *size*. The *size* argument can be NULL; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in *size*), regardless of whether there are any other null code points.

In the case of an error, NULL is returned with an exception set and no *size* is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer. The buffer is deallocated and pointers to it become invalid when the Unicode object is garbage collected.

Novo na versão 3.3.

Alterado na versão 3.7: The return type is now `const char *` rather of `char *`.

Alterado na versão 3.10: This function is a part of the *limited API*.

**const char \*PyUnicode\_AsUTF8** (*PyObject* \*unicode)  
As *PyUnicode\_AsUTF8AndSize()*, but does not store the size.

Novo na versão 3.3.

Alterado na versão 3.7: The return type is now `const char *` rather of `char *`.

*PyObject* \*PyUnicode\_EncodeUTF8 (**const** *Py\_UNICODE* \*s, *Py\_ssize\_t* size, **const** char \*errors)  
*Retorna valor:* Nova referência. Encode the *Py\_UNICODE* buffer *s* of the given *size* using UTF-8 and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsUTF8String()*, *PyUnicode\_AsUTF8AndSize()* or *PyUnicode\_AsEncodedString()*.

## UTF-32 Codecs

These are the UTF-32 codec APIs:

*PyObject* \*PyUnicode\_DecompileUTF32 (**const** char \*s, *Py\_ssize\_t* size, **const** char \*errors, int \*byteorder)  
*Retorna valor:* Nova referência. Part of the *Stable ABI*. Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to “strict”.

If *byteorder* is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0:  native order
*byteorder == 1:  big endian
```

If *\*byteorder* is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *\*byteorder* is -1 or 1, any byte order mark is copied to the output.

After completion, *\*byteorder* is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

*PyObject* \*PyUnicode\_DecompileUTF32Stateful (**const** char \*s, *Py\_ssize\_t* size, **const** char \*errors, int \*byteorder, *Py\_ssize\_t* \*consumed)  
*Retorna valor:* Nova referência. Part of the *Stable ABI*. If *consumed* is NULL, behave like *PyUnicode\_DecompileUTF32()*. If *consumed* is not NULL, *PyUnicode\_DecompileUTF32Stateful()* will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \*PyUnicode\_AsUTF32String (*PyObject* \*unicode)  
*Retorna valor:* Nova referência. Part of the *Stable ABI*. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is “strict”. Return NULL if an exception was raised by the codec.

**PyObject\*PyUnicode\_EncodeUTF32** (const *Py\_UNICODE* \*s, *Py\_ssize\_t* size, const char \*errors, int  
byteorder)

*Retorna valor:* Nova referência. Return a Python bytes object holding the UTF-32 encoded value of the Unicode data in *s*. Output is written according to the following byte order:

```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If *byteorder* is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If *Py\_UNICODE\_WIDE* is not defined, surrogate pairs will be output as a single code point.

Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsUTF32String()* or *PyUnicode\_AsEncodedString()*.

## UTF-16 Codecs

These are the UTF-16 codec APIs:

**PyObject\*PyUnicode\_DecodeUTF16** (const char \*s, *Py\_ssize\_t* size, const char \*errors, int \*byteorder)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Decode *size* bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to “strict”.

If *byteorder* is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0: native order
*byteorder == 1: big endian
```

If *\*byteorder* is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *\*byteorder* is -1 or 1, any byte order mark is copied to the output (where it will result in either a `\ufeff` or a `\ufffe` character).

After completion, *\*byteorder* is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

**PyObject\*PyUnicode\_DecodeUTF16Stateful** (const char \*s, *Py\_ssize\_t* size, const char \*errors, int  
\*byteorder, *Py\_ssize\_t* \*consumed)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). If *consumed* is NULL, behave like *PyUnicode\_DecodeUTF16()*. If *consumed* is not NULL, *PyUnicode\_DecodeUTF16Stateful()* will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

**PyObject\*PyUnicode\_AsUTF16String** (PyObject \*unicode)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is “strict”. Return NULL if an exception was raised by the codec.

**PyObject\*PyUnicode\_EncodeUTF16** (const *Py\_UNICODE* \*s, *Py\_ssize\_t* size, const char \*errors, int  
byteorder)

*Retorna valor:* Nova referência. Return a Python bytes object holding the UTF-16 encoded value of the Unicode data in *s*. Output is written according to the following byte order:



```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If `byteorder` is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If `Py_UNICODE_WIDE` is defined, a single `Py_UNICODE` value may get represented as a surrogate pair. If it is not defined, each `Py_UNICODE` value is interpreted as a UCS-2 character.

Return `NULL` if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsUTF16String()` or `PyUnicode_AsEncodedString()`.

## UTF-7 Codecs

These are the UTF-7 codec APIs:

*PyObject* \***PyUnicode\_DecodeUTF7**(const char \*s, Py\_ssize\_t size, const char \*errors)

*Retorna valor:* Nova referência. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *s*. Return `NULL` if an exception was raised by the codec.

*PyObject* \***PyUnicode\_DecodeUTF7Stateful**(const char \*s, Py\_ssize\_t size, const char \*errors, Py\_ssize\_t \*consumed)

*Retorna valor:* Nova referência. Part of the Stable ABI. If *consumed* is `NULL`, behave like `PyUnicode_DecodeUTF7()`. If *consumed* is not `NULL`, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

*PyObject* \***PyUnicode\_EncodeUTF7**(const Py\_UNICODE \*s, Py\_ssize\_t size, int base64SetO, int base64WhiteSpace, const char \*errors)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given size using UTF-7 and return a Python bytes object. Return `NULL` if an exception was raised by the codec.

If *base64SetO* is nonzero, “Set O” (punctuation that has no otherwise special meaning) will be encoded in base-64. If *base64WhiteSpace* is nonzero, whitespace will be encoded in base-64. Both are set to zero for the Python “utf-7” codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsEncodedString()`.

## Unicode-Escape Codecs

These are the “Unicode Escape” codec APIs:

*PyObject* \***PyUnicode\_DecodeUnicodeEscape**(const char \*s, Py\_ssize\_t size, const char \*errors)

*Retorna valor:* Nova referência. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *s*. Return `NULL` if an exception was raised by the codec.

*PyObject* \***PyUnicode\_AsUnicodeEscapeString**(PyObject \*unicode)

*Retorna valor:* Nova referência. Part of the Stable ABI. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is “strict”. Return `NULL` if an exception was raised by the codec.

*PyObject* \***PyUnicode\_EncodeUnicodeEscape**(const Py\_UNICODE \*s, Py\_ssize\_t size)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given *size* using Unicode-Escape and return a bytes object. Return `NULL` if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsUnicodeEscapeString()`.

### Raw-Unicode-Escape Codecs

These are the “Raw Unicode Escape” codec APIs:

**`PyObject *PyUnicode_DecodeRawUnicodeEscape`** (`const char *s`, `Py_ssize_t size`, `const char *errors`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *s*. Return NULL if an exception was raised by the codec.

**`PyObject *PyUnicode_AsRawUnicodeEscapeString`** (`PyObject *unicode`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.

**`PyObject *PyUnicode_EncodeRawUnicodeEscape`** (`const Py_UNICODE *s`, `Py_ssize_t size`)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given *size* using Raw-Unicode-Escape and return a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsRawUnicodeEscapeString()` or `PyUnicode_AsEncodedString()`.

### Latin-1 Codecs

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

**`PyObject *PyUnicode_DecodeLatin1`** (`const char *s`, `Py_ssize_t size`, `const char *errors`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *s*. Return NULL if an exception was raised by the codec.

**`PyObject *PyUnicode_AsLatin1String`** (`PyObject *unicode`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.

**`PyObject *PyUnicode_EncodeLatin1`** (`const Py_UNICODE *s`, `Py_ssize_t size`, `const char *errors`)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given *size* using Latin-1 and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsLatin1String()` or `PyUnicode_AsEncodedString()`.

### ASCII Codecs

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

**`PyObject *PyUnicode_DecodeASCII`** (`const char *s`, `Py_ssize_t size`, `const char *errors`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding *size* bytes of the ASCII encoded string *s*. Return NULL if an exception was raised by the codec.

**`PyObject *PyUnicode_AsASCIIString`** (`PyObject *unicode`)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.



*PyObject* \*PyUnicode\_EncodeASCII (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given `size` using ASCII and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsASCIIString()` or `PyUnicode_AsEncodedString()`.

## Character Map Codecs

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the `encodings` package). The codec uses mappings to encode and decode characters. The mapping objects provided must support the `__getitem__()` mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

*PyObject* \*PyUnicode\_DecomposeCharmap (const char \*data, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a Unicode object by decoding `size` bytes of the encoded string `s` using the given `mapping` object. Return NULL if an exception was raised by the codec.

If `mapping` is NULL, Latin-1 decoding will be applied. Else `mapping` must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes – ones which cause a `LookupError`, as well as ones which get mapped to None, `0xFFFE` or `'\ufffe'`, are treated as undefined mappings and cause an error.

*PyObject* \*PyUnicode\_AsCharmapString (PyObject \*unicode, PyObject \*mapping)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Encode a Unicode object using the given `mapping` object and return the result as a bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.

The `mapping` object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a `LookupError`) as well as mapped to None are treated as “undefined mapping” and cause an error.

*PyObject* \*PyUnicode\_EncodeCharmap (const Py\_UNICODE \*s, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given `size` using the given `mapping` object and return the result as a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsCharmapString()` or `PyUnicode_AsEncodedString()`.

The following codec API is special in that maps Unicode to Unicode.

*PyObject* \*PyUnicode\_Translate (PyObject \*str, PyObject \*table, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Translate a string by applying a character mapping table to it and return the resulting Unicode object. Return NULL if an exception was raised by the codec.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the `__getitem__()` interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a `LookupError`) are left untouched and are copied as-is.

`errors` has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

*PyObject* \*PyUnicode\_TranslateCharmap (const Py\_UNICODE \*s, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

*Retorna valor:* Nova referência. Translate a `Py_UNICODE` buffer of the given `size` by applying a character `mapping` table to it and return the resulting Unicode object. Return NULL when an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 3.11: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_Translate()`. or *generic codec based API*

## MBCS codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

*PyObject* \***PyUnicode\_DecodeMBCS** (const char \*s, Py\_ssize\_t size, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) on Windows since version 3.7. Create a Unicode object by decoding size bytes of the MBCS encoded string s. Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_DecodeMBCSStateful** (const char \*s, Py\_ssize\_t size, const char \*errors, Py\_ssize\_t \*consumed)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) on Windows since version 3.7. If consumed is NULL, behave like `PyUnicode_DecodeMBCS()`. If consumed is not NULL, `PyUnicode_DecodeMBCSStateful()` will not decode trailing lead byte and the number of bytes that have been decoded will be stored in consumed.

*PyObject* \***PyUnicode\_AsMBCSString** (PyObject \*unicode)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) on Windows since version 3.7. Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is “strict”. Return NULL if an exception was raised by the codec.

*PyObject* \***PyUnicode\_EncodeCodePage** (int code\_page, PyObject \*unicode, const char \*errors)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) on Windows since version 3.7. Encode the Unicode object using the specified code page and return a Python bytes object. Return NULL if an exception was raised by the codec. Use CP\_ACP code page to get the MBCS encoder.

Novo na versão 3.3.

*PyObject* \***PyUnicode\_EncodeMBCS** (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Retorna valor:* Nova referência. Encode the `Py_UNICODE` buffer of the given size using MBCS and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style `Py_UNICODE` API; please migrate to using `PyUnicode_AsMBCSString()`, `PyUnicode_EncodeCodePage()` or `PyUnicode_AsEncodedString()`.

## Methods & Slots

### Methods and Slot Functions

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or -1 if an exception occurs.

*PyObject* \***PyUnicode\_Concat** (PyObject \*left, PyObject \*right)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Concat two strings giving a new Unicode string.

*PyObject* \***PyUnicode\_Split** (PyObject \*s, PyObject \*sep, Py\_ssize\_t maxsplit)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Split a string giving a list of Unicode strings. If sep is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most maxsplit splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

*PyObject* \*PyUnicode\_Splitlines (*PyObject* \*s, int keepend)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If *keepend* is 0, the line break characters are not included in the resulting strings.

*PyObject* \*PyUnicode\_Join (*PyObject* \*separator, *PyObject* \*seq)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Join a sequence of strings using the given *separator* and return the resulting Unicode string.

*Py\_ssize\_t* PyUnicode\_Tailmatch (*PyObject* \*str, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Part of the [Stable ABI](#). Return 1 if *substr* matches *str*[start:end] at the given tail end (*direction* == -1 means to do a prefix match, *direction* == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.

*Py\_ssize\_t* PyUnicode\_Find (*PyObject* \*str, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Part of the [Stable ABI](#). Return the first position of *substr* in *str*[start:end] using the given *direction* (*direction* == 1 means to do a forward search, *direction* == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

*Py\_ssize\_t* PyUnicode\_FindChar (*PyObject* \*str, *Py\_UCS4* ch, *Py\_ssize\_t* start, *Py\_ssize\_t* end, int direction)

Part of the [Stable ABI](#) since version 3.7. Return the first position of the character *ch* in *str*[start:end] using the given *direction* (*direction* == 1 means to do a forward search, *direction* == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Novo na versão 3.3.

Alterado na versão 3.7: *start* and *end* are now adjusted to behave like *str*[start:end].

*Py\_ssize\_t* PyUnicode\_Count (*PyObject* \*str, *PyObject* \*substr, *Py\_ssize\_t* start, *Py\_ssize\_t* end)

Part of the [Stable ABI](#). Return the number of non-overlapping occurrences of *substr* in *str*[start:end]. Return -1 if an error occurred.

*PyObject* \*PyUnicode\_Replace (*PyObject* \*str, *PyObject* \*substr, *PyObject* \*replstr, *Py\_ssize\_t* maxcount)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Replace at most *maxcount* occurrences of *substr* in *str* with *replstr* and return the resulting Unicode object. *maxcount* == -1 means replace all occurrences.

int PyUnicode\_Compare (*PyObject* \*left, *PyObject* \*right)

Part of the [Stable ABI](#). Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively.

This function returns -1 upon failure, so one should call *PyErr\_Occurred()* to check for errors.

int PyUnicode\_CompareWithASCIIString (*PyObject* \*uni, const char \*string)

Part of the [Stable ABI](#). Compare a Unicode object, *uni*, with *string* and return -1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

*PyObject* \*PyUnicode\_RichCompare (*PyObject* \*left, *PyObject* \*right, int op)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Rich compare two Unicode strings and return one of the following:

- NULL in case an exception was raised
- Py\_True or Py\_False for successful comparisons
- Py\_NotImplemented in case the type combination is unknown

Possible values for *op* are Py\_GT, Py\_GE, Py\_EQ, Py\_NE, Py\_LT, and Py\_LE.

*PyObject* \*PyUnicode\_Format (*PyObject* \*format, *PyObject* \*args)

Retorna valor: Nova referência. *Part of the Stable ABI*. Return a new string object from *format* and *args*; this is analogous to `format % args`.

int PyUnicode\_Contains (*PyObject* \*container, *PyObject* \*element)

*Part of the Stable ABI*. Check whether *element* is contained in *container* and return true or false accordingly.

*element* has to coerce to a one element Unicode string. -1 is returned if there was an error.

void PyUnicode\_InternInPlace (*PyObject* \*\*string)

*Part of the Stable ABI*. Intern the argument *\*string* in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as *\*string*, it sets *\*string* to it (releasing the reference to the old string object and creating a new *strong reference* to the interned string object), otherwise it leaves *\*string* alone and interns it (creating a new *strong reference*). (Clarification: even though there is a lot of talk about references, think of this function as reference-neutral; you own the object after the call if and only if you owned it before the call.)

*PyObject* \*PyUnicode\_InternFromString (const char \*v)

Retorna valor: Nova referência. *Part of the Stable ABI*. A combination of *PyUnicode\_FromString()* and *PyUnicode\_InternInPlace()*, returning either a new Unicode string object that has been interned, or a new (“owned”) reference to an earlier interned string object with the same value.

### 8.3.4 Objeto tupla

type PyTupleObject

Este subtipo de *PyObject* representa um objeto tupla em Python.

*PyTypeObject* PyTuple\_Type

*Part of the Stable ABI*. Esta instância de *PyTypeObject* representa o tipo tupla de Python; é o mesmo objeto que `tuple` na camada Python.

int PyTuple\_Check (*PyObject* \*p)

Retorna verdadeiro se *p* é um objeto tupla ou uma instância de um subtipo do tipo tupla. Esta função sempre tem sucesso.

int PyTuple\_CheckExact (*PyObject* \*p)

Retorna verdadeiro se *p* é um objeto tupla, mas não uma instância de um subtipo do tipo tupla. Esta função sempre tem sucesso.

*PyObject* \*PyTuple\_New (Py\_ssize\_t len)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto tupla de tamanho *len*, ou NULL em caso de falha.

*PyObject* \*PyTuple\_Pack (Py\_ssize\_t n, ...)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto tupla de tamanho *n*, ou NULL em caso de falha. Os valores da tupla são inicializados para os *n* argumentos C subsequentes apontando para objetos Python. `PyTuple_Pack(2, a, b)` é equivalente a `Py_BuildValue("(OO)", a, b)`.

Py\_ssize\_t PyTuple\_Size (*PyObject* \*p)

*Part of the Stable ABI*. Pega um ponteiro para um objeto tupla e retorna o tamanho dessa tupla.

Py\_ssize\_t PyTuple\_GET\_SIZE (*PyObject* \*p)

Retorna o tamanho da tupla *p*, que deve ser diferente de NULL e apontar para uma tupla; nenhuma verificação de erro é executada.

*PyObject* \*PyTuple\_GetItem (*PyObject* \*p, Py\_ssize\_t pos)

Retorna valor: Referência emprestada. *Part of the Stable ABI*. Retorna o objeto na posição *pos* na tupla apontada por *p*. Se *pos* estiver fora dos limites, retorna NULL e define uma exceção `IndexError`.

*PyObject* \*PyTuple\_GET\_ITEM(*PyObject* \*p, *Py\_ssize\_t* pos)

Retorna valor: Referência emprestada. Como `PyTuple_GetItem()`, mas faz nenhuma verificação de seus argumentos.

*PyObject* \*PyTuple\_GetSlice(*PyObject* \*p, *Py\_ssize\_t* low, *Py\_ssize\_t* high)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna a fatia da tupla apontada por *p* entre *low* (baixo) e *high* (alto), ou NULL em caso de falha. Este é o equivalente da expressão Python `p[low:high]`. A indexação do final da lista não é suportada.

int PyTuple\_SetItem(*PyObject* \*p, *Py\_ssize\_t* pos, *PyObject* \*o)

*Part of the Stable ABI*. Insere uma referência ao objeto *o* na posição *pos* da tupla apontada por *p*. Retorna 0 em caso de sucesso. Se *pos* estiver fora dos limites, retorne -1 e define uma exceção `IndexError`.

---

**Nota:** Esta função “rouba” uma referência a *o* e descarta uma referência a um item já na tupla na posição afetada.

---

void PyTuple\_SET\_ITEM(*PyObject* \*p, *Py\_ssize\_t* pos, *PyObject* \*o)

Como `PyTuple_SetItem()`, mas não verifica erros e deve *apenas* ser usado para preencher novas tuplas.

---

**Nota:** Esta macro “rouba” uma referência para *o* e, ao contrário de `PyTuple_SetItem()`, *não* descarta uma referência para nenhum item que esteja sendo substituído; qualquer referência na tupla na posição *pos* será perdida.

---

int \_PyTuple\_Resize(*PyObject* \*\*p, *Py\_ssize\_t* newsize)

Pode ser usado para redimensionar uma tupla. *newsize* será o novo comprimento da tupla. Como as tuplas são *supostamente* imutáveis, isso só deve ser usado se houver apenas uma referência ao objeto. *Não* use isto se a tupla já for conhecida por alguma outra parte do código. A tupla sempre aumentará ou diminuirá no final. Pense nisso como destruir a tupla antiga e criar uma nova, mas com mais eficiência. Retorna 0 em caso de sucesso. O código do cliente nunca deve presumir que o valor resultante de *\*p* será o mesmo de antes de chamar esta função. Se o objeto referenciado por *\*p* for substituído, o *\*p* original será destruído. Em caso de falha, retorna -1 e define *\*p* para NULL, e levanta `MemoryError` ou `SystemError`.

### 8.3.5 Objetos sequência de estrutura

Objetos sequência de estrutura são o equivalente em C dos objetos `namedtuple()`, ou seja, uma sequência cujos itens também podem ser acessados por meio de atributos. Para criar uma sequência de estrutura, você primeiro precisa criar um tipo de sequência de estrutura específico.

*PyTypeObject* \*PyStructSequence\_NewType(*PyStructSequence\_Desc* \*desc)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um novo tipo de sequência de estrutura a partir dos dados em *desc*, descrito abaixo. Instâncias do tipo resultante podem ser criadas com `PyStructSequence_New()`.

void PyStructSequence\_InitType(*PyTypeObject* \*type, *PyStructSequence\_Desc* \*desc)

Inicializa um tipo de sequência de estrutura *type* de *desc* no lugar.

int PyStructSequence\_InitType2(*PyTypeObject* \*type, *PyStructSequence\_Desc* \*desc)

O mesmo que `PyStructSequence_InitType`, mas retorna 0 em caso de sucesso e -1 em caso de falha.

Novo na versão 3.4.

type PyStructSequence\_Desc

*Part of the Stable ABI (including all members)*. Contém as metainformações de um tipo de sequência de estrutura a ser criado.

Campo	Tipo em C	Significado
name	const char *	nome do tipo sequência de estrutura
doc	const char *	ponteiro para docstring para o tipo ou NULL para omitir
fields	PyStructSequence_Field *	ponteiro para um vetor terminado em NULL com nomes de campos do novo tipo
n_in_sequence	int	número de campos visíveis para o lado Python (se usado como tupla)

**type PyStructSequence\_Field**

*Part of the Stable ABI (including all members).* Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as *PyObject\**. The index in the *fields* array of the *PyStructSequence\_Desc* determines which field of the struct sequence is described.

Campo	Tipo em C	Significado
name	const char *	nome do campo ou NULL para terminar a lista de campos nomeados; definida para <i>PyStructSequence_UnnamedField</i> para deixar sem nome
doc	const char *	campo docstring ou NULL para omitir

**const char \*const PyStructSequence\_UnnamedField**

Valor especial para um nome de campo para deixá-lo sem nome.

Alterado na versão 3.9: O tipo foi alterado de *char \**.

**PyObject \*PyStructSequence\_New (PyObject \*type)**

*Retorna valor:* Nova referência. *Part of the Stable ABI.* Cria um instância de *type*, que deve ser criada com *PyStructSequence\_NewType()*.

**PyObject \*PyStructSequence\_GetItem (PyObject \*p, Py\_ssize\_t pos)**

*Retorna valor:* Referência emprestada. *Part of the Stable ABI.* Retorna o objeto na posição *pos* na sequência de estrutura apontada por *p*. Nenhuma verificação de limites é executada.

**PyObject \*PyStructSequence\_GET\_ITEM (PyObject \*p, Py\_ssize\_t pos)**

*Retorna valor:* Referência emprestada. Macro equivalente de *PyStructSequence\_GetItem()*.

**void PyStructSequence\_SetItem (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)**

*Part of the Stable ABI.* Define o campo no índice *pos* da sequência de estrutura *p* para o valor *o*. Como *PyTuple\_SET\_ITEM()*, isto só deve ser usado para preencher novas instâncias.

---

**Nota:** Esta função “rouba” uma referência a *o*.

---

**void PyStructSequence\_SET\_ITEM (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)**

Macro equivalente de *PyStructSequence\_SetItem()*.

---

**Nota:** Esta função “rouba” uma referência a *o*.

---



### 8.3.6 Objeto List

#### type `PyListObject`

Este subtipo de `PyObject` representa um objeto de lista Python.

#### `PyTypeObject` `PyList_Type`

Part of the [Stable ABI](#). Esta instância de `PyTypeObject` representa o tipo de lista Python. Este é o mesmo objeto que `list` na camada Python.

#### int `PyList_Check` (`PyObject *p`)

Retorna verdadeiro se `p` é um objeto lista ou uma instância de um subtipo do tipo lista. Esta função sempre tem sucesso.

#### int `PyList_CheckExact` (`PyObject *p`)

Retorna verdadeiro se `p` é um objeto lista, mas não uma instância de um subtipo do tipo lista. Esta função sempre tem sucesso.

#### `PyObject *``PyList_New` (`Py_ssize_t len`)

Retorna valor: Nova referência. Part of the [Stable ABI](#). Retorna uma nova lista de comprimento `len` em caso de sucesso, ou `NULL` em caso de falha.

---

**Nota:** Se `len` for maior que zero, os itens do objeto de lista retornado são definidos como `NULL`. Portanto, você não pode usar funções API abstratas, como `PySequence_SetItem()` ou expor o objeto ao código Python antes de definir todos os itens para um objeto real com `PyList_SetItem()`.

---

#### `Py_ssize_t` `PyList_Size` (`PyObject *list`)

Part of the [Stable ABI](#). Retorna o comprimento do objeto de lista em `list`; isto é equivalente a `len(list)` em um objeto lista.

#### `Py_ssize_t` `PyList_GET_SIZE` (`PyObject *list`)

Forma macro de `PyList_Size()` sem verificação de erros.

#### `PyObject *``PyList_GetItem` (`PyObject *list`, `Py_ssize_t index`)

Retorna valor: Referência emprestada. Part of the [Stable ABI](#). Retorna o objeto na posição `index` na lista apontada por `list`. A posição deve ser não negativa; não há suporte à indexação do final da lista. Se `index` estiver fora dos limites (`<0` ou `>=len(list)`), retorna `NULL` e levanta uma exceção `IndexError`.

#### `PyObject *``PyList_GET_ITEM` (`PyObject *list`, `Py_ssize_t i`)

Retorna valor: Referência emprestada. Forma macro de `PyList_GetItem()` sem verificação de erros.

#### int `PyList_SetItem` (`PyObject *list`, `Py_ssize_t index`, `PyObject *item`)

Part of the [Stable ABI](#). Define o item no índice `index` na lista como `item`. Retorna 0 em caso de sucesso. Se `index` estiver fora dos limites, retorna -1 e levanta uma exceção `IndexError`.

---

**Nota:** Esta função “rouba” uma referência para o `item` e descarta uma referência para um item já presente na lista na posição afetada.

---

#### void `PyList_SET_ITEM` (`PyObject *list`, `Py_ssize_t i`, `PyObject *o`)

Forma macro de `PyList_SetItem()` sem verificação de erro. Este é normalmente usado apenas para preencher novas listas onde não há conteúdo anterior.

---

**Nota:** Esta macro “rouba” uma referência para o `item` e, ao contrário de `PyList_SetItem()`, não descarta uma referência para nenhum item que esteja sendo substituído; qualquer referência em `list` será perdida.

---

int **PyList\_Insert** (*PyObject* \*list, *Py\_ssize\_t* index, *PyObject* \*item)

*Part of the Stable ABI.* Insere o item *item* na lista *list* na frente do índice *index*. Retorna 0 se for bem-sucedido; retorna -1 e levanta uma exceção se malsucedido. Análogo a `list.insert(index, item)`.

int **PyList\_Append** (*PyObject* \*list, *PyObject* \*item)

*Part of the Stable ABI.* Adiciona o item *item* ao final da lista *list*. Retorna 0 se for bem-sucedido; retorna -1 e levanta uma exceção se malsucedido. Análogo a `list.append(item)`.

*PyObject* \***PyList\_GetSlice** (*PyObject* \*list, *Py\_ssize\_t* low, *Py\_ssize\_t* high)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna uma lista dos objetos em *list* contendo os objetos entre *low* e *alto*. Retorne NULL e levanta uma exceção se malsucedido. Análogo a `list[low:high]`. Não há suporte à indexação do final da lista.

int **PyList\_SetSlice** (*PyObject* \*list, *Py\_ssize\_t* low, *Py\_ssize\_t* high, *PyObject* \*itemlist)

*Part of the Stable ABI.* Define a fatia de *list* entre *low* e *high* para o conteúdo de *itemlist*. Análogo a `list[low:high] = itemlist`. *itemlist* pode ser NULL, indicando a atribuição de uma lista vazia (exclusão de fatia). Retorna 0 em caso de sucesso, -1 em caso de falha. Não há suporte à indexação do final da lista.

int **PyList\_Sort** (*PyObject* \*list)

*Part of the Stable ABI.* Ordena os itens de *list* no mesmo lugar. Retorna 0 em caso de sucesso, e -1 em caso de falha. Isso é o equivalente de `list.sort()`.

int **PyList\_Reverse** (*PyObject* \*list)

*Part of the Stable ABI.* Inverte os itens de *list* no mesmo lugar. Retorna 0 em caso de sucesso, e -1 em caso de falha. Isso é o equivalente de `list.reverse()`.

*PyObject* \***PyList\_AsTuple** (*PyObject* \*list)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna um novo objeto tupla contendo os conteúdos de *list*; equivale a `tuple(list)`.

## 8.4 Coleções

### 8.4.1 Objetos dicionários

**type** **PyDictObject**

Este subtipo do *PyObject* representa um objeto dicionário Python.

*PyTypeObject* **PyDict\_Type**

*Part of the Stable ABI.* Esta instância do *PyTypeObject* representa o tipo do dicionário Python. Este é o mesmo objeto `dict` na camada do Python.

int **PyDict\_Check** (*PyObject* \*p)

Retorna verdadeiro se *p* é um objeto dicionário ou uma instância de um subtipo do tipo dicionário. Esta função sempre tem sucesso.

int **PyDict\_CheckExact** (*PyObject* \*p)

Retorna verdadeiro se *p* é um objeto dicionário, mas não uma instância de um subtipo do tipo dicionário. Esta função sempre tem sucesso.

*PyObject* \***PyDict\_New** ()

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna um novo dicionário vazio ou NULL em caso de falha.

*PyObject* \***PyDictProxy\_New** (*PyObject* \*mapping)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna um objeto `types.MappingProxyType` para



um mapeamento que reforça o comportamento somente leitura. Isso normalmente é usado para criar uma visão para evitar a modificação do dicionário para tipos de classes não dinâmicas.

void **PyDict\_Clear** (*PyObject* \*p)

*Part of the Stable ABI.* Esvazia um dicionário existente de todos os pares chave-valor.

int **PyDict\_Contains** (*PyObject* \*p, *PyObject* \*key)

*Part of the Stable ABI.* Determina se o dicionário *p* contém *key*. Se um item em *p* corresponder à *key*, retorna 1, caso contrário, retorna 0. Em caso de erro, retorna -1. Isso é equivalente à expressão Python `key in p`.

*PyObject* \***PyDict\_Copy** (*PyObject* \*p)

Retorna valor: Nova referência. *Part of the Stable ABI.* Retorna um novo dicionário que contém o mesmo chave-valor como *p*.

int **PyDict\_SetItem** (*PyObject* \*p, *PyObject* \*key, *PyObject* \*val)

*Part of the Stable ABI.* Insere *val* no dicionário *p* com a tecla *key*. *key* deve ser *hasheável*; se não for, `TypeError` será levantada. Retorna 0 em caso de sucesso ou -1 em caso de falha. Esta função *não* rouba uma referência a *val*.

int **PyDict\_SetItemString** (*PyObject* \*p, const char \*key, *PyObject* \*val)

*Part of the Stable ABI.* Insere *val* no dicionário *p* usando *key* como uma chave. *key* deve ser a `const char*`. O objeto chave é criado usando `PyUnicode_FromString(key)`. Retorna 0 em caso de sucesso ou -1 em caso de falha. Esta função *não* rouba uma referência a *val*.

int **PyDict\_DelItem** (*PyObject* \*p, *PyObject* \*key)

*Part of the Stable ABI.* Remove a entrada no dicionário *p* com a chave *key*. *key* deve ser *hasheável*; se não for, `TypeError` é levantada. Se *key* não estiver no dicionário, `KeyError` é levantada. Retorna 0 em caso de sucesso ou -1 em caso de falha.

int **PyDict\_DelItemString** (*PyObject* \*p, const char \*key)

*Part of the Stable ABI.* Remove a entrada no dicionário *p* que tem uma chave especificada pela string *key*. Se *key* não estiver no dicionário, `KeyError` é levantada. Retorna 0 em caso de sucesso ou -1 em caso de falha.

*PyObject* \***PyDict\_GetItem** (*PyObject* \*p, *PyObject* \*key)

Retorna valor: Referência emprestada. *Part of the Stable ABI.* Retorna o objeto do dicionário *p* que possui uma chave *key*. Retorna NULL se a chave *key* não estiver presente, mas *sem* definir uma exceção.

Observe que as exceções que ocorrem ao chamar os métodos `__hash__()` e `__eq__()` serão suprimidas. Para obter o relatório de erros, use `PyDict_GetItemWithError()`.

Alterado na versão 3.10: Chamar esta API sem *GIL* retida era permitido por motivos históricos. Não é mais permitido.

*PyObject* \***PyDict\_GetItemWithError** (*PyObject* \*p, *PyObject* \*key)

Retorna valor: Referência emprestada. *Part of the Stable ABI.* Variante de `PyDict_GetItem()` que não suprime exceções. Retorna NULL com uma exceção definida se uma exceção ocorreu. Retorna NULL \*\* sem \*\* uma exceção definida se a chave não estiver presente.

*PyObject* \***PyDict\_GetItemString** (*PyObject* \*p, const char \*key)

Retorna valor: Referência emprestada. *Part of the Stable ABI.* É o mesmo que `PyDict_GetItem()`, mas *key* é especificada como um `const char*`, em vez de um `PyObject*`.

Observe que as exceções que ocorrem ao chamar os métodos `__hash__()` e `__eq__()` e criar um objeto string temporário serão suprimidas. Para obter o relatório de erros, use `PyDict_GetItemWithError()`.

*PyObject* \***PyDict\_SetDefault** (*PyObject* \*p, *PyObject* \*key, *PyObject* \*defaultobj)

Retorna valor: Referência emprestada. Isso é o mesmo que o `dict.setdefault()` de nível Python. Se presente, ele retorna o valor correspondente a *key* do dicionário *p*. Se a chave não estiver no dict, ela será inserida com o valor *defaultobj* e *defaultobj* será retornado. Esta função avalia a função hash de *key* apenas uma vez, em vez de avaliá-la independentemente para a pesquisa e a inserção.

Novo na versão 3.4.

*PyObject* \***PyDict\_Items** (*PyObject* \*p)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um *PyListObject* contendo todos os itens do dicionário.

*PyObject* \***PyDict\_Keys** (*PyObject* \*p)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um *PyListObject* contendo todas as chaves do dicionário.

*PyObject* \***PyDict\_Values** (*PyObject* \*p)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um *PyListObject* contendo todos os valores do dicionário p.

*Py\_ssize\_t* **PyDict\_Size** (*PyObject* \*p)

*Part of the Stable ABI*. Retorna o número de itens no dicionário. Isso é equivalente a `len(p)` em um dicionário.

int **PyDict\_Next** (*PyObject* \*p, *Py\_ssize\_t* \*ppos, *PyObject* \*\*pkey, *PyObject* \*\*pvalue)

*Part of the Stable ABI*. Itera todos os pares de valores-chave no dicionário p. O *Py\_ssize\_t* referido por ppos deve ser inicializado para 0 antes da primeira chamada para esta função para iniciar a iteração; a função retorna true para cada par no dicionário e false quando todos os pares forem relatados. Os parâmetros pkey e pvalue devem apontar para variáveis de *PyObject*\* que serão preenchidas com cada chave e valor, respectivamente, ou podem ser NULL. Todas as referências retornadas por meio deles são emprestadas. ppos não deve ser alterado durante a iteração. Seu valor representa deslocamentos dentro da estrutura do dicionário interno e, como a estrutura é esparsa, os deslocamentos não são consecutivos.

Por exemplo:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

O dicionário p não deve sofrer mutação durante a iteração. É seguro modificar os valores das chaves à medida que você itera no dicionário, mas apenas enquanto o conjunto de chaves não mudar. Por exemplo:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}
```

int **PyDict\_Merge** (*PyObject* \*a, *PyObject* \*b, int override)

*Part of the Stable ABI*. Itera sobre o objeto de mapeamento b adicionando pares de valores-chave ao dicionário a.

*b* pode ser um dicionário, ou qualquer objeto que suporte `PyMapping_Keys()` e `PyObject_GetItem()`. Se *override* for verdadeiro, os pares existentes em *a* serão substituídos se uma chave correspondente for encontrada em *b*, caso contrário, os pares serão adicionados apenas se não houver uma chave correspondente em *a*. Retorna 0 em caso de sucesso ou -1 se uma exceção foi levantada.

int **PyDict\_Update** (*PyObject* \**a*, *PyObject* \**b*)

*Part of the Stable ABI.* É o mesmo que `PyDict_Merge(a, b, 1)` em C, e é semelhante a `a.update(b)` em Python, exceto que `PyDict_Update()` não cai na iteração em uma sequência de pares de valores de chave se o segundo argumento não tiver o atributo “keys”. Retorna 0 em caso de sucesso ou -1 se uma exceção foi levantada.

int **PyDict\_MergeFromSeq2** (*PyObject* \**a*, *PyObject* \**seq2*, int *override*)

*Part of the Stable ABI.* Atualiza ou mescla no dicionário *a*, a partir dos pares de chave-valor em *seq2*. *seq2* deve ser um objeto iterável produzindo objetos iteráveis de comprimento 2, vistos como pares chave-valor. No caso de chaves duplicadas, a última vence se *override* for verdadeiro, caso contrário, a primeira vence. Retorne 0 em caso de sucesso ou -1 se uma exceção foi levantada. Python equivalente (exceto para o valor de retorno):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
            a[key] = value
```

## 8.4.2 Objeto Set

Esta seção detalha a API pública para os objetos `set` e `frozenset`. Qualquer funcionalidade não listada abaixo é melhor acessada usando o protocolo de objeto abstrato (incluindo `PyObject_CallMethod()`, `PyObject_RichCompareBool()`, `PyObject_Hash()`, `PyObject_Repr()`, `PyObject_IsTrue()`, `PyObject_Print()` e `PyObject_GetIter()`) ou o protocolo abstrato de número (incluindo `PyNumber_And()`, `PyNumber_Subtract()`, `PyNumber_Or()`, `PyNumber_Xor()`, `PyNumber_InPlaceAnd()`, `PyNumber_InPlaceSubtract()`, `PyNumber_InPlaceOr()` e `PyNumber_InPlaceXor()`).

**type PyObject**

Este subtipo de `PyObject` é usado para manter os dados internos para ambos os objetos `set` e `frozenset`. É como um `PyDictObject` em que tem um tamanho fixo para conjuntos pequenos (muito parecido com o armazenamento de tupla) e apontará para um bloco de memória de tamanho variável separado para conjuntos de tamanho médio e grande (muito parecido com lista armazenamento). Nenhum dos campos desta estrutura deve ser considerado público e todos estão sujeitos a alterações. Todo o acesso deve ser feito por meio da API documentada, em vez de manipular os valores na estrutura.

*PyTypeObject* **PySet\_Type**

*Part of the Stable ABI.* Essa é uma instância de `PyTypeObject` representando o tipo Python `set`

*PyTypeObject* **PyFrozenSet\_Type**

*Part of the Stable ABI.* Esta é uma instância de `PyTypeObject` representando o tipo Python `frozenset`.

As macros de verificação de tipo a seguir funcionam em ponteiros para qualquer objeto Python. Da mesma forma, as funções construtoras funcionam com qualquer objeto Python iterável.

int **PySet\_Check** (*PyObject* \**p*)

Retorna verdadeiro se *p* for um objeto `set` ou uma instância de um subtipo. Esta função sempre tem sucesso.

int **PyFrozenSet\_Check** (*PyObject* \**p*)

Retorna verdadeiro se *p* for um objeto `frozenset` ou uma instância de um subtipo. Esta função sempre tem sucesso.

int **PyAnySet\_Check** (*PyObject* \*p)

Retorna verdadeiro se *p* for um objeto `set`, um objeto `frozenset` ou uma instância de um subtipo. Esta função sempre tem sucesso.

int **PySet\_CheckExact** (*PyObject* \*p)

Retorna verdadeiro se *p* for um objeto `set`, mas não uma instância de um subtipo. Esta função sempre tem sucesso.

Novo na versão 3.10.

int **PyAnySet\_CheckExact** (*PyObject* \*p)

Retorna verdadeiro se *p* for um objeto `set` ou um objeto `frozenset`, mas não uma instância de um subtipo. Esta função sempre tem sucesso.

int **PyFrozenSet\_CheckExact** (*PyObject* \*p)

Retorna verdadeiro se *p* for um objeto `frozenset`, mas não uma instância de um subtipo. Esta função sempre tem sucesso.

*PyObject* \***PySet\_New** (*PyObject* \*iterable)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna uma nova `set` contendo objetos retornados pelo iterável *iterable*. O *iterable* pode ser `NULL` para criar um novo conjunto vazio. Retorna o novo conjunto em caso de sucesso ou `NULL` em caso de falha. Levanta `TypeError` se *iterable* não for realmente iterável. O construtor também é útil para copiar um conjunto (`c=set(s)`).

*PyObject* \***PyFrozenSet\_New** (*PyObject* \*iterable)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna uma nova `frozenset` contendo objetos retornados pelo iterável *iterable*. O *iterable* pode ser `NULL` para criar um novo `frozenset` vazio. Retorna o novo conjunto em caso de sucesso ou `NULL` em caso de falha. Levanta `TypeError` se *iterable* não for realmente iterável.

As seguintes funções e macros estão disponíveis para instâncias de `set` ou `frozenset` ou instâncias de seus subtipos.

*Py\_ssize\_t* **PySet\_Size** (*PyObject* \*anyset)

*Part of the Stable ABI*. Retorna o comprimento de um objeto `set` ou `frozenset`. Equivalente a `len(anyset)`. Levanta um `PyExc_SystemError` se *anyset* não for um `set`, `frozenset`, ou uma instância de um subtipo.

*Py\_ssize\_t* **PySet\_GET\_SIZE** (*PyObject* \*anyset)

Forma macro de `PySet_Size()` sem verificação de erros.

int **PySet\_Contains** (*PyObject* \*anyset, *PyObject* \*key)

*Part of the Stable ABI*. Retorna 1 se encontrado, 0 se não encontrado, e -1 se um erro é encontrado. Ao contrário do método Python `__contains__()`, esta função não converte automaticamente conjuntos não hasháveis em `frozensets` temporários. Levanta um `TypeError` se a *key* não for hashável. Levanta `PyExc_SystemError` se *anyset* não é um `set`, `frozenset`, ou uma instância de um subtipo.

int **PySet\_Add** (*PyObject* \*set, *PyObject* \*key)

*Part of the Stable ABI*. Adiciona *key* a uma instância de `set`. Também funciona com instâncias de `frozenset` (como `PyTuple_SetItem()`, ele pode ser usado para preencher os valores de novos conjuntos de congelamentos antes que eles sejam expostos a outro código). Retorna 0 em caso de sucesso ou -1 em caso de falha. Levanta um `TypeError` se a *key* não for hashável. Levanta uma `MemoryError` se não houver espaço para crescer. Levanta uma `SystemError` se *set* não for uma instância de `set` ou seu subtipo.

As seguintes funções estão disponíveis para instâncias de `set` ou seus subtipos, mas não para instâncias de `frozenset` ou seus subtipos.

int **PySet\_Discard** (*PyObject* \*set, *PyObject* \*key)

*Part of the Stable ABI*. Retorna 1 se encontrado e removido, 0 se não encontrado (nenhuma ação realizada) e -1 se um erro for encontrado. Não levanta `KeyError` para chaves ausentes. Levanta uma `TypeError` se a *key* não for hashável. Ao contrário do método Python `discard()`, esta função não converte automaticamente conjuntos não hasháveis em `frozensets` temporários. Levanta `PyExc_SystemError` se *set* não é uma instância de `set` ou seu subtipo.

*PyObject* \*PySet\_Pop (*PyObject* \*set)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna uma nova referência a um objeto arbitrário no *set* e remove o objeto do *set*. Retorna NULL em caso de falha. Levanta `KeyError` se o conjunto estiver vazio. Levanta uma `SystemError` se *set* não for uma instância de *set* ou seu subtipo.

int PySet\_Clear (*PyObject* \*set)

*Part of the Stable ABI*. Limpa todos os elementos de um conjunto existente

## 8.5 Objetos Function

### 8.5.1 Objetos Function

Existem algumas funções específicas para as funções do Python.

**type** PyFunctionObject

A estrutura C usada para funções.

*PyTypeObject* PyFunction\_Type

Esta é uma instância de *PyTypeObject* e representa o tipo de função Python. Está exposta a programadores Python como `types.FunctionType`.

int PyFunction\_Check (*PyObject* \*o)

Retorna verdadeiro se *o* for um objeto função (tem tipo *PyFunction\_Type*). O parâmetro não deve ser NULL. Esta função sempre obtém sucesso.

*PyObject* \*PyFunction\_New (*PyObject* \*code, *PyObject* \*globals)

Retorna valor: Nova referência. Retorna um novo objeto função associado ao objeto código *code*. *globals* deve ser um dicionário com as variáveis globais acessíveis à função.

A docstring e o nome da função são recuperados do objeto de código. `__module__` \* é recuperado de *\*globals*. Os padrões de argumento, as anotações e o encerramento são definidos como NULL. `__qualname__` está definido para o mesmo valor que o nome da função.

*PyObject* \*PyFunction\_NewWithQualName (*PyObject* \*code, *PyObject* \*globals, *PyObject* \*qualname)

Retorna valor: Nova referência. Como *PyFunction\_New()*, mas também permite configurar o atributo `__qualname__` do objeto da função. *qualname* deve ser um objeto unicode ou NULL; Se NULL, o atributo `__qualname__` é definido como o mesmo valor que o atributo `__name__`.

Novo na versão 3.3.

*PyObject* \*PyFunction\_GetCode (*PyObject* \*op)

Retorna valor: Referência emprestada. Retorna o objeto código associado ao objeto função *op*.

*PyObject* \*PyFunction\_GetGlobals (*PyObject* \*op)

Retorna valor: Referência emprestada. Retorna o dicionário global associado ao objeto função *op*.

*PyObject* \*PyFunction\_GetModule (*PyObject* \*op)

Retorna valor: Referência emprestada. Retorna uma referência emprestada para o atributo `__module__` do objeto função *op*. Pode ser NULL.

Esta é normalmente uma string contendo o nome do módulo, mas pode ser configurada para qualquer outro objeto pelo código Python.

*PyObject* \*PyFunction\_GetDefaults (*PyObject* \*op)

Retorna valor: Referência emprestada. Retorna os valores-padrão de argumentos do objeto função *op*. Pode ser uma tupla de argumentos ou NULL.

int PyFunction\_SetDefaults (*PyObject* \*op, *PyObject* \*defaults)

Define os valores-padrão dos argumentos do objeto função *op*. *defaults* deve ser `Py_None` ou uma tupla.

Levanta `SystemError` e retorna `-1` em caso de falha.

*PyObject* \***PyFunction\_GetClosure** (*PyObject* \**op*)

Retorna valor: *Referência emprestada*. Retorna o fechamento associado ao objeto função *op*. Pode ser `NULL` ou uma tupla de objetos célula.

int **PyFunction\_SetClosure** (*PyObject* \**op*, *PyObject* \**closure*)

Define o fechamento associado ao objeto função *op*. *closure* deve ser `Py_None` ou uma tupla de objetos de célula.

Levanta `SystemError` e retorna `-1` em caso de falha.

*PyObject* \***PyFunction\_GetAnnotations** (*PyObject* \**op*)

Retorna valor: *Referência emprestada*. Retorna as anotações do objeto função *op*. Este pode ser um dicionário mutável ou `NULL`.

int **PyFunction\_SetAnnotations** (*PyObject* \**op*, *PyObject* \**annotations*)

Define as anotações para o objeto função *op*. *annotations* deve ser um dicionário ou `Py_None`.

Levanta `SystemError` e retorna `-1` em caso de falha.

## 8.5.2 Objetos de Método de Instância

Um método de instância é um wrapper para um *PyCFunction* e a nova maneira de vincular um *PyCFunction* a um objeto de classe. Ele substitui a chamada anterior `PyMethod_New(func, NULL, class)`.

*PyTypeObject* **PyInstanceMethod\_Type**

Esta instância de *PyTypeObject* representa o tipo de método de instância Python. Não é exposto a programas Python.

int **PyInstanceMethod\_Check** (*PyObject* \**o*)

Retorna verdadeiro se *o* é um objeto de método de instância (tem tipo *PyInstanceMethod\_Type*). O parâmetro não deve ser `NULL`. Esta função sempre tem sucesso.

*PyObject* \***PyInstanceMethod\_New** (*PyObject* \**func*)

Retorna valor: *Nova referência*. Retorna um novo objeto de método de instância, com *func* sendo qualquer objeto chamável. *func* é a função que será chamada quando o método de instância for chamado.

*PyObject* \***PyInstanceMethod\_Function** (*PyObject* \**im*)

Retorna valor: *Referência emprestada*. Retorna o objeto função associado ao método de instância *im*.

*PyObject* \***PyInstanceMethod\_GET\_FUNCTION** (*PyObject* \**im*)

Retorna valor: *Referência emprestada*. Versão macro de *PyInstanceMethod\_Function()* que evita a verificação de erros.

## 8.5.3 Objetos método

Métodos são objetos função vinculados. Os métodos são sempre associados a uma instância de uma classe definida pelo usuário. Métodos não vinculados (métodos vinculados a um objeto de classe) não estão mais disponíveis.

*PyTypeObject* **PyMethod\_Type**

Esta instância de *PyTypeObject* representa o tipo de método Python. Isso é exposto a programas Python como `types.MethodType`.

int **PyMethod\_Check** (*PyObject* \**o*)

Retorna verdadeiro se *o* é um objeto de método (tem tipo *PyMethod\_Type*). O parâmetro não deve ser `NULL`. Esta função sempre tem sucesso.



*PyObject* \*PyMethod\_New (*PyObject* \*func, *PyObject* \*self)

Retorna valor: Nova referência. Retorna um novo objeto de método, com *func* sendo qualquer objeto chamável e *self* a instância à qual o método deve ser vinculado. *func* é a função que será chamada quando o método for chamado. *self* não deve ser NULL.

*PyObject* \*PyMethod\_Function (*PyObject* \*meth)

Retorna valor: Referência emprestada. Retorna o objeto função associado ao método *meth*.

*PyObject* \*PyMethod\_GET\_FUNCTION (*PyObject* \*meth)

Retorna valor: Referência emprestada. Versão macro de *PyMethod\_Function()* que evita a verificação de erros.

*PyObject* \*PyMethod\_Self (*PyObject* \*meth)

Retorna valor: Referência emprestada. Retorna a instância associada com o método *meth*.

*PyObject* \*PyMethod\_GET\_SELF (*PyObject* \*meth)

Retorna valor: Referência emprestada. Versão macro de *PyMethod\_Self()* que evita a verificação de erros.

## 8.5.4 Objeto célula

Objetos “cell” são usados para implementar variáveis referenciadas por múltiplos escopos. Para cada variável, um objeto célula é criado para armazenar o valor; as variáveis locais de cada quadro de pilha que referencia o valor contém uma referência para as células de escopos externos que também usam essa variável. Quando o valor é acessado, o valor contido na célula é usado em vez do próprio objeto da célula. Essa des-referência do objeto da célula requer suporte do código de bytes gerado; estes não são automaticamente desprezados quando acessados. Objetos de células provavelmente não serão úteis em outro lugar.

**type PyCellObject**

A estrutura C usada para objetos célula.

*PyTypeObject* PyCell\_Type

O objeto de tipo correspondente aos objetos célula.

int PyCell\_Check (ob)

Retorna verdadeiro se *ob* for um objeto célula; *ob* não deve ser NULL. Esta função sempre tem sucesso.

*PyObject* \*PyCell\_New (*PyObject* \*ob)

Retorna valor: Nova referência. Cria e retorna um novo objeto célula contendo o valor *ob*. O parâmetro pode ser NULL.

*PyObject* \*PyCell\_Get (*PyObject* \*cell)

Retorna valor: Nova referência. Retorna o conteúdo da célula *cell*.

*PyObject* \*PyCell\_GET (*PyObject* \*cell)

Retorna valor: Referência emprestada. Retorna o conteúdo da célula *cell*, mas sem verificar se *cell* não é NULL e um objeto célula.

int PyCell\_Set (*PyObject* \*cell, *PyObject* \*value)

Define o conteúdo do objeto da célula *cell* como *value*. Isso libera a referência a qualquer conteúdo atual da célula. *value* pode ser NULL. *cell* não pode ser NULL; se não for um objeto célula, -1 será retornado. Em caso de sucesso, 0 será retornado.

void PyCell\_SET (*PyObject* \*cell, *PyObject* \*value)

Define o valor do objeto da célula *cell* como *value*. Nenhuma contagem de referência é ajustada e nenhuma verificação é feita quanto à segurança; *cell* não pode ser NULL e deve ser um objeto célula.

## 8.5.5 Objetos código

Os objetos código são um detalhe de baixo nível da implementação do CPython. Cada um representa um pedaço de código executável que ainda não foi vinculado a uma função.

### **type** `PyCodeObject`

A estrutura C dos objetos usados para descrever objetos código. Os campos deste tipo estão sujeitos a alterações a qualquer momento.

### *PyTypeObject* `PyCode_Type`

Esta é uma instância de *PyTypeObject* representando o tipo Python `code`.

### `int` `PyCode_Check` (*PyObject* \**co*)

Retorna verdadeiro se *co* for um objeto `code`. Esta função sempre tem sucesso.

### `int` `PyCode_GetNumFree` (*PyCodeObject* \**co*)

Retorna o número de variáveis livres em *co*.

### *PyCodeObject* \*`PyCode_New` (`int` *argcount*, `int` *kwnonlyargcount*, `int` *nlocals*, `int` *stacksize*, `int` *flags*, *PyObject* \**code*, *PyObject* \**consts*, *PyObject* \**names*, *PyObject* \**varnames*, *PyObject* \**freevars*, *PyObject* \**cellvars*, *PyObject* \**filename*, *PyObject* \**name*, `int` *firstlineno*, *PyObject* \**notab*)

*Retorna valor:* Nova referência. Retorna um novo objeto código. Se você precisa de um objeto código fictício para criar um quadro, use `PyCode_NewEmpty()` no caso. Chamar `PyCode_New()` diretamente pode vinculá-lo a uma versão precisa do Python, uma vez que a definição do bytecode muda frequentemente.

### *PyCodeObject* \*`PyCode_NewWithPosOnlyArgs` (`int` *argcount*, `int` *posonlyargcount*, `int` *kwnonlyargcount*, `int` *nlocals*, `int` *stacksize*, `int` *flags*, *PyObject* \**code*, *PyObject* \**consts*, *PyObject* \**names*, *PyObject* \**varnames*, *PyObject* \**freevars*, *PyObject* \**cellvars*, *PyObject* \**filename*, *PyObject* \**name*, `int` *firstlineno*, *PyObject* \**notab*)

*Retorna valor:* Nova referência. Semelhante a `PyCode_New()`, mas com um “posonlyargcount” extra para argumentos apenas posicionais.

Novo na versão 3.8.

### *PyCodeObject* \*`PyCode_NewEmpty` (`const` `char` \**filename*, `const` `char` \**funcname*, `int` *firstlineno*)

*Retorna valor:* Nova referência. Retorna um novo objeto código vazio com o nome do arquivo especificado, o nome da função e o número da primeira linha. É ilegal executar `exec()` ou `eval()` no objeto código resultante.

### `int` `PyCode_Addr2Line` (*PyCodeObject* \**co*, `int` *byte\_offset*)

Retorna o número da linha da instrução que ocorre em ou antes de *byte\_offset* e termina depois disso. Se você só precisa do número da linha de um quadro, use `PyFrame_GetLineNumber()`.

Para iterar de forma eficiente os números de linha em um objeto código, use a API descrita no PEP 626.

## 8.6 Outros Objetos

### 8.6.1 Objetos arquivos

Essas APIs são uma emulação mínima da API C do Python 2 para objetos arquivo embutidos, que costumavam depender do suporte de E/S em buffer (`FILE*`) da biblioteca C padrão. No Python 3, arquivos e streams usam o novo módulo `io`, que define várias camadas sobre a E/S sem buffer de baixo nível do sistema operacional. As funções descritas a seguir são invólucros de conveniência para o C sobre essas novas APIs e são destinadas principalmente para relatórios de erros internos no interpretador; código de terceiros é recomendado para acessar as APIs de `io`.



*PyObject* \*PyFile\_FromFd (int *fd*, const char \**name*, const char \**mode*, int *buffering*, const char \**encoding*, const char \**errors*, const char \**newline*, int *closefd*)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um objeto arquivo Python a partir do descritor de arquivo de um arquivo já aberto *fd*. Os argumentos *name*, *encoding*, *errors* and *newline* podem ser NULL para usar os padrões; *buffering* pode ser -1 para usar o padrão. *name* é ignorado e mantido para compatibilidade com versões anteriores. Retorna NULL em caso de falha. Para uma descrição mais abrangente dos argumentos, consulte a documentação da função `io.open()`.

**Aviso:** Como os streams do Python têm sua própria camada de buffer, combiná-los com os descritores de arquivo no nível do sistema operacional pode produzir vários problemas (como ordenação inesperada de dados).

Alterado na versão 3.2: Ignora atributo *name*.

int PyObject\_AsFileDescriptor (*PyObject* \**p*)

*Part of the Stable ABI*. Retorna o descritor de arquivo associado a *p* como um `int`. Se o objeto for um inteiro, seu valor será retornado. Caso contrário, o método `fileno()` do objeto será chamado se existir; o método deve retornar um inteiro, que é retornado como o valor do descritor de arquivo. Define uma exceção e retorna -1 em caso de falha.

*PyObject* \*PyFile\_GetLine (*PyObject* \**p*, int *n*)

Retorna valor: Nova referência. *Part of the Stable ABI*. Equivalente a `p.readline([n])`, esta função lê uma linha do objeto *p*. *p* pode ser um objeto arquivo ou qualquer objeto com um método `readline()`. Se *n* for 0, exatamente uma linha é lida, independentemente do comprimento da linha. Se *n* for maior que 0, não mais do que *n* bytes serão lidos do arquivo; uma linha parcial pode ser retornada. Em ambos os casos, uma string vazia é retornada se o final do arquivo for alcançado imediatamente. Se *n* for menor que 0, entretanto, uma linha é lida independentemente do comprimento, mas `EOFError` é levantada se o final do arquivo for alcançado imediatamente.

int PyFile\_SetOpenCodeHook (Py\_OpenCodeHookFunction *handler*)

Substitui o comportamento normal de `io.open_code()` para passar seu parâmetro por meio do manipulador fornecido.

O manipulador é uma função do tipo `PyObject *(*)(PyObject *path, void *userData)`, sendo *path* garantido como sendo `PyUnicodeObject`.

O ponteiro *userData* é passado para a função de gancho. Como as funções de gancho podem ser chamadas de diferentes tempos de execução, esse ponteiro não deve se referir diretamente ao estado do Python.

Como este gancho é usado intencionalmente durante a importação, evite importar novos módulos durante sua execução, a menos que eles estejam congelados ou disponíveis em `sys.modules`.

Uma vez que um gancho foi definido, ele não pode ser removido ou substituído, e chamadas posteriores para `PyFile_SetOpenCodeHook()` irão falhar. Em caso de falha, a função retorna -1 e define uma exceção se o interpretador foi inicializado.

É seguro chamar esta função antes `Py_Initialize()`.

Levanta um evento de auditoria `setopencodehook` sem argumentos.

Novo na versão 3.8.

int PyFile\_WriteObject (*PyObject* \**obj*, *PyObject* \**p*, int *flags*)

*Part of the Stable ABI*. Escreve o objeto *obj* no objeto arquivo *p*. O único sinalizador suportado para *flags* é `Py_PRINT_RAW`; se fornecido, o `str()` do objeto é escrito em vez de `repr()`. Retorna 0 em caso de sucesso ou -1 em caso de falha; a exceção apropriada será definida.

int PyFile\_WriteString (const char \**s*, *PyObject* \**p*)

*Part of the Stable ABI*. Escreve a string *s* no objeto arquivo *p*. Retorna 0 em caso de sucesso ou -1 em caso de falha; a exceção apropriada será definida.

## 8.6.2 Objetos do Módulo

### *PyTypeObject* **PyModule\_Type**

*Part of the Stable ABI.* Esta instância de *PyTypeObject* representa o tipo de módulo Python. Isso é exposto a programas Python como `types.ModuleType`.

### **int PyModule\_Check** (*PyObject* \*p)

Retorna true se *p* for um objeto de módulo ou um subtipo de um objeto de módulo. Esta função sempre é bem-sucedida.

### **int PyModule\_CheckExact** (*PyObject* \*p)

Retorna true se *p* for um objeto de módulo, mas não um subtipo de *PyModule\_Type*. Essa função é sempre bem-sucedida.

### *PyObject* \***PyModule\_NewObject** (*PyObject* \*name)

*Retorna valor: Nova referência. Part of the Stable ABI since version 3.7.* Retorna um novo objeto de módulo com o atributo `__name__` definido como *name*. Os atributos de módulo `__name__`, `__doc__`, `__package__` e `__loader__` são preenchidos (todos exceto `__name__` são definidos como None); O chamador é responsável por providenciar um atributo `__file__`.

Novo na versão 3.3.

Alterado na versão 3.4: `__package__` e `__loader__` são definidos como None.

### *PyObject* \***PyModule\_New** (const char \*name)

*Retorna valor: Nova referência. Part of the Stable ABI.* Semelhante a *PyModule\_NewObject()*, mas o nome é uma string codificada em UTF-8 em vez de um objeto Unicode.

### *PyObject* \***PyModule\_GetDict** (*PyObject* \*module)

*Retorna valor: Referência emprestada. Part of the Stable ABI.* Retorna o objeto dicionário que implementa o espaço de nomes de *module*; este objeto é o mesmo que o atributo `__dict__` do objeto de módulo. Se *module* não for um objeto de módulo (ou um subtipo de um objeto de módulo), `SystemError` é levantada e NULL é retornado.

É recomendado que as extensões usem outras funções *PyModule\_\** e *PyObject\_\** em vez de manipular diretamente o `__dict__` de um módulo.

### *PyObject* \***PyModule\_GetNameObject** (*PyObject* \*module)

*Retorna valor: Nova referência. Part of the Stable ABI since version 3.7.* Retorna o valor `__name__` do módulo. Se o módulo não fornecer um, ou se não for uma string, `SystemError` é levantada e NULL é retornado.

Novo na versão 3.3.

### const char \***PyModule\_GetName** (*PyObject* \*module)

*Part of the Stable ABI.* Semelhante a *PyModule\_GetNameObject()* mas retorna o nome codificado em 'utf-8'

### void \***PyModule\_GetState** (*PyObject* \*module)

*Part of the Stable ABI.* Retorna o “estado” do módulo, ou seja, um ponteiro para o bloco de memória alocado no momento de criação do módulo, ou NULL. Ver *PyModuleDef.m\_size*.

### *PyModuleDef* \***PyModule\_GetDef** (*PyObject* \*module)

*Part of the Stable ABI.* Retorna um ponteiro para a estrutura *PyModuleDef* da qual o módulo foi criado, ou NULL se o módulo não foi criado de uma definição.

### *PyObject* \***PyModule\_GetFilenameObject** (*PyObject* \*module)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna o nome do arquivo do qual o módulo foi carregado usando o atributo `__file__` do módulo. Se não estiver definido, ou se não for uma string unicode, levanta `SystemError` e retorna NULL; Caso contrário, retorna uma referência a um objeto Unicode.

Novo na versão 3.2.

**const char \*PyModule\_GetFilename** (*PyObject \*module*)

*Part of the Stable ABI.* Semelhante a *PyModule\_GetFilenameObject()* mas retorna o nome do arquivo codificado em 'utf-8'.

Obsoleto desde a versão 3.2: *PyModule\_GetFilename()* raises *UnicodeEncodeError* on unencodable filenames, use *PyModule\_GetFilenameObject()* instead.

## Inicializando módulos C

Objetos de módulos são geralmente criados a partir de módulos de extensão (bibliotecas compartilhadas que exportam uma função de inicialização), ou módulos compilados (onde a função de inicialização é adicionada usando *PyImport\_AppendInittab()*). Ver *building* ou *extending-with-embedding* para mais detalhes.

A função de inicialização pode passar uma instância de definição de módulo para *PyModule\_Create()* e retornar o objeto de módulo resultante ou solicitar “inicialização multifásica” retornando a própria estrutura de definição.

**type PyModuleDef**

*Part of the Stable ABI (including all members).* A estrutura de definição de módulo, que contém todas as informações necessária para criar um objeto de módulo. Geralmente, há apenas uma variável inicializada estaticamente desse tipo para cada módulo.

**PyModuleDef\_Base m\_base**

Always initialize this member to *PyModuleDef\_HEAD\_INIT*.

**const char \*m\_name**

Nome para o novo módulo.

**const char \*m\_doc**

Docstring para o módulo; geralmente uma variável docstring criada com *PyDoc\_STRVAR* é usada.

**Py\_ssize\_t m\_size**

O estado do módulo pode ser mantido em uma área de memória por módulo que pode ser recuperada com *PyModule\_GetState()*, em vez de em globais estáticos. Isso torna os módulos seguros para uso em vários subinterpretadores.

This memory area is allocated based on *m\_size* on module creation, and freed when the module object is deallocated, after the *m\_free* function has been called, if present.

Definir *m\_size* como *-1* significa que o módulo não oferece suporte a subinterpretadores, porque ele tem estado global.

Defini-lo como um valor não negativo significa que o módulo pode ser reiniciado e especifica a quantidade adicional de memória necessária para seu estado. *m\_size* não negativo é necessário para inicialização multifásica.

Ver **PEP 3121** para mais detalhes.

**PyMethodDef \*m\_methods**

Um ponteiro para uma tabela de funções de nível de módulo, descritas por valores *PyMethodDef*. Pode ser *NULL* se nenhuma função estiver presente.

**PyModuleDef\_Slot \*m\_slots**

Uma matriz de definições de slot para inicialização multifásica, terminada por uma entrada *{0, NULL}*. Ao usar inicialização monofásica, *m\_slots* deve ser *NULL*.

Alterado na versão 3.5: Antes da versão 3.5, esse membro era sempre definido como *NULL* e era definido como:

*inquiry m\_reload*

***traverseproc* m\_traverse**

Uma função de travessia para chamar durante a travessia do GC do objeto do módulo, ou NULL se não for necessário.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is NULL.

Alterado na versão 3.9: Não é mais chamado antes que o estado do módulo seja alocado.

***inquiry* m\_clear**

Uma função de limpeza para chamar durante a limpeza do GC do objeto do módulo, ou NULL se não for necessário.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is NULL.

Assim como *PyTypeObject.tp\_clear*, esta função não é *sempre* chamada antes de um módulo ser desalocado. Por exemplo, quando a contagem de referências é suficiente para determinar que um objeto não é mais usado, o coletor de lixo cíclico não é envolvido e *m\_free* é chamado diretamente.

Alterado na versão 3.9: Não é mais chamado antes que o estado do módulo seja alocado.

***freefunc* m\_free**

Uma função para ser chamada durante a desalocação do objeto do módulo, ou NULL se não for necessário.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py\_mod\_exec* function). More precisely, this function is not called if *m\_size* is greater than 0 and the module state (as returned by *PyModule\_GetState()*) is NULL.

Alterado na versão 3.9: Não é mais chamado antes que o estado do módulo seja alocado.

## inicialização de fase única

A função de inicialização do módulo pode criar e retornar o objeto do módulo diretamente. Isso é chamado de “inicialização de fase única” e usa uma das duas funções de criação de módulo a seguir:

***PyObject* \*PyModule\_Create (*PyModuleDef* \*def)**

*Retorna valor:* Nova referência. Create a new module object, given the definition in *def*. This behaves like *PyModule\_Create2()* with *module\_api\_version* set to *PYTHON\_API\_VERSION*.

***PyObject* \*PyModule\_Create2 (*PyModuleDef* \*def, int *module\_api\_version*)**

*Retorna valor:* Nova referência. Part of the [Stable ABI](#). Create a new module object, given the definition in *def*, assuming the API version *module\_api\_version*. If that version does not match the version of the running interpreter, a *RuntimeWarning* is emitted.

---

**Nota:** A maioria dos usos dessa função deve ser feita com *PyModule\_Create()*; use-o apenas se tiver certeza de que precisa.

---

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like *PyModule\_AddObjectRef()*.

## Inicialização multifásica

An alternate way to specify extensions is to request “multi-phase initialization”. Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and the *execution phase*, when it is populated. The distinction is similar to the `__new__()` and `__init__()` methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the `sys.modules` entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection – as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using `PyModule_GetState()`), or its contents (such as the module’s `__dict__` or individual classes created with `PyType_FromSpec()`).

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (`PyInit_modulename`) returns a `PyModuleDef` instance with non-empty `m_slots`. Before it is returned, the `PyModuleDef` instance must be initialized with the following function:

*PyObject* \***PyModuleDef\_Init** (*PyModuleDef* \*def)

*Retorna valor: Referência emprestada. Part of the [Stable ABI](#) since version 3.5. Garante que uma definição de módulo é um objeto Python devidamente inicializado que reporta corretamente seu tipo e contagem de referências.*

Returns *def* cast to `PyObject *`, or `NULL` if an error occurred.

Novo na versão 3.5.

The `m_slots` member of the module definition must point to an array of `PyModuleDef_Slot` structures:

**type** `PyModuleDef_Slot`

`int slot`

Um ID de lot, escolhido a partir dos valores disponíveis explicados abaixo.

`void *value`

Valor do slot, cujo significado depende do ID do slot.

Novo na versão 3.5.

The `m_slots` array must be terminated by a slot with id 0.

Os tipos de slot disponíveis são:

**Py\_mod\_create**

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature:

*PyObject* \***create\_module** (*PyObject* \*spec, *PyModuleDef* \*def)

The function receives a `ModuleSpec` instance, as defined in [PEP 451](#), and the module definition. It should return a new module object, or set an error and return `NULL`.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Múltiplos slots `Py_mod_create` podem não estar especificados em uma definição de módulo.

If `Py_mod_create` is not specified, the import machinery will create a normal module object using `PyModule_New()`. The name is taken from *spec*, not the definition, to allow extension modules to dynami-

cally adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of `PyModule_Type`. Any type can be used, as long as it supports setting and getting import-related attributes. However, only `PyModule_Type` instances may be returned if the `PyModuleDef` has non-NULL `m_traverse`, `m_clear`, `m_free`; non-zero `m_size`; or slots other than `Py_mod_create`.

#### **Py\_mod\_exec**

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

```
int exec_module (PyObject *module)
```

Se vários slots `Py_mod_exec` forem especificados, eles serão processados na ordem em que aparecem no vetor `m_slots`.

Ver [PEP 489](#) para obter mais detalhes sobre a inicialização multifásica.

### **Funções de criação de módulo de baixo nível**

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both `PyModule_FromDefAndSpec` and `PyModule_ExecDef` must be called to fully initialize a module.

*PyObject* \***PyModule\_FromDefAndSpec** (*PyModuleDef* \*def, *PyObject* \*spec)

*Retorna valor:* Nova referência. Create a new module object, given the definition in *def* and the ModuleSpec *spec*. This behaves like `PyModule_FromDefAndSpec2()` with `module_api_version` set to `PYTHON_API_VERSION`.

Novo na versão 3.5.

*PyObject* \***PyModule\_FromDefAndSpec2** (*PyModuleDef* \*def, *PyObject* \*spec, int module\_api\_version)

*Retorna valor:* Nova referência. Part of the [Stable ABI](#) since version 3.7. Create a new module object, given the definition in *def* and the ModuleSpec *spec*, assuming the API version `module_api_version`. If that version does not match the version of the running interpreter, a `RuntimeWarning` is emitted.

---

**Nota:** Most uses of this function should be using `PyModule_FromDefAndSpec()` instead; only use this if you are sure you need it.

---

Novo na versão 3.5.

int **PyModule\_ExecDef** (*PyObject* \*module, *PyModuleDef* \*def)

Part of the [Stable ABI](#) since version 3.7. Process any execution slots (`Py_mod_exec`) given in *def*.

Novo na versão 3.5.

int **PyModule\_SetDocString** (*PyObject* \*module, const char \*docstring)

Part of the [Stable ABI](#) since version 3.7. Set the docstring for *module* to *docstring*. This function is called automatically when creating a module from `PyModuleDef`, using either `PyModule_Create` or `PyModule_FromDefAndSpec`.

Novo na versão 3.5.

int **PyModule\_AddFunctions** (*PyObject* \*module, *PyMethodDef* \*functions)

Part of the [Stable ABI](#) since version 3.7. Add the functions from the NULL terminated *functions* array to *module*. Refer to the `PyMethodDef` documentation for details on individual entries (due to the lack of a shared module namespace, module level “functions” implemented in C typically receive the module as their first parameter, making

them similar to instance methods on Python classes). This function is called automatically when creating a module from `PyModuleDef`, using either `PyModule_Create` or `PyModule_FromDefAndSpec`.

Novo na versão 3.5.

## Support functions

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

int **PyModule\_AddObjectRef** (*PyObject* \*module, **const** char \*name, *PyObject* \*value)

Part of the [Stable ABI](#) since version 3.10. Add an object to *module* as *name*. This is a convenience function which can be used from the module's initialization function.

On success, return 0. On error, raise an exception and return -1.

Return NULL if *value* is NULL. It must be called with an exception raised in this case.

Exemplo de uso:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_DECREF(obj);
    return res;
}
```

O exemplo também pode ser escrito sem verificar explicitamente se *obj* é NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_XDECREF(obj);
    return res;
}
```

Note that `Py_XDECREF()` should be used instead of `Py_DECREF()` in this case, since *obj* can be NULL.

Novo na versão 3.10.

int **PyModule\_AddObject** (*PyObject* \*module, **const** char \*name, *PyObject* \*value)

Part of the [Stable ABI](#). Similar to `PyModule_AddObjectRef()`, but steals a reference to *value* on success (if it returns 0).

The new `PyModule_AddObjectRef()` function is recommended, since it is easy to introduce reference leaks by misusing the `PyModule_AddObject()` function.

---

**Nota:** Unlike other functions that steal references, `PyModule_AddObject()` only releases the reference to *value* on success.

This means that its return value must be checked, and calling code must `Py_DECREF()` *value* manually on error.

---



Exemplo de uso:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_DECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}
```

O exemplo também pode ser escrito sem verificar explicitamente se *obj* é NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_XDECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}
```

Note that `Py_XDECREF()` should be used instead of `Py_DECREF()` in this case, since *obj* can be NULL.

int **PyModule\_AddIntConstant** (*PyObject* \*module, const char \*name, long value)

*Part of the Stable ABI.* Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

int **PyModule\_AddStringConstant** (*PyObject* \*module, const char \*name, const char \*value)

*Part of the Stable ABI.* Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be NULL-terminated. Return -1 on error, 0 on success.

int **PyModule\_AddIntMacro** (*PyObject* \*module, macro)

Add an int constant to *module*. The name and the value are taken from *macro*. For example `PyModule_AddIntMacro(module, AF_INET)` adds the int constant `AF_INET` with the value of `AF_INET` to *module*. Return -1 on error, 0 on success.

int **PyModule\_AddStringMacro** (*PyObject* \*module, macro)

Add a string constant to *module*.

int **PyModule\_AddType** (*PyObject* \*module, *PyTypeObject* \*type)

*Part of the Stable ABI since version 3.10.* Add a type object to *module*. The type object is finalized by calling internally `PyType_Ready()`. The name of the type object is taken from the last component of *tp\_name* after dot. Return -1 on error, 0 on success.

Novo na versão 3.9.



## Pesquisa por módulos

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

*PyObject* \*PyState\_FindModule(*PyModuleDef* \*def)

*Retorna valor: Referência emprestada. Part of the Stable ABI.* Returns the module object that was created from *def* for the current interpreter. This method requires that the module object has been attached to the interpreter state with *PyState\_AddModule()* beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

int PyState\_AddModule(*PyObject* \*module, *PyModuleDef* \*def)

*Part of the Stable ABI since version 3.3.* Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via *PyState\_FindModule()*.

Only effective on modules created using single-phase initialization.

Python calls *PyState\_AddModule* automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls *PyState\_FindModule*. The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

The caller must hold the GIL.

Return 0 on success or -1 on failure.

Novo na versão 3.3.

int PyState\_RemoveModule(*PyModuleDef* \*def)

*Part of the Stable ABI since version 3.3.* Removes the module object created from *def* from the interpreter state. Return 0 on success or -1 on failure.

The caller must hold the GIL.

Novo na versão 3.3.

## 8.6.3 Objetos Iteradores

O Python fornece dois objetos iteradores de propósito geral. O primeiro, um iterador de sequência, trabalha com uma sequência arbitrária suportando o método `__getitem__()`. O segundo trabalha com um objeto chamável e um valor de sentinela, chamando o chamável para cada item na sequência e finalizando a iteração quando o valor de sentinela é retornado.

*PyTypeObject* PySeqIter\_Type

*Part of the Stable ABI.* Objeto de tipo para objetos iteradores retornados por *PySeqIter\_New()* e a forma de um argumento da função embutida *iter()* para os tipos de sequência embutidos.

int PySeqIter\_Check(*op*)

Retorna true se o tipo de *op* for *PySeqIter\_Type*. Esta função sempre é bem-sucedida.

*PyObject* \*PySeqIter\_New(*PyObject* \*seq)

*Retorna valor: Nova referência. Part of the Stable ABI.* Retorna um iterador que funcione com um objeto de sequência geral, *seq*. A iteração termina quando a sequência levanta `IndexError` para a operação de assinatura.

*PyTypeObject* PyCallIter\_Type

*Part of the Stable ABI.* Objeto de tipo para objetos iteradores retornados por *PyCallIter\_New()* e a forma de dois argumentos da função embutida *iter()*.

int **PyCallIter\_Check** (op)

Retorna true se o tipo de *op* for *PyCallIter\_Type*. Esta função sempre é bem-sucedida.

*PyObject* \***PyCallIter\_New** (*PyObject* \*callable, *PyObject* \*sentinel)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo iterador. O primeiro parâmetro, *callable*, pode ser qualquer objeto chamável do Python que possa ser chamado sem parâmetros; cada chamada deve retornar o próximo item na iteração. Quando *callable* retorna um valor igual a *sentinel*, a iteração será encerrada.

## 8.6.4 Objetos Descritores

“Descritores” são objetos que descrevem algum atributo de um objeto. Eles são encontrados no dicionário de objetos de tipo.

*PyTypeObject* **PyProperty\_Type**

*Part of the Stable ABI*. O tipo de objeto para os tipos de descritores embutidos.

*PyObject* \***PyDescr\_NewGetSet** (*PyTypeObject* \*type, **struct** *PyGetSetDef* \*getset)

Retorna valor: Nova referência. *Part of the Stable ABI*.

*PyObject* \***PyDescr\_NewMember** (*PyTypeObject* \*type, **struct** *PyMemberDef* \*meth)

Retorna valor: Nova referência. *Part of the Stable ABI*.

*PyObject* \***PyDescr\_NewMethod** (*PyTypeObject* \*type, **struct** *PyMethodDef* \*meth)

Retorna valor: Nova referência. *Part of the Stable ABI*.

*PyObject* \***PyDescr\_NewWrapper** (*PyTypeObject* \*type, **struct** *wrapperbase* \*wrapper, void \*wrapped)

Retorna valor: Nova referência.

*PyObject* \***PyDescr\_NewClassMethod** (*PyTypeObject* \*type, *PyMethodDef* \*method)

Retorna valor: Nova referência. *Part of the Stable ABI*.

int **PyDescr\_IsData** (*PyObject* \*descr)

Retorna não-zero se os objetos descritores *descr* descrevem um atributo de dados, ou 0 se os mesmos descrevem um método. *descr* deve ser um objeto descritor; não há verificação de erros.

*PyObject* \***PyWrapper\_New** (*PyObject* \*, *PyObject* \*)

Retorna valor: Nova referência. *Part of the Stable ABI*.

## 8.6.5 Objetos Slice

*PyTypeObject* **PySlice\_Type**

*Part of the Stable ABI*. Tipo de objeto para objetos fatia. Isso é o mesmo que *slice* na camada Python.

int **PySlice\_Check** (*PyObject* \*ob)

Retorna true se *ob* for um objeto fatia; *ob* não deve ser NULL. Esta função sempre tem sucesso.

*PyObject* \***PySlice\_New** (*PyObject* \*start, *PyObject* \*stop, *PyObject* \*step)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um novo objeto fatia com os valores fornecidos. Os parâmetros *start*, *stop* e *step* são usados como os valores dos atributos do objeto fatia com os mesmos nomes. Qualquer um dos valores pode ser NULL, caso em que None será usado para o atributo correspondente. Retorna NULL se o novo objeto não puder ser alocado.

int **PySlice\_GetIndices** (*PyObject* \*slice, *Py\_ssize\_t* length, *Py\_ssize\_t* \*start, *Py\_ssize\_t* \*stop, *Py\_ssize\_t* \*step)

*Part of the Stable ABI*. Recupera os índices de início, parada e intermediário do objeto fatia *slice*, presumindo uma sequência de comprimento *length*. Trata índices maiores que *length* como erros.

Retorna 0 em caso de sucesso e -1 em caso de erro sem exceção definida (a menos que um dos índices não fosse None e falhou ao ser convertido para um inteiro, neste caso -1 é retornado com uma exceção definida).

Você provavelmente não deseja usar esta função.

Alterado na versão 3.2: O tipo de parâmetro para o parâmetro *slice* era antes de `PySliceObject*`.

`int PySlice_GetIndicesEx(PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step, Py_ssize_t *slicelength)`

*Part of the Stable ABI.* Substituição utilizável para `PySlice_GetIndices()`. Recupera os índices de início, parada e intermediário do objeto fatia *slice* presumindo uma sequência de comprimento *length* e armazena o comprimento da fatia em *slicelength*. Índices fora dos limites são cortados de maneira consistente com o tratamento de fatias normais.

Retorna 0 em caso de sucesso e -1 em caso de erro com exceção definida.

**Nota:** Esta função não é considerada segura para sequências redimensionáveis. Sua invocação deve ser substituída por uma combinação de `PySlice_Unpack()` e `PySlice_AdjustIndices()` sendo

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength) < 0) {
    // return error
}
```

substituído por

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);
```

Alterado na versão 3.2: O tipo de parâmetro para o parâmetro *slice* era antes de `PySliceObject*`.

Alterado na versão 3.6.1: Se `Py_LIMITED_API` não estiver definido ou estiver definido com um valor entre 0x03050400 e 0x03060000 (não incluso) ou 0x03060100 ou mais alto, `PySlice_GetIndicesEx()` é implementado como uma macro usando `PySlice_Unpack()` e `PySlice_AdjustIndices()`. Os argumentos *start*, *stop* e *step* são avaliados mais de uma vez.

Obsoleto desde a versão 3.6.1: Se `Py_LIMITED_API` estiver definido para um valor menor que 0x03050400 ou entre 0x03060000 e 0x03060100 (não incluso), `PySlice_GetIndicesEx()` é uma função descontinuada.

`int PySlice_Unpack(PyObject *slice, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)`

*Part of the Stable ABI since version 3.7.* Extrai os membros de dados de início, parada e intermediário de um objeto fatia como C inteiros. Reduz silenciosamente os valores maiores do que `PY_SSIZE_T_MAX` para `PY_SSIZE_T_MAX`, aumenta silenciosamente os valores de início e parada menores que `PY_SSIZE_T_MIN` para `PY_SSIZE_T_MIN`, e silenciosamente aumenta os valores de intermediário menores que `-PY_SSIZE_T_MAX` para `-PY_SSIZE_T_MAX`.

Retorna -1 em caso de erro, 0 em caso de sucesso.

Novo na versão 3.6.1.

`Py_ssize_t PySlice_AdjustIndices(Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)`

*Part of the Stable ABI since version 3.7.* Ajusta os índices de fatias inicial/final presumindo uma sequência do comprimento especificado. Índices fora dos limites são cortados de maneira consistente com o tratamento de fatias normais.

Retorna o comprimento da fatia. Sempre bem-sucedido. Não chama o código Python.

Novo na versão 3.6.1.

## 8.6.6 Objeto Ellipsis

### *PyObject* \*Py\_Ellipsis

O objeto Python `Ellipsis`. Este objeto não possui métodos. Ele precisa ser tratado como qualquer outro objeto no que diz respeito às contagens de referências. Como *Py\_None*, é um objeto singleton.

## 8.6.7 Objetos MemoryView

Um objeto `memoryview` expõe a *interface de buffer* a nível de C como um objeto Python que pode ser passado como qualquer outro objeto.

### *PyObject* \*PyMemoryView\_FromObject (*PyObject* \*obj)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um objeto `memoryview` a partir de um objeto que fornece a interface do buffer. Se *obj* tiver suporte a exportações de buffer graváveis, o objeto `memoryview` será de leitura/gravação; caso contrário, poderá ser somente leitura ou leitura/gravação, a critério do exportador.

### *PyObject* \*PyMemoryView\_FromMemory (char \*mem, *Py\_ssize\_t* size, int flags)

Retorna valor: Nova referência. *Part of the Stable ABI since version 3.7*. Cria um objeto `memoryview` usando *mem* como o buffer subjacente. *flags* pode ser um dos seguintes `PyBUF_READ` ou `PyBUF_WRITE`.

Novo na versão 3.3.

### *PyObject* \*PyMemoryView\_FromBuffer (*Py\_buffer* \*view)

Retorna valor: Nova referência. Cria um objeto de `memoryview` envolvendo a estrutura de buffer *view* fornecida. Para buffers de bytes simples, *PyMemoryView\_FromMemory()* é a função preferida.

### *PyObject* \*PyMemoryView\_GetContiguous (*PyObject* \*obj, int buffertype, char order)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um objeto `memoryview` para um pedaço *contíguo* de memória (na ordem 'C' ou 'Fortran, representada por *order*) a partir de um objeto que define a interface do buffer. Se a memória for contígua, o objeto `memoryview` apontará para a memória original. Caso contrário, é feita uma cópia e a visualização da memória aponta para um novo objeto bytes.

### int PyMemoryView\_Check (*PyObject* \*obj)

Retorna true se o objeto *obj* for um objeto `memoryview`. Atualmente, não é permitido criar subclasses de `memoryview`. Esta função sempre tem sucesso.

### *Py\_buffer* \*PyMemoryView\_GET\_BUFFER (*PyObject* \*mview)

Retorna um ponteiro para a cópia privada da memória do buffer do exportador. *mview* **deve** ser uma instância de `memoryview`; Se essa macro não verificar seu tipo, faça você mesmo ou corre o risco de travar.

### *PyObject* \*PyMemoryView\_GET\_BASE (*PyObject* \*mview)

Retorna um ponteiro para o objeto de exportação no qual a memória é baseada ou NULL se a memória tiver sido criada por uma das funções *PyMemoryView\_FromMemory()* ou *PyMemoryView\_FromBuffer()*. *mview* **deve** ser uma instância de `memoryview`.

## 8.6.8 Objetos referência fraca

O Python oferece suporte a *referências fracas* como objetos de primeira classe. Existem dois tipos de objetos específicos que implementam diretamente referências fracas. O primeiro é um objeto de referência simples, e o segundo atua como um intermediário ao objeto original tanto quanto ele pode.

### int PyWeakref\_Check (ob)

Retorna verdadeiro se *ob* for um objeto referência ou um objeto intermediário. Esta função sempre tem sucesso.

### int PyWeakref\_CheckRef (ob)

Retorna verdadeiro se *ob* for um objeto referência. Esta função sempre tem sucesso.

int **PyWeakref\_CheckProxy** (ob)

Retorna verdadeiro se *ob* for um objeto intermediário. Esta função sempre tem sucesso.

*PyObject* \***PyWeakref\_NewRef** (*PyObject* \*ob, *PyObject* \*callback)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um objeto de referência fraca para o objeto *ob*. Isso sempre retornará uma nova referência, mas não é garantido para criar um novo objeto; um objeto de referência existente pode ser retornado. O segundo parâmetro, *callback*, pode ser um objeto chamável que recebe notificação quando *ob* for lixo coletado; ele deve aceitar um único parâmetro, que será o objeto de referência fraca propriamente dito. *callback* também pode ser *None* ou *NULL*. Se *ob* não for um objeto fracamente referenciável, ou se *callback* não for um chamável, *None*, ou *NULL*, isso retornará *NULL* e levantará a *TypeError*.

*PyObject* \***PyWeakref\_NewProxy** (*PyObject* \*ob, *PyObject* \*callback)

Retorna valor: Nova referência. *Part of the Stable ABI*. Retorna um objeto de proxy de referência fraca para o objeto *ob*. Isso sempre retornará uma nova referência, mas não é garantido para criar um novo objeto; um objeto de proxy existente pode ser retornado. O segundo parâmetro, *callback*, pode ser um objeto chamável que recebe notificação quando *ob* for lixo coletado; ele deve aceitar um único parâmetro, que será o objeto de referência fraca propriamente dito. *callback* também pode ser *None* ou *NULL*. Se *ob* não for um objeto fracamente referenciável, ou se *callback* não for um chamável, *None*, ou *NULL*, isso retornará *NULL* e levantará a *TypeError*.

*PyObject* \***PyWeakref\_GetObject** (*PyObject* \*ref)

Retorna valor: Referência emprestada. *Part of the Stable ABI*. Retorna o objeto referenciado de uma referência fraca, *ref*. Se o referente não estiver mais em tempo real, retorna *Py\_None*.

---

**Nota:** Esta função retorna uma *referência emprestada* para o objeto referenciado. Isso significa que você deve sempre chamar *Py\_INCREF()* no objeto, exceto quando ele não puder ser destruído antes do último uso da referência emprestada.

---

*PyObject* \***PyWeakref\_GET\_OBJECT** (*PyObject* \*ref)

Retorna valor: Referência emprestada. Semelhante a *PyWeakref\_GetObject()*, mas implementado como uma macro que não verifica erros.

void **PyObject\_ClearWeakRefs** (*PyObject* \*object)

*Part of the Stable ABI*. Esta função é chamada pelo tratador *tp\_dealloc* para limpar referências fracas.

Isso itera pelas referências fracas para *object* e chama retornos de chamada para as referências que possuem um. Ele retorna quando todos os retornos de chamada foram tentados.

## 8.6.9 Capsules

Consulte *using-capsules* para obter mais informações sobre o uso desses objetos.

Novo na versão 3.1.

**type PyCapsule**

Este subtipo de *PyObject* representa um valor opaco, útil para módulos de extensão C que precisam passar um valor opaco (como ponteiro *void\**) através do código Python para outro código C. É frequentemente usado para disponibilizar um ponteiro de função C definido em um módulo para outros módulos, para que o mecanismo de importação regular possa ser usado para acessar APIs C definidas em módulos carregados dinamicamente.

**type PyCapsule\_Destructor**

*Part of the Stable ABI*. O tipo de um retorno de chamada destruidor para uma cápsula. Definido como:

```
typedef void (*PyCapsule_Destructor) (PyObject *);
```

Veja *PyCapsule\_New()* para a semântica dos retornos de chamada *PyCapsule\_Destructor*.

int **PyCapsule\_CheckExact** (*PyObject* \*p)

Retorna true se seu argumento é um *PyCapsule*. Esta função sempre tem sucesso.

*PyObject* \***PyCapsule\_New** (void \*pointer, const char \*name, *PyCapsule\_Destructor* destructor)

Retorna valor: Nova referência. *Part of the Stable ABI*. Cria um *PyCapsule* que encapsula o ponteiro. O argumento *pointer* pode não ser NULL.

Em caso de falha, define uma exceção e retorna NULL.

A string *name* pode ser NULL ou um ponteiro para uma string C válida. Se não for NULL, essa string deverá sobreviver à cápsula. (Embora seja permitido liberá-lo dentro do *destructor*.)

Se o argumento *destructor* não for NULL, ele será chamado com a cápsula como argumento quando for destruído.

Se esta cápsula for armazenada como um atributo de um módulo, o *name* deve ser especificado como `module.name`. Isso permitirá que outros módulos importem a cápsula usando *PyCapsule\_Import()*.

void \***PyCapsule\_GetPointer** (*PyObject* \*capsule, const char \*name)

*Part of the Stable ABI*. Recupera o *pointer* armazenado na cápsula. Em caso de falha, define uma exceção e retorna NULL.

O parâmetro *name* deve ser comparado exatamente com o nome armazenado na cápsula. Se o nome armazenado na cápsula for NULL, o *name* passado também deve ser NULL. Python usa a função C `strcmp()` para comparar nomes de cápsulas.

*PyCapsule\_Destructor* **PyCapsule\_GetDestructor** (*PyObject* \*capsule)

*Part of the Stable ABI*. Retorna o destruidor atual armazenado na cápsula. Em caso de falha, define uma exceção e retorna NULL.

É legal para uma cápsula ter um destruidor NULL. Isso torna um código de retorno NULL um tanto ambíguo; use *PyCapsule\_IsValid()* ou *PyErr\_Occurred()* para desambiguar.

void \***PyCapsule\_GetContext** (*PyObject* \*capsule)

*Part of the Stable ABI*. Retorna o contexto atual armazenado na cápsula. Em caso de falha, define uma exceção e retorna NULL.

É legal para uma cápsula ter um contexto NULL. Isso torna um código de retorno NULL um tanto ambíguo; use *PyCapsule\_IsValid()* ou *PyErr\_Occurred()* para desambiguar.

const char \***PyCapsule\_GetName** (*PyObject* \*capsule)

*Part of the Stable ABI*. Retorna o nome atual armazenado na cápsula. Em caso de falha, define uma exceção e retorna NULL.

É legal para uma cápsula ter um nome NULL. Isso torna um código de retorno NULL um tanto ambíguo; use *PyCapsule\_IsValid()* ou *PyErr\_Occurred()* para desambiguar.

void \***PyCapsule\_Import** (const char \*name, int no\_block)

*Part of the Stable ABI*. Importa um ponteiro para um objeto C de um atributo capsule em um módulo. O parâmetro *name* deve especificar o nome completo do atributo, como em `module.attribute`. O nome armazenado na cápsula deve corresponder exatamente a essa sequência. Se *no\_block* for verdadeiro, importa o módulo sem bloquear (usando *PyImport\_ImportModuleNoBlock()*). Se *no\_block* for falso, importa o módulo convencionalmente (usando *PyImport\_ImportModule()*).

Retorna o ponteiro interno *pointer* da cápsula com sucesso. Em caso de falha, define uma exceção e retorna NULL.

int **PyCapsule\_IsValid** (*PyObject* \*capsule, const char \*name)

*Part of the Stable ABI*. Determina se *capsule* é ou não uma cápsula válida. Uma cápsula válida é diferente de NULL, passa *PyCapsule\_CheckExact()*, possui um ponteiro diferente de NULL armazenado e seu nome interno corresponde ao parâmetro *name*. (Consulte *PyCapsule\_GetPointer()* para obter informações sobre como os nomes das cápsulas são comparados.)



Em outras palavras, se `PyCapsule_IsValid()` retornar um valor verdadeiro, as chamadas para qualquer um dos acessadores (qualquer função que comece com `PyCapsule_Get()`) terão êxito garantido.

Retorna um valor diferente de zero se o objeto for válido e corresponder ao nome passado. Retorna 0 caso contrário. Esta função não falhará.

int **PyCapsule\_SetContext** (*PyObject* \*capsule, void \*context)

*Part of the Stable ABI.* Define o ponteiro de contexto dentro de *capsule* para *context*.

Retorna 0 em caso de sucesso. Retorna diferente de zero e define uma exceção em caso de falha.

int **PyCapsule\_SetDestructor** (*PyObject* \*capsule, *PyCapsule\_Destructor* destructor)

*Part of the Stable ABI.* Define o destrutor dentro de *capsule* para *destructor*.

Retorna 0 em caso de sucesso. Retorna diferente de zero e define uma exceção em caso de falha.

int **PyCapsule\_SetName** (*PyObject* \*capsule, const char \*name)

*Part of the Stable ABI.* Define o nome dentro de *capsule* como *name*. Se não for NULL, o nome deve sobreviver à cápsula. Se o *name* anterior armazenado na cápsula não era NULL, nenhuma tentativa será feita para liberá-lo.

Retorna 0 em caso de sucesso. Retorna diferente de zero e define uma exceção em caso de falha.

int **PyCapsule\_SetPointer** (*PyObject* \*capsule, void \*pointer)

*Part of the Stable ABI.* Define o ponteiro nulo dentro de *capsule* para *pointer*. O ponteiro não pode ser NULL.

Retorna 0 em caso de sucesso. Retorna diferente de zero e define uma exceção em caso de falha.

## 8.6.10 Objetos Geradores

Objetos geradores são o que o Python usa para implementar iteradores geradores. Eles são normalmente criados por iteração sobre uma função que produz valores, em vez de invocar explicitamente `PyGen_New()` ou `PyGen_NewWithQualName()`.

**type PyGenObject**

A estrutura C usada para objetos geradores.

*PyTypeObject* **PyGen\_Type**

O objeto de tipo correspondendo a objetos geradores.

int **PyGen\_Check** (*PyObject* \*ob)

Retorna verdadeiro se *ob* for um objeto gerador; *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyGen\_CheckExact** (*PyObject* \*ob)

Retorna verdadeiro se o tipo do *ob* é *PyGen\_Type*; *ob* não deve ser NULL. Esta função sempre tem sucesso.

*PyObject* \***PyGen\_New** (*PyFrameObject* \*frame)

*Retorna valor:* Nova referência. Cria e retorna um novo objeto gerador com base no objeto *frame*. Uma referência a *quadro* é roubada por esta função. O argumento não deve ser NULL.

*PyObject* \***PyGen\_NewWithQualName** (*PyFrameObject* \*frame, *PyObject* \*name, *PyObject* \*qualname)

*Retorna valor:* Nova referência. Cria e retorna um novo objeto gerador com base no objeto *frame*, com `__name__` e `__qualname__` definidos como *name* e *qualname*. Uma referência a *frame* é roubada por esta função. O argumento *frame* não deve ser NULL.

### 8.6.11 Objetos corrotina

Novo na versão 3.5.

Os objetos corrotina são aquelas funções declaradas com um retorno de palavra-chave `async`.

**type** `PyCoroObject`

A estrutura C utilizada para objetos corrotinas.

*PyTypeObject* `PyCoro_Type`

O tipo de objeto correspondente a objetos corrotina.

`int` `PyCoro_CheckExact` (*PyObject* \**ob*)

Retorna true se o tipo do *ob* é `PyCoro_Type`; *ob* não deve ser NULL. Esta função sempre tem sucesso.

*PyObject* \*`PyCoro_New` (*PyFrameObject* \**frame*, *PyObject* \**name*, *PyObject* \**qualname*)

Retorna valor: Nova referência. Cria e retorna um novo objeto de corrotina com base no objeto *frame*, com `__name__` e `__qualname__` definido como *name* e *qualname*. Uma referência a *frame* é roubada por esta função. O argumento *frame* não deve ser NULL.

### 8.6.12 Objetos de variáveis de contexto

---

**Nota:** Alterado na versão 3.7.1: No Python 3.7.1, as assinaturas de todas as APIs C de variáveis de contexto foram alteradas para usar ponteiros *PyObject* em vez de *PyContext*, *PyContextVar* e *PyContextToken*. Por exemplo:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

Veja [bpo-34762](#) para mais detalhes.

---

Novo na versão 3.7.

Esta seção detalha a API C pública para o módulo `contextvars`.

**type** `PyContext`

A estrutura C usada para representar um objeto `contextvars.Context`.

**type** `PyContextVar`

A estrutura C usada para representar um objeto `contextvars.ContextVar`.

**type** `PyContextToken`

A estrutura C usada para representar um objeto `contextvars.Token`.

*PyTypeObject* `PyContext_Type`

O objeto de tipo que representa o tipo de *contexto*.

*PyTypeObject* `PyContextVar_Type`

O objeto de tipo que representa o tipo de *variável de contexto*.

*PyTypeObject* `PyContextToken_Type`

O objeto de tipo que representa o tipo de *token de variável de contexto*.

Macros de verificação de tipo:



`int PyContext_CheckExact (PyObject *o)`

Retorna verdadeiro se *o* for do tipo *PyContext\_Type*. *o* não deve ser NULL. Esta função sempre tem sucesso.

`int PyContextVar_CheckExact (PyObject *o)`

Retorna verdadeiro se *o* for do tipo *PyContextVar\_Type*. *o* não deve ser NULL. Esta função sempre tem sucesso.

`int PyContextToken_CheckExact (PyObject *o)`

Retorna verdadeiro se *o* for do tipo *PyContextToken\_Type*. *o* não deve ser NULL. Esta função sempre tem sucesso.

Funções de gerenciamento de objetos de contexto:

*PyObject* \*`PyContext_New` (void)

Retorna valor: Nova referência. Cria um novo objeto de contexto vazio. Retorna NULL se um erro ocorreu.

*PyObject* \*`PyContext_Copy` (PyObject \*ctx)

Retorna valor: Nova referência. Cria uma cópia rasa do objeto de contexto *ctx* passado. Retorna NULL se um erro ocorreu.

*PyObject* \*`PyContext_CopyCurrent` (void)

Retorna valor: Nova referência. Cria uma cópia rasa do contexto da thread atual. Retorna NULL se um erro ocorreu.

`int PyContext_Enter` (PyObject \*ctx)

Define *ctx* como o contexto atual para o thread atual. Retorna 0 em caso de sucesso e -1 em caso de erro.

`int PyContext_Exit` (PyObject \*ctx)

Desativa o contexto *ctx* e restaura o contexto anterior como o contexto atual para a thread atual. Retorna 0 em caso de sucesso e -1 em caso de erro.

Funções de variável de contexto:

*PyObject* \*`PyContextVar_New` (const char \*name, PyObject \*def)

Retorna valor: Nova referência. Cria um novo objeto ContextVar. O parâmetro *name* é usado para fins de introspecção e depuração. O parâmetro *def* especifica um valor padrão para a variável de contexto, ou NULL para nenhum padrão. Se ocorrer um erro, esta função retorna NULL.

`int PyContextVar_Get` (PyObject \*var, PyObject \*default\_value, PyObject \*\*value)

Obtém o valor de uma variável de contexto. Retorna -1 se um erro ocorreu durante a pesquisa, e 0 se nenhum erro ocorreu, se um valor foi encontrado ou não.

Se a variável de contexto foi encontrada, *value* será um ponteiro para ela. Se a variável de contexto não foi encontrada, *value* apontará para:

- *default\_value*, se não for NULL;
- o valor padrão de *var*, se não for NULL;
- NULL

Exceto para NULL, a função retorna uma nova referência.

*PyObject* \*`PyContextVar_Set` (PyObject \*var, PyObject \*value)

Retorna valor: Nova referência. Define o valor de *var* como *value* no contexto atual. Retorna um novo objeto token para esta alteração, ou NULL se um erro ocorreu.

`int PyContextVar_Reset` (PyObject \*var, PyObject \*token)

Redefine o estado da variável de contexto *var* para o estado que anterior a *PyContextVar\_Set* () que retornou o *token* foi chamado. Esta função retorna 0 em caso de sucesso e -1 em caso de erro.

### 8.6.13 Objetos DateTime

Vários objetos de data e hora são fornecidos pelo módulo `datetime`. Antes de usar qualquer uma dessas funções, o arquivo de cabeçalho `datetime.h` deve ser incluído na sua fonte (observe que isso não é incluído por `Python.h`) e a macro `PyDateTime_IMPORT` deve ser chamada, geralmente como parte da função de inicialização do módulo. A macro coloca um ponteiro para uma estrutura C em uma variável estática, `PyDateTimeAPI`, usada pelas macros a seguir.

Macro para acesso ao singleton UTC:

*PyObject* \***PyDateTime\_TimeZone\_UTC**

Retorna um singleton do fuso horário representando o UTC, o mesmo objeto que `datetime.timezone.utc`.

Novo na versão 3.7.

Macros de verificação de tipo:

int **PyDate\_Check** (*PyObject* \**ob*)

Retorna true se *ob* for do tipo `PyDateTime_DateType` ou um subtipo de `PyDateTime_DateType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyDate\_CheckExact** (*PyObject* \**ob*)

Retorna verdadeiro se *ob* for do tipo `PyDateTime_DateType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyDateTime\_Check** (*PyObject* \**ob*)

Retorna true se *ob* é do tipo `PyDateTime_DateTimeType` ou um subtipo de `PyDateTime_DateTimeType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyDateTime\_CheckExact** (*PyObject* \**ob*)

Retorna verdadeiro se *ob* for do tipo `PyDateTime_DateTimeType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyTime\_Check** (*PyObject* \**ob*)

Retorna true se *ob* é do tipo `PyDateTime_TimeType` ou um subtipo de `PyDateTime_TimeType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyTime\_CheckExact** (*PyObject* \**ob*)

Retorna verdadeiro se *ob* for do tipo `PyDateTime_TimeType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyDelta\_Check** (*PyObject* \**ob*)

Retorna true se *ob* é do tipo `PyDateTime_DeltaType` ou um subtipo de `PyDateTime_DeltaType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyDelta\_CheckExact** (*PyObject* \**ob*)

Retorna verdadeiro se *ob* for do tipo `PyDateTime_DeltaType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyTZInfo\_Check** (*PyObject* \**ob*)

Retorna true se *ob* é do tipo `PyDateTime_TZInfoType` ou um subtipo de `PyDateTime_TZInfoType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

int **PyTZInfo\_CheckExact** (*PyObject* \**ob*)

Retorna verdadeiro se *ob* for do tipo `PyDateTime_TZInfoType`. *ob* não deve ser NULL. Esta função sempre tem sucesso.

Macros para criar objetos:

*PyObject* \***PyDate\_FromDate** (int *year*, int *month*, int *day*)

Retorna valor: Nova referência. Retorna um objeto `datetime.date` com o ano, mês e dia especificados.

*PyObject* \***PyDateTime\_FromDateAndTime** (int year, int month, int day, int hour, int minute, int second, int usecond)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.datetime` com o ano, mês, dia, hora, minuto, segundo, microssegundo especificados.

*PyObject* \***PyDateTime\_FromDateAndTimeAndFold** (int year, int month, int day, int hour, int minute, int second, int usecond, int fold)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.datetime` com o ano, mês, dia, hora, minuto, segundo, microssegundo e a dobra especificados.

Novo na versão 3.6.

*PyObject* \***PyTime\_FromTime** (int hour, int minute, int second, int usecond)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.time` com a hora, minuto, segundo e microssegundo especificados.

*PyObject* \***PyTime\_FromTimeAndFold** (int hour, int minute, int second, int usecond, int fold)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.time` com a hora, minuto, segundo, microssegundo e a dobra especificados.

Novo na versão 3.6.

*PyObject* \***PyDelta\_FromDSU** (int days, int seconds, int useconds)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.timedelta` representando o número especificado de dias, segundos e microssegundos. A normalização é realizada para que o número resultante de microssegundos e segundos esteja nos intervalos documentados para objetos de `datetime.timedelta`.

*PyObject* \***PyTimeZone\_FromOffset** (PyDateTime\_DeltaType \*offset)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.timezone` com um deslocamento fixo sem nome representado pelo argumento *offset*.

Novo na versão 3.7.

*PyObject* \***PyTimeZone\_FromOffsetAndName** (PyDateTime\_DeltaType \*offset, PyUnicode \*name)

*Retorna valor:* Nova referência. Retorna um objeto `datetime.timezone` com um deslocamento fixo representado pelo argumento *offset* e com *tzname name*.

Novo na versão 3.7.

Macros para extrair campos de objetos de data. O argumento deve ser uma instância de `PyDateTime_Date`, incluindo subclasses (como `PyDateTime_DateTime`). O argumento não deve ser NULL e o tipo não está marcado:

int **PyDateTime\_GET\_YEAR** (PyDateTime\_Date \*o)

Retorna o ano, como um inteiro positivo.

int **PyDateTime\_GET\_MONTH** (PyDateTime\_Date \*o)

Retorna o mês, como um inteiro de 1 a 12.

int **PyDateTime\_GET\_DAY** (PyDateTime\_Date \*o)

Retorna o dia, como um inteiro de 1 a 31.

Macros para extrair campos de objetos de data e hora. O argumento deve ser uma instância de `PyDateTime_DateTime`, incluindo subclasses. O argumento não deve ser NULL e o tipo não é verificado:

int **PyDateTime\_DATE\_GET\_HOUR** (PyDateTime\_DateTime \*o)

Retorna a hora, como um inteiro de 0 a 23.

int **PyDateTime\_DATE\_GET\_MINUTE** (PyDateTime\_DateTime \*o)

Retorna o minuto, como um inteiro de 0 a 59.

int **PyDateTime\_DATE\_GET\_SECOND** (PyDateTime\_DateTime \*o)

Retorna o segundo, como um inteiro de 0 a 59.

int **PyDateTime\_DATE\_GET\_MICROSECOND** (PyDateTime\_DateTime \*o)

Retorna o microssegundo, como um inteiro de 0 a 999999.

int **PyDateTime\_DATE\_GET\_FOLD** (PyDateTime\_DateTime \*o)

Retorna a dobra, como um inteiro de 0 a 1.

Novo na versão 3.6.

*PyObject* \***PyDateTime\_DATE\_GET\_TZINFO** (PyDateTime\_DateTime \*o)

Retorna o tzinfo (que pode ser None).

Novo na versão 3.10.

Macros para extrair campos de objetos de tempo. O argumento deve ser uma instância de `PyDateTime_Time`, incluindo subclasses. O argumento não deve ser NULL e o tipo não é verificado:

int **PyDateTime\_TIME\_GET\_HOUR** (PyDateTime\_Time \*o)

Retorna a hora, como um inteiro de 0 a 23.

int **PyDateTime\_TIME\_GET\_MINUTE** (PyDateTime\_Time \*o)

Retorna o minuto, como um inteiro de 0 a 59.

int **PyDateTime\_TIME\_GET\_SECOND** (PyDateTime\_Time \*o)

Retorna o segundo, como um inteiro de 0 a 59.

int **PyDateTime\_TIME\_GET\_MICROSECOND** (PyDateTime\_Time \*o)

Retorna o microssegundo, como um inteiro de 0 a 999999.

int **PyDateTime\_TIME\_GET\_FOLD** (PyDateTime\_Time \*o)

Retorna a dobra, como um inteiro de 0 a 1.

Novo na versão 3.6.

*PyObject* \***PyDateTime\_TIME\_GET\_TZINFO** (PyDateTime\_Time \*o)

Retorna o tzinfo (que pode ser None).

Novo na versão 3.10.

Macros para extrair campos de objetos time delta. O argumento deve ser uma instância de `PyDateTime_Delta`, incluindo subclasses. O argumento não deve ser NULL, e o tipo não é checado:

int **PyDateTime\_DELTA\_GET\_DAYS** (PyDateTime\_Delta \*o)

Retorna o número de dias, como um inteiro de -999999999 a 999999999.

Novo na versão 3.3.

int **PyDateTime\_DELTA\_GET\_SECONDS** (PyDateTime\_Delta \*o)

Retorna o número de segundos, como um inteiro de 0 a 86399.

Novo na versão 3.3.

int **PyDateTime\_DELTA\_GET\_MICROSECONDS** (PyDateTime\_Delta \*o)

Retorna o número de microssegundos, como um inteiro de 0 a 999999.

Novo na versão 3.3.

Macros para a conveniência de módulos implementando a API de DB:

*PyObject* \***PyDateTime\_FromTimestamp** (*PyObject* \*args)

*Retorna valor:* Nova referência. Cria e retorna um novo objeto `datetime.datetime`, com uma tupla de argumentos adequada para passar para `datetime.datetime.fromtimestamp()`.

*PyObject* \***PyDate\_FromTimestamp** (*PyObject* \*args)

*Retorna valor:* Nova referência. Cria e retorna um novo objeto `datetime.date`, com uma tupla de argumentos adequada para passar para `datetime.date.fromtimestamp()`.

### 8.6.14 Objetos de indicação de tipos

São fornecidos vários tipos embutidos para sugestão de tipo. Atualmente, dois tipos existem – GenericAlias e Union. Apenas GenericAlias está exposto ao C.

*PyObject\** **Py\_GenericAlias** (*PyObject\** *origin*, *PyObject\** *args*)

*Part of the Stable ABI since version 3.9.* Cria um objeto GenericAlias. Equivalente a chamar a classe Python `types.GenericAlias`. Os argumentos *origin* e *args* definem os atributos `__origin__` e `__args__` de GenericAlias respectivamente. *origin* deve ser um *PyTypeObject\**, e *args* pode ser um *PyTupleObject\** ou qualquer *PyObject\**. Se *args* passado não for uma tupla, uma tupla de 1 elemento é construída automaticamente e `__args__` é definido como `(args,)`. A verificação mínima é feita para os argumentos, então a função terá sucesso mesmo se *origin* não for um tipo. O atributo `__parameters__` de GenericAlias é construído lentamente a partir de `__args__`. Em caso de falha, uma exceção é levantada e NULL é retornado.

Aqui está um exemplo de como tornar um tipo de extensão genérico:

```
...
static PyMethodDef my_obj_methods[] = {
    // Other methods.
    ...
    {"__class_getitem__", (PyCFunction)Py_GenericAlias, METH_O|METH_CLASS, "See_
↪ PEP 585"}
    ...
}
```

#### Ver também:

O método de modelo de dados `__class_getitem__()`.

Novo na versão 3.9.

*PyTypeObject* **Py\_GenericAliasType**

*Part of the Stable ABI since version 3.9.* O tipo C do objeto retornado por *Py\_GenericAlias()*. Equivalente a `types.GenericAlias` no Python.

Novo na versão 3.9.



---

## Inicialização, finalização e threads

---

Consulte também *Configuração de Inicialização do Python*.

### 9.1 Antes da inicialização do Python

Em uma aplicação que incorpora Python, a função `Py_Initialize()` deve ser chamada antes de usar qualquer outra função da API Python/C; com exceção de algumas funções e as *variáveis globais de configuração*.

As seguintes funções podem ser seguramente chamadas antes da inicialização do Python.

- Funções de configuração:

- `PyImport_AppendInittab()`
- `PyImport_ExtendInittab()`
- `PyInitFrozenExtensions()`
- `PyMem_SetAllocator()`
- `PyMem_SetupDebugHooks()`
- `PyObject_SetArenaAllocator()`
- `Py_SetPath()`
- `Py_SetProgramName()`
- `Py_SetPythonHome()`
- `Py_SetStandardStreamEncoding()`
- `PySys_AddWarnOption()`
- `PySys_AddXOption()`
- `PySys_ResetWarnOptions()`

- Funções informativas:

- `Py_IsInitialized()`
- `PyMem_GetAllocator()`
- `PyObject_GetArenaAllocator()`
- `Py_GetBuildInfo()`
- `Py_GetCompiler()`
- `Py_GetCopyright()`
- `Py_GetPlatform()`
- `Py_GetVersion()`

- Utilitários:

- `Py_DecodeLocale()`

- Alocadores de memória:

- `PyMem_RawMalloc()`
  - `PyMem_RawRealloc()`
  - `PyMem_RawCalloc()`
  - `PyMem_RawFree()`

---

**Nota:** As seguintes funções **não devem ser chamadas** antes `Py_Initialize()`: `Py_EncodeLocale()`, `Py_GetPath()`, `Py_GetPrefix()`, `Py_GetExecPrefix()`, `Py_GetProgramFullPath()`, `Py_GetPythonHome()`, `Py_GetProgramName()` e `PyEval_InitThreads()`.

---

## 9.2 Variáveis de configuração global

Python tem variáveis para a configuração global a fim de controlar diferentes características e opções. Por padrão, estes sinalizadores são controlados por opções de linha de comando.

Quando um sinalizador é definido por uma opção, o valor do sinalizador é o número de vezes que a opção foi definida. Por exemplo, “-b” define `Py_BytesWarningFlag` para 1 e “-bb” define `Py_BytesWarningFlag` para 2.

### int `Py_BytesWarningFlag`

Emite um aviso ao comparar `bytes` ou `bytearray` com `str` ou `bytes` com `int`. Emite um erro se for maior ou igual a 2.

Definida pela opção `-b`.

### int `Py_DebugFlag`

Ativa a saída de depuração do analisador sintático (somente para especialistas, dependendo das opções de compilação).

Definida pela opção `-d` e a variável de ambiente `PYTHONDEBUG`.

### int `Py_DontWriteBytecodeFlag`

Se definida como diferente de zero, o Python não tentará escrever arquivos `.pyc` na importação de módulos fonte.

Definida pela opção `-B` e pela variável de ambiente `PYTHONDONTWRITEBYTECODE`.



**int `Py_FrozenFlag`**

Suprime mensagens de erro ao calcular o caminho de pesquisa do módulo em `Py_GetPath()`.

Sinalizador privado usado pelos programas `_freeze_importlib` e `frozenmain`.

**int `Py_HashRandomizationFlag`**

Definida como 1 se a variável de ambiente `PYTHONHASHSEED` estiver definida como uma string não vazia.

Se o sinalizador for diferente de zero, lê a variável de ambiente `PYTHONHASHSEED` para inicializar a semente de hash secreta.

**int `Py_IgnoreEnvironmentFlag`**

Ignora todas as variáveis de ambiente `PYTHON*`, por exemplo `PYTHONPATH` e `PYTHONHOME`, que pode ser definido.

Definida pelas opções `-E` e `-I`.

**int `Py_InspectFlag`**

Quando um script é passado como primeiro argumento ou a opção `-c` é usada, entre no modo interativo após executar o script ou o comando, mesmo quando `sys.stdin` não parece ser um terminal.

Definida pela opção `-i` e pela variável de ambiente `PYTHONINSPECT`.

**int `Py_InteractiveFlag`**

Definida pela opção `-i`.

**int `Py_IsolatedFlag`**

Executa o Python no modo isolado. No modo isolado, `sys.path` não contém nem o diretório do script nem o diretório de pacotes de sites do usuário.

Definida pela opção `-I`.

Novo na versão 3.4.

**int `Py_LegacyWindowsFSEncodingFlag`**

Se o sinalizador for diferente de zero, use a codificação `mbcs` com o tratador de erros `replace`, em vez da codificação `UTF-8` com o tratador de erros `surrogatepass`, para a codificação do sistema de arquivos e *tratador de erros e codificação do sistema de arquivos*.

Definida como 1 se a variável de ambiente `PYTHONLEGACYWINDOWSFSENCODING` estiver definida como uma string não vazia.

Veja [PEP 529](#) para mais detalhes.

Disponibilidade: Windows.

**int `Py_LegacyWindowsStdioFlag`**

Se o sinalizador for diferente de zero, usa `io.FileIO` em vez de `WindowsConsoleIO` para fluxos padrão `sys`.

Definida como 1 se a variável de ambiente `PYTHONLEGACYWINDOWSSTDIO` estiver definida como uma string não vazia.

Veja a [PEP 528](#) para mais detalhes.

Disponibilidade: Windows.

**int `Py_NoSiteFlag`**

Desabilita a importação do módulo `site` e as manipulações dependentes do site de `sys.path` que isso acarreta. Também desabilita essas manipulações se `site` for explicitamente importado mais tarde (chame `site.main()` se você quiser que eles sejam acionados).

Definida pela opção `-S`.

int **Py\_NoUserSiteDirectory**

Não adiciona o diretório `site-packages` de usuário a `sys.path`.

Definida pelas opções `-s` e `-I`, e pela variável de ambiente `PYTHONNOUSERSITE`.

int **Py\_OptimizeFlag**

Definida pela opção `-O` e pela variável de ambiente `PYTHONOPTIMIZE`.

int **Py\_QuietFlag**

Não exibe as mensagens de direitos autorais e de versão nem mesmo no modo interativo.

Definida pela opção `-q`.

Novo na versão 3.2.

int **Py\_UnbufferedStdioFlag**

Força os fluxos `stdout` e `stderr` a não serem armazenados em `buffer`.

Definida pela opção `-u` e pela variável de ambiente `PYTHONUNBUFFERED`.

int **Py\_VerboseFlag**

Exibe uma mensagem cada vez que um módulo é inicializado, mostrando o local (nome do arquivo ou módulo embutido) de onde ele é carregado. Se maior ou igual a 2, exibe uma mensagem para cada arquivo que é verificado durante a busca por um módulo. Também fornece informações sobre a limpeza do módulo na saída.

Definida pela opção `-v` e a variável de ambiente `PYTHONVERBOSE`.

## 9.3 Inicializando e encerrando o interpretador

void **Py\_Initialize()**

*Part of the Stable ABI.* Inicializa o interpretador Python. Em uma aplicação que incorpora o Python, isto deve ser chamado antes do uso de qualquer outra função do Python/C API; veja *Antes da Inicialização do Python* para algumas exceções.

This initializes the table of loaded modules (`sys.modules`), and creates the fundamental modules `builtins`, `__main__` and `sys`. It also initializes the module search path (`sys.path`). It does not set `sys.argv`; use `PySys_SetArgvEx()` for that. This is a no-op when called for a second time (without calling `Py_FinalizeEx()` first). There is no return value; it is a fatal error if the initialization fails.

---

**Nota:** No Windows, altera o modo do console de `O_TEXT` para `O_BINARY`, o que também afetará usos não Python do console usando o Runtime C.

---

void **Py\_InitializeEx**(int *initsigs*)

*Part of the Stable ABI.* This function works like `Py_Initialize()` if *initsigs* is 1. If *initsigs* is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

int **Py\_IsInitialized()**

*Part of the Stable ABI.* Retorna true (diferente de zero) quando o interpretador Python foi inicializado, false (zero) se não. Após `Py_FinalizeEx()` ser chamado, isso retorna false até que `Py_Initialize()` seja chamado novamente.

int **Py\_FinalizeEx()**

*Part of the Stable ABI since version 3.6.* Undo all initializations made by `Py_Initialize()` and subsequent use of Python/C API functions, and destroy all sub-interpreters (see `Py_NewInterpreter()` below) that were created and not yet destroyed since the last call to `Py_Initialize()`. Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling `Py_Initialize()`

again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

Esta função é fornecida por vários motivos. Uma aplicação de incorporação pode querer reiniciar o Python sem precisar reiniciar a própria aplicação. Uma aplicação que carregou o interpretador Python de uma biblioteca carregável dinamicamente (ou DLL) pode querer liberar toda a memória alocada pelo Python antes de descarregar a DLL. Durante uma busca por vazamentos de memória em uma aplicação, um desenvolvedor pode querer liberar toda a memória alocada pelo Python antes de sair da aplicação.

**Bugs and caveats:** The destruction of modules and objects in modules is done in random order; this may cause destructors (`__del__()` methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls `Py_Initialize()` and `Py_FinalizeEx()` more than once.

Levanta um evento de auditoria `cpython._PySys_ClearAuditHooks` sem argumentos.

Novo na versão 3.6.

void **Py\_Finalize()**

*Part of the Stable ABI.* Esta é uma versão compatível com retrocompatibilidade de `Py_FinalizeEx()` que desconsidera o valor de retorno.

## 9.4 Process-wide parameters

int **Py\_SetStandardStreamEncoding**(const char \*encoding, const char \*errors)

This function should be called before `Py_Initialize()`, if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in `str.encode()`.

It overrides `PYTHONIOENCODING` values, and allows embedding code to control IO encoding when the environment variable does not work.

*encoding* and/or *errors* may be NULL to use `PYTHONIOENCODING` and/or default values (depending on other settings).

Note that `sys.stderr` always uses the “backslashreplace” error handler, regardless of this (or any other) setting.

If `Py_FinalizeEx()` is called, this function will need to be called again in order to affect subsequent calls to `Py_Initialize()`.

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized).

Novo na versão 3.4.

void **Py\_SetProgramName**(const wchar\_t \*name)

*Part of the Stable ABI.* Esta função deve ser chamada antes de `Py_Initialize()` ser chamada pela primeira vez, caso seja solicitada. Ela diz ao interpretador o valor do argumento `argv[0]` para a função `main()` do programa (convertido em caracteres amplos). Isto é utilizado por `Py_GetPath()` e algumas outras funções abaixo para encontrar as bibliotecas de tempo de execução relativas ao executável do interpretador. O valor padrão é `'python'`. O argumento deve apontar para um caractere string amplo terminado em zero no armazenamento estático, cujo conteúdo não mudará durante a execução do programa. Nenhum código no interpretador Python mudará o conteúdo deste armazenamento.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

wchar\_t \*Py\_GetProgramName ()

*Part of the [Stable ABI](#).* Return the program name set with `Py_SetProgramName()`, or the default. The returned string points into static storage; the caller should not modify its value.

This function should not be called before `Py_Initialize()`, otherwise it returns NULL.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

wchar\_t \*Py\_GetPrefix ()

*Part of the [Stable ABI](#).* Return the *prefix* for installed platform-independent files. This is derived through a number of complicated rules from the program name set with `Py_SetProgramName()` and some environment variables; for example, if the program name is `"/usr/local/bin/python"`, the prefix is `"/usr/local"`. The returned string points into static storage; the caller should not modify its value. This corresponds to the **prefix** variable in the top-level Makefile and the `--prefix` argument to the **configure** script at build time. The value is available to Python code as `sys.prefix`. It is only useful on Unix. See also the next function.

This function should not be called before `Py_Initialize()`, otherwise it returns NULL.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

wchar\_t \*Py\_GetExecPrefix ()

*Part of the [Stable ABI](#).* Return the *exec-prefix* for installed platform-dependent files. This is derived through a number of complicated rules from the program name set with `Py_SetProgramName()` and some environment variables; for example, if the program name is `"/usr/local/bin/python"`, the exec-prefix is `"/usr/local"`. The returned string points into static storage; the caller should not modify its value. This corresponds to the **exec\_prefix** variable in the top-level Makefile and the `--exec-prefix` argument to the **configure** script at build time. The value is available to Python code as `sys.exec_prefix`. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the `/usr/local/plat` subtree while platform independent may be installed in `/usr/local`.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share `/usr/local` between platforms while having `/usr/local/plat` be a different filesystem for each platform.

This function should not be called before `Py_Initialize()`, otherwise it returns NULL.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

wchar\_t \*Py\_GetProgramFullPath ()

*Part of the [Stable ABI](#).* Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by `Py_SetProgramName()` above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.executable`.

This function should not be called before `Py_Initialize()`, otherwise it returns NULL.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

wchar\_t \*Py\_GetPath ()

*Part of the [Stable ABI](#).* Return the default module search path; this is computed from the program name (set by `Py_SetProgramName()` above) and some environment variables. The returned string consists of a series of

directory names separated by a platform dependent delimiter character. The delimiter character is ':' on Unix and macOS, ';' on Windows. The returned string points into static storage; the caller should not modify its value. The list `sys.path` is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

This function should not be called before `Py_Initialize()`, otherwise it returns NULL.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

void **Py\_SetPath**(const wchar\_t\*)

*Part of the Stable ABI since version 3.7.* Set the default module search path. If this function is called before `Py_Initialize()`, then `Py_GetPath()` won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is ':' on Unix and macOS, ';' on Windows.

This also causes `sys.executable` to be set to the program full path (see `Py_GetProgramFullPath()`) and for `sys.prefix` and `sys.exec_prefix` to be empty. It is up to the caller to modify these if required after calling `Py_Initialize()`.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

O argumento caminho é copiado internamente, então o chamador pode liberá-lo depois da finalização da chamada.

Alterado na versão 3.8: O caminho completo do programa agora é utilizado para `sys.executable`, em vez do nome do programa.

const char\* **Py\_GetVersion**()

*Part of the Stable ABI.* Retorna a versão deste interpretador Python. Esta é uma string que se parece com

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.version`.

const char\* **Py\_GetPlatform**()

*Part of the Stable ABI.* Return the platform identifier for the current platform. On Unix, this is formed from the “official” name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On macOS, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.platform`.

const char\* **Py\_GetCopyright**()

*Part of the Stable ABI.* Retorna a string oficial de direitos autorais para a versão atual do Python, por exemplo

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.copyright`.

const char\* **Py\_GetCompiler**()

*Part of the Stable ABI.* Retorna uma indicação do compilador usado para construir a atual versão do Python, em colchetes, por exemplo:

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

**const** char \*Py\_GetBuildInfo ()

*Part of the Stable ABI.* Retorna informação sobre o número de sequência e a data e hora da construção da instância atual do interpretador Python, por exemplo

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

void **PySys\_SetArgvEx** (int argc, wchar\_t \*\*argv, int updatepath)

*Part of the Stable ABI.* Set `sys.argv` based on `argc` and `argv`. These parameters are similar to those passed to the program's `main()` function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in `argv` can be an empty string. If this function fails to initialize `sys.argv`, a fatal condition is signalled using `Py_FatalError()`.

Se `updatepath` é zero, isto é tudo o que a função faz. Se `updatepath` não é zero, a função também modifica `sys.path` de acordo com o seguinte algoritmo:

- If the name of an existing script is passed in `argv[0]`, the absolute path of the directory where the script is located is prepended to `sys.path`.
- Otherwise (that is, if `argc` is 0 or `argv[0]` doesn't point to an existing file name), an empty string is prepended to `sys.path`, which is the same as prepending the current working directory (" . ").

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_*` string.

---

**Nota:** It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as `updatepath`, and update `sys.path` themselves if desired. See [CVE-2008-5983](#).

On versions before 3.1.3, you can achieve the same effect by manually popping the first `sys.path` element after having called `PySys_SetArgv()`, for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

---

Novo na versão 3.1.3.

void **PySys\_SetArgv** (int argc, wchar\_t \*\*argv)

*Part of the Stable ABI.* This function works like `PySys_SetArgvEx()` with `updatepath` set to 1 unless the **python** interpreter was started with the `-I`.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_*` string.

Alterado na versão 3.4: The `updatepath` value depends on `-I`.

void **Py\_SetPythonHome** (const wchar\_t \*home)

*Part of the Stable ABI.* Set the default “home” directory, that is, the location of the standard Python libraries. See `PYTHONHOME` for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_*` string.

wchar\_t \***Py\_GetPythonHome** ()

*Part of the Stable ABI.* Return the default “home”, that is, the value set by a previous call to `Py_SetPythonHome()`, or the value of the `PYTHONHOME` environment variable if it is set.

This function should not be called before `Py_Initialize()`, otherwise it returns `NULL`.

Alterado na versão 3.10: It now returns NULL if called before `Py_Initialize()`.

## 9.5 Estado de thread e trava global do interpretador

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Portanto, existe a regra de que somente a thread que adquiriu a *GIL* pode operar em objetos Python ou chamar funções da API C/Python. Para emular a simultaneidade de execução, o interpretador tenta alternar threads regularmente (consulte `sys.setswitchinterval()`). A trava também é liberada em operações de E/S potencialmente bloqueantes, como ler ou escrever um arquivo, para que outras threads Python possam ser executadas enquanto isso.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called *PyThreadState*. There's also one global variable pointing to the current *PyThreadState*: it can be retrieved using `PyThreadState_Get()`.

### 9.5.1 Releasing the GIL from extension code

A maioria dos códigos de extensão que manipulam a *GIL* tem a seguinte estrutura:

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

A macro `Py_BEGIN_ALLOW_THREADS` abre um novo bloco e declara uma variável local oculta; a macro `Py_END_ALLOW_THREADS` fecha o bloco.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

**Nota:** Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic



functions operating over memory buffers. For example, the standard `zlib` and `hashlib` modules release the GIL when compressing or hashing data.

---

### 9.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the `threading` module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The `PyGILState_Ensure()` and `PyGILState_Release()` functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the `PyGILState_*` functions assume there is only one global interpreter (created automatically by `Py_Initialize()`). Python supports the creation of additional interpreters (using `Py_NewInterpreter()`), but mixing multiple interpreters and the `PyGILState_*` API is unsupported.

### 9.5.3 Cuidados com o uso de `fork()`

Another important thing to note about threads is their behaviour in the face of the C `fork()` call. On most systems with `fork()`, after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the “current” thread remains means any locks held by other threads will never be released. Python solves this for `os.fork()` by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as `pthread_atfork()` would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling `fork()` directly rather than through `os.fork()` (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork. `PyOS_AfterFork_Child()` tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which `os.fork()` does. This means finalizing all other `PyThreadState` objects belonging to the current interpreter and all other `PyInterpreterState` objects. Due to this and the special nature of the “main” interpreter, `fork()` should only be called in that interpreter's “main” thread, where the CPython global runtime was originally initialized. The only exception is if `exec()` will be called immediately after.



## 9.5.4 High-level API

Estes são os tipos e as funções mais comumente usados na escrita de um código de extensão em C, ou ao incorporar o interpretador Python:

### type `PyInterpreterState`

*Part of the [Limited API](#) (as an opaque struct).* This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

### type `PyThreadState`

*Part of the [Limited API](#) (as an opaque struct).* This data structure represents the state of a single thread. The only public data member is `interp` (`PyInterpreterState*`), which points to this thread's interpreter state.

### void `PyEval_InitThreads()`

*Part of the [Stable ABI](#).* Função descontinuada que não faz nada.

In Python 3.6 and older, this function created the GIL if it didn't exist.

Alterado na versão 3.9: The function now does nothing.

Alterado na versão 3.7: Esta função agora é chamada por `Py_Initialize()`, então não há mais necessidade de você chamá-la.

Alterado na versão 3.2: Esta função não pode mais ser chamada antes de `Py_Initialize()`.

Deprecated since version 3.9, will be removed in version 3.11.

### int `PyEval_ThreadsInitialized()`

*Part of the [Stable ABI](#).* Returns a non-zero value if `PyEval_InitThreads()` has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

Alterado na versão 3.7: The [GIL](#) is now initialized by `Py_Initialize()`.

Deprecated since version 3.9, will be removed in version 3.11.

### `PyThreadState*` `PyEval_SaveThread()`

*Part of the [Stable ABI](#).* Release the global interpreter lock (if it has been created) and reset the thread state to NULL, returning the previous thread state (which is not NULL). If the lock has been created, the current thread must have acquired it.

### void `PyEval_RestoreThread(PyThreadState *tstate)`

*Part of the [Stable ABI](#).* Acquire the global interpreter lock (if it has been created) and set the thread state to `tstate`, which must not be NULL. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

---

**Nota:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use `_Py_IsFinalizing()` or `sys.is_finalizing()` to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

### `PyThreadState*` `PyThreadState_Get()`

*Part of the [Stable ABI](#).* Return the current thread state. The global interpreter lock must be held. When the current thread state is NULL, this issues a fatal error (so that the caller needn't check for NULL).

*PyThreadState* \***PyThreadState\_Swap** (*PyThreadState* \**tstate*)

*Part of the Stable ABI.* Swap the current thread state with the thread state given by the argument *tstate*, which may be NULL. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

**PyGILState\_STATE** **PyGILState\_Ensure** ()

*Part of the Stable ABI.* Certifique-se de que a thread atual esteja pronta para chamar a API Python C, independentemente do estado atual do Python ou da trava global do interpretador (GIL). Isso pode ser chamado quantas vezes desejar por uma thread, desde que cada chamada corresponda a uma chamada para *PyGILState\_Release* (). Em geral, outras APIs relacionadas a threads podem ser usadas entre chamadas *PyGILState\_Ensure* () e *PyGILState\_Release* () desde que o estado da thread seja restaurado ao seu estado anterior antes de *Release* (). Por exemplo, o uso normal das macros *Py\_BEGIN\_ALLOW\_THREADS* e *Py\_END\_ALLOW\_THREADS* é aceitável.

The return value is an opaque “handle” to the thread state when *PyGILState\_Ensure* () was called, and must be passed to *PyGILState\_Release* () to ensure Python is left in the same state. Even though recursive calls are allowed, these handles *cannot* be shared - each unique call to *PyGILState\_Ensure* () must save the handle for its call to *PyGILState\_Release* ().

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

---

**Nota:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use *\_Py\_IsFinalizing* () or *sys.is\_finalizing* () to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

void **PyGILState\_Release** (*PyGILState\_STATE*)

*Part of the Stable ABI.* Release any resources previously acquired. After this call, Python’s state will be the same as it was prior to the corresponding *PyGILState\_Ensure* () call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to *PyGILState\_Ensure* () must be matched by a call to *PyGILState\_Release* () on the same thread.

*PyThreadState* \***PyGILState\_GetThisThreadState** ()

*Part of the Stable ABI.* Get the current thread state for this thread. May return NULL if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

int **PyGILState\_Check** ()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

Novo na versão 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

**Py\_BEGIN\_ALLOW\_THREADS**

*Part of the Stable ABI.* Esta macro se expande para { *PyThreadState* \*\_save; \_save = *PyEval\_SaveThread* (); . Observe que ele contém uma chave de abertura; ele deve ser combinado com a seguinte macro *Py\_END\_ALLOW\_THREADS*. Veja acima para uma discussão mais aprofundada desta macro.

**Py\_END\_ALLOW\_THREADS**

*Part of the Stable ABI.* Esta macro se expande para `PyEval_RestoreThread(_save);`. Observe que ele contém uma chave de fechamento; ele deve ser combinado com uma macro `Py_BEGIN_ALLOW_THREADS` anterior. Veja acima para uma discussão mais aprofundada desta macro.

**Py\_BLOCK\_THREADS**

*Part of the Stable ABI.* Esta macro se expande para `PyEval_RestoreThread(_save);`; é equivalente a `Py_END_ALLOW_THREADS` sem a chave de fechamento.

**Py\_UNBLOCK\_THREADS**

*Part of the Stable ABI.* Esta macro se expande para `_save = PyEval_SaveThread();`; é equivalente a `Py_BEGIN_ALLOW_THREADS` sem a chave de abertura e declaração de variável.

## 9.5.5 Low-level API

All of the following functions must be called after `Py_Initialize()`.

Alterado na versão 3.7: `Py_Initialize()` now initializes the *GIL*.

*PyInterpreterState* \***PyInterpreterState\_New**()

*Part of the Stable ABI.* Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Levanta um evento de auditoria `cpython.PyInterpreterState_New` sem argumentos.

void **PyInterpreterState\_Clear**(*PyInterpreterState* \*interp)

*Part of the Stable ABI.* Reset all information in an interpreter state object. The global interpreter lock must be held.

Levanta um evento de auditoria `cpython.PyInterpreterState_Clear` sem argumentos.

void **PyInterpreterState\_Delete**(*PyInterpreterState* \*interp)

*Part of the Stable ABI.* Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to `PyInterpreterState_Clear()`.

*PyThreadState* \***PyThreadState\_New**(*PyInterpreterState* \*interp)

*Part of the Stable ABI.* Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

void **PyThreadState\_Clear**(*PyThreadState* \*tstate)

*Part of the Stable ABI.* Reset all information in a thread state object. The global interpreter lock must be held.

Alterado na versão 3.9: This function now calls the `PyThreadState.on_delete` callback. Previously, that happened in `PyThreadState_Delete()`.

void **PyThreadState\_Delete**(*PyThreadState* \*tstate)

*Part of the Stable ABI.* Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to `PyThreadState_Clear()`.

void **PyThreadState\_DeleteCurrent**(void)

Destroy the current thread state and release the global interpreter lock. Like `PyThreadState_Delete()`, the global interpreter lock need not be held. The thread state must have been reset with a previous call to `PyThreadState_Clear()`.

*PyFrameObject* \***PyThreadState\_GetFrame**(*PyThreadState* \*tstate)

*Part of the Stable ABI since version 3.10.* Get the current frame of the Python thread state *tstate*.

Return a *strong reference*. Return NULL if no frame is currently executing.

See also `PyEval_GetFrame()`.

*tstate* must not be NULL.

Novo na versão 3.9.

uint64\_t **PyThreadState\_GetID** (*PyThreadState* \**tstate*)

Part of the [Stable ABI](#) since version 3.10. Get the unique thread state identifier of the Python thread state *tstate*.

*tstate* must not be NULL.

Novo na versão 3.9.

*PyInterpreterState* \***PyThreadState\_GetInterpreter** (*PyThreadState* \**tstate*)

Part of the [Stable ABI](#) since version 3.10. Get the interpreter of the Python thread state *tstate*.

*tstate* must not be NULL.

Novo na versão 3.9.

*PyInterpreterState* \***PyInterpreterState\_Get** (void)

Part of the [Stable ABI](#) since version 3.9. Get the current interpreter.

Issue a fatal error if there no current Python thread state or no current interpreter. It cannot return NULL.

The caller must hold the GIL.

Novo na versão 3.9.

int64\_t **PyInterpreterState\_GetID** (*PyInterpreterState* \**interp*)

Part of the [Stable ABI](#) since version 3.7. Return the interpreter's unique ID. If there was any error in doing so then -1 is returned and an error is set.

The caller must hold the GIL.

Novo na versão 3.7.

*PyObject* \***PyInterpreterState\_GetDict** (*PyInterpreterState* \**interp*)

Part of the [Stable ABI](#) since version 3.8. Return a dictionary in which interpreter-specific data may be stored. If this function returns NULL then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for *PyModule\_GetState* (), which extensions should use to store interpreter-specific state information.

Novo na versão 3.8.

**typedef** *PyObject* \*(\***\_PyFrameEvalFunction**) (*PyThreadState* \**tstate*, *PyFrameObject* \**frame*, int *throwflag*)

Type of a frame evaluation function.

The *throwflag* parameter is used by the *throw* () method of generators: if non-zero, handle the current exception.

Alterado na versão 3.9: The function now takes a *tstate* parameter.

*\_PyFrameEvalFunction* **\_PyInterpreterState\_GetEvalFrameFunc** (*PyInterpreterState* \**interp*)

Get the frame evaluation function.

See the [PEP 523](#) “Adding a frame evaluation API to CPython”.

Novo na versão 3.9.

void **\_PyInterpreterState\_SetEvalFrameFunc** (*PyInterpreterState* \**interp*, *\_PyFrameEvalFunction* *eval\_frame*)

Set the frame evaluation function.

See the [PEP 523](#) “Adding a frame evaluation API to CPython”.

Novo na versão 3.9.

*PyObject* \*PyThreadState\_GetDict ()

*Retorna valor: Referência emprestada. Part of the Stable ABI.* Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

int PyThreadState\_SetAsyncExc (unsigned long *id*, *PyObject* \**exc*)

*Part of the Stable ABI.* Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

Alterado na versão 3.7: The type of the *id* parameter changed from long to unsigned long.

void PyEval\_AcquireThread (*PyThreadState* \**tstate*)

*Part of the Stable ABI.* Acquire the global interpreter lock and set the current thread state to *tstate*, which must not be NULL. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

---

**Nota:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use `_Py_IsFinalizing()` or `sys.is_finalizing()` to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

Alterado na versão 3.8: Updated to be consistent with `PyEval_RestoreThread()`, `Py_END_ALLOW_THREADS()`, and `PyGILState_Ensure()`, and terminate the current thread if called while the interpreter is finalizing.

`PyEval_RestoreThread()` is a higher-level function which is always available (even when threads have not been initialized).

void PyEval\_ReleaseThread (*PyThreadState* \**tstate*)

*Part of the Stable ABI.* Reset the current thread state to NULL and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be NULL, is only used to check that it represents the current thread state — if it isn't, a fatal error is reported.

`PyEval_SaveThread()` is a higher-level function which is always available (even when threads have not been initialized).

void PyEval\_AcquireLock ()

*Part of the Stable ABI.* Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

Obsoleto desde a versão 3.2: This function does not update the current thread state. Please use `PyEval_RestoreThread()` or `PyEval_AcquireThread()` instead.

---

**Nota:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use `_Py_IsFinalizing()` or `sys.is_finalizing()` to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

---

Alterado na versão 3.8: Updated to be consistent with `PyEval_RestoreThread()`, `Py_END_ALLOW_THREADS()`, and `PyGILState_Ensure()`, and terminate the current thread if called while the interpreter is finalizing.

void PyEval\_ReleaseLock ()

*Part of the Stable ABI.* Release the global interpreter lock. The lock must have been created earlier.

Obsoleto desde a versão 3.2: This function does not update the current thread state. Please use `PyEval_SaveThread()` or `PyEval_ReleaseThread()` instead.

## 9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The “main” interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The `PyInterpreterState_Main()` function returns a pointer to its state.

You can switch between sub-interpreters using the `PyThreadState_Swap()` function. You can create and destroy them using the following functions:

**`PyThreadState *Py_NewInterpreter()`**

*Part of the Stable ABI.* Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules `builtins`, `__main__` and `sys`. The table of loaded modules (`sys.modules`) and the module search path (`sys.path`) are also separate. The new environment has no `sys.argv` variable. It has new standard I/O stream file objects `sys.stdin`, `sys.stdout` and `sys.stderr` (however these refer to the same underlying file descriptors).

The return value points to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, `NULL` is returned; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state. (Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns; however, unlike most other Python/C API functions, there needn't be a current thread state on entry.)

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. `PyModule_FromDefAndSpec()`, a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g. `PyModule_Create()`, the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's `init` function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see *Bugs and caveats* below).

Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling `Py_FinalizeEx()` and `Py_Initialize()`; in that case, the extension's `initmodule` function is called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

**`void Py_EndInterpreter(PyThreadState *tstate)`**

*Part of the Stable ABI.* Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is `NULL`. All thread states associated with this interpreter are destroyed. (The global interpreter lock must be held before calling this function and is still held when it returns.) `Py_FinalizeEx()` will destroy all sub-interpreters that haven't been explicitly destroyed at that point.



### 9.6.1 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect — for example, using low-level file operations like `os.close()` they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with `PyGILState_*` APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching `PyGILState_Ensure()` and `PyGILState_Release()` calls. Furthermore, extensions (such as `ctypes`) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

## 9.7 Notificações assíncronas

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int **Py\_AddPendingCall** (int (\**func*)) void\*

, void \**arg* Part of the [Stable ABI](#). Schedule a function to be called from the main interpreter thread. On success, 0 is returned and *func* is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

- on a [bytecode](#) boundary;
- with the main thread holding the [global interpreter lock](#) (*func* can therefore use the full C API).

*func* must return 0 on success, or -1 on failure with an exception set. *func* won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

To call this function in a subinterpreter, the caller must hold the GIL. Otherwise, the function *func* can be scheduled to be called from the wrong interpreter.

**Aviso:** This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the [PyGILState API](#).

Alterado na versão 3.9: If this function is called in a subinterpreter, the function *func* is now scheduled to be called from the subinterpreter, rather than being called from the main interpreter. Each subinterpreter now has its own list of scheduled calls.

Novo na versão 3.1.

## 9.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

**typedef** int (\***Py\_tracefunc**) (*PyObject* \*obj, *PyFrameObject* \*frame, int what, *PyObject* \*arg)

The type of the trace function registered using *PyEval\_SetProfile()* and *PyEval\_SetTrace()*. The first parameter is the object passed to the registration function as *obj*, *frame* is the frame object to which the event pertains, *what* is one of the constants *PyTrace\_CALL*, *PyTrace\_EXCEPTION*, *PyTrace\_LINE*, *PyTrace\_RETURN*, *PyTrace\_C\_CALL*, *PyTrace\_C\_EXCEPTION*, *PyTrace\_C\_RETURN*, or *PyTrace\_OPCODE*, and *arg* depends on the value of *what*:

Value of <i>what</i>	Meaning of <i>arg</i>
<i>PyTrace_CALL</i>	Always <i>Py_None</i> .
<i>PyTrace_EXCEPTION</i>	Exception information as returned by <i>sys.exc_info()</i> .
<i>PyTrace_LINE</i>	Always <i>Py_None</i> .
<i>PyTrace_RETURN</i>	Value being returned to the caller, or NULL if caused by an exception.
<i>PyTrace_C_CALL</i>	Function object being called.
<i>PyTrace_C_EXCEPTION</i>	Function object being called.
<i>PyTrace_C_RETURN</i>	Function object being called.
<i>PyTrace_OPCODE</i>	Always <i>Py_None</i> .

int **PyTrace\_CALL**

The value of the *what* parameter to a *Py\_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

int **PyTrace\_EXCEPTION**

The value of the *what* parameter to a *Py\_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

int **PyTrace\_LINE**

The value passed as the *what* parameter to a *Py\_tracefunc* function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting *f\_trace\_lines* to 0 on that frame.

int **PyTrace\_RETURN**

The value for the *what* parameter to *Py\_tracefunc* functions when a call is about to return.

int **PyTrace\_C\_CALL**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function is about to be called.

int **PyTrace\_C\_EXCEPTION**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function has raised an exception.

int **PyTrace\_C\_RETURN**

The value for the *what* parameter to *Py\_tracefunc* functions when a C function has returned.



int **PyTrace\_OPCODE**

The value for the *what* parameter to *Py\_tracefunc* functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting *f\_trace\_opcodes* to 1 on the frame.

void **PyEval\_SetProfile** (*Py\_tracefunc func*, *PyObject \*obj*)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or NULL. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except *PyTrace\_LINE*, *PyTrace\_OPCODE* and *PyTrace\_EXCEPTION*.

The caller must hold the *GIL*.

void **PyEval\_SetTrace** (*Py\_tracefunc func*, *PyObject \*obj*)

Set the tracing function to *func*. This is similar to *PyEval\_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval\_SetTrace()* will not receive *PyTrace\_C\_CALL*, *PyTrace\_C\_EXCEPTION* or *PyTrace\_C\_RETURN* as a value for the *what* parameter.

The caller must hold the *GIL*.

## 9.9 Advanced Debugger Support

These functions are only intended to be used by advanced debugging tools.

*PyInterpreterState \****PyInterpreterState\_Head** ()

Return the interpreter state object at the head of the list of all such objects.

*PyInterpreterState \****PyInterpreterState\_Main** ()

Return the main interpreter state object.

*PyInterpreterState \****PyInterpreterState\_Next** (*PyInterpreterState \*interp*)

Return the next interpreter state object after *interp* from the list of all such objects.

*PyThreadState \****PyInterpreterState\_ThreadHead** (*PyInterpreterState \*interp*)

Return the pointer to the first *PyThreadState* object in the list of threads associated with the interpreter *interp*.

*PyThreadState \****PyThreadState\_Next** (*PyThreadState \*tstate*)

Return the next thread state object after *tstate* from the list of all such objects belonging to the same *PyInterpreterState* object.

## 9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (*threading.local*). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a *void\** value per thread.

The GIL does *not* need to be held when calling these functions; they supply their own locking.

Note that *Python.h* does not include the declaration of the TLS APIs, you need to include *pthread.h* to use thread-local storage.

**Nota:** None of these API functions handle memory management on behalf of the *void\** values. You need to allocate and deallocate them yourself. If the *void\** values happen to be *PyObject\**, these functions don't do refcount

operations on them either.

---

### 9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type `Py_tss_t` instead of `int` to represent thread keys.

Novo na versão 3.7.

#### Ver também:

“A New C-API for Thread-Local Storage in CPython” ([PEP 539](#))

#### type `Py_tss_t`

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key’s initialization state. There are no public members in this structure.

Quando `Py_LIMITED_API` não é definido, a alocação estática deste tipo por `Py_tss_NEEDS_INIT` é permitida.

#### `Py_tss_NEEDS_INIT`

This macro expands to the initializer for `Py_tss_t` variables. Note that this macro won’t be defined with `Py_LIMITED_API`.

### Alocação dinâmica

Dynamic allocation of the `Py_tss_t`, required in extension modules built with `Py_LIMITED_API`, where static allocation of this type is not possible due to its implementation being opaque at build time.

#### `Py_tss_t *PyThread_tss_alloc()`

*Part of the Stable ABI since version 3.7.* Retorna um valor que é o mesmo estado de um valor inicializado com `Py_tss_NEEDS_INIT`, ou `NULL` no caso de falha de alocação dinâmica.

#### `void PyThread_tss_free(Py_tss_t *key)`

*Part of the Stable ABI since version 3.7.* Free the given `key` allocated by `PyThread_tss_alloc()`, after first calling `PyThread_tss_delete()` to ensure any associated thread locals have been unassigned. This is a no-op if the `key` argument is `NULL`.

---

**Nota:** A freed key becomes a dangling pointer. You should reset the key to `NULL`.

---

### Métodos

The parameter `key` of these functions must not be `NULL`. Moreover, the behaviors of `PyThread_tss_set()` and `PyThread_tss_get()` are undefined if the given `Py_tss_t` has not been initialized by `PyThread_tss_create()`.

#### `int PyThread_tss_is_created(Py_tss_t *key)`

*Part of the Stable ABI since version 3.7.* Return a non-zero value if the given `Py_tss_t` has been initialized by `PyThread_tss_create()`.

#### `int PyThread_tss_create(Py_tss_t *key)`

*Part of the Stable ABI since version 3.7.* Retorna um valor zero na inicialização bem-sucedida de uma chave TSS. O comportamento é indefinido se o valor apontado pelo argumento `key` não for inicializado por

*Py\_tss\_NEEDS\_INIT*. Essa função pode ser chamada repetidamente na mesma tecla – chamá-la em uma tecla já inicializada não funciona e retorna imediatamente com sucesso.

void **PyThread\_tss\_delete** (*Py\_tss\_t* \*key)

Part of the [Stable ABI](#) since version 3.7. Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by *PyThread\_tss\_create()*. This function can be called repeatedly on the same key – calling it on an already destroyed key is a no-op.

int **PyThread\_tss\_set** (*Py\_tss\_t* \*key, void \*value)

Part of the [Stable ABI](#) since version 3.7. Return a zero value to indicate successfully associating a void\* value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a void\* value.

void \***PyThread\_tss\_get** (*Py\_tss\_t* \*key)

Part of the [Stable ABI](#) since version 3.7. Return the void\* value associated with a TSS key in the current thread. This returns NULL if no value is associated with the key in the current thread.

## 9.10.2 Thread Local Storage (TLS) API

Obsoleto desde a versão 3.7: This API is superseded by *Thread Specific Storage (TSS) API*.

---

**Nota:** This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to `int`. On such platforms, *PyThread\_create\_key()* will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

---

Due to the compatibility problem noted above, this version of the API should not be used in new code.

int **PyThread\_create\_key** ()

Part of the [Stable ABI](#).

void **PyThread\_delete\_key** (int key)

Part of the [Stable ABI](#).

int **PyThread\_set\_key\_value** (int key, void \*value)

Part of the [Stable ABI](#).

void \***PyThread\_get\_key\_value** (int key)

Part of the [Stable ABI](#).

void **PyThread\_delete\_key\_value** (int key)

Part of the [Stable ABI](#).

void **PyThread\_ReInitTLS** ()

Part of the [Stable ABI](#).



---

## Configuração de Inicialização do Python

---

Novo na versão 3.8.

Python pode ser inicializado com `Py_InitializeFromConfig()` e a estrutura `PyConfig`. Pode ser pré-inicializado com `Py_PreInitialize()` e a estrutura `PyPreConfig`.

Existem dois tipos de configuração:

- A *Python Configuration* pode ser usada para construir um Python personalizado que se comporta como um Python comum. Por exemplo, variáveis de ambiente e argumento de linha de comando são usados para configurar Python.
- A *Configuração isolada* pode ser usada para incorporar Python em uma aplicação. Isso isola Python de um sistema. Por exemplo, variáveis de ambiente são ignoradas, a variável local `LC_CTYPE` fica inalterada e nenhum manipulador de sinal é registrado.

A função `Py_RunMain()` pode ser usada para escrever um programa Python personalizado.

Veja também *Inicialização, Finalização e Threads*.

**Ver também:**

**PEP 587** “Configuração da inicialização do Python”.

### 10.1 Exemplo

Exemplo de Python personalizado sendo executado sempre em um modo isolado:

```
int main(int argc, char **argv)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config.isolated = 1;
```

(continua na próxima página)

(continuação da página anterior)

```

/* Decode command line arguments.
   Implicitly preinitialize Python (in isolated mode). */
status = PyConfig_SetBytesArgv(&config, argc, argv);
if (PyStatus_Exception(status)) {
    goto exception;
}

status = Py_InitializeFromConfig(&config);
if (PyStatus_Exception(status)) {
    goto exception;
}
PyConfig_Clear(&config);

return Py_RunMain();

exception:
PyConfig_Clear(&config);
if (PyStatus_IsExit(status)) {
    return status.exitcode;
}
/* Display the error message and exit the process with
   non-zero exit code */
Py_ExitStatusException(status);
}

```

## 10.2 PyWideStringList

**type PyWideStringList**

Lista de strings `wchar_t*`.

Se *length* é diferente de zero, *items* deve ser diferente de NULL e todas as strings devem ser diferentes de NULL.

Métodos:

*PyStatus* **PyWideStringList\_Append** (*PyWideStringList* \*list, **const** `wchar_t` \*item)

Anexa *item* a *list*.

Python deve ser inicializado previamente antes de chamar essa função.

*PyStatus* **PyWideStringList\_Insert** (*PyWideStringList* \*list, *Py\_ssize\_t* index, **const** `wchar_t` \*item)

Insere *item* na *list* na posição *index*.

Se *index* for maior ou igual ao comprimento da *list*, anexa o *item* a *list*.

*index* deve ser maior que ou igual a 0.

Python deve ser inicializado previamente antes de chamar essa função.

Campos de estrutura:

*Py\_ssize\_t* **length**

Comprimento da lista.

`wchar_t` \*\***items**

Itens da lista.

## 10.3 PyStatus

### type **PyStatus**

Estrutura para armazenar o status de uma função de inicialização: sucesso, erro ou saída.

Para um erro, ela pode armazenar o nome da função C que criou o erro.

Campos de estrutura:

int **exitcode**

Código de saída. Argumento passado para `exit()`.

const char \***err\_msg**

Mensagem de erro.

const char \***func**

Nome da função que criou um erro. Pode ser NULL.

Funções para criar um status:

*PyStatus* **PyStatus\_Ok** (void)

Sucesso.

*PyStatus* **PyStatus\_Error** (const char \**err\_msg*)

Erro de inicialização com uma mensagem.

*err\_msg* não deve ser NULL.

*PyStatus* **PyStatus\_NoMemory** (void)

Falha de alocação de memória (sem memória).

*PyStatus* **PyStatus\_Exit** (int *exitcode*)

Sai do Python com o código de saída especificado.

Funções para manipular um status:

int **PyStatus\_Exception** (*PyStatus status*)

O status é um erro ou uma saída? Se verdadeiro, a exceção deve ser tratada; chamando `Py_ExitStatusException()`, por exemplo.

int **PyStatus\_IsError** (*PyStatus status*)

O resultado é um erro?

int **PyStatus\_IsExit** (*PyStatus status*)

O resultado é uma saída?

void **Py\_ExitStatusException** (*PyStatus status*)

Chama `exit(exitcode)` se *status* for uma saída. Exibe a mensagem de erro e sai com um código de saída diferente de zero se *status* for um erro. Deve ser chamado apenas se `PyStatus_Exception(status)` for diferente de zero.

---

**Nota:** Internamente, Python usa macros que definem `PyStatus.func`, enquanto funções para criar um status definem `func` para NULL.

---

Exemplo:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
```

(continua na próxima página)

(continuação da página anterior)

```

        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}

int main(int argc, char **argv)
{
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
    PyMem_Free(ptr);
    return 0;
}

```

## 10.4 PyPreConfig

### type **PyPreConfig**

Estrutura usada para pré-inicializar o Python.

A função para inicializar uma pré-configuração:

void **PyPreConfig\_InitPythonConfig** (*PyPreConfig \*preconfig*)

Inicializa a pré-configuração com *Configuração do Python*.

void **PyPreConfig\_InitIsolatedConfig** (*PyPreConfig \*preconfig*)

Inicializa a pré-configuração com *Configuração isolada*.

Campos de estrutura:

#### int **allocator**

Nome de alocadores de memória em Python:

- `PYMEM_ALLOCATOR_NOT_SET (0)`: não altera os alocadores de memória (usa o padrão).
- `PYMEM_ALLOCATOR_DEFAULT (1)`: *alocadores de memória padrão*.
- `PYMEM_ALLOCATOR_DEBUG (2)`: *alocadores de memória padrão com ganchos de depuração*.
- `PYMEM_ALLOCATOR_MALLOC (3)`: usa `malloc()` da biblioteca C.
- `PYMEM_ALLOCATOR_MALLOC_DEBUG (4)`: força uso de `malloc()` com *ganchos de depuração*.
- `PYMEM_ALLOCATOR_PYMALLOC (5)`: *alocador de memória do Python pymalloc*.
- `PYMEM_ALLOCATOR_PYMALLOC_DEBUG (6)`: *alocador de memória do Python pymalloc com ganchos de depuração*.

`PYMEM_ALLOCATOR_PYMALLOC` e `PYMEM_ALLOCATOR_PYMALLOC_DEBUG` não são suportados se o Python estiver configurado usando `--without-pymalloc`.

Veja *Gerenciamento de memória*.

Padrão: `PYMEM_ALLOCATOR_NOT_SET`.

#### int **configure\_locale**

Define a localidade `LC_CTYPE` para a localidade preferida do usuário.

If equals to 0, set `coerce_c_locale` and `coerce_c_locale_warn` members to 0.



Veja a *codificação da localidade*.

Padrão: 1 na configuração do Python, 0 na configuração isolada.

**int `coerce_c_locale`**

If equals to 2, coerce the C locale.

If equals to 1, read the LC\_CTYPE locale to decide if it should be coerced.

Veja a *codificação da localidade*.

Padrão: -1 na configuração do Python, 0 na configuração isolada.

**int `coerce_c_locale_warn`**

Se diferente de zero, emite um aviso se a localidade C for forçada.

Padrão: -1 na configuração do Python, 0 na configuração isolada.

**int `dev_mode`**

If non-zero, enables the Python Development Mode: see *PyConfig.dev\_mode*.

Padrão: -1 no modo do Python, 0 no modo isolado.

**int `isolated`**

Modo isolado: veja *PyConfig.isolated*.

Padrão: 0 no modo do Python, 1 no modo isolado.

**int `legacy_windows_fs_encoding`**

Se não zero:

- Define *PyPreConfig.utf8\_mode* para 0,
- Define *PyConfig.filesystem\_encoding* para "mbcs",
- Define *PyConfig.filesystem\_errors* para "replace".

Inicializado a partir do valor da variável de ambiente PYTHONLEGACYWINDOWSFSENCODING.

Disponível apenas no Windows. A macro `#ifdef MS_WINDOWS` pode ser usada para código específico do Windows.

Padrão: 0.

**int `parse_argv`**

Se diferente de zero, *Py\_PreInitializeFromArgs()* e *Py\_PreInitializeFromBytesArgs()* analisam seu argumento `argv` da mesma forma que o Python regular analisa argumentos de linha de comando: veja Argumentos de linha de comando.

Padrão: 1 na configuração do Python, 0 na configuração isolada.

**int `use_environment`**

Usar variáveis de ambiente? Veja *PyConfig.use\_environment*.

Padrão: 1 na configuração do Python e 0 na configuração isolada.

**int `utf8_mode`**

Se não zero, habilita o modo UTF-8 do Python.

Set by the `-X utf8` command line option and the PYTHONUTF8 environment variable.

Padrão: -1 na configuração do Python e 0 na configuração isolada.

## 10.5 Pré-inicializar Python com PyPreConfig

A pré-inicialização do Python:

- Define os alocadores de memória Python (*PyPreConfig.allocator*)
- Configura a localidade LC\_CTYPE (*codificação da localidade*)
- Define o Modo UTF-8 do Python (*PyPreConfig.utf8\_mode*)

A pré-configuração atual (tipo *PyPreConfig*) é armazenada em *\_PyRuntime.preconfig*.

Funções para pré-inicializar Python:

*PyStatus* **Py\_PreInitialize** (*const PyPreConfig \*preconfig*)

Pré-inicializa o Python a partir da pré-configuração *preconfig*.

*preconfig* não pode ser NULL..

*PyStatus* **Py\_PreInitializeFromBytesArgs** (*const PyPreConfig \*preconfig*, *int argc*, *char \*const \*argv*)

Pré-inicializa o Python a partir da pré-configuração *preconfig*.

Analisa argumentos de linha de comando *argv* (strings de bytes) se *parse\_argv* de *preconfig* for diferente de zero.

*preconfig* não pode ser NULL..

*PyStatus* **Py\_PreInitializeFromArgs** (*const PyPreConfig \*preconfig*, *int argc*, *wchar\_t \*const \*argv*)

Pré-inicializa o Python a partir da pré-configuração *preconfig*.

Analisa argumentos de linha de comando *argv* (strings largas) se *parse\_argv* de *preconfig* for diferente de zero.

*preconfig* não pode ser NULL..

O chamador é responsável por manipular exceções (erro ou saída) usando *PyStatus\_Exception()* e *Py\_ExitStatusException()*.

Para *configuração do Python* (*PyPreConfig\_InitPythonConfig()*), se o Python for inicializado com argumentos de linha de comando, os argumentos de linha de comando também devem ser passados para pré-inicializar o Python, pois eles têm um efeito na pré-configuração como codificações. Por exemplo, a opção de linha de comando *-X utf8* habilita o Modo UTF-8 do Python.

*PyMem\_SetAllocator()* pode ser chamado depois de *Py\_PreInitialize()* e antes de *Py\_InitializeFromConfig()* para instalar um alocador de memória personalizado. Ele pode ser chamado antes de *Py\_PreInitialize()* se *PyPreConfig.allocator* estiver definido como *PYMEM\_ALLOCATOR\_NOT\_SET*.

Funções de alocação de memória do Python como *PyMem\_RawMalloc()* não devem ser usadas antes da pré-inicialização do Python, enquanto chamar diretamente *malloc()* e *free()* é sempre seguro. *Py\_DecodeLocale()* não deve ser chamado antes da pré-inicialização do Python.

Exemplo usando a pré-inicialização para habilitar o modo UTF-8 do Python.

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
```

(continua na próxima página)

(continuação da página anterior)

```

    Py_ExitStatusException(status);
}

/* at this point, Python speaks UTF-8 */

Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();

```

## 10.6 PyConfig

### type **PyConfig**

Estrutura contendo a maioria dos parâmetros para configurar o Python.

Ao terminar, a função `PyConfig_Clear()` deve ser usada para liberar a memória de configuração.

Structure methods:

void **PyConfig\_InitPythonConfig** (*PyConfig* \**config*)  
Initialize configuration with the *Python Configuration*.

void **PyConfig\_InitIsolatedConfig** (*PyConfig* \**config*)  
Initialize configuration with the *Isolated Configuration*.

*PyStatus* **PyConfig\_SetString** (*PyConfig* \**config*, wchar\_t \***const** \**config\_str*, **const** wchar\_t \**str*)  
Copy the wide character string *str* into \**config\_str*.  
*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetBytesString** (*PyConfig* \**config*, wchar\_t \***const** \**config\_str*, **const** char \**str*)  
Decode *str* using `Py_DecodeLocale()` and set the result into \**config\_str*.  
*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetArgv** (*PyConfig* \**config*, int *argc*, wchar\_t \***const** \**argv*)  
Set command line arguments (*argv* member of *config*) from the *argv* list of wide character strings.  
*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetBytesArgv** (*PyConfig* \**config*, int *argc*, char \***const** \**argv*)  
Set command line arguments (*argv* member of *config*) from the *argv* list of bytes strings. Decode bytes using `Py_DecodeLocale()`.  
*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_SetWideStringList** (*PyConfig* \**config*, *PyWideStringList* \**list*, *Py\_ssize\_t* *length*, wchar\_t \*\**items*)  
Set the list of wide strings *list* to *length* and *items*.  
*Preinitialize Python* if needed.

*PyStatus* **PyConfig\_Read** (*PyConfig* \**config*)  
Read all Python configuration.

Fields which are already initialized are left unchanged.

The `PyConfig_Read()` function only parses `PyConfig.argv` arguments once: `PyConfig.parse_argv` is set to 2 after arguments are parsed. Since Python arguments are stripped from `PyConfig.argv`, parsing arguments twice would parse the application options as Python options.

*Preinitialize Python* if needed.

Alterado na versão 3.10: The *PyConfig.argv* arguments are now only parsed once, *PyConfig.parse\_argv* is set to 2 after arguments are parsed, and arguments are only parsed if *PyConfig.parse\_argv* equals 1.

void **PyConfig\_Clear** (*PyConfig \*config*)

Release configuration memory.

Most *PyConfig* methods *preinitialize Python* if needed. In that case, the Python preinitialization configuration (*PyPreConfig*) is based on the *PyConfig*. If configuration fields which are in common with *PyPreConfig* are tuned, they must be set before calling a *PyConfig* method:

- *PyConfig.dev\_mode*
- *PyConfig.isolated*
- *PyConfig.parse\_argv*
- *PyConfig.use\_environment*

Moreover, if *PyConfig\_SetArgv()* or *PyConfig\_SetBytesArgv()* is used, this method must be called before other methods, since the preinitialization configuration depends on command line arguments (if *parse\_argv* is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using *PyStatus\_Exception()* and *Py\_ExitStatusException()*.

Campos de estrutura:

*PyWideStringList* **argv**

Command line arguments: *sys.argv*.

Set *parse\_argv* to 1 to parse *argv* the same way the regular Python parses Python command line arguments and then to strip Python arguments from *argv*.

If *argv* is empty, an empty string is added to ensure that *sys.argv* always exists and is never empty.

Padrão: NULL.

See also the *orig\_argv* member.

wchar\_t \***base\_exec\_prefix**

*sys.base\_exec\_prefix*.

Padrão: NULL.

Part of the *Python Path Configuration* output.

wchar\_t \***base\_executable**

Python base executable: *sys.\_base\_executable*.

Set by the `__PYENV_LAUNCHER__` environment variable.

Set from *PyConfig.executable* if NULL.

Padrão: NULL.

Part of the *Python Path Configuration* output.

wchar\_t \***base\_prefix**

*sys.base\_prefix*.

Padrão: NULL.

Part of the *Python Path Configuration* output.

**int buffered\_stdio**

If equals to 0 and `configure_c_stdio` is non-zero, disable buffering on the C streams stdout and stderr.

Set to 0 by the `-u` command line option and the `PYTHONUNBUFFERED` environment variable.

stdin is always opened in buffered mode.

Padrão: 1.

**int bytes\_warning**

If equals to 1, issue a warning when comparing `bytes` or `bytearray` with `str`, or comparing `bytes` with `int`.

If equal or greater to 2, raise a `BytesWarning` exception in these cases.

Incremented by the `-b` command line option.

Padrão: 0.

**int warn\_default\_encoding**

If non-zero, emit a `EncodingWarning` warning when `io.TextIOWrapper` uses its default encoding. See `io-encoding-warning` for details.

Padrão: 0.

Novo na versão 3.10.

**wchar\_t \*check\_hash\_pycs\_mode**

Control the validation behavior of hash-based `.pyc` files: value of the `--check-hash-based-pycs` command line option.

Valores válidos:

- `L"always"`: Hash the source file for invalidation regardless of value of the `'check_source'` flag.
- `L"never"`: Assume that hash-based pycs always are valid.
- `L"default"`: The `'check_source'` flag in hash-based pycs determines invalidation.

Default: `L"default"`.

See also [PEP 552](#) “Deterministic pycs”.

**int configure\_c\_stdio**

If non-zero, configure C standard streams:

- On Windows, set the binary mode (`O_BINARY`) on stdin, stdout and stderr.
- If `buffered_stdio` equals zero, disable buffering of stdin, stdout and stderr streams.
- If `interactive` is non-zero, enable stream buffering on stdin and stdout (only stdout on Windows).

Padrão: 1 na configuração do Python, 0 na configuração isolada.

**int dev\_mode**

If non-zero, enable the Python Development Mode.

Padrão: `-1` no modo do Python, 0 no modo isolado.

**int dump\_refs**

Dump Python references?

If non-zero, dump all objects which are still alive at exit.

Set to 1 by the `PYTHONDUMPREFS` environment variable.

Need a special build of Python with the `Py_TRACE_REFS` macro defined: see the `configure --with-trace-refs` option.

Padrão: 0.

wchar\_t \***exec\_prefix**

The site-specific directory prefix where the platform-dependent Python files are installed: `sys.exec_prefix`.

Padrão: NULL.

Part of the *Python Path Configuration* output.

wchar\_t \***executable**

The absolute path of the executable binary for the Python interpreter: `sys.executable`.

Padrão: NULL.

Part of the *Python Path Configuration* output.

int **faulthandler**

Enable faulthandler?

If non-zero, call `faulthandler.enable()` at startup.

Set to 1 by `-X faulthandler` and the `PYTHONFAULTHANDLER` environment variable.

Padrão: -1 no modo do Python, 0 no modo isolado.

wchar\_t \***filesystem\_encoding**

*Filesystem encoding*: `sys.getfilesystemencoding()`.

On macOS, Android and VxWorks: use "utf-8" by default.

On Windows: use "utf-8" by default, or "mbcs" if *legacy\_windows\_fs\_encoding* of *PyPreConfig* is non-zero.

Default encoding on other platforms:

- "utf-8" if *PyPreConfig.utf8\_mode* is non-zero.
- "ascii" if Python detects that `nl_langinfo(CODESET)` announces the ASCII encoding, whereas the `mbstowcs()` function decodes from a different encoding (usually Latin1).
- "utf-8" if `nl_langinfo(CODESET)` returns an empty string.
- Otherwise, use the *locale encoding*: `nl_langinfo(CODESET)` result.

At Python startup, the encoding name is normalized to the Python codec name. For example, "ANSI\_X3.4-1968" is replaced with "ascii".

See also the *filesystem\_errors* member.

wchar\_t \***filesystem\_errors**

*Filesystem error handler*: `sys.getfilesystemencodeerrors()`.

On Windows: use "surrogatepass" by default, or "replace" if *legacy\_windows\_fs\_encoding* of *PyPreConfig* is non-zero.

On other platforms: use "surrogateescape" by default.

Supported error handlers:

- "strict"
- "surrogateescape"
- "surrogatepass" (only supported with the UTF-8 encoding)

See also the *filesystem\_encoding* member.

unsigned long **hash\_seed**

int **use\_hash\_seed**

Randomized hash function seed.

If *use\_hash\_seed* is zero, a seed is chosen randomly at Python startup, and *hash\_seed* is ignored.

Set by the PYTHONHASHSEED environment variable.

Default *use\_hash\_seed* value: -1 in Python mode, 0 in isolated mode.

wchar\_t \***home**

Python home directory.

If *Py\_SetPythonHome()* has been called, use its argument if it is not NULL.

Set by the PYTHONHOME environment variable.

Padrão: NULL.

Part of the *Python Path Configuration* input.

int **import\_time**

If non-zero, profile import time.

Set the 1 by the `-X importtime` option and the PYTHONPROFILEIMPORTTIME environment variable.

Padrão: 0.

int **inspect**

Enter interactive mode after executing a script or a command.

If greater than 0, enable inspect: when a script is passed as first argument or the `-c` option is used, enter interactive mode after executing the script or the command, even when `sys.stdin` does not appear to be a terminal.

Incremented by the `-i` command line option. Set to 1 if the PYTHONINSPECT environment variable is non-empty.

Padrão: 0.

int **install\_signal\_handlers**

Install Python signal handlers?

Default: 1 in Python mode, 0 in isolated mode.

int **interactive**

If greater than 0, enable the interactive mode (REPL).

Incremented by the `-i` command line option.

Padrão: 0.

int **isolated**

If greater than 0, enable isolated mode:

- `sys.path` contains neither the script's directory (computed from `argv[0]` or the current directory) nor the user's site-packages directory.
- Python REPL doesn't import `readline` nor enable default readline configuration on interactive prompts.
- Set *use\_environment* and *user\_site\_directory* to 0.

Padrão: 0 no modo do Python, 1 no modo isolado.

Veja também *PyPreConfig.isolated*.

**int legacy\_windows\_stdio**

If non-zero, use `io.FileIO` instead of `io.WindowsConsoleIO` for `sys.stdin`, `sys.stdout` and `sys.stderr`.

Definida como 1 se a variável de ambiente `PYTHONLEGACYWINDOWSSTDIO` estiver definida como uma string não vazia.

Disponível apenas no Windows. A macro `#ifdef MS_WINDOWS` pode ser usada para código específico do Windows.

Padrão: 0.

See also the [PEP 528](#) (Change Windows console encoding to UTF-8).

**int malloc\_stats**

If non-zero, dump statistics on *Python pymalloc memory allocator* at exit.

Set to 1 by the `PYTHONMALLOCSTATS` environment variable.

The option is ignored if Python is configured using the `--without-pymalloc` option.

Padrão: 0.

**wchar\_t \*platlibdir**

Platform library directory name: `sys.platlibdir`.

Set by the `PYTHONPLATLIBDIR` environment variable.

Default: value of the `PLATLIBDIR` macro which is set by the configure `--with-platlibdir` option (default: `"lib"`).

Part of the *Python Path Configuration* input.

Novo na versão 3.9.

**wchar\_t \*pythonpath\_env**

Module search paths (`sys.path`) as a string separated by `DELIM(os.path.pathsep)`.

Set by the `PYTHONPATH` environment variable.

Padrão: `NULL`.

Part of the *Python Path Configuration* input.

***PyWideStringList* module\_search\_paths****int module\_search\_paths\_set**

Module search paths: `sys.path`.

If `module_search_paths_set` is equal to 0, the function calculating the *Python Path Configuration* overrides the `module_search_paths` and sets `module_search_paths_set` to 1.

Default: empty list (`module_search_paths`) and 0 (`module_search_paths_set`).

Part of the *Python Path Configuration* output.

**int optimization\_level**

Compilation optimization level:

- 0: Peephole optimizer, set `__debug__` to `True`.
- 1: Level 0, remove assertions, set `__debug__` to `False`.
- 2: Level 1, strip docstrings.

Incremented by the `-O` command line option. Set to the `PYTHONOPTIMIZE` environment variable value.

Padrão: 0.



**PyWideStringList orig\_argv**

The list of the original command line arguments passed to the Python executable: `sys.orig_argv`.

If `orig_argv` list is empty and `argv` is not a list only containing an empty string, `PyConfig_Read()` copies `argv` into `orig_argv` before modifying `argv` (if `parse_argv` is non-zero).

See also the `argv` member and the `Py_GetArgcArgv()` function.

Padrão: lista vazia.

Novo na versão 3.10.

**int parse\_argv**

Parse command line arguments?

If equals to 1, parse `argv` the same way the regular Python parses command line arguments, and strip Python arguments from `argv`.

The `PyConfig_Read()` function only parses `PyConfig.argv` arguments once: `PyConfig.parse_argv` is set to 2 after arguments are parsed. Since Python arguments are stripped from `PyConfig.argv`, parsing arguments twice would parse the application options as Python options.

Default: 1 in Python mode, 0 in isolated mode.

Alterado na versão 3.10: The `PyConfig.argv` arguments are now only parsed if `PyConfig.parse_argv` equals to 1.

**int parser\_debug**

Parser debug mode. If greater than 0, turn on parser debugging output (for expert only, depending on compilation options).

Incremented by the `-d` command line option. Set to the `PYTHONDEBUG` environment variable value.

Padrão: 0.

**int pathconfig\_warnings**

On Unix, if non-zero, calculating the *Python Path Configuration* can log warnings into `stderr`. If equals to 0, suppress these warnings.

It has no effect on Windows.

Default: 1 in Python mode, 0 in isolated mode.

Part of the *Python Path Configuration* input.

**wchar\_t \*prefix**

The site-specific directory prefix where the platform independent Python files are installed: `sys.prefix`.

Padrão: NULL.

Part of the *Python Path Configuration* output.

**wchar\_t \*program\_name**

Program name used to initialize *executable* and in early error messages during Python initialization.

- If `Py_SetProgramName()` has been called, use its argument.
- On macOS, use `PYTHONEXECUTABLE` environment variable if set.
- If the `WITH_NEXT_FRAMEWORK` macro is defined, use `__PYENVV_LAUNCHER__` environment variable if set.
- Use `argv[0]` of `argv` if available and non-empty.
- Otherwise, use `L"python"` on Windows, or `L"python3"` on other platforms.

Padrão: `NULL`.

Part of the *Python Path Configuration* input.

`wchar_t *pycache_prefix`

Directory where cached `.pyc` files are written: `sys.pycache_prefix`.

Set by the `-X pycache_prefix=PATH` command line option and the `PYTHONPYCACHEPREFIX` environment variable.

If `NULL`, `sys.pycache_prefix` is set to `None`.

Padrão: `NULL`.

`int quiet`

Quiet mode. If greater than 0, don't display the copyright and version at Python startup in interactive mode.

Incremented by the `-q` command line option.

Padrão: 0.

`wchar_t *run_command`

Value of the `-c` command line option.

Used by *Py\_RunMain()*.

Padrão: `NULL`.

`wchar_t *run_filename`

Filename passed on the command line: trailing command line argument without `-c` or `-m`.

For example, it is set to `script.py` by the `python3 script.py arg` command.

Used by *Py\_RunMain()*.

Padrão: `NULL`.

`wchar_t *run_module`

Value of the `-m` command line option.

Used by *Py\_RunMain()*.

Padrão: `NULL`.

`int show_ref_count`

Show total reference count at exit?

Set to 1 by `-X showrefcount` command line option.

Need a debug build of Python (the `Py_REF_DEBUG` macro must be defined).

Padrão: 0.

`int site_import`

Import the `site` module at startup?

If equal to zero, disable the import of the module `site` and the site-dependent manipulations of `sys.path` that it entails.

Also disable these manipulations if the `site` module is explicitly imported later (call `site.main()` if you want them to be triggered).

Set to 0 by the `-S` command line option.

`sys.flags.no_site` is set to the inverted value of *site\_import*.

Padrão: 1.

**int skip\_source\_first\_line**

If non-zero, skip the first line of the `PyConfig.run_filename` source.

It allows the usage of non-Unix forms of `#!cmd`. This is intended for a DOS specific hack only.

Set to 1 by the `-x` command line option.

Padrão: 0.

**wchar\_t \*stdio\_encoding****wchar\_t \*stdio\_errors**

Encoding and encoding errors of `sys.stdin`, `sys.stdout` and `sys.stderr` (but `sys.stderr` always uses "backslashreplace" error handler).

If `Py_SetStandardStreamEncoding()` has been called, use its *error* and *errors* arguments if they are not NULL.

Use the `PYTHONIOENCODING` environment variable if it is non-empty.

Codificação padrão:

- "UTF-8" if `PyPreConfig.utf8_mode` is non-zero.
- Otherwise, use the *locale encoding*.

Tratador de erros padrão:

- On Windows: use "surrogateescape".
- "surrogateescape" if `PyPreConfig.utf8_mode` is non-zero, or if the `LC_CTYPE` locale is "C" or "POSIX".
- "strict" otherwise.

**int tracemalloc**

Enable tracemalloc?

If non-zero, call `tracemalloc.start()` at startup.

Set by `-X tracemalloc=N` command line option and by the `PYTHONTRACEMALLOC` environment variable.

Padrão: -1 no modo do Python, 0 no modo isolado.

**int use\_environment**

Use environment variables?

If equals to zero, ignore the environment variables.

Padrão: 1 na configuração do Python e 0 na configuração isolada.

**int user\_site\_directory**

If non-zero, add the user site directory to `sys.path`.

Set to 0 by the `-s` and `-I` command line options.

Set to 0 by the `PYTHONNOUSERSITE` environment variable.

Default: 1 in Python mode, 0 in isolated mode.

**int verbose**

Verbose mode. If greater than 0, print a message each time a module is imported, showing the place (filename or built-in module) from which it is loaded.

If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Incremented by the `-v` command line option.

Set to the `PYTHONVERBOSE` environment variable value.

Padrão: 0.

#### *PyWideStringList* **warnoptions**

Options of the `warnings` module to build warnings filters, lowest to highest priority: `sys.warnoptions`.

The `warnings` module adds `sys.warnoptions` in the reverse order: the last *PyConfig.warnoptions* item becomes the first item of `warnings.filters` which is checked first (highest priority).

The `-W` command line options adds its value to *warnoptions*, it can be used multiple times.

The `PYTHONWARNINGS` environment variable can also be used to add warning options. Multiple options can be specified, separated by commas (,).

Padrão: lista vazia.

#### **int write\_bytecode**

If equal to 0, Python won't try to write `.pyc` files on the import of source modules.

Set to 0 by the `-B` command line option and the `PYTHONDONTWRITEBYTECODE` environment variable.

`sys.dont_write_bytecode` is initialized to the inverted value of *write\_bytecode*.

Padrão: 1.

#### *PyWideStringList* **xoptions**

Values of the `-X` command line options: `sys.__xoptions`.

Padrão: lista vazia.

If *parse\_argv* is non-zero, *argv* arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from *argv*.

The *xoptions* options are parsed to set other options: see the `-X` command line option.

Alterado na versão 3.9: The `show_alloc_count` field has been removed.

## 10.7 Initialization with PyConfig

Function to initialize Python:

*PyStatus* **Py\_InitializeFromConfig** (*const PyConfig \*config*)

Initialize Python from *config* configuration.

O chamador é responsável por manipular exceções (erro ou saída) usando `PyStatus_Exception()` e `Py_ExitStatusException()`.

If *PyImport\_FrozenModules()*, *PyImport\_AppendInittab()* or *PyImport\_ExtendInittab()* are used, they must be set or called after Python preinitialization and before the Python initialization. If Python is initialized multiple times, *PyImport\_AppendInittab()* or *PyImport\_ExtendInittab()* must be called before each Python initialization.

The current configuration (`PyConfig` type) is stored in `PyInterpreterState.config`.

Example setting the program name:

```

void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name. Implicitly preinitialize Python. */
    status = PyConfig_SetString(&config, &config.program_name,
                               L"/path/to/my_program");
    if (PyStatus_Exception(status)) {
        goto exception;
    }

    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto exception;
    }
    PyConfig_Clear(&config);
    return;

exception:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
}

```

More complete example modifying the default configuration, read the configuration, and then override some parameters:

```

PyStatus init_python(const char *program_name)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).

       Implicitly preinitialize Python. */
    status = PyConfig_SetBytesString(&config, &config.program_name,
                                     program_name);
    if (PyStatus_Exception(status)) {
        goto done;
    }

    /* Read all configuration at once */
    status = PyConfig_Read(&config);
    if (PyStatus_Exception(status)) {
        goto done;
    }

    /* Append our custom search path to sys.path */
    status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
    if (PyStatus_Exception(status)) {
        goto done;
    }
}

```

(continua na próxima página)

(continuação da página anterior)

```
/* Override executable computed by PyConfig_Read() */
status = PyConfig_SetString(&config, &config.executable,
                           L"/path/to/my_executable");
if (PyStatus_Exception(status)) {
    goto done;
}

status = Py_InitializeFromConfig(&config);

done:
    PyConfig_Clear(&config);
    return status;
}
```

## 10.8 Isolated Configuration

`PyPreConfig_InitIsolatedConfig()` and `PyConfig_InitIsolatedConfig()` functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environment variables, command line arguments (`PyConfig.argv` is not parsed) and user site directory. The C standard streams (ex: `stdout`) and the `LC_CTYPE` locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration. Set the *Python Path Configuration* (“output fields”) to ignore these configuration files and avoid the function computing the default path configuration.

## 10.9 Configuração do Python

`PyPreConfig_InitPythonConfig()` and `PyConfig_InitPythonConfig()` functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (**PEP 538**) and Python UTF-8 Mode (**PEP 540**) depending on the `LC_CTYPE` locale, `PYTHONUTF8` and `PYTHONCOERCECLOCALE` environment variables.

## 10.10 Python Path Configuration

`PyConfig` contains multiple fields for the path configuration:

- Path configuration inputs:
  - `PyConfig.home`
  - `PyConfig.platlibdir`
  - `PyConfig.pathconfig_warnings`
  - `PyConfig.program_name`
  - `PyConfig.pythonpath_env`

- current working directory: to get absolute paths
- PATH environment variable to get the program full path (from `PyConfig.program_name`)
- `__PYENV_LAUNCHER__` environment variable
- (Windows only) Application paths in the registry under “SoftwarePythonPythonCoreX.YPythonPath” of HKEY\_CURRENT\_USER and HKEY\_LOCAL\_MACHINE (where X.Y is the Python version).
- Path configuration output fields:
  - `PyConfig.base_exec_prefix`
  - `PyConfig.base_executable`
  - `PyConfig.base_prefix`
  - `PyConfig.exec_prefix`
  - `PyConfig.executable`
  - `PyConfig.module_search_paths_set`, `PyConfig.module_search_paths`
  - `PyConfig.prefix`

If at least one “output field” is not set, Python calculates the path configuration to fill unset fields. If `module_search_paths_set` is equal to 0, `module_search_paths` is overridden and `module_search_paths_set` is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. `module_search_paths` is considered as set if `module_search_paths_set` is set to 1. In this case, path configuration input fields are ignored as well.

Set `pathconfig_warnings` to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If `base_prefix` or `base_exec_prefix` fields are not set, they inherit their value from `prefix` and `exec_prefix` respectively.

`Py_RunMain()` and `Py_Main()` modify `sys.path`:

- If `run_filename` is set and is a directory which contains a `__main__.py` script, prepend `run_filename` to `sys.path`.
- If `isolated` is zero:
  - If `run_module` is set, prepend the current directory to `sys.path`. Do nothing if the current directory cannot be read.
  - If `run_filename` is set, prepend the directory of the filename to `sys.path`.
  - Otherwise, prepend an empty string to `sys.path`.

If `site_import` is non-zero, `sys.path` can be modified by the `site` module. If `user_site_directory` is non-zero and the user’s site-package directory exists, the `site` module appends the user’s site-package directory to `sys.path`.

The following configuration files are used by the path configuration:

- `pyvenv.cfg`
- `python._pth` (Windows only)
- `pybuilddir.txt` (Unix only)

The `__PYENV_LAUNCHER__` environment variable is used to set `PyConfig.base_executable`

## 10.11 Py\_RunMain()

int **Py\_RunMain** (void)

Execute the command (*PyConfig.run\_command*), the script (*PyConfig.run\_filename*) or the module (*PyConfig.run\_module*) specified on the command line or in the configuration.

By default and when if `-i` option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the `exit()` function.

See *Python Configuration* for an example of customized Python always running in isolated mode using *Py\_RunMain()*.

## 10.12 Py\_GetArgcArgv()

void **Py\_GetArgcArgv** (int \*argc, wchar\_t \*\*\*argv)

Get the original command line arguments, before Python modified them.

See also *PyConfig.orig\_argv* member.

## 10.13 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of **PEP 432**:

- “Core” initialization phase, “bare minimum Python”:
  - Builtin types;
  - Builtin exceptions;
  - Builtin and frozen modules;
  - The `sys` module is only partially initialized (ex: `sys.path` doesn’t exist yet).
- “Main” initialization phase, Python is fully initialized:
  - Install and configure `importlib`;
  - Apply the *Path Configuration*;
  - Install signal handlers;
  - Finish `sys` module initialization (ex: create `sys.stdout` and `sys.path`);
  - Enable optional features like `faulthandler` and `tracemalloc`;
  - Import the `site` module;
  - etc.

Private provisional API:

- *PyConfig.\_init\_main*: if set to 0, *Py\_InitializeFromConfig()* stops at the “Core” initialization phase.
- *PyConfig.\_isolated\_interpreter*: if non-zero, disallow threads, subprocesses and fork.

*PyStatus* **\_Py\_InitializeMain** (void)

Move to the “Main” initialization phase, finish the Python initialization.



No module is imported during the “Core” phase and the `importlib` module is not configured: the *Path Configuration* is only applied during the “Main” phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom `sys.meta_path` importer or an import hook, etc.

It may become possible to calculate the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the [PEP 432](#) motivation.

The “Core” phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between “Core” and “Main” initialization phases:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config._init_main = 0;

    /* ... customize 'config' configuration ... */

    status = Py_InitializeFromConfig(&config);
    PyConfig_Clear(&config);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }

    /* Use sys.stderr because sys.stdout is only created
       by _Py_InitializeMain() */
    int res = PyRun_SimpleString(
        "import sys; "
        "print('Run Python code before _Py_InitializeMain', "
        "      'file=sys.stderr');");
    if (res < 0) {
        exit(1);
    }

    /* ... put more configuration code here ... */

    status = _Py_InitializeMain();
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
}
```



## 11.1 Visão Geral

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: `malloc()`, `calloc()`, `realloc()` and `free()`. This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
```

(continua na próxima página)

(continuação da página anterior)

```
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

### Ver também:

The `PYTHONMALLOC` environment variable can be used to configure the memory allocators used by Python.

The `PYTHONMALLOCSTATS` environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

## 11.2 Allocator Domains

All allocating functions belong to one of three different “domains” (see also *PyMemAllocatorDomain*). These domains represent different allocation strategies and are optimized for different purposes. The specific details on how every domain allocates memory or what internal functions each domain calls is considered an implementation detail, but for debugging purposes a simplified table can be found at [here](#). There is no hard requirement to use the memory returned by the allocation functions belonging to a given domain for only the purposes hinted by that domain (although this is the recommended practice). For example, one could use the memory returned by *PyMem\_RawMalloc()* for allocating Python objects or the memory returned by *PyObject\_Malloc()* for allocating memory for buffers.

The three allocation domains are:

- Raw domain: intended for allocating memory for general-purpose memory buffers where the allocation *must* go to the system allocator or where the allocator can operate without the *GIL*. The memory is requested directly to the system.
- “Mem” domain: intended for allocating memory for Python buffers and general-purpose memory buffers where the allocation must be performed with the *GIL* held. The memory is taken from the Python private heap.
- Object domain: intended for allocating memory belonging to Python objects. The memory is taken from the Python private heap.

When freeing memory previously allocated by the allocating functions belonging to a given domain, the matching specific deallocating functions must be used. For example, *PyMem\_Free()* must be used to free memory allocated using *PyMem\_Malloc()*.

## 11.3 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, the *GIL* does not need to be held.

The *default raw memory allocator* uses the following functions: `malloc()`, `calloc()`, `realloc()` and `free()`; call `malloc(1)` (or `calloc(1, 1)`) when requesting zero bytes.

Novo na versão 3.4.

void **\*PyMem\_RawMalloc** (size\_t *n*)

Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawMalloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyMem\_RawCalloc** (size\_t *nelem*, size\_t *elsize*)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawCalloc(1, 1)` had been called instead.

Novo na versão 3.5.

void **\*PyMem\_RawRealloc** (void \**p*, size\_t *n*)

Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyMem_RawMalloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to `PyMem_RawMalloc()`, `PyMem_RawRealloc()` or `PyMem_RawCalloc()`.

If the request fails, `PyMem_RawRealloc()` returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyMem\_RawFree** (void \**p*)

Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyMem_RawMalloc()`, `PyMem_RawRealloc()` or `PyMem_RawCalloc()`. Otherwise, or if `PyMem_RawFree(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

## 11.4 Interface da Memória

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The *default memory allocator* uses the *pymalloc memory allocator*.

**Aviso:** The *GIL* must be held when using these functions.

Alterado na versão 3.6: The default allocator is now `pymalloc` instead of `system malloc()`.

void **\*PyMem\_Malloc** (size\_t *n*)

*Part of the [Stable ABI](#).* Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyMem\_Calloc** (size\_t *nelem*, size\_t *elsize*)

*Part of the [Stable ABI](#) since version 3.7.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Calloc(1, 1)` had been called instead.

Novo na versão 3.5.

void **\*PyMem\_Realloc** (void \**p*, size\_t *n*)

*Part of the [Stable ABI](#).* Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyMem_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to `PyMem_Malloc()`, `PyMem_Realloc()` or `PyMem_Calloc()`.

If the request fails, `PyMem_Realloc()` returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyMem\_Free** (void \**p*)

*Part of the [Stable ABI](#).* Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyMem_Malloc()`, `PyMem_Realloc()` or `PyMem_Calloc()`. Otherwise, or if `PyMem_Free(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

The following type-oriented macros are provided for convenience. Note that *TYPE* refers to any C type.

TYPE **\*PyMem\_New** (TYPE, size\_t *n*)

Same as `PyMem_Malloc()`, but allocates  $(n * \text{sizeof}(\text{TYPE}))$  bytes of memory. Returns a pointer cast to `TYPE*`. The memory will not have been initialized in any way.

TYPE **\*PyMem\_Resize** (void \**p*, TYPE, size\_t *n*)

Same as `PyMem_Realloc()`, but the memory block is resized to  $(n * \text{sizeof}(\text{TYPE}))$  bytes. Returns a pointer cast to `TYPE*`. On return, *p* will be a pointer to the new memory area, or `NULL` in the event of failure.

This is a C preprocessor macro; *p* is always reassigned. Save the original value of *p* to avoid losing memory when handling errors.

void **PyMem\_Del** (void \**p*)

Same as `PyMem_Free()`.

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- `PyMem_MALLOC(size)`
- `PyMem_NEW(type, size)`
- `PyMem_REALLOC(ptr, size)`
- `PyMem_RESIZE(ptr, type, size)`

- `PyMem_FREE(ptr)`
- `PyMem_DEL(ptr)`

## 11.5 Alocadores de objeto

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

**Nota:** There is no guarantee that the memory returned by these allocators can be successfully cast to a Python object when intercepting the allocating functions in this domain by the methods described in the [Customize Memory Allocators](#) section.

The *default object allocator* uses the *pymalloc memory allocator*.

**Aviso:** The *GIL* must be held when using these functions.

void **\*PyObject\_Malloc** (size\_t *n*)

*Part of the Stable ABI.* Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void **\*PyObject\_Calloc** (size\_t *nelem*, size\_t *elsize*)

*Part of the Stable ABI since version 3.7.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Calloc(1, 1)` had been called instead.

Novo na versão 3.5.

void **\*PyObject\_Realloc** (void \**p*, size\_t *n*)

*Part of the Stable ABI.* Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyObject_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to `PyObject_Malloc()`, `PyObject_Realloc()` or `PyObject_Calloc()`.

If the request fails, `PyObject_Realloc()` returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyObject\_Free** (void \**p*)

*Part of the Stable ABI.* Frees the memory block pointed to by *p*, which must have been returned by a previous call to `PyObject_Malloc()`, `PyObject_Realloc()` or `PyObject_Calloc()`. Otherwise, or if `PyObject_Free(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

## 11.6 Alocadores de memória padrão

Alocadores de memória padrão:

Configuração	Nome	Py-Mem_RawMalloc	PyMem_Malloc	PyObject_Malloc
Release build	"pymalloc"	malloc	pymalloc	pymalloc
Debug build	"pymalloc_debug"	malloc + debug	pymalloc + debug	pymalloc + debug
Release build, without pymalloc	"malloc"	malloc	malloc	malloc
Debug build, without pymalloc	"malloc_debug"	malloc + debug	malloc + debug	malloc + debug

Legend:

- Name: value for PYTHONMALLOC environment variable.
- malloc: system allocators from the standard C library, C functions: `malloc()`, `calloc()`, `realloc()` and `free()`.
- pymalloc: *pymalloc memory allocator*.
- “+ debug”: with *debug hooks on the Python memory allocators*.
- “Debug build”: Python build in debug mode.

## 11.7 Alocadores de memória

Novo na versão 3.4.

**type PyMemAllocatorEx**

Structure used to describe a memory block allocator. The structure has the following fields:

Campo	Significado
<code>void *ctx</code>	user context passed as first argument
<code>void* malloc(void *ctx, size_t size)</code>	allocate a memory block
<code>void* calloc(void *ctx, size_t nelem, size_t elsize)</code>	allocate a memory block initialized with zeros
<code>void* realloc(void *ctx, void *ptr, size_t new_size)</code>	allocate or resize a memory block
<code>void free(void *ctx, void *ptr)</code>	free a memory block

Alterado na versão 3.5: A estrutura `PyMemAllocator` foi renomeada para *PyMemAllocatorEx* e um novo campo `calloc` foi adicionado.

**type PyMemAllocatorDomain**

Enum used to identify an allocator domain. Domains:

**PYMEM\_DOMAIN\_RAW**

Funções:

- *PyMem\_RawMalloc()*
- *PyMem\_RawRealloc()*



- `PyMem_RawCalloc()`
- `PyMem_RawFree()`

**PYMEM\_DOMAIN\_MEM**

Funções:

- `PyMem_Malloc()`,
- `PyMem_Realloc()`
- `PyMem_Calloc()`
- `PyMem_Free()`

**PYMEM\_DOMAIN\_OBJ**

Funções:

- `PyObject_Malloc()`
- `PyObject_Realloc()`
- `PyObject_Calloc()`
- `PyObject_Free()`

void **PyMem\_GetAllocator** (*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* \*allocator)

Get the memory block allocator of the specified domain.

void **PyMem\_SetAllocator** (*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* \*allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the `PYMEM_DOMAIN_RAW` domain, the allocator must be thread-safe: the *GIL* is not held when the allocator is called.

If the new allocator is not a hook (does not call the previous allocator), the `PyMem_SetupDebugHooks()` function must be called to reinstall the debug hooks on top on the new allocator.

**Aviso:** `PyMem_SetAllocator()` does have the following contract:

- It can be called after `Py_PreInitialize()` and before `Py_InitializeFromConfig()` to install a custom memory allocator. There are no restrictions over the installed allocator other than the ones imposed by the domain (for instance, the Raw Domain allows the allocator to be called without the GIL held). See *the section on allocator domains* for more information.
- If called after Python has finish initializing (after `Py_InitializeFromConfig()` has been called) the allocator **must** wrap the existing allocator. Substituting the current allocator for some other arbitrary one is **not supported**.

void **PyMem\_SetupDebugHooks** (void)

Setup *debug hooks in the Python memory allocators* to detect memory errors.

## 11.8 Debug hooks on the Python memory allocators

When Python is built in debug mode, the `PyMem_SetupDebugHooks()` function is called at the *Python preinitialization* to setup debug hooks on Python memory allocators to detect memory errors.

The `PYTHONMALLOC` environment variable can be used to install debug hooks on a Python compiled in release mode (ex: `PYTHONMALLOC=debug`).

The `PyMem_SetupDebugHooks()` function can be used to set debug hooks after calling `PyMem_SetAllocator()`.

These debug hooks fill dynamically allocated memory blocks with special, recognizable bit patterns. Newly allocated memory is filled with the byte `0xCD` (`PYMEM_CLEANBYTE`), freed memory is filled with the byte `0xDD` (`PYMEM_DEADBYTE`). Memory blocks are surrounded by “forbidden bytes” filled with the byte `0xFD` (`PYMEM_FORBIDDENBYTE`). Strings of these bytes are unlikely to be valid addresses, floats, or ASCII strings.

Checagens em Tempo de Execução:

- Detect API violations. For example, detect if `PyObject_Free()` is called on a memory block allocated by `PyMem_Malloc()`.
- Detect write before the start of the buffer (buffer underflow).
- Detect write after the end of the buffer (buffer overflow).
- Check that the *GIL* is held when allocator functions of `PYMEM_DOMAIN_OBJ` (ex: `PyObject_Malloc()`) and `PYMEM_DOMAIN_MEM` (ex: `PyMem_Malloc()`) domains are called.

On error, the debug hooks use the `tracemalloc` module to get the traceback where a memory block was allocated. The traceback is only displayed if `tracemalloc` is tracing Python memory allocations and the memory block was traced.

Let  $S = \text{sizeof}(\text{size\_t})$ .  $2 \cdot S$  bytes are added at each end of each block of  $N$  bytes requested. The memory layout is like so, where  $p$  represents the address returned by a `malloc`-like or `realloc`-like function ( $p[i:j]$  means the slice of bytes from  $*(p+i)$  inclusive up to  $*(p+j)$  exclusive; note that the treatment of negative indices differs from a Python slice):

**$p[-2 \cdot S:-S]$**  Number of bytes originally asked for. This is a `size_t`, big-endian (easier to read in a memory dump).

**$p[-S]$**  API identifier (ASCII character):

- 'r' for `PYMEM_DOMAIN_RAW`.
- 'm' for `PYMEM_DOMAIN_MEM`.
- 'o' for `PYMEM_DOMAIN_OBJ`.

**$p[-S+1:0]$**  Copies of `PYMEM_FORBIDDENBYTE`. Used to catch under- writes and reads.

**$p[0:N]$**  The requested memory, filled with copies of `PYMEM_CLEANBYTE`, used to catch reference to uninitialized memory. When a `realloc`-like function is called requesting a larger memory block, the new excess bytes are also filled with `PYMEM_CLEANBYTE`. When a `free`-like function is called, these are overwritten with `PYMEM_DEADBYTE`, to catch reference to freed memory. When a `realloc`-like function is called requesting a smaller memory block, the excess old bytes are also filled with `PYMEM_DEADBYTE`.

**$p[N:N+S]$**  Copies of `PYMEM_FORBIDDENBYTE`. Used to catch over- writes and reads.

**$p[N+S:N+2 \cdot S]$**  Only used if the `PYMEM_DEBUG_SERIALNO` macro is defined (not defined by default).

A serial number, incremented by 1 on each call to a `malloc`-like or `realloc`-like function. Big-endian `size_t`. If “bad memory” is detected later, the serial number gives an excellent way to set a breakpoint on the next run, to capture the instant at which this block was passed out. The static function `bumpserialno()` in `obmalloc.c` is the only place the serial number is incremented, and exists so you can set such a breakpoint easily.

A realloc-like or free-like function first checks that the `PYMEM_FORBIDDENBYTE` bytes at each end are intact. If they've been altered, diagnostic output is written to `stderr`, and the program is aborted via `Py_FatalError()`. The other main failure mode is provoking a memory error when a program reads up one of the special bit patterns and tries to use it as an address. If you get in a debugger then and look at the object, you're likely to see that it's entirely filled with `PYMEM_DEADBYTE` (meaning freed memory is getting used) or `PYMEM_CLEANBYTE` (meaning uninitialized memory is getting used).

Alterado na versão 3.6: The `PyMem_SetupDebugHooks()` function now also works on Python compiled in release mode. On error, the debug hooks now use `tracemalloc` to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of `PYMEM_DOMAIN_OBJ` and `PYMEM_DOMAIN_MEM` domains are called.

Alterado na versão 3.8: Byte patterns `0xCB` (`PYMEM_CLEANBYTE`), `0xDB` (`PYMEM_DEADBYTE`) and `0xFB` (`PYMEM_FORBIDDENBYTE`) have been replaced with `0xCD`, `0xDD` and `0xFD` to use the same values than Windows CRT debug `malloc()` and `free()`.

## 11.9 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called “arenas” with a fixed size of 256 KiB. It falls back to `PyMem_RawMalloc()` and `PyMem_RawRealloc()` for allocations larger than 512 bytes.

*pymalloc* is the *default allocator* of the `PYMEM_DOMAIN_MEM` (ex: `PyMem_Malloc()`) and `PYMEM_DOMAIN_OBJ` (ex: `PyObject_Malloc()`) domains.

The arena allocator uses the following functions:

- `VirtualAlloc()` e `VirtualFree()` no Windows,
- `mmap()` e `munmap()` se disponível,
- `malloc()` e `free()` do contrário.

This allocator is disabled if Python is configured with the `--without-pymalloc` option. It can also be disabled at runtime using the `PYTHONMALLOC` environment variable (ex: `PYTHONMALLOC=malloc`).

### 11.9.1 Customize pymalloc Arena Allocator

Novo na versão 3.4.

**type** `PyObjectArenaAllocator`

Structure used to describe an arena allocator. The structure has three fields:

Campo	Significado
<code>void *ctx</code>	user context passed as first argument
<code>void* alloc(void *ctx, size_t size)</code>	allocate an arena of size bytes
<code>void free(void *ctx, void *ptr, size_t size)</code>	free an arena

`void PyObject_GetArenaAllocator (PyObjectArenaAllocator *allocator)`

Get the arena allocator.

`void PyObject_SetArenaAllocator (PyObjectArenaAllocator *allocator)`

Set the arena allocator.

## 11.10 tracemalloc C API

Novo na versão 3.7.

int **PyTraceMalloc\_Track** (unsigned int *domain*, uintptr\_t *ptr*, size\_t *size*)

Track an allocated memory block in the `tracemalloc` module.

Return 0 on success, return -1 on error (failed to allocate memory to store the trace). Return -2 if `tracemalloc` is disabled.

If memory block is already tracked, update the existing trace.

int **PyTraceMalloc\_Untrack** (unsigned int *domain*, uintptr\_t *ptr*)

Untrack an allocated memory block in the `tracemalloc` module. Do nothing if the block was not tracked.

Return -2 if `tracemalloc` is disabled, otherwise return 0.

## 11.11 Exemplos

Here is the example from section *Visão Geral*, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2);      /* Right -- allocated via malloc() */
free(buf1);      /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with `PyObject_New()`, `PyObject_NewVar()` and `PyObject_Del()`.

These will be explained in the next chapter on defining and implementing new object types in C.



---

## Suporte a implementação de Objetos

---

Este capítulo descreve as funções, tipos e macros usados ao definir novos tipos de objeto.

### 12.1 Alocando objetos na heap

*PyObject* \***PyObject\_New** (*PyTypeObject* \*type)

*Retorna valor:* Nova referência.

*PyVarObject* \***PyObject\_NewVar** (*PyTypeObject* \*type, *Py\_ssize\_t* size)

*Retorna valor:* Nova referência.

*PyObject* \***PyObject\_Init** (*PyObject* \*op, *PyTypeObject* \*type)

*Retorna valor:* Referência emprestada. *Part of the Stable ABI.* Inicializa um objeto *op* recém-alocado com seu tipo e referência inicial. Retorna o objeto inicializado. Se o *type* indica que o objeto participa no detector de lixo cíclico ele é adicionado ao grupo do detector de objetos observados. Outros campos do objeto não são afetados.

*PyVarObject* \***PyObject\_InitVar** (*PyVarObject* \*op, *PyTypeObject* \*type, *Py\_ssize\_t* size)

*Retorna valor:* Referência emprestada. *Part of the Stable ABI.* Isto faz tudo que o *PyObject\_Init()* faz e também inicializa a informação de comprimento para um objeto de tamanho variável.

**TYPE** \***PyObject\_New** (**TYPE**, *PyTypeObject* \*type)

*Retorna valor:* Nova referência. Allocate a new Python object using the C structure type *TYPE* and the Python type object *type*. Fields not defined by the Python object header are not initialized. The caller will own the only reference to the object (i.e. its reference count will be one). The size of the memory allocation is determined from the *tp\_basicsize* field of the type object.

**TYPE** \***PyObject\_NewVar** (**TYPE**, *PyTypeObject* \*type, *Py\_ssize\_t* size)

*Retorna valor:* Nova referência. Aloca um novo objeto Python usando o tipo de estrutura do C *TYPE* e o objeto Python do tipo *type*. Campos não definidos pelo cabeçalho do objeto Python não são inicializados. A memória alocada permite a estrutura *TYPE* e os campos *size* do tamanho dado pelo campo *tp\_itemsize* do tipo *type*. Isto é útil para implementar objetos como tuplas, as quais são capazes de determinar seu tamanho no tempo da construção. Incorporando o vetor de campos dentro da mesma alocação diminuindo o numero de alocações, melhorando a eficiência do gerenciamento de memória.

void **PyObject\_Del** (void \*op)

Libera memória alocada a um objeto usando `PyObject_New()` ou `PyObject_NewVar()`. Isto é normalmente chamado pelo `tp_dealloc` manipulador especificado no tipo do objeto. Os campos do objeto não devem ser acessados após esta chamada como a memória não é mais um objeto Python válido.

`PyObject_Py_NoneStruct`

Objeto o qual é visível no Python como `None`. Isto só deve ser acessado usando a macro `Py_None`, o qual avalia como um ponteiro para este objeto.

**Ver também:**

`PyModule_Create()` Para alocar e criar módulos de extensão.

## 12.2 Estruturas comuns de objetos

Existe um grande número de estruturas usadas para a definição de tipos objeto para o Python. Esta seção descreve essas estruturas e como são usadas.

### 12.2.1 Base object types and macros

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the `PyObject` and `PyVarObject` types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects.

**type `PyObject`**

*Part of the [Limited API](#). (Only some members are part of the stable ABI.)* All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal “release” build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a `PyObject`, but every pointer to a Python object can be cast to a `PyObject*`. Access to the members must be done by using the macros `Py_REFCNT` and `Py_TYPE`.

**type `PyVarObject`**

*Part of the [Limited API](#). (Only some members are part of the stable ABI.)* This is an extension of `PyObject` that adds the `ob_size` field. This is only used for objects that have some notion of *length*. This type does not often appear in the Python/C API. Access to the members must be done by using the macros `Py_REFCNT`, `Py_TYPE`, and `Py_SIZE`.

**`PyObject_HEAD`**

Este é um macro usado ao declarar novos tipos que representam objetos sem comprimento variável. O macro `PyObject_HEAD` se expande para:

```
PyObject ob_base;
```

Veja documentação de `PyObject` acima.

**`PyObject_VAR_HEAD`**

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The `PyObject_VAR_HEAD` macro expands to:

```
PyVarObject ob_base;
```

Veja documentação de `PyVarObject` acima.

int **`Py_Is`** (`const PyObject *x`, `const PyObject *y`)

*Part of the [Stable ABI since version 3.10](#).* Testa se o objeto `x` é o objeto `y`, o mesmo que `x is y` em Python.



Novo na versão 3.10.

int **Py\_IsNone** (**const** *PyObject* \*x)

Part of the [Stable ABI](#) since version 3.10. Test if an object is the None singleton, the same as `x is None` in Python.

Novo na versão 3.10.

int **Py\_IsTrue** (**const** *PyObject* \*x)

Part of the [Stable ABI](#) since version 3.10. Test if an object is the True singleton, the same as `x is True` in Python.

Novo na versão 3.10.

int **Py\_IsFalse** (**const** *PyObject* \*x)

Part of the [Stable ABI](#) since version 3.10. Test if an object is the False singleton, the same as `x is False` in Python.

Novo na versão 3.10.

*PyTypeObject* \***Py\_TYPE** (**const** *PyObject* \*o)

Get the type of the Python object *o*.

Return a *borrowed reference*.

Use the [Py\\_SET\\_TYPE\(\)](#) function to set an object type.

int **Py\_IS\_TYPE** (*PyObject* \*o, *PyTypeObject* \*type)

Return non-zero if the object *o* type is *type*. Return zero otherwise. Equivalent to: `Py_TYPE(o) == type`.

Novo na versão 3.9.

void **Py\_SET\_TYPE** (*PyObject* \*o, *PyTypeObject* \*type)

Set the object *o* type to *type*.

Novo na versão 3.9.

*Py\_ssize\_t* **Py\_REFCNT** (**const** *PyObject* \*o)

Get the reference count of the Python object *o*.

Alterado na versão 3.10: [Py\\_REFCNT\(\)](#) is changed to the inline static function. Use [Py\\_SET\\_REFCNT\(\)](#) to set an object reference count.

void **Py\_SET\_REFCNT** (*PyObject* \*o, *Py\_ssize\_t* refcnt)

Set the object *o* reference counter to *refcnt*.

Novo na versão 3.9.

*Py\_ssize\_t* **Py\_SIZE** (**const** *PyVarObject* \*o)

Get the size of the Python object *o*.

Use the [Py\\_SET\\_SIZE\(\)](#) function to set an object size.

void **Py\_SET\_SIZE** (*PyVarObject* \*o, *Py\_ssize\_t* size)

Set the object *o* size to *size*.

Novo na versão 3.9.

**PyObject\_HEAD\_INIT** (type)

This is a macro which expands to initialization values for a new *PyObject* type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

**PyVarObject\_HEAD\_INIT** (*type*, *size*)

This is a macro which expands to initialization values for a new *PyVarObject* type, including the *ob\_size* field. This macro expands to:

```
_PyObject_EXTRA_INIT  
1, type, size,
```

## 12.2.2 Implementing functions and methods

**type PyCFunction**

*Part of the Stable ABI.* Type of the functions used to implement most Python callables in C. Functions of this type take two *PyObject\** parameters and return one such value. If the return value is NULL, an exception shall have been set. If not NULL, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

A assinatura da função é:

```
PyObject *PyCFunction(PyObject *self,  
                      PyObject *args);
```

**type PyCFunctionWithKeywords**

*Part of the Stable ABI.* Type of the functions used to implement Python callables in C with signature *METH\_VARARGS* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *PyCFunctionWithKeywords(PyObject *self,  
                                  PyObject *args,  
                                  PyObject *kwargs);
```

**type \_PyCFunctionFast**

Type of the functions used to implement Python callables in C with signature *METH\_FASTCALL*. The function signature is:

```
PyObject *_PyCFunctionFast(PyObject *self,  
                           PyObject *const *args,  
                           Py_ssize_t nargs);
```

**type \_PyCFunctionFastWithKeywords**

Type of the functions used to implement Python callables in C with signature *METH\_FASTCALL* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *_PyCFunctionFastWithKeywords(PyObject *self,  
                                       PyObject *const *args,  
                                       Py_ssize_t nargs,  
                                       PyObject *kwnames);
```

**type PyCMethod**

Type of the functions used to implement Python callables in C with signature *METH\_METHOD* | *METH\_FASTCALL* | *METH\_KEYWORDS*. The function signature is:

```
PyObject *PyCMethod(PyObject *self,  
                    PyTypeObject *defining_class,  
                    PyObject *const *args,  
                    Py_ssize_t nargs,  
                    PyObject *kwnames)
```

Novo na versão 3.9.

**type PyMethodDef**

Part of the [Stable ABI](#) (including all members). Structure used to describe a method of an extension type. This structure has four fields:

```
const char *ml_name
    name of the method

PyCFunction ml_meth
    pointer to the C implementation

int ml_flags
    flags bits indicating how the call should be constructed

const char *ml_doc
    points to the contents of the docstring
```

The `ml_meth` is a C function pointer. The functions may be of different types, but they always return `PyObject*`. If the function is not of the `PyCFunction`, the compiler will require a cast in the method table. Even though `PyCFunction` defines the first parameter as `PyObject*`, it is common that the method implementation uses the specific C type of the *self* object.

The `ml_flags` field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are these calling conventions:

**METH\_VARARGS**

This is the typical calling convention, where the methods have the type `PyCFunction`. The function expects two `PyObject*` values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using `PyArg_ParseTuple()` or `PyArg_UnpackTuple()`.

**METH\_VARARGS | METH\_KEYWORDS**

Methods with these flags must be of type `PyCFunctionWithKeywords`. The function expects three parameters: *self*, *args*, *kwargs* where *kwargs* is a dictionary of all the keyword arguments or possibly `NULL` if there are no keyword arguments. The parameters are typically processed using `PyArg_ParseTupleAndKeywords()`.

**METH\_FASTCALL**

Fast calling convention supporting only positional arguments. The methods have the type `_PyCFunctionFast`. The first parameter is *self*, the second parameter is a C array of `PyObject*` values indicating the arguments and the third parameter is the number of arguments (the length of the array).

Novo na versão 3.7.

Alterado na versão 3.10: `METH_FASTCALL` is now part of the stable ABI.

**METH\_FASTCALL | METH\_KEYWORDS**

Extension of `METH_FASTCALL` supporting also keyword arguments, with methods of type `_PyCFunctionFastWithKeywords`. Keyword arguments are passed the same way as in the *vector-call protocol*: there is an additional fourth `PyObject*` parameter which is a tuple representing the names of the keyword arguments (which are guaranteed to be strings) or possibly `NULL` if there are no keywords. The values of the keyword arguments are stored in the *args* array, after the positional arguments.

Novo na versão 3.7.

**METH\_METHOD | METH\_FASTCALL | METH\_KEYWORDS**

Extension of `METH_FASTCALL | METH_KEYWORDS` supporting the *defining class*, that is, the class that contains the method in question. The defining class might be a superclass of `Py_TYPE(self)`.

The method needs to be of type `PyCMethod`, the same as for `METH_FASTCALL | METH_KEYWORDS` with `defining_class` argument added after *self*.

Novo na versão 3.9.

**METH\_NOARGS**

Methods without parameters don't need to check whether arguments are given if they are listed with the `METH_NOARGS` flag. They need to be of type `PyCFunction`. The first parameter is typically named *self* and will hold a reference to the module or object instance. In all cases the second parameter will be `NULL`.

**METH\_O**

Methods with a single object argument can be listed with the `METH_O` flag, instead of invoking `PyArg_ParseTuple()` with a "O" argument. They have the type `PyCFunction`, with the *self* parameter, and a `PyObject*` parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

**METH\_CLASS**

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the `classmethod()` built-in function.

**METH\_STATIC**

The method will be passed `NULL` as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the `staticmethod()` built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

**METH\_COEXIST**

The method will be loaded in place of existing definitions. Without `METH_COEXIST`, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a `sq_contains` slot, for example, would generate a wrapped method named `__contains__()` and preclude the loading of a corresponding `PyCFunction` with the same name. With the flag defined, the `PyCFunction` will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to `PyCFunctions` are optimized more than wrapper object calls.

## 12.2.3 Accessing attributes of extension types

**type PyMemberDef**

Part of the [Stable ABI](#) (including all members). Structure which describes an attribute of a type which corresponds to a C struct member. Its fields are:

Campo	Tipo em C	Significado
name	const char *	name of the member
type	int	the type of the member in the C struct
offset	Py_ssize_t	the offset in bytes that the member is located on the type's object struct
flags	int	flag bits indicating if the field should be read-only or writable
doc	const char *	points to the contents of the docstring

`type` can be one of many `T_` macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type.

Macro name	Tipo em C
T_SHORT	short
T_INT	int
T_LONG	long
T_FLOAT	ponto flutuante
T_DOUBLE	double
T_STRING	const char *
T_OBJECT	PyObject *
T_OBJECT_EX	PyObject *
T_CHAR	char
T_BYTE	char
T_UBYTE	unsigned char
T_UINT	unsigned int
T_USHORT	unsigned short
T_ULONG	unsigned long
T_BOOL	char
T_LONGLONG	long long
T_ULONGLONG	unsigned long long
T_PYSSIZET	Py_ssize_t

T\_OBJECT and T\_OBJECT\_EX differ in that T\_OBJECT returns None if the member is NULL and T\_OBJECT\_EX raises an AttributeError. Try to use T\_OBJECT\_EX over T\_OBJECT because T\_OBJECT\_EX handles use of the del statement on that attribute more correctly than T\_OBJECT.

flags can be 0 for write and read access or READONLY for read-only access. Using T\_STRING for type implies READONLY. T\_STRING data is interpreted as UTF-8. Only T\_OBJECT and T\_OBJECT\_EX members can be deleted. (They are set to NULL).

Heap allocated types (created using `PyType_FromSpec()` or similar), PyMemberDef may contain definitions for the special members `__dictoffset__`, `__weaklistoffset__` and `__vectorcalloffset__`, corresponding to `tp_dictoffset`, `tp_weaklistoffset` and `tp_vectorcall_offset` in type objects. These must be defined with T\_PYSSIZET and READONLY, for example:

```
static PyMemberDef spam_type_members[] = {
    {"__dictoffset__", T_PYSSIZET, offsetof(Spam_object, dict), READONLY},
    {NULL} /* Sentinel */
};
```

*PyObject \****PyMember\_GetOne** (**const** char \**obj\_addr*, **struct** *PyMemberDef* \**m*)

Get an attribute belonging to the object at address *obj\_addr*. The attribute is described by *PyMemberDef* *m*. Returns NULL on error.

**int** **PyMember\_SetOne** (char \**obj\_addr*, **struct** *PyMemberDef* \**m*, *PyObject* \**o*)

Set an attribute belonging to the object at address *obj\_addr* to object *o*. The attribute to set is described by *PyMemberDef* *m*. Returns 0 if successful and a negative value on failure.

**type** **PyGetSetDef**

Part of the [Stable ABI](#) (including all members). Structure to define property-like access for a type. See also description of the `PyTypeObject.tp_getset` slot.

Campo	Tipo em C	Significado
nome	const char *	attribute name
get	getter	C function to get the attribute
set	setter	optional C function to set or delete the attribute, if omitted the attribute is readonly
doc	const char *	optional docstring
closure	void *	optional function pointer, providing additional data for getter and setter

The `get` function takes one `PyObject*` parameter (the instance) and a function pointer (the associated closure):

```
typedef PyObject *(*getter)(PyObject *, void *);
```

It should return a new reference on success or NULL with a set exception on failure.

`set` functions take two `PyObject*` parameters (the instance and the value to be set) and a function pointer (the associated closure):

```
typedef int (*setter)(PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

## 12.3 Objetos tipo

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the `PyTypeObject` structure. Type objects can be handled using any of the `PyObject_*` or `PyType_*` functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Os objetos de tipo são bastante grandes em comparação com a maioria dos tipos padrão. A razão para o tamanho é que cada objeto de tipo armazena um grande número de valores, principalmente indicadores de função C, cada um dos quais implementa uma pequena parte da funcionalidade do tipo. Os campos do objeto de tipo são examinados em detalhes nesta seção. Os campos serão descritos na ordem em que ocorrem na estrutura.

Além da referência rápida a seguir, a seção [Exemplos](#) fornece uma visão geral do significado e uso de `PyTypeObject`.

### 12.3.1 Referências rápidas

“slots tp”

Slot de <code>PyTypeObject</code> <sup>1</sup>	Tipo	métodos/atributos especiais	Info <sup>2</sup>				
			O	T	D	I	
<R> <code>tp_name</code>	const char *	<code>__name__</code>	X	X			
<code>tp_basicsize</code>	<code>Py_ssize_t</code>		X	X		X	
<code>tp_itemsize</code>	<code>Py_ssize_t</code>			X		X	
<code>tp_dealloc</code>	destructor		X	X		X	
<code>tp_vectorcall_offset</code>	<code>Py_ssize_t</code>			X		X	
( <code>tp_getattr</code> )	<code>getattrfunc</code>	<code>__getattribute__</code> , <code>__getattr__</code>					G
( <code>tp_setattr</code> )	<code>setattrfunc</code>	<code>__setattr__</code> , <code>__delattr__</code>					G
<code>tp_as_async</code>	<code>PyAsyncMethods</code> *	<code>sub-slots</code>					%

continua na próxima página

Tabela 1 – continuação da página anterior

Slot de PyTypeObject <sup>1</sup>	Tipo	métodos/atributos especiais	Info <sup>2</sup>				
			O	T	D	I	
<code>tp_repr</code>	<code>reprfunc</code>	<code>__repr__</code>	X	X			X
<code>tp_as_number</code>	<code>PyNumberMethods *</code>	<code>sub-slots</code>					%
<code>tp_as_sequence</code>	<code>PySequenceMethods *</code>	<code>sub-slots</code>					%
<code>tp_as_mapping</code>	<code>PyMappingMethods *</code>	<code>sub-slots</code>					%
<code>tp_hash</code>	<code>hashfunc</code>	<code>__hash__</code>	X				G
<code>tp_call</code>	<code>ternaryfunc</code>	<code>__call__</code>		X			X
<code>tp_str</code>	<code>reprfunc</code>	<code>__str__</code>	X				X
<code>tp_getattro</code>	<code>getattrofunc</code>	<code>__getattr__</code> , <code>__getattribute__</code>	X	X			G
<code>tp_setattro</code>	<code>setattrofunc</code>	<code>__setattr__</code> , <code>__delattr__</code>	X	X			G
<code>tp_as_buffer</code>	<code>PyBufferProcs *</code>						%
<code>tp_flags</code>	<code>unsigned long</code>		X	X			?
<code>tp_doc</code>	<code>const char *</code>	<code>__doc__</code>	X	X			
<code>tp_traverse</code>	<code>traverseproc</code>			X			G
<code>tp_clear</code>	<code>inquiry</code>			X			G
<code>tp_richcompare</code>	<code>richcmpfunc</code>	<code>__lt__</code> , <code>__le__</code> , <code>__eq__</code> , <code>__ne__</code> , <code>__gt__</code> , <code>__ge__</code>	X				G
<code>tp_weaklistoffset</code>	<code>Py_ssize_t</code>			X			?
<code>tp_iter</code>	<code>getiterfunc</code>	<code>__iter__</code>					X
<code>tp_iternext</code>	<code>iternextfunc</code>	<code>__next__</code>					X
<code>tp_methods</code>	<code>PyMethodDef []</code>		X	X			
<code>tp_members</code>	<code>PyMemberDef []</code>			X			
<code>tp_getset</code>	<code>PyGetSetDef []</code>		X	X			
<code>tp_base</code>	<code>PyTypeObject *</code>	<code>__base__</code>			X		
<code>tp_dict</code>	<code>PyObject *</code>	<code>__dict__</code>			?		
<code>tp_descr_get</code>	<code>descrgetfunc</code>	<code>__get__</code>					X
<code>tp_descr_set</code>	<code>descrsetfunc</code>	<code>__set__</code> , <code>__delete__</code>					X
<code>tp_dictoffset</code>	<code>Py_ssize_t</code>			X			?
<code>tp_init</code>	<code>initproc</code>	<code>__init__</code>	X	X			X
<code>tp_alloc</code>	<code>allocfunc</code>		X		?	?	
<code>tp_new</code>	<code>newfunc</code>	<code>__new__</code>	X	X	?	?	
<code>tp_free</code>	<code>freefunc</code>		X	X	?	?	
<code>tp_is_gc</code>	<code>inquiry</code>			X			X
<code>&lt;tp_bases&gt;</code>	<code>PyObject *</code>	<code>__bases__</code>			~		
<code>&lt;tp_mro&gt;</code>	<code>PyObject *</code>	<code>__mro__</code>			~		
<code>[tp_cache]</code>	<code>PyObject *</code>						
<code>[tp_subclasses]</code>	<code>PyObject *</code>	<code>__subclasses__</code>					
<code>[tp_weaklist]</code>	<code>PyObject *</code>						
<code>(tp_del)</code>	<code>destructor</code>						
<code>[tp_version_tag]</code>	<code>unsigned int</code>						
<code>tp_finalize</code>	<code>destructor</code>	<code>__del__</code>					X
<code>tp_vectorcall</code>	<code>vectorcallfunc</code>						

<sup>1</sup> (): A slot name in parentheses indicates it is (effectively) deprecated.

&lt;&gt;: Names in angle brackets should be initially set to NULL and treated as read-only.

[]: Names in square brackets are for internal use only.

&lt;R&gt; (as a prefix) means the field is required (must be non-NULL).

<sup>2</sup> Columns:“O”: set on `PyBaseObject_Type`“T”: set on `PyType_Type`

“D”: default (if slot is set to NULL)

## sub-slots

Slot	Tipo	special methods
<code>am_await</code>	<code>unaryfunc</code>	<code>__await__</code>
<code>am_aiter</code>	<code>unaryfunc</code>	<code>__aiter__</code>
<code>am_anext</code>	<code>unaryfunc</code>	<code>__anext__</code>
<code>am_send</code>	<code>sendfunc</code>	
<code>nb_add</code>	<code>binaryfunc</code>	<code>__add__</code> <code>__radd__</code>
<code>nb_inplace_add</code>	<code>binaryfunc</code>	<code>__iadd__</code>
<code>nb_subtract</code>	<code>binaryfunc</code>	<code>__sub__</code> <code>__rsub__</code>
<code>nb_inplace_subtract</code>	<code>binaryfunc</code>	<code>__isub__</code>
<code>nb_multiply</code>	<code>binaryfunc</code>	<code>__mul__</code> <code>__rmul__</code>
<code>nb_inplace_multiply</code>	<code>binaryfunc</code>	<code>__imul__</code>
<code>nb_remainder</code>	<code>binaryfunc</code>	<code>__mod__</code> <code>__rmod__</code>
<code>nb_inplace_remainder</code>	<code>binaryfunc</code>	<code>__imod__</code>
<code>nb_divmod</code>	<code>binaryfunc</code>	<code>__divmod__</code> <code>__rdivmod__</code>
<code>nb_power</code>	<code>ternaryfunc</code>	<code>__pow__</code> <code>__rpow__</code>
<code>nb_inplace_power</code>	<code>ternaryfunc</code>	<code>__ipow__</code>
<code>nb_negative</code>	<code>unaryfunc</code>	<code>__neg__</code>
<code>nb_positive</code>	<code>unaryfunc</code>	<code>__pos__</code>
<code>nb_absolute</code>	<code>unaryfunc</code>	<code>__abs__</code>
<code>nb_bool</code>	<code>inquiry</code>	<code>__bool__</code>
<code>nb_invert</code>	<code>unaryfunc</code>	<code>__invert__</code>
<code>nb_lshift</code>	<code>binaryfunc</code>	<code>__lshift__</code> <code>__rlshift__</code>
<code>nb_inplace_lshift</code>	<code>binaryfunc</code>	<code>__ilshift__</code>
<code>nb_rshift</code>	<code>binaryfunc</code>	<code>__rshift__</code> <code>__rrshift__</code>
<code>nb_inplace_rshift</code>	<code>binaryfunc</code>	<code>__irshift__</code>
<code>nb_and</code>	<code>binaryfunc</code>	<code>__and__</code> <code>__rand__</code>
<code>nb_inplace_and</code>	<code>binaryfunc</code>	<code>__iand__</code>
<code>nb_xor</code>	<code>binaryfunc</code>	<code>__xor__</code> <code>__rxor__</code>
<code>nb_inplace_xor</code>	<code>binaryfunc</code>	<code>__ixor__</code>
<code>nb_or</code>	<code>binaryfunc</code>	<code>__or__</code> <code>__ror__</code>
<code>nb_inplace_or</code>	<code>binaryfunc</code>	<code>__ior__</code>
<code>nb_int</code>	<code>unaryfunc</code>	<code>__int__</code>
<code>nb_reserved</code>	<code>void *</code>	
<code>nb_float</code>	<code>unaryfunc</code>	<code>__float__</code>
<code>nb_floor_divide</code>	<code>binaryfunc</code>	<code>__floordiv__</code>
<code>nb_inplace_floor_divide</code>	<code>binaryfunc</code>	<code>__ifloordiv__</code>
<code>nb_true_divide</code>	<code>binaryfunc</code>	<code>__truediv__</code>

X - PyType\_Ready sets this value if it is NULL  
~ - PyType\_Ready always sets this value (it should be NULL)  
? - PyType\_Ready may set this value depending on other slots

Also see the inheritance column ("I").

"I": inheritance

X - type slot is inherited via \*PyType\_Ready\* if defined with a \*NULL\* value  
% - the slots of the sub-struct are inherited individually  
G - inherited, but only in combination with other slots; see the slot's description  
? - it's complicated; see the slot's description

Note that some slots are effectively inherited through the normal attribute lookup chain.



Tabela 2 – continuação da página anterior

Slot	Tipo	special methods
<i>nb_matrix_multiply</i>	<i>binaryfunc</i>	<code>__matmul__</code> <code>__rmatmul__</code>
<i>nb_inplace_matrix_multiply</i>	<i>binaryfunc</i>	<code>__imatmul__</code>
<i>mp_length</i>	<i>lenfunc</i>	<code>__len__</code>
<i>mp_subscript</i>	<i>binaryfunc</i>	<code>__getitem__</code>
<i>mp_ass_subscript</i>	<i>objobjargproc</i>	<code>__setitem__</code> , <code>__delitem__</code>
<i>sq_length</i>	<i>lenfunc</i>	<code>__len__</code>
<i>sq_concat</i>	<i>binaryfunc</i>	<code>__add__</code>
<i>sq_repeat</i>	<i>ssizeargfunc</i>	<code>__mul__</code>
<i>sq_item</i>	<i>ssizeargfunc</i>	<code>__getitem__</code>
<i>sq_ass_item</i>	<i>ssizeobjargproc</i>	<code>__setitem__</code> <code>__delitem__</code>
<i>sq_contains</i>	<i>objobjproc</i>	<code>__contains__</code>
<i>sq_inplace_concat</i>	<i>binaryfunc</i>	<code>__iadd__</code>
<i>sq_inplace_repeat</i>	<i>ssizeargfunc</i>	<code>__imul__</code>
<i>bf_getbuffer</i>	<i>getbufferproc()</i>	
<i>bf_releasebuffer</i>	<i>releasebufferproc()</i>	

## slot typedefs

typedef	Parameter Types	Return Type
<i>allocfunc</i>	<i>PyTypeObject</i> * <i>Py_ssize_t</i>	<i>PyObject</i> *
<i>destructor</i>	<b>void</b> *	<b>void</b>
<i>freefunc</i>	<b>void</b> *	<b>void</b>
<i>traverseproc</i>	<b>void</b> * <i>visitproc</i> <b>void</b> *	<b>int</b>
<i>newfunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<i>initproc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<b>int</b>
<i>reprfunc</i>	<i>PyObject</i> *	<i>PyObject</i> *
<i>getattrfunc</i>	<i>PyObject</i> * <b>const char</b> *	<i>PyObject</i> *
<i>setattrfunc</i>	<i>PyObject</i> * <b>const char</b> * <i>PyObject</i> *	<b>int</b>
<i>getattrofunc</i>	<i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<i>setattrofunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<b>int</b>
<i>descrgetfunc</i>	<i>PyObject</i> * <i>PyObject</i> * <i>PyObject</i> *	<i>PyObject</i> *
<b>250</b> <i>descrsetfunc</i>	<i>PyObject</i> * <i>PyObject</i> *	<b>int</b>

See *Slot Type typedefs* below for more detail.

### 12.3.2 PyTypeObject Definition

The structure definition for *PyTypeObject* can be found in `Include/object.h`. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
    PyObject_VAR_HEAD
    const char *tp_name; /* For printing, in format "<module>.<name>" */
    Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */

    /* Methods to implement standard operations */

    destructor tp_dealloc;
    Py_ssize_t tp_vectorcall_offset;
    getattrofunc tp_getattr;
    setattrofunc tp_setattr;
    PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                   or tp_reserved (Python 3) */
    reprfunc tp_repr;

    /* Method suites for standard classes */

    PyNumberMethods *tp_as_number;
    PySequenceMethods *tp_as_sequence;
    PyMappingMethods *tp_as_mapping;

    /* More standard operations (here for binary compatibility) */

    hashfunc tp_hash;
    ternaryfunc tp_call;
    reprfunc tp_str;
    getattrofunc tp_getattro;
    setattrofunc tp_setattro;

    /* Functions to access object as input/output buffer */
    PyBufferProcs *tp_as_buffer;

    /* Flags to define presence of optional/expanded features */
    unsigned long tp_flags;

    const char *tp_doc; /* Documentation string */

    /* Assigned meaning in release 2.0 */
    /* call function for all accessible objects */
    traverseproc tp_traverse;

    /* delete references to contained objects */
    inquiry tp_clear;

    /* Assigned meaning in release 2.1 */
    /* rich comparisons */
    richcmpfunc tp_richcompare;

    /* weak reference enabler */
    Py_ssize_t tp_weaklistoffset;
```

(continua na próxima página)

```

/* Iterators */
getiterfunc tp_iter;
iternextfunc tp_iternext;

/* Attribute descriptor and subclassing stuff */
struct PyMethodDef *tp_methods;
struct PyMemberDef *tp_members;
struct PyGetSetDef *tp_getset;
// Strong reference on a heap type, borrowed reference on a static type
struct _typeobject *tp_base;
PyObject *tp_dict;
descrgetfunc tp_descr_get;
descrsetfunc tp_descr_set;
Py_ssize_t tp_dictoffset;
initproc tp_init;
allocfunc tp_alloc;
newfunc tp_new;
freefunc tp_free; /* Low-level free-memory routine */
inquiry tp_is_gc; /* For PyObject_IS_GC */
PyObject *tp_bases;
PyObject *tp_mro; /* method resolution order */
PyObject *tp_cache;
PyObject *tp_subclasses;
PyObject *tp_weaklist;
destructor tp_del;

/* Type attribute cache version tag. Added in version 2.6 */
unsigned int tp_version_tag;

destructor tp_finalize;
vectorcallfunc tp_vectorcall;
} PyTypeObject;

```

### 12.3.3 PyObject Slots

The type object structure extends the *PyVarObject* structure. The *ob\_size* field is used for dynamic types (created by *type\_new()*, usually called from a class statement). Note that *PyType\_Type* (the metatype) initializes *tp\_itemsize*, which means that its instances (i.e. type objects) *must* have the *ob\_size* field.

#### *Py\_ssize\_t* *PyObject.ob\_refcnt*

*Part of the Stable ABI.* This is the type object's reference count, initialized to 1 by the *PyObject\_HEAD\_INIT* macro. Note that for *statically allocated type objects*, the type's instances (objects whose *ob\_type* points back to the type) do *not* count as references. But for *dynamically allocated type objects*, the instances *do* count as references.

#### Inheritance:

This field is not inherited by subtypes.

#### *PyTypeObject* \**PyObject.ob\_type*

*Part of the Stable ABI.* This is the type's type, in other words its metatype. It is initialized by the argument to the *PyObject\_HEAD\_INIT* macro, and its value should normally be *&PyType\_Type*. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass *NULL* to the *PyObject\_HEAD\_INIT* macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. `PyType_Ready()` checks if `ob_type` is NULL, and if so, initializes it to the `ob_type` field of the base class. `PyType_Ready()` will not change this field if it is non-zero.

**Inheritance:**

This field is inherited by subtypes.

*PyObject* \**PyObject*.**\_\_ob\_next**

*PyObject* \**PyObject*.**\_\_ob\_prev**

These fields are only present when the macro `Py_TRACE_REFS` is defined (see the configure `--with-trace-refs` option).

Their initialization to NULL is taken care of by the `PyObject_HEAD_INIT` macro. For *statically allocated objects*, these fields always remain NULL. For *dynamically allocated objects*, these two fields are used to link the object into a doubly linked list of *all* live objects on the heap.

This could be used for various debugging purposes; currently the only uses are the `sys.getobjects()` function and to print the objects that are still alive at the end of a run when the environment variable `PYTHONDUMPREFS` is set.

**Inheritance:**

These fields are not inherited by subtypes.

### 12.3.4 PyVarObject Slots

*Py\_ssize\_t* *PyVarObject*.**ob\_size**

*Part of the Stable ABI.* For *statically allocated type objects*, this should be initialized to zero. For *dynamically allocated type objects*, this field has a special internal meaning.

**Inheritance:**

This field is not inherited by subtypes.

### 12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If `PyType_Ready()` may set a value when the field is set to NULL then there will also be a “Default” section. (Note that many fields set on `PyBaseObject_Type` and `PyType_Type` effectively act as defaults.)

**const char** \**PyTypeObject*.**tp\_name**

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named `T` defined in module `M` in subpackage `Q` in package `P` should have the `tp_name` initializer `"P.Q.M.T"`.

For *dynamically allocated type objects*, this should just be the type name, and the module name explicitly stored in the type dict as the value for key `'__module__'`.

For *statically allocated type objects*, the `tp_name` field should contain a dot. Everything before the last dot is made accessible as the `__module__` attribute, and everything after the last dot is made accessible as the `__name__` attribute.

If no dot is present, the entire `tp_name` field is made accessible as the `__name__` attribute, and the `__module__` attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with `pydoc`.

This field must not be `NULL`. It is the only required field in `PyTypeObject()` (other than potentially `tp_itemsize`).

**Inheritance:**

This field is not inherited by subtypes.

*Py\_ssize\_t* `PyTypeObject.tp_basicsize`

*Py\_ssize\_t* `PyTypeObject.tp_itemsize`

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero `tp_itemsize` field, types with variable-length instances have a non-zero `tp_itemsize` field. For a type with fixed-length instances, all instances have the same size, given in `tp_basicsize`.

For a type with variable-length instances, the instances must have an `ob_size` field, and the instance size is `tp_basicsize` plus N times `tp_itemsize`, where N is the “length” of the object. The value of N is typically stored in the instance’s `ob_size` field. There are exceptions: for example, ints use a negative `ob_size` to indicate a negative number, and N is `abs(ob_size)` there. Also, the presence of an `ob_size` field in the instance layout doesn’t mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful `ob_size` field).

The basic size includes the fields in the instance declared by the macro `PyObject_HEAD` or `PyObject_VAR_HEAD` (whichever is used to declare the instance struct) and this in turn includes the `_ob_prev` and `_ob_next` fields if they are present. This means that the only correct way to get an initializer for the `tp_basicsize` is to use the `sizeof` operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of `tp_basicsize`. Example: suppose a type implements an array of double. `tp_itemsize` is `sizeof(double)`. It is the programmer’s responsibility that `tp_basicsize` is a multiple of `sizeof(double)` (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be `NULL`.

**Inheritance:**

These fields are inherited separately by subtypes. If the base type has a non-zero `tp_itemsize`, it is generally not safe to set `tp_itemsize` to a different non-zero value in a subtype (though this depends on the implementation of the base type).

*destructor* `PyTypeObject.tp_dealloc`

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons `None` and `Ellipsis`). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the `Py_DECREF()` and `Py_XDECREF()` macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type’s `tp_free` function. If the type is not subtypable (doesn’t have the `Py_TPFLAGS_BASETYPE` flag bit set), it is permissible to call the object deallocator directly instead of via `tp_free`. The object deallocator

should be the one used to allocate the instance; this is normally `PyObject_Del()` if the instance was allocated using `PyObject_New()` or `PyObject_VarNew()`, or `PyObject_GC_Del()` if the instance was allocated using `PyObject_GC_New()` or `PyObject_GC_NewVar()`.

If the type supports garbage collection (has the `Py_TPFLAGS_HAVE_GC` flag bit set), the destructor should call `PyObject_GC_UnTrack()` before clearing any member fields.

```
static void foo_dealloc(foo_object *self) {
    PyObject_GC_UnTrack(self);
    Py_CLEAR(self->ref);
    Py_TYPE(self)->tp_free((PyObject *)self);
}
```

Finally, if the type is heap allocated (`Py_TPFLAGS_HEAPTYPE`), the deallocator should release the owned reference to its type object (via `Py_DECREF()`) after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is:

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
    // free references and buffers here
    tp->tp_free(self);
    Py_DECREF(tp);
}
```

#### Inheritance:

This field is inherited by subtypes.

#### `Py_ssize_t PyTypeObject.tp_vectorcall_offset`

An optional offset to a per-instance function that implements calling the object using the *vectorcall protocol*, a more efficient alternative of the simpler `tp_call`.

This field is only used if the flag `Py_TPFLAGS_HAVE_VECTORCALL` is set. If so, this must be a positive integer containing the offset in the instance of a *vectorcallfunc* pointer.

The *vectorcallfunc* pointer may be NULL, in which case the instance behaves as if `Py_TPFLAGS_HAVE_VECTORCALL` was not set: calling the instance falls back to `tp_call`.

Any class that sets `Py_TPFLAGS_HAVE_VECTORCALL` must also set `tp_call` and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting `tp_call` to `PyVectorcall_Call()`.

**Aviso:** It is not recommended for *heap types* to implement the vectorcall protocol. When a user sets `__call__` in Python code, only `tp_call` is updated, likely making it inconsistent with the vectorcall function.

Alterado na versão 3.8: Before version 3.8, this slot was named `tp_print`. In Python 2.x, it was used for printing to a file. In Python 3.0 to 3.7, it was unused.

#### Inheritance:

This field is always inherited. However, the `Py_TPFLAGS_HAVE_VECTORCALL` flag is not always inherited. If it's not, then the subclass won't use *vectorcall*, except when `PyVectorcall_Call()` is explicitly called. This is in particular the case for *heap types* (including subclasses defined in Python).

#### `getattrfunc PyTypeObject.tp_getattr`

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the `tp_getattro` function, but taking a C string instead of a Python string object to give the attribute name.

**Inheritance:**

Group: `tp_getattr`, `tp_getattro`

This field is inherited by subtypes together with `tp_getattro`: a subtype inherits both `tp_getattr` and `tp_getattro` from its base type when the subtype's `tp_getattr` and `tp_getattro` are both NULL.

*setattrfunc* `PyTypeObject.tp_setattr`

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the `tp_setattro` function, but taking a C string instead of a Python string object to give the attribute name.

**Inheritance:**

Group: `tp_setattr`, `tp_setattro`

This field is inherited by subtypes together with `tp_setattro`: a subtype inherits both `tp_setattr` and `tp_setattro` from its base type when the subtype's `tp_setattr` and `tp_setattro` are both NULL.

*PyAsyncMethods* \*`PyTypeObject.tp_as_async`

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

Novo na versão 3.5: Formerly known as `tp_compare` and `tp_reserved`.

**Inheritance:**

The `tp_as_async` field is not inherited, but the contained fields are inherited individually.

*reprfunc* `PyTypeObject.tp_repr`

An optional pointer to a function that implements the built-in function `repr()`.

The signature is the same as for `PyObject_Repr()`:

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to `eval()`, given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '`<`' and ending with '`>`' from which both the type and the value of the object can be deduced.

**Inheritance:**

This field is inherited by subtypes.

**Padrão:**

When this field is not set, a string of the form `<%s object at %p>` is returned, where `%s` is replaced by the type name, and `%p` by the object's memory address.

*PyNumberMethods* \*`PyTypeObject.tp_as_number`

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

**Inheritance:**

The `tp_as_number` field is not inherited, but the contained fields are inherited individually.

*PySequenceMethods* \*`PyTypeObject.tp_as_sequence`

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

**Inheritance:**

The `tp_as_sequence` field is not inherited, but the contained fields are inherited individually.



*PyMappingMethods* \*PyTypeObject.tp\_as\_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

**Inheritance:**

The *tp\_as\_mapping* field is not inherited, but the contained fields are inherited individually.

*hashfunc* PyTypeObject.tp\_hash

An optional pointer to a function that implements the built-in function `hash()`.

The signature is the same as for *PyObject\_Hash()*:

```
Py_hash_t tp_hash(PyObject *);
```

The value `-1` should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return `-1`.

When this field is not set (and *tp\_richcompare* is not set), an attempt to take the hash of the object raises `TypeError`. This is the same as setting it to *PyObject\_HashNotImplemented()*.

This field can be set explicitly to *PyObject\_HashNotImplemented()* to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of `__hash__ = None` at the Python level, causing `isinstance(o, collections.Hashable)` to correctly return `False`. Note that the converse is also true - setting `__hash__ = None` on a class at the Python level will result in the *tp\_hash* slot being set to *PyObject\_HashNotImplemented()*.

**Inheritance:**

Group: *tp\_hash*, *tp\_richcompare*

This field is inherited by subtypes together with *tp\_richcompare*: a subtype inherits both of *tp\_richcompare* and *tp\_hash*, when the subtype's *tp\_richcompare* and *tp\_hash* are both `NULL`.

*ternaryfunc* PyTypeObject.tp\_call

An optional pointer to a function that implements calling the object. This should be `NULL` if the object is not callable. The signature is the same as for *PyObject\_Call()*:

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

**Inheritance:**

This field is inherited by subtypes.

*reprfunc* PyTypeObject.tp\_str

An optional pointer to a function that implements the built-in operation `str()`. (Note that `str` is a type now, and `str()` calls the constructor for that type. This constructor calls *PyObject\_Str()* to do the actual work, and *PyObject\_Str()* will call this handler.)

The signature is the same as for *PyObject\_Str()*:

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a “friendly” string representation of the object, as this is the representation that will be used, among other things, by the `print()` function.

**Inheritance:**

This field is inherited by subtypes.

**Padrão:**

When this field is not set, *PyObject\_Repr()* is called to return a string representation.

*getattrofunc* `PyTypeObject.tp_getattro`

An optional pointer to the get-attribute function.

The signature is the same as for `PyObject_GetAttr()`:

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to `PyObject_GenericGetAttr()`, which implements the normal way of looking for object attributes.

**Inheritance:**

Group: `tp_getattr`, `tp_getattro`

This field is inherited by subtypes together with `tp_getattr`: a subtype inherits both `tp_getattr` and `tp_getattro` from its base type when the subtype's `tp_getattr` and `tp_getattro` are both NULL.

**Padrão:**

`PyBaseObject_Type` uses `PyObject_GenericGetAttr()`.

*setattrofunc* `PyTypeObject.tp_setattro`

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for `PyObject_SetAttr()`:

```
int tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to NULL to delete an attribute must be supported. It is usually convenient to set this field to `PyObject_GenericSetAttr()`, which implements the normal way of setting object attributes.

**Inheritance:**

Group: `tp_setattr`, `tp_setattro`

This field is inherited by subtypes together with `tp_setattr`: a subtype inherits both `tp_setattr` and `tp_setattro` from its base type when the subtype's `tp_setattr` and `tp_setattro` are both NULL.

**Padrão:**

`PyBaseObject_Type` uses `PyObject_GenericSetAttr()`.

*PyBufferProcs* \*`PyTypeObject.tp_as_buffer`

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

**Inheritance:**

The `tp_as_buffer` field is not inherited, but the contained fields are inherited individually.

unsigned long `PyTypeObject.tp_flags`

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via `tp_as_number`, `tp_as_sequence`, `tp_as_mapping`, and `tp_as_buffer`) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

**Inheritance:**

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The `Py_TPFLAGS_HAVE_GC` flag bit is inherited together with the

`tp_traverse` and `tp_clear` fields, i.e. if the `Py_TPFLAGS_HAVE_GC` flag bit is clear in the subtype and the `tp_traverse` and `tp_clear` fields in the subtype exist and have NULL values.

**Padrão:**

`PyBaseObject_Type` uses `Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE`.

**Bit Masks:**

The following bit masks are currently defined; these can be ORed together using the `|` operator to form the value of the `tp_flags` field. The macro `PyType_HasFeature()` takes a type and a flags value, `tp` and `f`, and checks whether `tp->tp_flags & f` is non-zero.

**Py\_TPFLAGS\_HEAPTYPE**

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using `PyType_FromSpec()`. In this case, the `ob_type` field of its instances is considered a reference to the type, and the type object is INCREf'ed when a new instance is created, and DECREf'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's `ob_type` gets INCREf'ed or DECREf'ed).

**Inheritance:**

???

**Py\_TPFLAGS\_BASETYPE**

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a “final” class in Java).

**Inheritance:**

???

**Py\_TPFLAGS\_READY**

This bit is set when the type object has been fully initialized by `PyType_Ready()`.

**Inheritance:**

???

**Py\_TPFLAGS\_READYING**

This bit is set while `PyType_Ready()` is in the process of initializing the type object.

**Inheritance:**

???

**Py\_TPFLAGS\_HAVE\_GC**

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using `PyObject_GC_New()` and destroyed using `PyObject_GC_Del()`. More information in section *Suporte a Coleta Cíclica de Lixo*. This bit also implies that the GC-related fields `tp_traverse` and `tp_clear` are present in the type object.

**Inheritance:**

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

The `Py_TPFLAGS_HAVE_GC` flag bit is inherited together with the `tp_traverse` and `tp_clear` fields, i.e. if the `Py_TPFLAGS_HAVE_GC` flag bit is clear in the subtype and the `tp_traverse` and `tp_clear` fields in the subtype exist and have NULL values.

**Py\_TPFLAGS\_DEFAULT**

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: `Py_TPFLAGS_HAVE_STACKLESS_EXTENSION`.

**Inheritance:**

???

**Py\_TPFLAGS\_METHOD\_DESCRIPTOR**

This bit indicates that objects behave like unbound methods.

If this flag is set for `type(meth)`, then:

- `meth.__get__(obj, cls)(*args, **kwds)` (with `obj` not `None`) must be equivalent to `meth(obj, *args, **kwds)`.
- `meth.__get__(None, cls)(*args, **kwds)` must be equivalent to `meth(*args, **kwds)`.

This flag enables an optimization for typical method calls like `obj.meth()`: it avoids creating a temporary “bound method” object for `obj.meth`.

Novo na versão 3.8.

**Inheritance:**

This flag is never inherited by *heap types*. For extension types, it is inherited whenever `tp_descr_get` is inherited.

**Py\_TPFLAGS\_LONG\_SUBCLASS****Py\_TPFLAGS\_LIST\_SUBCLASS****Py\_TPFLAGS\_TUPLE\_SUBCLASS****Py\_TPFLAGS\_BYTES\_SUBCLASS****Py\_TPFLAGS\_UNICODE\_SUBCLASS****Py\_TPFLAGS\_DICT\_SUBCLASS****Py\_TPFLAGS\_BASE\_EXC\_SUBCLASS****Py\_TPFLAGS\_TYPE\_SUBCLASS**

These flags are used by functions such as `PyLong_Check()` to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like `PyObject_IsInstance()`. Custom types that inherit from built-ins should have their `tp_flags` set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

**Py\_TPFLAGS\_HAVE\_FINALIZE**

This bit is set when the `tp_finalize` slot is present in the type structure.

Novo na versão 3.4.

Obsoleto desde a versão 3.8: This flag isn’t necessary anymore, as the interpreter assumes the `tp_finalize` slot is always present in the type structure.

**Py\_TPFLAGS\_HAVE\_VECTORCALL**

This bit is set when the class implements the *vectorcall protocol*. See `tp_vectorcall_offset` for details.

**Inheritance:**

This bit is inherited for *static subtypes* if `tp_call` is also inherited. *Heap types* do not inherit `Py_TPFLAGS_HAVE_VECTORCALL`.

Novo na versão 3.9.

**Py\_TPFLAGS\_IMMUTABLETYPE**

This bit is set for type objects that are immutable: type attributes cannot be set nor deleted.

`PyType_Ready()` automatically applies this flag to *static types*.

**Inheritance:**

This flag is not inherited.

Novo na versão 3.10.

**Py\_TPFLAGS\_DISALLOW\_INSTANTIATION**

Disallow creating instances of the type: set `tp_new` to NULL and don't create the `__new__` key in the type dictionary.

The flag must be set before creating the type, not after. For example, it must be set before `PyType_Ready()` is called on the type.

The flag is set automatically on *static types* if `tp_base` is NULL or `&PyBaseObject_Type` and `tp_new` is NULL.

**Inheritance:**

This flag is not inherited. However, subclasses will not be instantiable unless they provide a non-NULL `tp_new` (which is only possible via the C API).

---

**Nota:** To disallow instantiating a class directly but allow instantiating its subclasses (e.g. for an *abstract base class*), do not use this flag. Instead, make `tp_new` only succeed for subclasses.

---

Novo na versão 3.10.

**Py\_TPFLAGS\_MAPPING**

This bit indicates that instances of the class may match mapping patterns when used as the subject of a match block. It is automatically set when registering or subclassing `collections.abc.Mapping`, and unset when registering `collections.abc.Sequence`.

---

**Nota:** `Py_TPFLAGS_MAPPING` and `Py_TPFLAGS_SEQUENCE` are mutually exclusive; it is an error to enable both flags simultaneously.

---

**Inheritance:**

This flag is inherited by types that do not already set `Py_TPFLAGS_SEQUENCE`.

**Ver também:**

**PEP 634** – Structural Pattern Matching: Specification

Novo na versão 3.10.

**Py\_TPFLAGS\_SEQUENCE**

This bit indicates that instances of the class may match sequence patterns when used as the subject of a match block. It is automatically set when registering or subclassing `collections.abc.Sequence`, and unset when registering `collections.abc.Mapping`.

---

**Nota:** `Py_TPFLAGS_MAPPING` and `Py_TPFLAGS_SEQUENCE` are mutually exclusive; it is an error to enable both flags simultaneously.

---

**Inheritance:**

This flag is inherited by types that do not already set `Py_TPFLAGS_MAPPING`.

**Ver também:**

**PEP 634** – Structural Pattern Matching: Specification

Novo na versão 3.10.

**const** char \**PyTypeObject*.**tp\_doc**

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the `__doc__` attribute on the type and instances of the type.

**Inheritance:**

This field is *not* inherited by subtypes.

*traverseproc* *PyTypeObject*.**tp\_traverse**

An optional pointer to a traversal function for the garbage collector. This is only used if the `Py_TPFLAGS_HAVE_GC` flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section *Suporte a Coleta Cíclica de Lixo*.

The `tp_traverse` pointer is used by the garbage collector to detect reference cycles. A typical implementation of a `tp_traverse` function simply calls `Py_VISIT()` on each of the instance's members that are Python objects that the instance owns. For example, this is function `local_traverse()` from the `_thread` extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that `Py_VISIT()` is called only on those members that can participate in reference cycles. Although there is also a `self->key` member, it can only be NULL or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the `gc` module's `get_referents()` function will include it.

**Aviso:** When implementing `tp_traverse`, only the members that the instance *owns* (by having *strong references* to them) must be visited. For instance, if an object supports weak references via the `tp_weaklist` slot, the pointer supporting the linked list (what `tp_weaklist` points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that `Py_VISIT()` requires the `visit` and `arg` parameters to `local_traverse()` to have these specific names; don't name them just anything.

Instances of *heap-allocated types* hold a reference to their type. Their traversal function must therefore either visit `Py_TYPE(self)`, or delegate this responsibility by calling `tp_traverse` of another heap-allocated type (such as a heap-allocated superclass). If they do not, the type object may not be garbage-collected.

Alterado na versão 3.9: Heap-allocated types are expected to visit `Py_TYPE(self)` in `tp_traverse`. In earlier versions of Python, due to [bug 40217](#), doing this may lead to crashes in subclasses.

**Inheritance:**

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

This field is inherited by subtypes together with `tp_clear` and the `Py_TPFLAGS_HAVE_GC` flag bit: the flag bit, `tp_traverse`, and `tp_clear` are all inherited from the base type if they are all zero in the subtype.

#### *inquiry* `PyTypeObject.tp_clear`

An optional pointer to a clear function for the garbage collector. This is only used if the `Py_TPFLAGS_HAVE_GC` flag bit is set. The signature is:

```
int tp_clear(PyObject *);
```

The `tp_clear` member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all `tp_clear` functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a `tp_clear` function. For example, the tuple type does not implement a `tp_clear` function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the `tp_clear` functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing `tp_clear`.

Implementations of `tp_clear` should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to NULL, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->dict);
    return 0;
}
```

The `Py_CLEAR()` macro should be used, because clearing references is delicate: the reference to the contained object must not be released (via `Py_DECREF()`) until after the pointer to the contained object is set to NULL. This is because releasing the reference may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference *self* again, it's important that the pointer to the contained object be NULL at that time, so that *self* knows the contained object can no longer be used. The `Py_CLEAR()` macro performs the operations in a safe order.

Note that `tp_clear` is not *always* called before an instance is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and `tp_dealloc` is called directly.

Because the goal of `tp_clear` functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's `tp_dealloc` function to invoke `tp_clear`.

More information about Python's garbage collection scheme can be found in section *Suporte a Coleta Cíclica de Lixo*.

#### **Inheritance:**

Group: `Py_TPFLAGS_HAVE_GC`, `tp_traverse`, `tp_clear`

This field is inherited by subtypes together with `tp_traverse` and the `Py_TPFLAGS_HAVE_GC` flag bit: the flag bit, `tp_traverse`, and `tp_clear` are all inherited from the base type if they are all zero in the subtype.

#### *richcmpfunc* `PyTypeObject.tp_richcompare`

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by *PyTypeObject*.

The function should return the result of the comparison (usually *Py\_True* or *Py\_False*). If the comparison is undefined, it must return *Py\_NotImplemented*, if another error occurred it must return *NULL* and set an exception condition.

The following constants are defined to be used as the third argument for *tp\_richcompare* and for *PyObject\_RichCompare()*:

Constante	Comparação
<i>Py_LT</i>	<
<i>Py_LE</i>	<=
<i>Py_EQ</i>	==
<i>Py_NE</i>	!=
<i>Py_GT</i>	>
<i>Py_GE</i>	>=

The following macro is defined to ease writing rich comparison functions:

**Py\_RETURN\_RICHCOMPARE** (*VAL\_A*, *VAL\_B*, *op*)

Return *Py\_True* or *Py\_False* from the function, depending on the result of a comparison. *VAL\_A* and *VAL\_B* must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for *PyObject\_RichCompare()*.

The returned value is a new *strong reference*.

On error, sets an exception and returns *NULL* from the function.

Novo na versão 3.7.

### Inheritance:

Group: *tp\_hash*, *tp\_richcompare*

This field is inherited by subtypes together with *tp\_hash*: a subtype inherits *tp\_richcompare* and *tp\_hash* when the subtype's *tp\_richcompare* and *tp\_hash* are both *NULL*.

### Padrão:

*PyBaseObject\_Type* provides a *tp\_richcompare* implementation, which may be inherited. However, if only *tp\_hash* is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

*Py\_ssize\_t* *PyTypeObject.tp\_weaklistoffset*

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by *PyObject\_ClearWeakRefs()* and the *PyWeakref\_\** functions. The instance structure needs to include a field of type *PyObject\** which is initialized to *NULL*.

Do not confuse this field with *tp\_weaklist*; that is the list head for weak references to the type object itself.

### Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via *tp\_weaklistoffset*, this should not be a problem.



When a type defined by a class statement has no `__slots__` declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the `tp_weaklistoffset` of that slot's offset.

When a type's `__slots__` declaration contains a slot named `__weakref__`, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's `tp_weaklistoffset`.

When a type's `__slots__` declaration does not contain a slot named `__weakref__`, the type inherits its `tp_weaklistoffset` from its base type.

#### *getterfunc* `PyTypeObject.tp_iter`

An optional pointer to a function that returns an *iterator* for the object. Its presence normally signals that the instances of this type are *iterable* (although sequences may be iterable without this function).

This function has the same signature as `PyObject_GetIter()`:

```
PyObject *tp_iter(PyObject *self);
```

#### **Inheritance:**

This field is inherited by subtypes.

#### *iternextfunc* `PyTypeObject.tp_iternext`

An optional pointer to a function that returns the next item in an *iterator*. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return `NULL`; a `StopIteration` exception may or may not be set. When another error occurs, it must return `NULL` too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the `tp_iter` function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as `PyIter_Next()`.

#### **Inheritance:**

This field is inherited by subtypes.

#### **struct** `PyMethodDef *PyTypeObject.tp_methods`

An optional pointer to a static `NULL`-terminated array of `PyMethodDef` structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see `tp_dict` below) containing a method descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (methods are inherited through a different mechanism).

#### **struct** `PyMemberDef *PyTypeObject.tp_members`

An optional pointer to a static `NULL`-terminated array of `PyMemberDef` structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see `tp_dict` below) containing a member descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (members are inherited through a different mechanism).

#### **struct** `PyGetSetDef *PyTypeObject.tp_getset`

An optional pointer to a static `NULL`-terminated array of `PyGetSetDef` structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type’s dictionary (see *tp\_dict* below) containing a getset descriptor.

**Inheritance:**

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

*PyObject* \**PyTypeObject*.**tp\_base**

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

---

**Nota:** Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be “address constants”. Function designators like *PyType\_GenericNew()*, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary ‘&’ operator applied to a non-static variable like *PyBaseObject\_Type()* is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, *tp\_base* should be set in the extension module’s init function.

---

**Inheritance:**

This field is not inherited by subtypes (obviously).

**Padrão:**

This field defaults to *&PyBaseObject\_Type* (which to Python programmers is known as the type object).

*PyObject* \**PyTypeObject*.**tp\_dict**

The type’s dictionary is stored here by *PyType\_Ready()*.

This field should normally be initialized to NULL before *PyType\_Ready* is called; it may also be initialized to a dictionary containing initial attributes for the type. Once *PyType\_Ready()* has initialized the type, extra attributes for the type may be added to this dictionary only if they don’t correspond to overloaded operations (like *\_\_add\_\_()*).

**Inheritance:**

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

**Padrão:**

If this field is NULL, *PyType\_Ready()* will assign a new dictionary to it.

**Aviso:** It is not safe to use *PyDict\_SetItem()* on or otherwise modify *tp\_dict* with the dictionary C-API.

*descrgetfunc* *PyTypeObject*.**tp\_descr\_get**

An optional pointer to a “descriptor get” function.

A assinatura da função é:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

**Inheritance:**

This field is inherited by subtypes.

*descrsetfunc* `PyTypeObject.tp_descr_set`

An optional pointer to a function for setting and deleting a descriptor's value.

A assinatura da função é:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to NULL to delete the value.

**Inheritance:**

This field is inherited by subtypes.

*Py\_ssize\_t* `PyTypeObject.tp_dictoffset`

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by `PyObject_GenericGetAttr()`.

Do not confuse this field with `tp_dict`; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the *end* of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of `str` or `tuple`. Note that the `tp_basicsize` field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes, `tp_dictoffset` should be set to -4 to indicate that the dictionary is at the very end of the structure.

The real dictionary offset in an instance can be computed from a negative `tp_dictoffset` as follows:

```
dictoffset = tp_basicsize + abs(ob_size)*tp_itemsize + tp_dictoffset
if dictoffset is not aligned on sizeof(void*):
    round up to sizeof(void*)
```

where `tp_basicsize`, `tp_itemsize` and `tp_dictoffset` are taken from the type object, and `ob_size` is taken from the instance. The absolute value is taken because ints use the sign of `ob_size` to store the sign of the number. (There's never a need to do this calculation yourself; it is done for you by `_PyObject_GetDictPtr()`.)

**Inheritance:**

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via `tp_dictoffset`, this should not be a problem.

When a type defined by a class statement has no `__slots__` declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the `tp_dictoffset` is set to that slot's offset.

When a type defined by a class statement has a `__slots__` declaration, the type inherits its `tp_dictoffset` from its base type.

(Adding a slot named `__dict__` to the `__slots__` declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like `__weakref__` though.)

**Padrão:**

This slot has no default. For *static types*, if the field is NULL then no `__dict__` gets created for instances.

*initproc* `PyTypeObject.tp_init`

An optional pointer to an instance initialization function.

This function corresponds to the `__init__()` method of classes. Like `__init__()`, it is possible to create an instance without calling `__init__()`, and it is possible to reinitialize an instance by calling its `__init__()` method again.

A assinatura da função é:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwargs);
```

The `self` argument is the instance to be initialized; the `args` and `kwargs` arguments represent positional and keyword arguments of the call to `__init__()`.

The `tp_init` function, if not `NULL`, is called when an instance is created normally by calling its type, after the type's `tp_new` function has returned an instance of the type. If the `tp_new` function returns an instance of some other type that is not a subtype of the original type, no `tp_init` function is called; if `tp_new` returns an instance of a subtype of the original type, the subtype's `tp_init` is called.

Returns 0 on success, -1 and sets an exception on error.

#### Inheritance:

This field is inherited by subtypes.

#### Padrão:

For *static types* this field does not have a default.

#### *allocfunc* `PyTypeObject.tp_alloc`

An optional pointer to an instance allocation function.

A assinatura da função é:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

#### Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

#### Padrão:

For dynamic subtypes, this field is always set to `PyType_GenericAlloc()`, to force a standard heap allocation strategy.

For static subtypes, `PyBaseObject_Type` uses `PyType_GenericAlloc()`. That is the recommended value for all statically defined types.

#### *newfunc* `PyTypeObject.tp_new`

An optional pointer to an instance creation function.

A assinatura da função é:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwargs);
```

The `subtype` argument is the type of the object being created; the `args` and `kwargs` arguments represent positional and keyword arguments of the call to the type. Note that `subtype` doesn't have to equal the type whose `tp_new` function is called; it may be a subtype of that type (but not an unrelated type).

The `tp_new` function should call `subtype->tp_alloc(subtype, nitems)` to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the `tp_init` handler. A good rule of thumb is that for immutable types, all initialization should take place in `tp_new`, while for mutable types, most initialization should be deferred to `tp_init`.

Set the `Py_TPFLAGS_DISALLOW_INSTANTIATION` flag to disallow creating instances of the type in Python.

**Inheritance:**

This field is inherited by subtypes, except it is not inherited by *static types* whose *tp\_base* is NULL or `&PyBaseObject_Type`.

**Padrão:**

For *static types* this field has no default. This means if the slot is defined as NULL, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

*freefunc* `PyTypeObject.tp_free`

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is `PyObject_Free()`.

**Inheritance:**

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

**Padrão:**

In dynamic subtypes, this field is set to a deallocator suitable to match `PyType_GenericAlloc()` and the value of the `Py_TPFLAGS_HAVE_GC` flag bit.

For static subtypes, `PyBaseObject_Type` uses `PyObject_Del`.

*inquiry* `PyTypeObject.tp_is_gc`

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's *tp\_flags* field, and check the `Py_TPFLAGS_HAVE_GC` flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype, `PyType_Type`, defines this function to distinguish between statically and *dynamically allocated types*.)

**Inheritance:**

This field is inherited by subtypes.

**Padrão:**

This slot has no default. If this field is NULL, `Py_TPFLAGS_HAVE_GC` is used as the functional equivalent.

*PyObject\** `PyTypeObject.tp_bases`

Tuple of base types.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is *initialized*.

For dynamically created classes, the `Py_tp_bases` slot can be used instead of the *bases* argument of `PyType_FromSpecWithBases()`. The argument form is preferred.

**Aviso:** Multiple inheritance does not work well for statically defined types. If you set `tp_bases` to a tuple, Python will not raise an error, but some slots will only be inherited from the first base.

**Inheritance:**

This field is not inherited.

*PyObject* \**PyTypeObject*.**tp\_mro**

Tuple containing the expanded set of base types, starting with the type itself and ending with `object`, in Method Resolution Order.

This field should be set to `NULL` and treated as read-only. Python will fill it in when the type is *initialized*.

**Inheritance:**

This field is not inherited; it is calculated fresh by *PyType\_Ready()*.

*PyObject* \**PyTypeObject*.**tp\_cache**

Unused. Internal use only.

**Inheritance:**

This field is not inherited.

*PyObject* \**PyTypeObject*.**tp\_subclasses**

List of weak references to subclasses. Internal use only.

**Inheritance:**

This field is not inherited.

*PyObject* \**PyTypeObject*.**tp\_weaklist**

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

**Inheritance:**

This field is not inherited.

*destructor* *PyTypeObject*.**tp\_del**

This field is deprecated. Use *tp\_finalize* instead.

unsigned int *PyTypeObject*.**tp\_version\_tag**

Used to index into the method cache. Internal use only.

**Inheritance:**

This field is not inherited.

*destructor* *PyTypeObject*.**tp\_finalize**

An optional pointer to an instance finalization function. Its signature is:

```
void tp_finalize(PyObject *self);
```

If *tp\_finalize* is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

*tp\_finalize* should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);
```

(continua na próxima página)

(continuação da página anterior)

```

/* ... */

/* Restore the saved exception. */
PyErr_Restore(error_type, error_value, error_traceback);
}

```

Also, note that, in a garbage collected Python, `tp_dealloc` may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which `tp_dealloc` is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called `tp_dealloc` will not violate any assumptions of the library.

**Inheritance:**

This field is inherited by subtypes.

Novo na versão 3.4.

Alterado na versão 3.8: Before version 3.8 it was necessary to set the `Py_TPFLAGS_HAVE_FINALIZE` flags bit in order for this field to be used. This is no longer required.

**Ver também:**

“Finalização segura de objetos” (PEP 442)

*vectorcallfunc* `PyTypeObject.tp_vectorcall`

Vectorcall function to use for calls of this type object. In other words, it is used to implement *vectorcall* for `type.__call__`. If `tp_vectorcall` is NULL, the default call implementation using `__new__` and `__init__` is used.

**Inheritance:**

This field is never inherited.

Novo na versão 3.9: (the field exists since 3.8 but it's only used since 3.9)

## 12.3.6 Static Types

Traditionally, types defined in C code are *static*, that is, a static `PyTypeObject` structure is defined directly in code and initialized using `PyType_Ready()`.

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state.

Also, since `PyTypeObject` is only part of the *Limited API* as an opaque struct, any extension modules using static types must be compiled for a specific Python minor version.

### 12.3.7 Tipos no heap

An alternative to *static types* is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's `class` statement. Heap types have the `Py_TPFLAGS_HEAPTYPE` flag set.

This is done by filling a `PyType_Spec` structure and calling `PyType_FromSpec()`, `PyType_FromSpecWithBases()`, or `PyType_FromModuleAndSpec()`.

## 12.4 Number Object Structures

### type `PyNumberMethods`

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Protocolo de número* section.

Here is the structure definition:

```
typedef struct {
    binaryfunc nb_add;
    binaryfunc nb_subtract;
    binaryfunc nb_multiply;
    binaryfunc nb_remainder;
    binaryfunc nb_divmod;
    ternaryfunc nb_power;
    unaryfunc nb_negative;
    unaryfunc nb_positive;
    unaryfunc nb_absolute;
    inquiry nb_bool;
    unaryfunc nb_invert;
    binaryfunc nb_lshift;
    binaryfunc nb_rshift;
    binaryfunc nb_and;
    binaryfunc nb_xor;
    binaryfunc nb_or;
    unaryfunc nb_int;
    void *nb_reserved;
    unaryfunc nb_float;

    binaryfunc nb_inplace_add;
    binaryfunc nb_inplace_subtract;
    binaryfunc nb_inplace_multiply;
    binaryfunc nb_inplace_remainder;
    ternaryfunc nb_inplace_power;
    binaryfunc nb_inplace_lshift;
    binaryfunc nb_inplace_rshift;
    binaryfunc nb_inplace_and;
    binaryfunc nb_inplace_xor;
    binaryfunc nb_inplace_or;

    binaryfunc nb_floor_divide;
    binaryfunc nb_true_divide;
    binaryfunc nb_inplace_floor_divide;
    binaryfunc nb_inplace_true_divide;

    unaryfunc nb_index;

    binaryfunc nb_matrix_multiply;
```

(continua na próxima página)



(continuação da página anterior)

```

    binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;

```

**Nota:** Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return `Py_NotImplemented`, if another error occurred they must return `NULL` and set an exception.

**Nota:** The `nb_reserved` field should always be `NULL`. It was previously called `nb_long`, and was renamed in Python 3.0.1.

```

binaryfunc PyNumberMethods.nb_add
binaryfunc PyNumberMethods.nb_subtract
binaryfunc PyNumberMethods.nb_multiply
binaryfunc PyNumberMethods.nb_remainder
binaryfunc PyNumberMethods.nb_divmod
ternaryfunc PyNumberMethods.nb_power
unaryfunc PyNumberMethods.nb_negative
unaryfunc PyNumberMethods.nb_positive
unaryfunc PyNumberMethods.nb_absolute
inquiry PyNumberMethods.nb_bool
unaryfunc PyNumberMethods.nb_invert
binaryfunc PyNumberMethods.nb_lshift
binaryfunc PyNumberMethods.nb_rshift
binaryfunc PyNumberMethods.nb_and
binaryfunc PyNumberMethods.nb_xor
binaryfunc PyNumberMethods.nb_or
unaryfunc PyNumberMethods.nb_int
void *PyNumberMethods.nb_reserved
unaryfunc PyNumberMethods.nb_float
binaryfunc PyNumberMethods.nb_inplace_add
binaryfunc PyNumberMethods.nb_inplace_subtract
binaryfunc PyNumberMethods.nb_inplace_multiply
binaryfunc PyNumberMethods.nb_inplace_remainder
ternaryfunc PyNumberMethods.nb_inplace_power
binaryfunc PyNumberMethods.nb_inplace_lshift
binaryfunc PyNumberMethods.nb_inplace_rshift

```

*binaryfunc* *PyNumberMethods*.**nb\_inplace\_and**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_xor**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_or**  
*binaryfunc* *PyNumberMethods*.**nb\_floor\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_true\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_floor\_divide**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_true\_divide**  
*unaryfunc* *PyNumberMethods*.**nb\_index**  
*binaryfunc* *PyNumberMethods*.**nb\_matrix\_multiply**  
*binaryfunc* *PyNumberMethods*.**nb\_inplace\_matrix\_multiply**

## 12.5 Mapping Object Structures

### **type** **PyMappingMethods**

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

*lenfunc* *PyMappingMethods*.**mp\_length**

This function is used by *PyMapping\_Size()* and *PyObject\_Size()*, and has the same signature. This slot may be set to NULL if the object has no defined length.

*binaryfunc* *PyMappingMethods*.**mp\_subscript**

This function is used by *PyObject\_GetItem()* and *PySequence\_GetSlice()*, and has the same signature as *PyObject\_GetItem()*. This slot must be filled for the *PyMapping\_Check()* function to return 1, it can be NULL otherwise.

*objobjargproc* *PyMappingMethods*.**mp\_ass\_subscript**

This function is used by *PyObject\_SetItem()*, *PyObject\_DelItem()*, *PyObject\_SetSlice()* and *PyObject\_DelSlice()*. It has the same signature as *PyObject\_SetItem()*, but *v* can also be set to NULL to delete an item. If this slot is NULL, the object does not support item assignment and deletion.

## 12.6 Sequence Object Structures

### **type** **PySequenceMethods**

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

*lenfunc* *PySequenceMethods*.**sq\_length**

This function is used by *PySequence\_Size()* and *PyObject\_Size()*, and has the same signature. It is also used for handling negative indices via the *sq\_item* and the *sq\_ass\_item* slots.

*binaryfunc* *PySequenceMethods*.**sq\_concat**

This function is used by *PySequence\_Concat()* and has the same signature. It is also used by the *+* operator, after trying the numeric addition via the *nb\_add* slot.

*ssizeargfunc* *PySequenceMethods*.**sq\_repeat**

This function is used by *PySequence\_Repeat()* and has the same signature. It is also used by the *\** operator, after trying numeric multiplication via the *nb\_multiply* slot.

*ssizeargfunc* `PySequenceMethods.sq_item`

This function is used by `PySequence_GetItem()` and has the same signature. It is also used by `PyObject_GetItem()`, after trying the subscription via the `mp_subscript` slot. This slot must be filled for the `PySequence_Check()` function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the `sq_length` slot is filled, it is called and the sequence length is used to compute a positive index which is passed to `sq_item`. If `sq_length` is NULL, the index is passed as is to the function.

*ssizeobjargproc* `PySequenceMethods.sq_ass_item`

This function is used by `PySequence_SetItem()` and has the same signature. It is also used by `PyObject_SetItem()` and `PyObject_DelItem()`, after trying the item assignment and deletion via the `mp_ass_subscript` slot. This slot may be left to NULL if the object does not support item assignment and deletion.

*objobjproc* `PySequenceMethods.sq_contains`

This function may be used by `PySequence_Contains()` and has the same signature. This slot may be left to NULL, in this case `PySequence_Contains()` simply traverses the sequence until it finds a match.

*binaryfunc* `PySequenceMethods.sq_inplace_concat`

This function is used by `PySequence_InPlaceConcat()` and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case `PySequence_InPlaceConcat()` will fall back to `PySequence_Concat()`. It is also used by the augmented assignment `+=`, after trying numeric in-place addition via the `nb_inplace_add` slot.

*ssizeargfunc* `PySequenceMethods.sq_inplace_repeat`

This function is used by `PySequence_InPlaceRepeat()` and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case `PySequence_InPlaceRepeat()` will fall back to `PySequence_Repeat()`. It is also used by the augmented assignment `*=`, after trying numeric in-place multiplication via the `nb_inplace_multiply` slot.

## 12.7 Buffer Object Structures

**type** `PyBufferProcs`

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

*getbufferproc* `PyBufferProcs.bf_getbuffer`

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function **MUST** take these steps:

- (1) Check if the request can be met. If not, raise `PyExc_BufferError`, set `view->obj` to NULL and return -1.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set `view->obj` to *exporter* and increment `view->obj`.
- (5) Return 0.

If *exporter* is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets `view->obj` to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, `view->obj` will be a new reference to the root object.

The individual fields of `view` are described in section [Buffer structure](#), the rules how an exporter must react to specific requests are in section [Buffer request types](#).

All memory pointed to in the `Py_buffer` structure belongs to the exporter and must remain valid until there are no consumers left. `format`, `shape`, `strides`, `suboffsets` and `internal` are read-only for the consumer.

`PyBuffer_FillInfo()` provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

`PyObject_GetBuffer()` is the interface for the consumer that wraps this function.

`releasebufferproc` `PyBufferProcs.bf_releasebuffer`

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, `PyBufferProcs.bf_releasebuffer` may be `NULL`. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is 0, free all memory associated with `view`.

The exporter **MUST** use the `internal` field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer **MAY** pass a copy of the original buffer as the `view` argument.

This function **MUST NOT** decrement `view->obj`, since that is done automatically in `PyBuffer_Release()` (this scheme is useful for breaking reference cycles).

`PyBuffer_Release()` is the interface for the consumer that wraps this function.

## 12.8 Async Object Structures

Novo na versão 3.5.

**type** `PyAsyncMethods`

This structure holds pointers to the functions required to implement [awaitable](#) and [asynchronous iterator](#) objects.

Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
    sendfunc am_send;
} PyAsyncMethods;
```

`unaryfunc` `PyAsyncMethods.am_await`

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an *iterator*, i.e. `PyIter_Check()` must return 1 for it.

This slot may be set to NULL if an object is not an *awaitable*.

*unaryfunc* `PyAsyncMethods.am_aiter`

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an *asynchronous iterator* object. See `__anext__()` for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

*unaryfunc* `PyAsyncMethods.am_anext`

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an *awaitable* object. See `__anext__()` for details. This slot may be set to NULL.

*sendfunc* `PyAsyncMethods.am_send`

The signature of this function is:

```
PySendResult am_send(PyObject *self, PyObject *arg, PyObject **result);
```

See `PyIter_Send()` for details. This slot may be set to NULL.

Novo na versão 3.10.

## 12.9 Slot Type typedefs

**typedef** `PyObject *(*allocfunc)` (`PyTypeObject *cls`, `Py_ssize_t nitems`)

*Part of the Stable ABI.* The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with `ob_refcnt` set to 1 and `ob_type` set to the type argument. If the type's `tp_itemsize` is non-zero, the object's `ob_size` field should be initialized to `nitems` and the length of the allocated memory block should be `tp_basicsize + nitems*tp_itemsize`, rounded up to a multiple of `sizeof(void*)`; otherwise, `nitems` is not used and the length of the block should be `tp_basicsize`.

This function should not do any other instance initialization, not even to allocate additional memory; that should be done by `tp_new`.

**typedef** `void (*destructor)` (`PyObject*`)

*Part of the Stable ABI.*

**typedef** `void (*freefunc)` (`void*`)

See `tp_free`.

**typedef** `PyObject *(*newfunc)` (`PyObject*`, `PyObject*`, `PyObject*`)

*Part of the Stable ABI.* See `tp_new`.

**typedef** `int (*initproc)` (`PyObject*`, `PyObject*`, `PyObject*`)

*Part of the Stable ABI.* See `tp_init`.

**typedef** `PyObject *(*reprfunc)` (`PyObject*`)

*Part of the Stable ABI.* See `tp_repr`.

**typedef** `PyObject *(*getattrfunc)` (`PyObject *self`, `char *attr`)

*Part of the Stable ABI.* Return the value of the named attribute for the object.

**typedef** int (\***setattrfunc**) (PyObject \*self, char \*attr, PyObject \*value)

Part of the [Stable ABI](#). Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.

**typedef** PyObject \*(\***getattrfunc**) (PyObject \*self, PyObject \*attr)

Part of the [Stable ABI](#). Return the value of the named attribute for the object.

See [tp\\_getattro](#).

**typedef** int (\***setattrofunc**) (PyObject \*self, PyObject \*attr, PyObject \*value)

Part of the [Stable ABI](#). Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.

See [tp\\_setattro](#).

**typedef** PyObject \*(\***descrgetfunc**) (PyObject\*, PyObject\*, PyObject\*)

Part of the [Stable ABI](#). See [tp\\_descr\\_get](#).

**typedef** int (\***descrsetfunc**) (PyObject\*, PyObject\*, PyObject\*)

Part of the [Stable ABI](#). See [tp\\_descr\\_set](#).

**typedef** Py\_hash\_t (\***hashfunc**) (PyObject\*)

Part of the [Stable ABI](#). See [tp\\_hash](#).

**typedef** PyObject \*(\***richcmpfunc**) (PyObject\*, PyObject\*, int)

Part of the [Stable ABI](#). See [tp\\_richcompare](#).

**typedef** PyObject \*(\***getiterfunc**) (PyObject\*)

Part of the [Stable ABI](#). See [tp\\_iter](#).

**typedef** PyObject \*(\***iternextfunc**) (PyObject\*)

Part of the [Stable ABI](#). See [tp\\_iternext](#).

**typedef** Py\_ssize\_t (\***lenfunc**) (PyObject\*)

Part of the [Stable ABI](#).

**typedef** int (\***getbufferproc**) (PyObject\*, Py\_buffer\*, int)

**typedef** void (\***releasebufferproc**) (PyObject\*, Py\_buffer\*)

**typedef** PyObject \*(\***unaryfunc**) (PyObject\*)

Part of the [Stable ABI](#).

**typedef** PyObject \*(\***binaryfunc**) (PyObject\*, PyObject\*)

Part of the [Stable ABI](#).

**typedef** PySendResult (\***sendfunc**) (PyObject\*, PyObject\*, PyObject\*\*)

See [am\\_send](#).

**typedef** PyObject \*(\***ternaryfunc**) (PyObject\*, PyObject\*, PyObject\*)

Part of the [Stable ABI](#).

**typedef** PyObject \*(\***ssizeargfunc**) (PyObject\*, Py\_ssize\_t)

Part of the [Stable ABI](#).

**typedef** int (\***ssizeobjargproc**) (PyObject\*, Py\_ssize\_t, PyObject\*)

Part of the [Stable ABI](#).

**typedef** int (\***objobjproc**) (PyObject\*, PyObject\*)

Part of the [Stable ABI](#).

**typedef** int (\***objobjargproc**) (PyObject\*, PyObject\*, PyObject\*)

Part of the [Stable ABI](#).

## 12.10 Exemplos

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see [defining-new-types](#) and [new-types-topics](#).

A basic *static type*:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} PyObject;

static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

```
static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    "mymod.MyObject",           /* tp_name */
    sizeof(MyObject),           /* tp_basicsize */
    0,                           /* tp_itemsize */
    (destructor)myobj_dealloc,  /* tp_dealloc */
    0,                           /* tp_vectorcall_offset */
    0,                           /* tp_getattr */
    0,                           /* tp_setattr */
    0,                           /* tp_as_async */
    (reprfunc)myobj_repr,       /* tp_repr */
    0,                           /* tp_as_number */
    0,                           /* tp_as_sequence */
    0,                           /* tp_as_mapping */
    0,                           /* tp_hash */
    0,                           /* tp_call */
    0,                           /* tp_str */
    0,                           /* tp_getattro */
    0,                           /* tp_setattro */
    0,                           /* tp_as_buffer */
    0,                           /* tp_flags */
    PyDoc_STR("My objects"),     /* tp_doc */
    0,                           /* tp_traverse */
    0,                           /* tp_clear */
    0,                           /* tp_richcompare */
    0,                           /* tp_weaklistoffset */
    0,                           /* tp_iter */
    0,                           /* tp_iternext */
    0,                           /* tp_methods */
    0,                           /* tp_members */
    0,                           /* tp_getset */
    0,                           /* tp_base */
};
```

(continua na próxima página)

(continuação da página anterior)

```

0,          /* tp_dict */
0,          /* tp_descr_get */
0,          /* tp_descr_set */
0,          /* tp_dictoffset */
0,          /* tp_init */
0,          /* tp_alloc */
myobj_new,  /* tp_new */
};

```

A type that supports weakrefs, instance dicts, and hashing:

```

typedef struct {
    PyObject_HEAD
    const char *data;
    PyObject *inst_dict;
    PyObject *weakreflist;
} PyObject;

static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_weaklistoffset = offsetof(MyObject, weakreflist),
    .tp_dictoffset = offsetof(MyObject, inst_dict),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE | Py_TPFLAGS_HAVE_GC,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
    .tp_hash = (hashfunc)myobj_hash,
    .tp_richcompare = PyBaseObject_Type.tp_richcompare,
};

```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func) using `Py_TPFLAGS_DISALLOW_INSTANTIATION` flag:

```

typedef struct {
    PyUnicodeObject raw;
    char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = PyDoc_STR("my custom str"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_DISALLOW_INSTANTIATION,
    .tp_repr = (reprfunc)myobj_repr,
};

```

The simplest *static type* with fixed-length instances:



```
typedef struct {
    PyObject_HEAD
} PyObject;

static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest *static type* with variable-length instances:

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} PyObject;

static PyTypeObject PyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(PyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};
```

## 12.11 Suporte a Coleta Cíclica de Lixo

O suporte do Python para detectar e coletar o lixo, que envolve referências circulares, requer suporte dos tipos de objetos que são “contêineres” para outros objetos que também podem ser contêineres. Tipos que não armazenam referências a outros tipos de objetos, ou que apenas armazenam referências a tipos atômicos (como números ou strings), não precisam fornecer nenhum suporte explícito para coleta de lixo.

To create a container type, the *tp\_flags* field of the type object must include the *Py\_TPFLAGS\_HAVE\_GC* and provide an implementation of the *tp\_traverse* handler. If instances of the type are mutable, a *tp\_clear* implementation must also be provided.

### **Py\_TPFLAGS\_HAVE\_GC**

Objetos com esse tipo de sinalizador definido devem estar em conformidade com regras documentadas aqui. Por conveniência esses objetos serão referenciados como objetos de contêiner.

Construtores para tipos de contêiner devem obedecer a duas regras:

1. A memória para o objeto deve ser alocada usando *PyObject\_GC\_New()* ou *PyObject\_GC\_NewVar()*.
2. Uma vez que todos os campos que podem conter referências a outros containers foram inicializados, deve-se chamar *PyObject\_GC\_Track()*.

Da mesma forma, o desalocador para o objeto deve estar em conformidade com regras semelhantes:

1. Antes que os campos que fazer referência a outros containers sejam invalidados, *PyObject\_GC\_UnTrack()* deve ser chamado.
2. A memória destinada ao objeto deve ser desalocada usando *PyObject\_GC\_Del()*.

**Aviso:** If a type adds the *Py\_TPFLAGS\_HAVE\_GC*, then it *must* implement at least a *tp\_traverse* handler or explicitly use one from its subclass or subclasses.

When calling `PyType_Ready()` or some of the APIs that indirectly call it like `PyType_FromSpecWithBases()` or `PyType_FromSpec()` the interpreter will automatically populate the `tp_flags`, `tp_traverse` and `tp_clear` fields if the type inherits from a class that implements the garbage collector protocol and the child class does *not* include the `Py_TPFLAGS_HAVE_GC` flag.

TYPE **\*PyObject\_GC\_New** (TYPE, *PyTypeObject* \*type)

Analogous to `PyObject_New()` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

TYPE **\*PyObject\_GC\_NewVar** (TYPE, *PyTypeObject* \*type, *Py\_ssize\_t* size)

Analogous to `PyObject_NewVar()` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

TYPE **\*PyObject\_GC\_Resize** (TYPE, *PyVarObject* \*op, *Py\_ssize\_t* newsize)

Resize an object allocated by `PyObject_NewVar()`. Returns the resized object or NULL on failure. *op* must not be tracked by the collector yet.

void **PyObject\_GC\_Track** (*PyObject* \*op)

*Part of the Stable ABI.* Adds the object *op* to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the `tp_traverse` handler become valid, usually near the end of the constructor.

int **PyObject\_IS\_GC** (*PyObject* \*obj)

Returns non-zero if the object implements the garbage collector protocol, otherwise returns 0.

The object cannot be tracked by the garbage collector if this function returns 0.

int **PyObject\_GC\_IsTracked** (*PyObject* \*op)

*Part of the Stable ABI since version 3.9.* Returns 1 if the object type of *op* implements the GC protocol and *op* is being currently tracked by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_tracked()`.

Novo na versão 3.9.

int **PyObject\_GC\_IsFinalized** (*PyObject* \*op)

*Part of the Stable ABI since version 3.9.* Returns 1 if the object type of *op* implements the GC protocol and *op* has been already finalized by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_finalized()`.

Novo na versão 3.9.

void **PyObject\_GC\_Del** (void \*op)

*Part of the Stable ABI.* Releases memory allocated to an object using `PyObject_GC_New()` or `PyObject_GC_NewVar()`.

void **PyObject\_GC\_UnTrack** (void \*op)

*Part of the Stable ABI.* Remove the object *op* from the set of container objects tracked by the collector. Note that `PyObject_GC_Track()` can be called again on this object to add it back to the set of tracked objects. The deallocator (`tp_dealloc` handler) should call this for the object before any of the fields used by the `tp_traverse` handler become invalid.

Alterado na versão 3.8: The `_PyObject_GC_TRACK()` and `_PyObject_GC_UNTRACK()` macros have been removed from the public C API.

The `tp_traverse` handler accepts a function parameter of this type:

**typedef** int (\***visitproc**) (*PyObject* \*object, void \*arg)

*Part of the Stable ABI.* Type of the visitor function passed to the `tp_traverse` handler. The function should be called with an object to traverse as *object* and the third parameter to the `tp_traverse` handler as *arg*. The

Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The `tp_traverse` handler must have the following type:

**typedef** int (\***traverseproc**) (PyObject \*self, visitproc visit, void \*arg)

*Part of the Stable ABI.* Traversal function for a container object. Implementations must call the `visit` function for each object directly contained by `self`, with the parameters to `visit` being the contained object and the `arg` value passed to the handler. The `visit` function must not be called with a NULL object argument. If `visit` returns a non-zero value that value should be returned immediately.

To simplify writing `tp_traverse` handlers, a `Py_VISIT()` macro is provided. In order to use this macro, the `tp_traverse` implementation must name its arguments exactly `visit` and `arg`:

void **Py\_VISIT** (PyObject \*o)

If `o` is not NULL, call the `visit` callback, with arguments `o` and `arg`. If `visit` returns a non-zero value, then return it. Using this macro, `tp_traverse` handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The `tp_clear` handler must be of the `inquiry` type, or NULL if the object is immutable.

**typedef** int (\***inquiry**) (PyObject \*self)

*Part of the Stable ABI.* Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after calling this method (don't just call `Py_DECREF()` on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

### 12.11.1 Controlando o estado do coletor de lixo

The C-API provides the following functions for controlling garbage collection runs.

`Py_ssize_t` **PyGC\_Collect** (void)

*Part of the Stable ABI.* Perform a full garbage collection, if the garbage collector is enabled. (Note that `gc.collect()` runs it unconditionally.)

Returns the number of collected + unreachable objects which cannot be collected. If the garbage collector is disabled or already collecting, returns 0 immediately. Errors during garbage collection are passed to `sys.unraisablehook`. This function does not raise exceptions.

int **PyGC\_Enable** (void)

*Part of the Stable ABI since version 3.10.* Enable the garbage collector: similar to `gc.enable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Novo na versão 3.10.

int **PyGC\_Disable** (void)

*Part of the Stable ABI since version 3.10.* Disable the garbage collector: similar to `gc.disable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Novo na versão 3.10.

int **PyGC\_IsEnabled**(void)

*Part of the [Stable ABI](#) since version 3.10.* Query the state of the garbage collector: similar to `gc.isenabled()`. Returns the current state, 0 for disabled and 1 for enabled.

Novo na versão 3.10.

---

API e Versionamento de ABI

---

O CPython expõe seu número de versão nas seguintes macros. Note que estes correspondem com o código da versão que está **construída**, não necessariamente a versão usada no **run time**.

Veja *Estabilidade da API C* para uma discussão da estabilidade da API e ABI através das versões.

**PY\_MAJOR\_VERSION**

O 3 em 3.4.1a2.

**PY\_MINOR\_VERSION**

O 4 em 3.4.1a2.

**PY\_MICRO\_VERSION**

O 1 em 3.4.1a2.

**PY\_RELEASE\_LEVEL**

O a em 3.4.1a2. Isto pode ser 0xA para alfa, 0xB para beta, 0xC para o candidato a lançamento ou 0xF para final.

**PY\_RELEASE\_SERIAL**

O 2 em 3.4.1a2. Zero para os lançamentos finais.

**PY\_VERSION\_HEX**

O número da versão do Python codificado em um único inteiro.

As informações da versão subjacente podem ser achadas tratando-as como um número de 32 bits da seguinte maneira:

Bytes	Bits (big endian order)	Significado	Valor para 3.4.1a2
1	1-8	PY_MAJOR_VERSION	0x03
2	9-16	PY_MINOR_VERSION	0x04
3	17-24	PY_MICRO_VERSION	0x01
4	25-28	PY_RELEASE_LEVEL	0xA
	29-32	PY_RELEASE_SERIAL	0x2

Assim 3.4.1a2 é a versão hex 0x030401a2 e 3.10.0 é a versões hex 0x030a00f0.

Todas as macros dadas estão definidas em [Include/patchlevel.h](#).

**>>>** O prompt padrão do console interativo do Python. Normalmente visto em exemplos de código que podem ser executados interativamente no interpretador.

... Pode se referir a:

- O prompt padrão do shell interativo do Python ao inserir o código para um bloco de código recuado, quando dentro de um par de delimitadores correspondentes esquerdo e direito (parênteses, colchetes, chaves ou aspas triplas) ou após especificar um decorador.
- A constante embutida `Ellipsis`.

**2to3** Uma ferramenta que tenta converter código Python 2.x em código Python 3.x tratando a maioria das incompatibilidades que podem ser detectadas com análise do código-fonte e navegação na árvore sintática.

O 2to3 está disponível na biblioteca padrão como `lib2to3`; um ponto de entrada é disponibilizado como `Tools/scripts/2to3`. Veja `2to3-reference`.

**classe base abstrata** Classes bases abstratas complementam *tipagem pato*, fornecendo uma maneira de definir interfaces quando outras técnicas, como `hasattr()`, seriam desajeitadas ou sutilmente erradas (por exemplo, com métodos mágicos). ABCs introduzem subclasses virtuais, classes que não herdam de uma classe mas ainda são reconhecidas por `isinstance()` e `issubclass()`; veja a documentação do módulo `abc`. Python vem com muitas ABCs embutidas para estruturas de dados (no módulo `collections.abc`), números (no módulo `numbers`), fluxos (no módulo `io`), localizadores e carregadores de importação (no módulo `importlib.abc`). Você pode criar suas próprias ABCs com o módulo `abc`.

**anotação** Um rótulo associado a uma variável, um atributo de classe ou um parâmetro de função ou valor de retorno, usado por convenção como *dica de tipo*.

Anotações de variáveis locais não podem ser acessadas em tempo de execução, mas anotações de variáveis globais, atributos de classe e funções são armazenadas no atributo especial `__annotations__` de módulos, classes e funções, respectivamente.

Veja *anotação de variável*, *anotação de função*, **PEP 484** e **PEP 526**, que descrevem esta funcionalidade. Veja também `annotations-howto` para as melhores práticas sobre como trabalhar com anotações.

**argumento** Um valor passado para uma *função* (ou *método*) ao chamar a função. Existem dois tipos de argumento:

- *argumento nomeado*: um argumento precedido por um identificador (por exemplo, `name=`) na chamada de uma função ou passada como um valor em um dicionário precedido por `**`. Por exemplo, 3 e 5 são ambos argumentos nomeados na chamada da função `complex()` a seguir:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

- *argumento posicional*: um argumento que não é um argumento nomeado. Argumentos posicionais podem aparecer no início da lista de argumentos e/ou podem ser passados com elementos de um *iterável* precedido por `*`. Por exemplo, 3 e 5 são ambos argumentos posicionais nas chamadas a seguir:

```
complex(3, 5)
complex(*(3, 5))
```

Argumentos são atribuídos às variáveis locais nomeadas no corpo da função. Veja a seção *calls* para as regras de atribuição. Sintaticamente, qualquer expressão pode ser usada para representar um argumento; avaliada a expressão, o valor é atribuído à variável local.

Veja também o termo *parâmetro* no glossário, a pergunta no FAQ sobre a diferença entre argumentos e parâmetros e [PEP 362](#).

**gerenciador de contexto assíncrono** Um objeto que controla o ambiente visto numa instrução `async with` por meio da definição dos métodos `__aenter__()` e `__aexit__()`. Introduzido pela [PEP 492](#).

**gerador assíncrono** Uma função que retorna um *iterador gerador assíncrono*. É parecida com uma função de corrotina definida com `async def` exceto pelo fato de conter instruções `yield` para produzir uma série de valores que podem ser usados em um laço `async for`.

Normalmente se refere a uma função geradora assíncrona, mas pode se referir a um *iterador gerador assíncrono* em alguns contextos. Em casos em que o significado não esteja claro, usar o termo completo evita a ambiguidade.

Uma função geradora assíncrona pode conter expressões `await` e também as instruções `async for` e `async with`.

**iterador gerador assíncrono** Um objeto criado por uma função *geradora assíncrona*.

Este é um *iterador assíncrono* que, quando chamado usando o método `__anext__()`, retorna um objeto aguardável que executará o corpo da função geradora assíncrona até a próxima expressão `yield`.

Cada `yield` suspende temporariamente o processamento, lembrando o estado de execução do local (incluindo variáveis locais e instruções `try` pendentes). Quando o *iterador gerador assíncrono* é efetivamente retomado com outro aguardável retornado por `__anext__()`, ele inicia de onde parou. Veja [PEP 492](#) e [PEP 525](#).

**iterável assíncrono** Um objeto que pode ser usado em uma instrução `async for`. Deve retornar um *iterador assíncrono* do seu método `__aiter__()`. Introduzido por [PEP 492](#).

**iterador assíncrono** Um objeto que implementa os métodos `__aiter__()` e `__anext__()`. `__anext__` deve retornar um objeto *aguardável*. `async for` resolve os aguardáveis retornados por um método `__anext__()` do iterador assíncrono até que ele levante uma exceção `StopAsyncIteration`. Introduzido pela [PEP 492](#).

**atributo** Um valor associado a um objeto que é geralmente referenciado pelo nome separado por um ponto. Por exemplo, se um objeto *o* tem um atributo *a* esse seria referenciado como *o.a*.

É possível dar a um objeto um atributo cujo nome não seja um identificador conforme definido por *identifiers*, por exemplo usando `setattr()`, se o objeto permitir. Tal atributo não será acessível usando uma expressão pontilhada e, em vez disso, precisaria ser recuperado com `getattr()`.

**aguardável** Um objeto que pode ser usado em uma expressão `await`. Pode ser uma *corrotina* ou um objeto com um método `__await__()`. Veja também [PEP 492](#).

**BDFL** Abreviação da expressão da língua inglesa “Benevolent Dictator for Life” (em português, “Ditador Benevolente Vitalício”), referindo-se a [Guido van Rossum](#), criador do Python.



**arquivo binário** Um *objeto arquivo* capaz de ler e gravar em *objetos byte ou similar*. Exemplos de arquivos binários são arquivos abertos no modo binário ('rb', 'wb' ou 'rb+'), `sys.stdin.buffer`, `sys.stdout.buffer` e instâncias de `io.BytesIO` e `gzip.GzipFile`.

Veja também *arquivo texto* para um objeto arquivo capaz de ler e gravar em objetos `str`.

**referência emprestada** Na API C do Python, uma referência emprestada é uma referência a um objeto que não é dona da referência. Ela se torna um ponteiro solto se o objeto for destruído. Por exemplo, uma coleta de lixo pode remover a última *referência forte* para o objeto e assim destruí-lo.

Chamar `Py_INCREF()` na *referência emprestada* é recomendado para convertê-lo, internamente, em uma *referência forte*, exceto quando o objeto não pode ser destruído antes do último uso da referência emprestada. A função `Py_NewRef()` pode ser usada para criar uma nova *referência forte*.

**objeto bytes ou similar** Um objeto com suporte ao *Protocolo de Buffer* e que pode exportar um buffer C *contíguo*. Isso inclui todos os objetos `bytes`, `bytearray` e `array.array`, além de muitos objetos `memoryview` comuns. Objetos bytes ou similares podem ser usados para várias operações que funcionam com dados binários; isso inclui compactação, salvamento em um arquivo binário e envio por um soquete.

Algumas operações precisam que os dados binários sejam mutáveis. A documentação geralmente se refere a eles como “objetos bytes ou similares para leitura e escrita”. Exemplos de objetos de buffer mutável incluem `bytearray` e um `memoryview` de um `bytearray`. Outras operações exigem que os dados binários sejam armazenados em objetos imutáveis (“objetos bytes ou similares para somente leitura”); exemplos disso incluem `bytes` e a `memoryview` de um objeto `bytes`.

**bytecode** O código-fonte Python é compilado para bytecode, a representação interna de um programa em Python no interpretador CPython. O bytecode também é mantido em cache em arquivos `.pyc` e `.pyo`, de forma que executar um mesmo arquivo é mais rápido na segunda vez (a recompilação dos fontes para bytecode não é necessária). Esta “linguagem intermediária” é adequada para execução em uma *máquina virtual*, que executa o código de máquina correspondente para cada bytecode. Tenha em mente que não se espera que bytecodes sejam executados entre máquinas virtuais Python diferentes, nem que se mantenham estáveis entre versões de Python.

Uma lista de instruções bytecode pode ser encontrada na documentação para o módulo `dis`.

**chamável** Um chamável é um objeto que pode ser chamado, possivelmente com um conjunto de argumentos (veja *argumento*), com a seguinte sintaxe:

```
callable(argument1, argument2, ...)
```

Uma *função*, e por extensão um *método*, é um chamável. Uma instância de uma classe que implementa o método `__call__()` também é um chamável.

**função de retorno** Também conhecida como callback, é uma função sub-rotina que é passada como um argumento a ser executado em algum ponto no futuro.

**classe** Um modelo para criação de objetos definidos pelo usuário. Definições de classe normalmente contém definições de métodos que operam sobre instâncias da classe.

**variável de classe** Uma variável definida em uma classe e destinada a ser modificada apenas no nível da classe (ou seja, não em uma instância da classe).

**coerção** A conversão implícita de uma instância de um tipo para outro durante uma operação que envolve dois argumentos do mesmo tipo. Por exemplo, `int(3.15)` converte o número do ponto flutuante no número inteiro 3, mas em `3+4.5`, cada argumento é de um tipo diferente (um `int`, um `float`), e ambos devem ser convertidos para o mesmo tipo antes de poderem ser adicionados ou isso levantará um `TypeError`. Sem coerção, todos os argumentos de tipos compatíveis teriam que ser normalizados com o mesmo valor pelo programador, por exemplo, `float(3)+4.5` em vez de apenas `3+4.5`.

**número complexo** Uma extensão ao familiar sistema de números reais em que todos os números são expressos como uma soma de uma parte real e uma parte imaginária. Números imaginários são múltiplos reais da unidade imaginária (a raiz quadrada de  $-1$ ), normalmente escrita como `i` em matemática ou `j` em engenharia. O Python tem suporte

nativo para números complexos, que são escritos com esta última notação; a parte imaginária escrita com um sufixo `j`, p.ex., `3+1j`. Para ter acesso aos equivalentes para números complexos do módulo `math`, utilize `cmath`. O uso de números complexos é uma funcionalidade matemática bastante avançada. Se você não sabe se irá precisar deles, é quase certo que você pode ignorá-los sem problemas.

**gerenciador de contexto** Um objeto que controla o ambiente visto numa instrução `with` por meio da definição dos métodos `__enter__()` e `__exit__()`. Veja [PEP 343](#).

**variável de contexto** Uma variável que pode ter valores diferentes, dependendo do seu contexto. Isso é semelhante ao armazenamento local de threads, no qual cada thread pode ter um valor diferente para uma variável. No entanto, com variáveis de contexto, pode haver vários contextos em uma thread e o principal uso para variáveis de contexto é acompanhar as variáveis em tarefas assíncronas simultâneas. Veja `contextvars`.

**contíguo** Um buffer é considerado contíguo exatamente se for *contíguo C* ou *contíguo Fortran*. Os buffers de dimensão zero são contíguos C e Fortran. Em vetores unidimensionais, os itens devem ser dispostos na memória próximos um do outro, em ordem crescente de índices, começando do zero. Em vetores multidimensionais contíguos C, o último índice varia mais rapidamente ao visitar itens em ordem de endereço de memória. No entanto, nos vetores contíguos do Fortran, o primeiro índice varia mais rapidamente.

**corrotina** Corrotinas são uma forma mais generalizada de sub-rotinas. Sub-rotinas tem a entrada iniciada em um ponto, e a saída em outro ponto. Corrotinas podem entrar, sair, e continuar em muitos pontos diferentes. Elas podem ser implementadas com a instrução `async def`. Veja também [PEP 492](#).

**função de corrotina** Uma função que retorna um objeto do tipo *corrotina*. Uma função de corrotina pode ser definida com a instrução `async def`, e pode conter as palavras chaves `await`, `async for`, e `async with`. Isso foi introduzido pela [PEP 492](#).

**CPython** A implementação canônica da linguagem de programação Python, como disponibilizada pelo [python.org](#). O termo “CPython” é usado quando necessário distinguir esta implementação de outras como Jython ou IronPython.

**decorador** Uma função que retorna outra função, geralmente aplicada como uma transformação de função usando a sintaxe `@wrapper`. Exemplos comuns para decoradores são `classmethod()` e `staticmethod()`.

A sintaxe do decorador é meramente um açúcar sintático, as duas definições de funções a seguir são semanticamente equivalentes:

```
def f(arg):
    ...
f = staticmethod(f)

@staticmethod
def f(arg):
    ...
```

O mesmo conceito existe para as classes, mas não é comumente utilizado. Veja a documentação de definições de função e definições de classe para obter mais informações sobre decoradores.

**descriptor** Qualquer objeto que define os métodos `__get__()`, `__set__()` ou `__delete__()`. Quando um atributo de classe é um descriptor, seu comportamento de associação especial é acionado no acesso a um atributo. Normalmente, ao se utilizar `a.b` para se obter, definir ou excluir, um atributo dispara uma busca no objeto chamado `b` no dicionário de classe de `a`, mas se `b` for um descriptor, o respectivo método descriptor é chamado. Compreender descriptors é a chave para um profundo entendimento de Python pois eles são a base de muitas funcionalidades incluindo funções, métodos, propriedades, métodos de classe, métodos estáticos e referências para superclasses.

Para obter mais informações sobre os métodos dos descriptors, veja: `descriptors` ou o Guia de Descriptors.

**dicionário** Um vetor associativo em que chaves arbitrárias são mapeadas para valores. As chaves podem ser quaisquer objetos que possuam os métodos `__hash__()` e `__eq__()`. Dicionários são estruturas chamadas de hash na linguagem Perl.

**compreensão de dicionário** Uma maneira compacta de processar todos ou parte dos elementos de um iterável e retornar um dicionário com os resultados. `results = {n: n ** 2 for n in range(10)}` gera um dicionário contendo a chave `n` mapeada para o valor `n ** 2`. Veja [comprehensions](#).

**visão de dicionário** Os objetos retornados por `dict.keys()`, `dict.values()` e `dict.items()` são chamados de visões de dicionário. Eles fornecem uma visão dinâmica das entradas do dicionário, o que significa que quando o dicionário é alterado, a visão reflete essas alterações. Para forçar a visão de dicionário a se tornar uma lista completa use `list(dictview)`. Veja [dict-views](#).

**docstring** Abreviatura de “documentation string” (string de documentação). Uma string literal que aparece como primeira expressão numa classe, função ou módulo. Ainda que sejam ignoradas quando a suíte é executada, é reconhecida pelo compilador que a coloca no atributo `__doc__` da classe, função ou módulo que a encapsula. Como ficam disponíveis por meio de introspecção, docstrings são o lugar canônico para documentação do objeto.

**tipagem pato** Também conhecida como *duck-typing*, é um estilo de programação que não verifica o tipo do objeto para determinar se ele possui a interface correta; em vez disso, o método ou atributo é simplesmente chamado ou utilizado (“Se se parece com um pato e grasna como um pato, então deve ser um pato.”) Enfatizando interfaces ao invés de tipos específicos, o código bem desenvolvido aprimora sua flexibilidade por permitir substituição polimórfica. Tipagem pato evita necessidade de testes que usem `type()` ou `isinstance()`. (Note, porém, que a tipagem pato pode ser complementada com o uso de [classes base abstratas](#).) Ao invés disso, são normalmente empregados testes `hasattr()` ou programação [EAFP](#).

**EAFP** Iniciais da expressão em inglês “easier to ask for forgiveness than permission” que significa “é mais fácil pedir perdão que permissão”. Este estilo de codificação comum no Python presume a existência de chaves ou atributos válidos e captura exceções caso essa premissa se prove falsa. Este estilo limpo e rápido se caracteriza pela presença de várias instruções `try` e `except`. A técnica diverge do estilo [LBYL](#), comum em outras linguagens como C, por exemplo.

**expressão** Uma parte da sintaxe que pode ser avaliada para algum valor. Em outras palavras, uma expressão é a acumulação de elementos de expressão como literais, nomes, atributos de acesso, operadores ou chamadas de funções, todos os quais retornam um valor. Em contraste com muitas outras linguagens, nem todas as construções de linguagem são expressões. Também existem *instruções*, as quais não podem ser usadas como expressões, como, por exemplo, `while`. Atribuições também são instruções, não expressões.

**módulo de extensão** Um módulo escrito em C ou C++, usando a API C do Python para interagir tanto com código de usuário quanto do núcleo.

**f-string** Literais string prefixadas com `'f'` ou `'F'` são conhecidas como “f-strings” que é uma abreviação de formatted string literals. Veja também [PEP 498](#).

**objeto arquivo** Um objeto que expõe uma API orientada a arquivos (com métodos tais como `read()` ou `write()`) para um recurso subjacente. Dependendo da maneira como foi criado, um objeto arquivo pode mediar o acesso a um arquivo real no disco ou outro tipo de dispositivo de armazenamento ou de comunicação (por exemplo a entrada/saída padrão, buffers em memória, soquetes, pipes, etc.). Objetos arquivo também são chamados de *objetos arquivo ou similares* ou *fluxos*.

Atualmente há três categorias de objetos arquivo: *arquivos binários brutos*, *arquivos binários em buffer* e *arquivos textos*. Suas interfaces estão definidas no módulo `io`. A forma canônica para criar um objeto arquivo é usando a função `open()`.

**objeto arquivo ou similar** Um sinônimo do termo *objeto arquivo*.

**tratador de erros e codificação do sistema de arquivos** Tratador de erros e codificação usado pelo Python para decodificar bytes do sistema operacional e codificar Unicode para o sistema operacional.

A codificação do sistema de arquivos deve garantir a decodificação bem-sucedida de todos os bytes abaixo de 128. Se a codificação do sistema de arquivos falhar em fornecer essa garantia, as funções da API podem levantar `UnicodeError`.

As funções `sys.getfilesystemencoding()` e `sys.getfilesystemencodeerrors()` podem ser usadas para obter o tratador de erros e codificação do sistema de arquivos.

O *tratador de erros e codificação do sistema de arquivos* são configurados na inicialização do Python pela função `PyConfig_Read()`: veja os membros `filesystem_encoding` e `filesystem_errors` do `PyConfig`.

Veja também *codificação da localidade*.

**localizador** Um objeto que tenta encontrar o *carregador* para um módulo que está sendo importado.

Desde o Python 3.3, existem dois tipos de localizador: *localizadores de metacaminho* para uso com `sys.meta_path`, e *localizadores de entrada de caminho* para uso com `sys.path_hooks`.

Veja [PEP 302](#), [PEP 420](#) e [PEP 451](#) para mais informações.

**divisão pelo piso** Divisão matemática que arredonda para baixo para o inteiro mais próximo. O operador de divisão pelo piso é `//`. Por exemplo, a expressão `11 // 4` retorna o valor 2 ao invés de 2.75, que seria retornado pela divisão de ponto flutuante. Note que `(-11) // 4` é -3 porque é -2.75 arredondado *para baixo*. Consulte a [PEP 238](#).

**função** Uma série de instruções que retorna algum valor para um chamador. Também pode ser passado zero ou mais *argumentos* que podem ser usados na execução do corpo. Veja também *parâmetro*, *método* e a seção *function*.

**anotação de função** Uma *anotação* de um parâmetro de função ou valor de retorno.

Anotações de função são comumente usados por *dicas de tipo*: por exemplo, essa função espera receber dois argumentos `int` e também é esperado que devolva um valor `int`:

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

A sintaxe de anotação de função é explicada na seção *function*.

Veja *anotação de variável* e [PEP 484](#), que descrevem esta funcionalidade. Veja também *annotations-howto* para as melhores práticas sobre como trabalhar com anotações.

**\_\_future\_\_** A instrução `future`, `from __future__ import <feature>`, direciona o compilador a compilar o módulo atual usando sintaxe ou semântica que será padrão em uma versão futura de Python. O módulo `__future__` documenta os possíveis valores de *feature*. Importando esse módulo e avaliando suas variáveis, você pode ver quando um novo recurso foi inicialmente adicionado à linguagem e quando será (ou se já é) o padrão:

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

**coleta de lixo** Também conhecido como *garbage collection*, é o processo de liberar a memória quando ela não é mais utilizada. Python executa a liberação da memória através da contagem de referências e um coletor de lixo cíclico que é capaz de detectar e interromper referências cíclicas. O coletor de lixo pode ser controlado usando o módulo `gc`.

**gerador** Uma função que retorna um *iterador gerador*. É parecida com uma função normal, exceto pelo fato de conter expressões `yield` para produzir uma série de valores que podem ser usados em um laço “for” ou que podem ser obtidos um de cada vez com a função `next()`.

Normalmente refere-se a uma função geradora, mas pode referir-se a um *iterador gerador* em alguns contextos. Em alguns casos onde o significado desejado não está claro, usar o termo completo evita ambiguidade.

**iterador gerador** Um objeto criado por uma função *geradora*.

Cada `yield` suspende temporariamente o processamento, memorizando o estado da execução local (incluindo variáveis locais e instruções try pendentes). Quando o *iterador gerador* retorna, ele se recupera do último ponto onde estava (em contrapartida as funções que iniciam uma nova execução a cada vez que são invocadas).

**expressão geradora** Uma expressão que retorna um iterador. Parece uma expressão normal, seguido de uma cláusula `for` definindo uma variável de loop, um `range`, e uma cláusula `if` opcional. A expressão combinada gera valores para uma função encapsuladora:

```
>>> sum(i*i for i in range(10))      # sum of squares 0, 1, 4, ... 81
285
```

**função genérica** Uma função composta por várias funções implementando a mesma operação para diferentes tipos. Qual implementação deverá ser usada durante a execução é determinada pelo algoritmo de despacho.

Veja também a entrada *despacho único* no glossário, o decorador `functools.singledispatch()`, e a [PEP 443](#).

**tipo genérico** Um *tipo* que pode ser parametrizado; tipicamente uma classe contêiner tal como `list` ou `dict`. Usado para *dicas de tipo* e *anotações*.

Para mais detalhes, veja tipo apelido genérico, [PEP 483](#), [PEP 484](#), [PEP 585](#), e o módulo `typing`.

**GIL** Veja *trava global do interpretador*.

**trava global do interpretador** O mecanismo utilizado pelo interpretador *CPython* para garantir que apenas uma thread execute o *bytecode* Python por vez. Isto simplifica a implementação do CPython ao fazer com que o modelo de objetos (incluindo tipos embutidos críticos como o `dict`) ganhem segurança implícita contra acesso concorrente. Travar todo o interpretador facilita que o interpretador em si seja multitarefa, às custas de muito do paralelismo já provido por máquinas multiprocessador.

No entanto, alguns módulos de extensão, tanto da biblioteca padrão quanto de terceiros, são desenvolvidos de forma a liberar a GIL ao realizar tarefas computacionalmente muito intensas, como compactação ou cálculos de hash. Além disso, a GIL é sempre liberado nas operações de E/S.

No passado, esforços para criar um interpretador que lidasse plenamente com threads (travando dados compartilhados numa granularidade bem mais fina) não foram bem sucedidos devido a queda no desempenho ao serem executados em processadores de apenas um núcleo. Acredita-se que superar essa questão de desempenho acabaria tornando a implementação muito mais complicada e bem mais difícil de manter.

**pyc baseado em hash** Um arquivo de cache em *bytecode* que usa hash ao invés do tempo, no qual o arquivo de código-fonte foi modificado pela última vez, para determinar a sua validade. Veja *pyc-invalidation*.

**hasheável** Um objeto é *hasheável* se tem um valor de hash que nunca muda durante seu ciclo de vida (precisa ter um método `__hash__()`) e pode ser comparado com outros objetos (precisa ter um método `__eq__()`). Objetos hasheáveis que são comparados como iguais devem ter o mesmo valor de hash.

A hasheabilidade faz com que um objeto possa ser usado como uma chave de dicionário e como um membro de conjunto, pois estas estruturas de dados utilizam os valores de hash internamente.

A maioria dos objetos embutidos imutáveis do Python são hasheáveis; containers mutáveis (tais como listas ou dicionários) não são; containers imutáveis (tais como tuplas e frozensets) são hasheáveis apenas se os seus elementos são hasheáveis. Objetos que são instâncias de classes definidas pelo usuário são hasheáveis por padrão. Todos eles comparam de forma desigual (exceto entre si mesmos), e o seu valor hash é derivado a partir do seu `id()`.

**IDLE** Um ambiente de desenvolvimento e aprendizado integrado para Python. `idle` é um editor básico e um ambiente interpretador que vem junto com a distribuição padrão do Python.

**imutável** Um objeto que possui um valor fixo. Objetos imutáveis incluem números, strings e tuplas. Estes objetos não podem ser alterados. Um novo objeto deve ser criado se um valor diferente tiver de ser armazenado. Objetos imutáveis têm um papel importante em lugares onde um valor constante de hash seja necessário, como por exemplo uma chave em um dicionário.

**caminho de importação** Uma lista de localizações (ou *entradas de caminho*) que são buscadas pelo *localizador baseado no caminho* por módulos para importar. Durante a importação, esta lista de localizações usualmente vem a partir de `sys.path`, mas para subpacotes ela também pode vir do atributo `__path__` de pacotes-pai.

**importação** O processo pelo qual o código Python em um módulo é disponibilizado para o código Python em outro módulo.

**importador** Um objeto que localiza e carrega um módulo; Tanto um *localizador* e o objeto *carregador*.

**iterativo** Python tem um interpretador interativo, o que significa que você pode digitar instruções e expressões no prompt do interpretador, executá-los imediatamente e ver seus resultados. Apenas execute `python` sem argumentos (possivelmente selecionando-o a partir do menu de aplicações de seu sistema operacional). O interpretador interativo é uma maneira poderosa de testar novas ideias ou aprender mais sobre módulos e pacotes (lembre-se do comando `help(x)`).

**interpretado** Python é uma linguagem interpretada, em oposição àquelas que são compiladas, embora esta distinção possa ser nebulosa devido à presença do compilador de bytecode. Isto significa que os arquivos-fontes podem ser executados diretamente sem necessidade explícita de se criar um arquivo executável. Linguagens interpretadas normalmente têm um ciclo de desenvolvimento/depuração mais curto que as linguagens compiladas, apesar de seus programas geralmente serem executados mais lentamente. Veja também *iterativo*.

**desligamento do interpretador** Quando solicitado para desligar, o interpretador Python entra em uma fase especial, onde ele gradualmente libera todos os recursos alocados, tais como módulos e várias estruturas internas críticas. Ele também faz diversas chamadas para o *coletor de lixo*. Isto pode disparar a execução de código em destrutores definidos pelo usuário ou função de retorno de referência fraca. Código executado durante a fase de desligamento pode encontrar diversas exceções, pois os recursos que ele depende podem não funcionar mais (exemplos comuns são os módulos de bibliotecas, ou os mecanismos de avisos).

A principal razão para o interpretador desligar, é que o módulo `__main__` ou o script sendo executado terminou sua execução.

**iterável** Um objeto capaz de retornar seus membros um de cada vez. Exemplos de iteráveis incluem todos os tipos de sequência (tais como `list`, `str` e `tuple`) e alguns tipos não sequenciais como `dict`, *objeto arquivo*, e objetos de qualquer classe que você definir com um método `__iter__()` ou com um método `__getitem__()` que implemente a semântica de *Sequência*.

Iteráveis podem ser usados em um laço `for` e em vários outros lugares em que uma sequência é necessária (`zip()`, `map()`, ...). Quando um objeto iterável é passado como argumento para a função nativa `iter()`, ela retorna um iterador para o objeto. Este iterador é adequado para se varrer todo o conjunto de valores. Ao usar iteráveis, normalmente não é necessário chamar `iter()` ou lidar com os objetos iteradores em si. A instrução `for` faz isso automaticamente para você, criando uma variável temporária para armazenar o iterador durante a execução do laço. Veja também *iterador*, *sequência*, e *gerador*.

**iterador** Um objeto que representa um fluxo de dados. Repetidas chamadas ao método `__next__()` de um iterador (ou passando o objeto para a função embutida `next()`) vão retornar itens sucessivos do fluxo. Quando não houver mais dados disponíveis uma exceção `StopIteration` será levantada. Neste ponto, o objeto iterador se esgotou e quaisquer chamadas subsequentes a seu método `__next__()` vão apenas levantar a exceção `StopIteration` novamente. Iteradores precisam ter um método `__iter__()` que retorne o objeto iterador em si, de forma que todo iterador também é iterável e pode ser usado na maioria dos lugares em que um iterável é requerido. Uma notável exceção é código que tenta realizar passagens em múltiplas iterações. Um objeto contêiner (como uma `list`) produz um novo iterador a cada vez que você passá-lo para a função `iter()` ou utilizá-lo em um laço `for`. Tentar isso com o mesmo iterador apenas iria retornar o mesmo objeto iterador esgotado já utilizado na iteração anterior, como se fosse um contêiner vazio.

Mais informações podem ser encontradas em `typeiter`.

**Detalhes da implementação do CPython:** O CPython não aplica consistentemente o requisito que um iterador define `__iter__()`.



**função chave** Uma função chave ou função colação é um chamável que retorna um valor usado para ordenação ou classificação. Por exemplo, `locale.strxfrm()` é usada para produzir uma chave de ordenação que leva o `locale` em consideração para fins de ordenação.

Uma porção de ferramentas no Python aceitam funções chave para controlar como os elementos são ordenados ou agrupados. Algumas delas incluem `min()`, `max()`, `sorted()`, `list.sort()`, `heapq.merge()`, `heapq.nsmallest()`, `heapq.nlargest()` e `itertools.groupby()`.

Há várias maneiras de se criar funções chave. Por exemplo, o método `str.lower()` pode servir como uma função chave para ordenações insensíveis à caixa. Alternativamente, uma função chave ad-hoc pode ser construída a partir de uma expressão `lambda`, como `lambda r: (r[0], r[2])`. Além disso, o módulo `operator` dispõe de três construtores para funções chave: `attrgetter()`, `itemgetter()` e o `methodcaller()`. Consulte o *HowTo de Ordenação* para ver exemplos de como criar e utilizar funções chave.

**argumento nomeado** Veja *argumento*.

**lambda** Uma função de linha anônima consistindo de uma única *expressão*, que é avaliada quando a função é chamada. A sintaxe para criar uma função `lambda` é `lambda [parameters]: expression`

**LBYL** Iniciais da expressão em inglês “look before you leap”, que significa algo como “olhe antes de pisar”. Este estilo de codificação testa as pré-condições explicitamente antes de fazer chamadas ou buscas. Este estilo contrasta com a abordagem *EAFP* e é caracterizada pela presença de muitas instruções `if`.

Em um ambiente multithread, a abordagem LBYL pode arriscar a introdução de uma condição de corrida entre “o olhar” e “o pisar”. Por exemplo, o código `if key in mapping: return mapping[key]` pode falhar se outra thread remover `key` do `mapping` após o teste, mas antes da olhada. Esse problema pode ser resolvido com travas ou usando a abordagem EAFP.

**codificação da localidade** No Unix, é a codificação da localidade do `LC_CTYPE`, que pode ser definida com `locale.setlocale(locale.LC_CTYPE, new_locale)`.

No Windows, é a página de código ANSI (ex: `cp1252`).

`locale.getpreferredencoding(False)` pode ser usado para obter da codificação da localidade.

Python usa *tratador de erros e codificação do sistema de arquivos* para converter entre nomes de arquivos e nomes de arquivos de bytes Unicode.

**lista** Uma *sequência* embutida no Python. Apesar do seu nome, é mais próximo de um vetor em outras linguagens do que uma lista encadeada, como o acesso aos elementos é da ordem  $O(1)$ .

**compreensão de lista** Uma maneira compacta de processar todos ou parte dos elementos de uma sequência e retornar os resultados em uma lista. `result = ['{:04x}'.format(x) for x in range(256) if x % 2 == 0]` gera uma lista de strings contendo números hexadecimais (0x..) no intervalo de 0 a 255. A cláusula `if` é opcional. Se omitida, todos os elementos no `range(256)` serão processados.

**carregador** Um objeto que carrega um módulo. Deve definir um método chamado `load_module()`. Um carregador é normalmente devolvido por um *localizador*. Veja a **PEP 302** para detalhes e `importlib.abc.Loader` para um *classe base abstrata*.

**método mágico** Um sinônimo informal para um *método especial*.

**mapeamento** Um objeto contêiner que suporta buscas por chaves arbitrárias e implementa os métodos especificados em classes base abstratas `Mapping` ou `MutableMapping`. Exemplos incluem `dict`, `collections.defaultdict`, `collections.OrderedDict` e `collections.Counter`.

**localizador de metacaminho** Um *localizador* retornado por uma busca de `sys.meta_path`. Localizadores de metacaminho são relacionados a, mas diferentes de, *localizadores de entrada de caminho*.

Veja `importlib.abc.MetaPathFinder` para os métodos que localizadores de metacaminho implementam.

**metaclasses** A classe de uma classe. Definições de classe criam um nome de classe, um dicionário de classe e uma lista de classes base. A metaclasses é responsável por receber estes três argumentos e criar a classe. A maioria das

linguagens de programação orientadas a objetos provê uma implementação default. O que torna o Python especial é o fato de ser possível criar metaclasses personalizadas. A maioria dos usuários nunca vai precisar deste recurso, mas quando houver necessidade, metaclasses possibilitam soluções poderosas e elegantes. Metaclasses têm sido utilizadas para gerar registros de acesso a atributos, para incluir proteção contra acesso concorrente, rastrear a criação de objetos, implementar singletons, dentre muitas outras tarefas.

Mais informações podem ser encontradas em metaclasses.

**método** Uma função que é definida dentro do corpo de uma classe. Se chamada como um atributo de uma instância daquela classe, o método receberá a instância do objeto como seu primeiro *argumento* (que comumente é chamado de `self`). Veja *função* e *escopo aninhado*.

**ordem de resolução de métodos** Ordem de resolução de métodos é a ordem em que os membros de uma classe base são buscados durante a pesquisa. Veja *A ordem de resolução de métodos do Python 2.3* para detalhes do algoritmo usado pelo interpretador do Python desde a versão 2.3.

**módulo** Um objeto que serve como uma unidade organizacional de código Python. Os módulos têm um espaço de nomes contendo objetos Python arbitrários. Os módulos são carregados pelo Python através do processo de *importação*.

Veja também *pacote*.

**spec de módulo** Um espaço de nomes que contém as informações relacionadas à importação usadas para carregar um módulo. Uma instância de `importlib.machinery.ModuleSpec`.

**MRO** Veja *ordem de resolução de métodos*.

**mutável** Objeto mutável é aquele que pode modificar seus valor mas manter seu `id()`. Veja também *imutável*.

**tupla nomeada** O termo “tupla nomeada” é aplicado a qualquer tipo ou classe que herda de `tuple` e cujos elementos indexáveis também são acessíveis usando atributos nomeados. O tipo ou classe pode ter outras funcionalidades também.

Diversos tipos embutidos são tuplas nomeadas, incluindo os valores retornados por `time.localtime()` e `os.stat()`. Outro exemplo é `sys.float_info`:

```
>>> sys.float_info[1]           # indexed access
1024
>>> sys.float_info.max_exp      # named field access
1024
>>> isinstance(sys.float_info, tuple) # kind of tuple
True
```

Algumas tuplas nomeadas são tipos embutidos (tal como os exemplos acima). Alternativamente, uma tupla nomeada pode ser criada a partir de uma definição de classe regular, que herde de `tuple` e que defina campos nomeados. Tal classe pode ser escrita a mão, ou ela pode ser criada com uma função fábrica `collections.namedtuple()`. A segunda técnica também adiciona alguns métodos extras, que podem não ser encontrados quando foi escrita manualmente, ou em tuplas nomeadas embutidas.

**espaço de nomes** O lugar em que uma variável é armazenada. Espaços de nomes são implementados como dicionários. Existem os espaços de nomes local, global e nativo, bem como espaços de nomes aninhados em objetos (em métodos). Espaços de nomes suportam modularidade ao prevenir conflitos de nomes. Por exemplo, as funções `__builtin__.open()` e `os.open()` são diferenciadas por seus espaços de nomes. Espaços de nomes também auxiliam na legibilidade e na manutenibilidade ao tornar mais claro quais módulos implementam uma função. Escrever `random.seed()` ou `itertools.izip()`, por exemplo, deixa claro que estas funções são implementadas pelos módulos `random` e `itertools` respectivamente.

**pacote de espaço de nomes** Um *pacote* da **PEP 420** que serve apenas como container para sub pacotes. Pacotes de espaços de nomes podem não ter representação física, e especificamente não são como um *pacote regular* porque eles não tem um arquivo `__init__.py`.

Veja também *módulo*.



**escopo aninhado** A habilidade de referir-se a uma variável em uma definição de fechamento. Por exemplo, uma função definida dentro de outra pode referenciar variáveis da função externa. Perceba que escopos aninhados por padrão funcionam apenas por referência e não por atribuição. Variáveis locais podem ler e escrever no escopo mais interno. De forma similar, variáveis globais podem ler e escrever para o espaço de nomes global. O `nonlocal` permite escrita para escopos externos.

**classe estilo novo** Antigo nome para o tipo de classes agora usado para todos os objetos de classes. Em versões anteriores do Python, apenas classes estilo podiam usar recursos novos e versáteis do Python, tais como `__slots__`, descritores, propriedades, `__getattr__()`, métodos de classe, e métodos estáticos.

**objeto** Qualquer dado que tenha estado (atributos ou valores) e comportamento definidos (métodos). Também a última classe base de qualquer *classe estilo novo*.

**pacote** Um *módulo* Python é capaz de conter submódulos ou recursivamente, subpacotes. Tecnicamente, um pacote é um módulo Python com um atributo `__path__`.

Vea também *pacote regular* e *pacote de espaço de nomes*.

**parâmetro** Uma entidade nomeada na definição de uma *função* (ou método) que especifica um *argumento* (ou em alguns casos, argumentos) que a função pode receber. Existem cinco tipos de parâmetros:

- *posicional-ou-nomeado*: especifica um argumento que pode ser tanto *posicional* quanto *nomeado*. Esse é o tipo padrão de parâmetro, por exemplo *foo* e *bar* a seguir:

```
def func(foo, bar=None): ...
```

- *somente-posicional*: especifica um argumento que pode ser fornecido apenas por posição. Parâmetros somente-posicionais podem ser definidos incluindo o caractere `/` na lista de parâmetros da definição da função após eles, por exemplo *somentepos1* e *somentepos2* a seguir:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

- *somente-nomeado*: especifica um argumento que pode ser passado para a função somente por nome. Parâmetros somente-nomeados podem ser definidos com um simples parâmetro var-posicional ou um `*` antes deles na lista de parâmetros na definição da função, por exemplo *somente\_nom1* and *somente\_nom2* a seguir:

```
def func(arg, *, kw_only1, kw_only2): ...
```

- *var-posicional*: especifica que uma sequência arbitrária de argumentos posicionais pode ser fornecida (em adição a qualquer argumento posicional já aceito por outros parâmetros). Tal parâmetro pode ser definido colocando um `*` antes do nome do parâmetro, por exemplo *args* a seguir:

```
def func(*args, **kwargs): ...
```

- *var-nomeado*: especifica que, arbitrariamente, muitos argumentos nomeados podem ser fornecidos (em adição a qualquer argumento nomeado já aceito por outros parâmetros). Tal parâmetro pode definido colocando-se `**` antes do nome, por exemplo *kwargs* no exemplo acima.

Parâmetros podem especificar tanto argumentos opcionais quanto obrigatórios, assim como valores padrão para alguns argumentos opcionais.

Vea também o termo *argumento* no glossário, a pergunta do FAQ sobre a diferença entre argumentos e parâmetros, a classe `inspect.Parameter`, a seção *function* e a [PEP 362](#).

**entrada de caminho** Um local único no *caminho de importação* que o *localizador baseado no caminho* consulta para encontrar módulos a serem importados.

**localizador de entrada de caminho** Um *localizador* retornado por um chamável em `sys.path_hooks` (ou seja, um *gancho de entrada de caminho*) que sabe como localizar os módulos *entrada de caminho*.

Veja `importlib.abc.PathEntryFinder` para os métodos que localizadores de entrada de caminho implementam.

**gancho de entrada de caminho** Um chamável na lista `sys.path_hook` que retorna um *localizador de entrada de caminho* caso saiba como localizar módulos em uma *entrada de caminho* específica.

**localizador baseado no caminho** Um dos *localizadores de metacaminho* padrão que procura por um *caminho de importação* de módulos.

**objeto caminho ou similar** Um objeto representando um caminho de sistema de arquivos. Um objeto caminho ou similar é ou um objeto `str` ou `bytes` representando um caminho, ou um objeto implementando o protocolo `os.PathLike`. Um objeto que suporta o protocolo `os.PathLike` pode ser convertido para um arquivo de caminho do sistema `str` ou `bytes`, através da chamada da função `os.fspath()`; `os.fsdecode()` e `os.fsencode()` podem ser usadas para garantir um `str` ou `bytes` como resultado, respectivamente. Introduzido na [PEP 519](#).

**PEP** Proposta de melhoria do Python. Uma PEP é um documento de design que fornece informação para a comunidade Python, ou descreve uma nova funcionalidade para o Python ou seus predecessores ou ambientes. PEPs devem prover uma especificação técnica concisa e um racional para funcionalidades propostas.

PEPs têm a intenção de ser os mecanismos primários para propor novas funcionalidades significativas, para coletar opiniões da comunidade sobre um problema, e para documentar as decisões de design que foram adicionadas ao Python. O autor da PEP é responsável por construir um consenso dentro da comunidade e documentar opiniões dissidentes.

Veja [PEP 1](#).

**porção** Um conjunto de arquivos em um único diretório (possivelmente armazenado em um arquivo zip) que contribuem para um pacote de espaço de nomes, conforme definido em [PEP 420](#).

**argumento posicional** Veja *argumento*.

**API provisória** Uma API provisória é uma API que foi deliberadamente excluída das bibliotecas padrões com compatibilidade retroativa garantida. Enquanto mudanças maiores para tais interfaces não são esperadas, contanto que elas sejam marcadas como provisórias, mudanças retroativas incompatíveis (até e incluindo a remoção da interface) podem ocorrer se consideradas necessárias pelos desenvolvedores principais. Tais mudanças não serão feitas gratuitamente – elas irão ocorrer apenas se sérias falhas fundamentais forem descobertas, que foram esquecidas anteriormente a inclusão da API.

Mesmo para APIs provisórias, mudanças retroativas incompatíveis são vistas como uma “solução em último caso” – cada tentativa ainda será feita para encontrar uma resolução retroativa compatível para quaisquer problemas encontrados.

Esse processo permite que a biblioteca padrão continue a evoluir com o passar do tempo, sem se prender em erros de design problemáticos por períodos de tempo prolongados. Veja [PEP 411](#) para mais detalhes.

**pacote provisório** Veja *API provisória*.

**Python 3000** Apelido para a linha de lançamento da versão do Python 3.x (cunhada há muito tempo, quando o lançamento da versão 3 era algo em um futuro muito distante.) Esse termo possui a seguinte abreviação: “Py3k”.

**Pythônico** Uma ideia ou um pedaço de código que segue de perto as formas de escritas mais comuns da linguagem Python, ao invés de implementar códigos usando conceitos comuns a outras linguagens. Por exemplo, um formato comum em Python é fazer um laço sobre todos os elementos de uma iterável usando a instrução `for`. Muitas outras linguagens não têm esse tipo de construção, então as pessoas que não estão familiarizadas com o Python usam um contador numérico:

```
for i in range(len(food)):
    print(food[i])
```

Ao contrário do método mais limpo, Pythônico:

```
for piece in food:
    print(piece)
```

**nome qualificado** Um nome pontilhado (quando 2 termos são ligados por um ponto) que mostra o “path” do escopo global de um módulo para uma classe, função ou método definido num determinado módulo, conforme definido pela [PEP 3155](#). Para funções e classes de nível superior, o nome qualificado é o mesmo que o nome do objeto:

```
>>> class C:
...     class D:
...         def meth(self):
...             pass
...
>>> C.__qualname__
'C'
>>> C.D.__qualname__
'C.D'
>>> C.D.meth.__qualname__
'C.D.meth'
```

Quando usado para se referir a módulos, o *nome totalmente qualificado* significa todo o caminho pontilhado para o módulo, incluindo quaisquer pacotes pai, por exemplo: `email.mime.text`:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

**contagem de referências** O número de referências para um objeto. Quando a contagem de referências de um objeto atinge zero, ele é desalocado. Contagem de referências geralmente não é visível no código Python, mas é um elemento chave da implementação *CPython*. O módulo `sys` define a função `getrefcount()` que programadores podem chamar para retornar a contagem de referências para um objeto em particular.

**pacote regular** Um *pacote* tradicional, como um diretório contendo um arquivo `__init__.py`.

Veja também *pacote de espaço de nomes*.

**\_\_slots\_\_** Uma declaração dentro de uma classe que economiza memória pré-declarando espaço para atributos de instâncias, e eliminando dicionários de instâncias. Apesar de popular, a técnica é um tanto quanto complicada de acertar, e é melhor se for reservada para casos raros, onde existe uma grande quantidade de instâncias em uma aplicação onde a memória é crítica.

**sequência** Um *iterável* com suporte para acesso eficiente a seus elementos através de índices inteiros via método especial `__getitem__()` e que define o método `__len__()` que devolve o tamanho da sequência. Alguns tipos de sequência embutidos são: `list`, `str`, `tuple`, e `bytes`. Note que `dict` também tem suporte para `__getitem__()` e `__len__()`, mas é considerado um mapa e não uma sequência porque a busca usa uma chave *imutável* arbitrária em vez de inteiros.

A classe base abstrata `collections.abc.Sequence` define uma interface mais rica que vai além de apenas `__getitem__()` e `__len__()`, adicionando `count()`, `index()`, `__contains__()`, e `__reversed__()`. Tipos que implementam essa interface podem ser explicitamente registrados usando `register()`.

**compreensão de conjunto** Uma maneira compacta de processar todos ou parte dos elementos em iterável e retornar um conjunto com os resultados. `results = {c for c in 'abracadabra' if c not in 'abc'}` gera um conjunto de strings `{ 'r', 'd' }`. Veja *compreensões*.

**despacho único** Uma forma de despacho de *função genérica* onde a implementação é escolhida com base no tipo de um único argumento.

**fatia** Um objeto geralmente contendo uma parte de uma *sequência*. Uma fatia é criada usando a notação de subscrito `[]` pode conter também até dois pontos entre números, como em `variable_name[1:3:5]`. A notação de suporte (subscrito) utiliza objetos `slice` internamente.

**método especial** Um método que é chamado implicitamente pelo Python para executar uma certa operação em um tipo, como uma adição por exemplo. Tais métodos tem nomes iniciando e terminando com dois underscores. Métodos especiais estão documentados em `specialnames`.

**instrução** Uma instrução é parte de uma suíte (um “bloco” de código). Uma instrução é ou uma *expressão* ou uma de várias construções com uma palavra reservada, tal como `if`, `while` ou `for`.

**referência forte** Na API C do Python, uma referência forte é uma referência a um objeto que pertence ao código que contém a referência. A referência forte é obtida chamando `Py_INCREF()` quando a referência é criada e liberada com `Py_DECREF()` quando a referência é excluída.

A função `Py_NewRef()` pode ser usada para criar uma referência forte para um objeto. Normalmente, a função `Py_DECREF()` deve ser chamada na referência forte antes de sair do escopo da referência forte, para evitar o vazamento de uma referência.

Veja também *referência emprestada*.

**codificador de texto** Uma string em Python é uma sequência de pontos de código Unicode (no intervalo U+0000–U+10FFFF). Para armazenar ou transferir uma string, ela precisa ser serializada como uma sequência de bytes.

A serialização de uma string em uma sequência de bytes é conhecida como “codificação” e a recriação da string a partir de uma sequência de bytes é conhecida como “decodificação”.

Há uma variedade de diferentes serializações de texto codecs, que são coletivamente chamadas de “codificações de texto”.

**arquivo texto** Um *objeto arquivo* apto a ler e escrever objetos `str`. Geralmente, um arquivo texto, na verdade, acessa um fluxo de dados de bytes e captura o *codificador de texto* automaticamente. Exemplos de arquivos texto são: arquivos abertos em modo texto (`'r'` or `'w'`), `sys.stdin`, `sys.stdout`, e instâncias de `io.StringIO`.

Veja também *arquivo binário* para um objeto arquivo apto a ler e escrever *objetos bytes ou similares*.

**aspas triplas** Uma string que está definida com três ocorrências de aspas duplas (”) ou apóstrofes (‘). Enquanto elas não fornecem nenhuma funcionalidade não disponível com strings de aspas simples, elas são úteis para inúmeras razões. Elas permitem que você inclua aspas simples e duplas não escapadas dentro de uma string, e elas podem utilizar múltiplas linhas sem o uso de caractere de continuação, fazendo-as especialmente úteis quando escrevemos documentação em docstrings.

**tipo** O tipo de um objeto Python determina qual tipo de objeto ele é; cada objeto tem um tipo. Um tipo de objeto é acessível pelo atributo `__class__` ou pode ser recuperado com `type(obj)`.

**apelido de tipo** Um sinônimo para um tipo, criado através da atribuição do tipo para um identificador.

Apelidos de tipo são úteis para simplificar *dicas de tipo*. Por exemplo:

```
def remove_gray_shades(
    colors: list[tuple[int, int, int]]) -> list[tuple[int, int, int]]:
    pass
```

pode tornar-se mais legível desta forma:

```
Color = tuple[int, int, int]

def remove_gray_shades(colors: list[Color]) -> list[Color]:
    pass
```

Veja `typing` e **PEP 484**, a qual descreve esta funcionalidade.

**dica de tipo** Uma *anotação* que especifica o tipo esperado para uma variável, um atributo de classe, ou um parâmetro de função ou um valor de retorno.

Dicas de tipo são opcionais e não são forçadas pelo Python, mas elas são úteis para ferramentas de análise de tipos estático, e ajudam IDEs a completar e refatorar código.

Dicas de tipos de variáveis globais, atributos de classes, e funções, mas não de variáveis locais, podem ser acessadas usando `typing.get_type_hints()`.

Veja `typing` e [PEP 484](#), a qual descreve esta funcionalidade.

**novas linhas universais** Uma maneira de interpretar fluxos de textos, na qual todos estes são reconhecidos como caracteres de fim de linha: a convenção para fim de linha no Unix `'\n'`, a convenção no Windows `'\r\n'`, e a antiga convenção no Macintosh `'\r'`. Veja [PEP 278](#) e [PEP 3116](#), bem como `bytes.splitlines()` para uso adicional.

**anotação de variável** Uma *anotação* de uma variável ou um atributo de classe.

Ao fazer uma anotação de uma variável ou um atributo de classe, a atribuição é opcional:

```
class C:
    field: 'annotation'
```

Anotações de variáveis são normalmente usadas para *dicas de tipo*: por exemplo, espera-se que esta variável receba valores do tipo `int`:

```
count: int = 0
```

A sintaxe de anotação de variável é explicada na seção `annassign`.

Veja *anotação de função*, [PEP 484](#) e [PEP 526](#), que descrevem esta funcionalidade. Veja também `annotations-howto` para as melhores práticas sobre como trabalhar com anotações.

**ambiente virtual** Um ambiente de execução isolado que permite usuários Python e aplicações instalarem e atualizarem pacotes Python sem interferir no comportamento de outras aplicações Python em execução no mesmo sistema.

Veja também `venv`.

**máquina virtual** Um computador definido inteiramente em software. A máquina virtual de Python executa o *bytecode* emitido pelo compilador de bytecode.

**Zen do Python** Lista de princípios de projeto e filosofias do Python que são úteis para a compreensão e uso da linguagem. A lista é exibida quando se digita `“import this”` no console interativo.



---

### Sobre esses documentos

---

Esses documentos são gerados a partir de [reStructuredText](#) pelo [Sphinx](#), um processador de documentos especificamente escrito para documentação Python.

O desenvolvimento da documentação e de suas ferramentas é um esforço totalmente voluntário, como Python em si. Se você quer contribuir, por favor dê uma olhada na página [reporting-bugs](#) para informações sobre como fazer. Novos voluntários são sempre bem-vindos!

Agradecimentos especiais para:

- Fred L. Drake, Jr., o criador do primeiro conjunto de ferramentas para documentar Python e escritor de boa parte do conteúdo;
- O projeto [Docutils](#) por criar [reStructuredText](#) e o pacote [Docutils](#);
- Fredrik Lundh, pelo seu projeto de referência alternativa em Python, do qual [Sphinx](#) pegou muitas boas ideias.

### B.1 Contribuidores da Documentação Python

Muitas pessoas tem contribuído para a linguagem Python, sua biblioteca padrão e sua documentação. Veja [Misc/ACKS](#) na distribuição do código do Python para ver uma lista parcial de contribuidores.

Tudo isso só foi possível com o esforço e a contribuição da comunidade Python, por isso temos essa maravilhosa documentação – Obrigado a todos!





## História e Licença

### C.1 História do software

O Python foi criado no início dos anos 1990 por Guido van Rossum na Stichting Mathematisch Centrum (CWI, veja <https://www.cwi.nl/>) na Holanda como um sucessor de uma linguagem chamada ABC. Guido continua a ser o principal autor de Python, embora inclua muitas contribuições de outros.

Em 1995, Guido continuou seu trabalho em Python na Corporação para Iniciativas Nacionais de Pesquisa (CNRI, veja <https://www.cnri.reston.va.us/>) em Reston, Virgínia, onde lançou várias versões do software.

Em maio de 2000, Guido e a equipe principal de desenvolvimento do Python mudaram-se para o BeOpen.com para formar a equipe BeOpen PythonLabs. Em outubro do mesmo ano, a equipe da PythonLabs mudou para a Digital Creations (agora Zope Corporation; veja <https://www.zope.org/>). Em 2001, formou-se a Python Software Foundation (PSF, veja <https://www.python.org/psf/>), uma organização sem fins lucrativos criada especificamente para possuir propriedade intelectual relacionada a Python. A Zope Corporation é um membro patrocinador do PSF.

Todas as versões do Python são de código aberto (consulte <https://opensource.org/> para a definição de código aberto). Historicamente, a maioria, mas não todas, versões do Python também são compatíveis com GPL; a tabela abaixo resume os vários lançamentos.

Versão	Derivada de	Ano	Proprietário	Compatível com a GPL?
0.9.0 a 1.2	n/a	1991-1995	CWI	sim
1.3 a 1.5.2	1.2	1995-1999	CNRI	sim
1.6	1.5.2	2000	CNRI	não
2.0	1.6	2000	BeOpen.com	não
1.6.1	1.6	2001	CNRI	não
2.1	2.0+1.6.1	2001	PSF	não
2.0.1	2.0+1.6.1	2001	PSF	sim
2.1.1	2.1+2.0.1	2001	PSF	sim
2.1.2	2.1.1	2002	PSF	sim
2.1.3	2.1.2	2002	PSF	sim
2.2 e acima	2.1.1	2001-agora	PSF	sim

**Nota:** Compatível com a GPL não significa que estamos distribuindo Python sob a GPL. Todas as licenças do Python, ao contrário da GPL, permitem distribuir uma versão modificada sem fazer alterações em código aberto. As licenças compatíveis com a GPL possibilitam combinar o Python com outro software lançado sob a GPL; os outros não.

---

Graças aos muitos voluntários externos que trabalharam sob a direção de Guido para tornar esses lançamentos possíveis.

## C.2 Termos e condições para acessar ou usar Python

O software e a documentação do Python são licenciados sob o *Acordo de Licenciamento PSF*.

A partir do Python 3.8.6, exemplos, receitas e outros códigos na documentação são licenciados duplamente sob o Acordo de Licenciamento PSF e a *Licença BSD de Zero Cláusula*.

Alguns softwares incorporados ao Python estão sob licenças diferentes. As licenças são listadas com o código abrangido por essa licença. Veja *Licenças e Reconhecimentos para Software Incorporado* para uma lista incompleta dessas licenças.

### C.2.1 ACORDO DE LICENCIAMENTO DA PSF PARA PYTHON 3.10.18

1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"),  
→and  
the Individual or Organization ("Licensee") accessing and otherwise using  
→Python  
3.10.18 software in source or binary form and its associated documentation.
2. Subject to the terms and conditions of this License Agreement, PSF hereby  
grants Licensee a nonexclusive, royalty-free, world-wide license to  
→reproduce,  
analyze, test, perform and/or display publicly, prepare derivative works,  
distribute, and otherwise use Python 3.10.18 alone or in any derivative  
version, provided, however, that PSF's License Agreement and PSF's notice  
→of  
copyright, i.e., "Copyright © 2001-2023 Python Software Foundation; All  
→Rights  
Reserved" are retained in Python 3.10.18 alone or in any derivative version  
prepared by Licensee.
3. In the event Licensee prepares a derivative work that is based on or  
incorporates Python 3.10.18 or any part thereof, and wants to make the  
derivative work available to others as provided herein, then Licensee  
→hereby  
agrees to include in any such work a brief summary of the changes made to  
→Python  
3.10.18.
4. PSF is making Python 3.10.18 available to Licensee on an "AS IS" basis.  
PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF  
EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION  
→OR  
WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT  
→THE  
USE OF PYTHON 3.10.18 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.10.18 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF  
 MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 3.10.18, OR ANY  
 DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
6. This License Agreement will automatically terminate upon a material breach of  
 its terms and conditions.
7. Nothing in this License Agreement shall be deemed to create any  
 relationship of agency, partnership, or joint venture between PSF and Licensee. This  
 License Agreement does not grant permission to use PSF trademarks or trade name in  
 a trademark sense to endorse or promote products or services of Licensee, or  
 any third party.
8. By copying, installing or otherwise using Python 3.10.18, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## C.2.2 ACORDO DE LICENCIAMENTO DA BEOPEN.COM PARA PYTHON 2.0

### ACORDO DE LICENCIAMENTO DA BEOPEN DE FONTE ABERTA DO PYTHON VERSÃO 1

1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
3. BeOpen is making the Software available to Licensee on an "AS IS" basis. BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
5. This License Agreement will automatically terminate upon a material breach of its terms and conditions.

(continua na próxima página)

(continuação da página anterior)

6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at <http://www.pythonlabs.com/logos.html> may be used according to the permissions granted on that web page.
7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## C.2.3 CONTRATO DE LICENÇA DA CNRI PARA O PYTHON 1.6.1

1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the internet using the following URL: <http://hdl.handle.net/1895.22/1013>."
3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
6. This License Agreement will automatically terminate upon a material breach of

(continua na próxima página)

(continuação da página anterior)

its terms and conditions.

7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## C.2.4 ACORDO DE LICENÇA DA CWI PARA PYTHON 0.9.0 A 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.2.5 LICENÇA BSD DE ZERO CLÁUSULA PARA CÓDIGO NA DOCUMENTAÇÃO DO PYTHON 3.10.18

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM

(continua na próxima página)

(continuação da página anterior)

LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3 Licenças e Reconhecimentos para Software Incorporado

Esta seção é uma lista incompleta, mas crescente, de licenças e reconhecimentos para softwares de terceiros incorporados na distribuição do Python.

### C.3.1 Mersenne Twister

O módulo `_random` inclui código baseado em um download de <http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/MT2002/emt19937ar.html>. A seguir estão os comentários literais do código original:

A C-program for MT19937, with initialization improved 2002/1/26.  
Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using `init_genrand(seed)`  
or `init_by_array(init_key, key_length)`.

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura,  
All rights reserved.

Redistribution and use in source and binary forms, with or without  
modification, are permitted provided that the following conditions  
are met:

1. Redistributions of source code must retain the above copyright  
notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright  
notice, this list of conditions and the following disclaimer in the  
documentation and/or other materials provided with the distribution.
3. The names of its contributors may not be used to endorse or promote  
products derived from this software without specific prior written  
permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS  
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT  
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR  
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR  
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,  
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,  
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR  
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF  
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING  
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS  
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome.

(continua na próxima página)

(continuação da página anterior)

```
http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html
email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)
```

## C.3.2 Soquetes

O módulo `socket` usa as funções `getaddrinfo()` e `getnameinfo()`, que são codificadas em arquivos de origem separados do Projeto WIDE, <https://www.wide.ad.jp/>.

```
Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project.
All rights reserved.
```

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

```
THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

## C.3.3 Serviços de soquete assíncrono

Os módulos `asynchat` e `asyncore` contêm o seguinte aviso:

```
Copyright 1996 by Sam Rushing
```

```
All Rights Reserved
```

```
Permission to use, copy, modify, and distribute this software and
its documentation for any purpose and without fee is hereby
granted, provided that the above copyright notice appear in all
copies and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of Sam
Rushing not be used in advertising or publicity pertaining to
distribution of the software without specific, written prior
permission.
```

```
SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE,
```

(continua na próxima página)

(continuação da página anterior)

```
INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN  
NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR  
CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS  
OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT,  
NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN  
CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.
```

### C.3.4 Gerenciamento de cookies

O módulo `http.cookies` contém o seguinte aviso:

```
Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>  
  
All Rights Reserved  
  
Permission to use, copy, modify, and distribute this software  
and its documentation for any purpose and without fee is hereby  
granted, provided that the above copyright notice appear in all  
copies and that both that copyright notice and this permission  
notice appear in supporting documentation, and that the name of  
Timothy O'Malley not be used in advertising or publicity  
pertaining to distribution of the software without specific, written  
prior permission.  
  
Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS  
SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY  
AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR  
ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES  
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,  
WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS  
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR  
PERFORMANCE OF THIS SOFTWARE.
```

### C.3.5 Rastreamento de execução

O módulo `trace` contém o seguinte aviso:

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...  
err... reserved and offered to the public under the terms of the  
Python 2.2 license.  
Author: Zooko O'Whielacronx  
http://zooko.com/  
mailto:zooko@zooko.com  
  
Copyright 2000, Mojam Media, Inc., all rights reserved.  
Author: Skip Montanaro  
  
Copyright 1999, Bioreason, Inc., all rights reserved.  
Author: Andrew Dalke  
  
Copyright 1995-1997, Automatrix, Inc., all rights reserved.  
Author: Skip Montanaro
```

(continua na próxima página)



(continuação da página anterior)

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of neither Automatrix, Bioreason or Mojam Media be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

### C.3.6 Funções UUencode e UUdecode

O módulo uu contém o seguinte aviso:

Copyright 1994 by Lance Ellinghouse  
Cathedral City, California Republic, United States of America.  
All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Lance Ellinghouse not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:

- Use binascii module to do the actual line-by-line conversion between ascii and binary. This results in a 1000-fold speedup. The C version is still 5 times faster, though.
- Arguments more compliant with Python standard

### C.3.7 Chamadas de procedimento remoto XML

O módulo xmlrpc.client contém o seguinte aviso:

The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB  
Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and

(continua na próxima página)

(continuação da página anterior)

its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

### C.3.8 test\_epoll

O módulo `test_epoll` contém o seguinte aviso:

Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

### C.3.9 kqueue de seleção

O módulo `select` contém o seguinte aviso para a interface do `kqueue`:

Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes  
All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright

(continua na próxima página)

(continuação da página anterior)

```

notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright
notice, this list of conditions and the following disclaimer in the
documentation and/or other materials provided with the distribution.

```

```

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS ``AS IS'' AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED.  IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.

```

### C.3.10 SipHash24

O arquivo `Python/pyhash.c` contém a implementação de Marek Majkowski do algoritmo SipHash24 de Dan Bernstein. Contém a seguinte nota:

```

<MIT License>
Copyright (c) 2013  Marek Majkowski <marek@popcount.org>

Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
</MIT License>

Original location:
  https://github.com/majek/csiphash/

Solution inspired by code from:
  Samuel Neves (supercop/crypto_auth/siphash24/little)
  djb (supercop/crypto_auth/siphash24/little2)
  Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)

```

### C.3.11 strtod e dtoa

O arquivo `Python/dtoa.c`, que fornece as funções C `dtoa` e `strtod` para conversão de duplas de C para e de strings, é derivado do arquivo com o mesmo nome de David M. Gay, atualmente disponível em <https://web.archive.org/web/20220517033456/http://www.netlib.org/fp/dtoa.c>. O arquivo original, conforme recuperado em 16 de março de 2009, contém os seguintes avisos de direitos autorais e de licenciamento:

```
/* *****  
 *  
 * The author of this software is David M. Gay.  
 *  
 * Copyright (c) 1991, 2000, 2001 by Lucent Technologies.  
 *  
 * Permission to use, copy, modify, and distribute this software for any  
 * purpose without fee is hereby granted, provided that this entire notice  
 * is included in all copies of any software which is or includes a copy  
 * or modification of this software and in all copies of the supporting  
 * documentation for such software.  
 *  
 * THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED  
 * WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY  
 * REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY  
 * OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.  
 *  
 ***** */
```

### C.3.12 OpenSSL

Os módulos `hashlib`, `posix`, `ssl`, `crypt` usam a biblioteca OpenSSL para desempenho adicional se forem disponibilizados pelo sistema operacional. Além disso, os instaladores do Windows e do Mac OS X para Python podem incluir uma cópia das bibliotecas do OpenSSL, portanto incluímos uma cópia da licença do OpenSSL aqui:

```
LICENSE ISSUES  
=====  
  
The OpenSSL toolkit stays under a dual license, i.e. both the conditions of  
the OpenSSL License and the original SSLeay license apply to the toolkit.  
See below for the actual license texts. Actually both licenses are BSD-style  
Open Source licenses. In case of any license issues related to OpenSSL  
please contact openssl-core@openssl.org.  
  
OpenSSL License  
-----  
  
/* =====  
 * Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved.  
 *  
 * Redistribution and use in source and binary forms, with or without  
 * modification, are permitted provided that the following conditions  
 * are met:  
 *  
 * 1. Redistributions of source code must retain the above copyright  
 * notice, this list of conditions and the following disclaimer.  
 *  
 * 2. Redistributions in binary form must reproduce the above copyright  
 * notice, this list of conditions and the following disclaimer in
```

(continua na próxima página)

(continuação da página anterior)

```

*   the documentation and/or other materials provided with the
*   distribution.
*
* 3. All advertising materials mentioning features or use of this
*   software must display the following acknowledgment:
*   "This product includes software developed by the OpenSSL Project
*   for use in the OpenSSL Toolkit. (http://www.openssl.org/)"
*
* 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to
*   endorse or promote products derived from this software without
*   prior written permission. For written permission, please contact
*   openssl-core@openssl.org.
*
* 5. Products derived from this software may not be called "OpenSSL"
*   nor may "OpenSSL" appear in their names without prior written
*   permission of the OpenSSL Project.
*
* 6. Redistributions of any form whatsoever must retain the following
*   acknowledgment:
*   "This product includes software developed by the OpenSSL Project
*   for use in the OpenSSL Toolkit (http://www.openssl.org/)"
*
* THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY
* EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
* IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
* PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR
* ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
* SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
* NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
* LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
* HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
* STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
* ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
* OF THE POSSIBILITY OF SUCH DAMAGE.
* =====
*
* This product includes cryptographic software written by Eric Young
* (eay@cryptsoft.com). This product includes software written by Tim
* Hudson (tjh@cryptsoft.com).
*
*/

```

Original SSLeay License

-----

```

/* Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com)
* All rights reserved.
*
* This package is an SSL implementation written
* by Eric Young (eay@cryptsoft.com).
* The implementation was written so as to conform with Netscapes SSL.
*
* This library is free for commercial and non-commercial use as long as
* the following conditions are aheared to. The following conditions
* apply to all code found in this distribution, be it the RC4, RSA,
* lhash, DES, etc., code; not just the SSL code. The SSL documentation
* included with this distribution is covered by the same copyright terms

```

(continua na próxima página)

(continuação da página anterior)

```

* except that the holder is Tim Hudson (tjh@cryptsoft.com).
*
* Copyright remains Eric Young's, and as such any Copyright notices in
* the code are not to be removed.
* If this package is used in a product, Eric Young should be given attribution
* as the author of the parts of the library used.
* This can be in the form of a textual message at program startup or
* in documentation (online or textual) provided with the package.
*
* Redistribution and use in source and binary forms, with or without
* modification, are permitted provided that the following conditions
* are met:
* 1. Redistributions of source code must retain the copyright
*   notice, this list of conditions and the following disclaimer.
* 2. Redistributions in binary form must reproduce the above copyright
*   notice, this list of conditions and the following disclaimer in the
*   documentation and/or other materials provided with the distribution.
* 3. All advertising materials mentioning features or use of this software
*   must display the following acknowledgement:
*   "This product includes cryptographic software written by
*    Eric Young (eay@cryptsoft.com)"
*   The word 'cryptographic' can be left out if the rouines from the library
*   being used are not cryptographic related :-).
* 4. If you include any Windows specific code (or a derivative thereof) from
*   the apps directory (application code) you must include an acknowledgement:
*   "This product includes software written by Tim Hudson (tjh@cryptsoft.com)"
*
* THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND
* ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
* IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
* ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
* FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
* DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
* OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
* HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
* LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
* OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
* SUCH DAMAGE.
*
* The licence and distribution terms for any publically available version or
* derivative of this code cannot be changed. i.e. this code cannot simply be
* copied and put under another distribution licence
* [including the GNU Public Licence.]
*/

```

### C.3.13 expat

A extensão pyexpat é construída usando uma cópia incluída das fontes de expatriadas, a menos que a compilação esteja configurada `--with-system-expat`:

```

Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd
and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the

```

(continua na próxima página)

(continuação da página anterior)

```
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:
```

```
The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.
```

```
THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT.
IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY
CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT,
TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE
SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

### C.3.14 libffi

A extensão `_ctypes` é construída usando uma cópia incluída das fontes libffi, a menos que a compilação esteja configurada `--with-system-libffi`:

```
Copyright (c) 1996-2008 Red Hat, Inc and others.
```

```
Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
`Software'), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:
```

```
The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.
```

```
THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT
HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY,
WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER
DEALINGS IN THE SOFTWARE.
```

### C.3.15 zlib

A extensão `zlib` é construída usando uma cópia incluída das fontes `zlib` se a versão do `zlib` encontrada no sistema for muito antiga para ser usada na construção:

```
Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied
warranty. In no event will the authors be held liable for any damages
arising from the use of this software.

Permission is granted to anyone to use this software for any purpose,
including commercial applications, and to alter it and redistribute it
freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not
   claim that you wrote the original software. If you use this software
   in a product, an acknowledgment in the product documentation would be
   appreciated but is not required.

2. Altered source versions must be plainly marked as such, and must not be
   misrepresented as being the original software.

3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly          Mark Adler
jloup@gzip.org            madler@alumni.caltech.edu
```

### C.3.16 cfuhash

A implementação da tabela de hash usada pelo `tracemalloc` é baseada no projeto `cfuhash`:

```
Copyright (c) 2005 Don Owens
All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

* Redistributions of source code must retain the above copyright
  notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above
  copyright notice, this list of conditions and the following
  disclaimer in the documentation and/or other materials provided
  with the distribution.

* Neither the name of the author nor the names of its
  contributors may be used to endorse or promote products derived
  from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
```

(continua na próxima página)



(continuação da página anterior)

```
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
(INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR
SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
OF THE POSSIBILITY OF SUCH DAMAGE.
```

### C.3.17 libmpdec

O módulo `_decimal` é construído usando uma cópia incluída da biblioteca `libmpdec`, a menos que a compilação esteja configurada `--with-system-libmpdec`:

```
Copyright (c) 2008-2020 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

### C.3.18 Conjunto de testes C14N do W3C

O conjunto de testes C14N 2.0 no pacote `test` (`Lib/test/xmltestdata/c14n-20/`) foi recuperado do site do W3C em <https://www.w3.org/TR/xml-c14n2-testcases/> e é distribuído sob a licença BSD de 3 cláusulas:

```
Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang),
All Rights Reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

* Redistributions of works must retain the original copyright notice,
```

(continua na próxima página)

(continuação da página anterior)

```
this list of conditions and the following disclaimer.
* Redistributions in binary form must reproduce the original copyright
  notice, this list of conditions and the following disclaimer in the
  documentation and/or other materials provided with the distribution.
* Neither the name of the W3C nor the names of its contributors may be
  used to endorse or promote products derived from this work without
  specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

### C.3.19 Audioop

O módulo audioop usa a base de código no arquivo g771.c do projeto SoX. <https://sourceforge.net/projects/sox/files/sox/12.17.7/sox-12.17.7.tar.gz>

Este código-fonte é um produto da Sun Microsystems, Inc. e é fornecido para uso irrestrito. Os usuários podem copiar ou modificar este código-fonte sem custo.

SUN SOURCE CODE IS PROVIDED AS IS WITH NO WARRANTIES OF ANY KIND INCLUDING THE WARRANTIES OF DESIGN, MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, OR ARISING FROM A COURSE OF DEALING, USAGE OR TRADE PRACTICE.

Sun source code is provided with no support and without any obligation on the part of Sun Microsystems, Inc. to assist in its use, correction, modification or enhancement.

SUN MICROSYSTEMS, INC. SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS, TRADE SECRETS OR ANY PATENTS BY THIS SOFTWARE OR ANY PART THEREOF.

In no event will Sun Microsystems, Inc. be liable for any lost revenue or profits or other special, indirect and consequential damages, even if Sun has been advised of the possibility of such damages.

Sun Microsystems, Inc. 2550 Garcia Avenue Mountain View, California 94043

## APÊNDICE D

---

### Direitos autorais

---

Python e essa documentação é:

Copyright © 2001-2023 Python Software Foundation. Todos os direitos reservados.

Copyright © 2000 BeOpen.com. Todos os direitos reservados.

Copyright © 1995-2000 Corporation for National Research Initiatives. Todos os direitos reservados.

Copyright © 1991-1995 Stichting Mathematisch Centrum. Todos os direitos reservados.

---

Veja: *História e Licença* para informações completas de licença e permissões.



## Não alfabético

..., [287](#)  
 2to3, [287](#)  
 >>>, [287](#)  
 \_\_all\_\_ (*package variable*), [70](#)  
 \_\_dict\_\_ (*module attribute*), [162](#)  
 \_\_doc\_\_ (*module attribute*), [162](#)  
 \_\_file\_\_ (*module attribute*), [162](#)  
 \_\_future\_\_, [292](#)  
 \_\_import\_\_  
     função interna, [70](#)  
 \_\_loader\_\_ (*module attribute*), [162](#)  
 \_\_main\_\_  
     módulo, [12](#), [186](#), [198](#)  
 \_\_name\_\_ (*module attribute*), [162](#)  
 \_\_package\_\_ (*module attribute*), [162](#)  
 \_\_PYENV\_LAUNCHER\_\_, [212](#), [217](#)  
 \_\_slots\_\_, [299](#)  
 \_frozen (*C struct*), [73](#)  
 \_inittab (*C struct*), [73](#)  
 \_Py\_c\_diff (*C function*), [124](#)  
 \_Py\_c\_neg (*C function*), [124](#)  
 \_Py\_c\_pow (*C function*), [124](#)  
 \_Py\_c\_prod (*C function*), [124](#)  
 \_Py\_c\_quot (*C function*), [124](#)  
 \_Py\_c\_sum (*C function*), [124](#)  
 \_Py\_InitializeMain (*C function*), [224](#)  
 \_Py\_NoneStruct (*C var*), [240](#)  
 \_PyBytes\_Resize (*C function*), [127](#)  
 \_PyCFunctionFast (*C type*), [242](#)  
 \_PyCFunctionFastWithKeywords (*C type*), [242](#)  
 \_PyFrameEvalFunction (*C type*), [196](#)  
 \_PyInterpreterState\_GetEvalFrameFunc (*C function*), [196](#)  
 \_PyInterpreterState\_SetEvalFrameFunc (*C function*), [196](#)  
 \_PyObject\_New (*C function*), [239](#)  
 \_PyObject\_NewVar (*C function*), [239](#)  
 \_PyTuple\_Resize (*C function*), [149](#)

\_thread  
     módulo, [193](#)

## A

abort(), [70](#)  
 abs  
     função interna, [99](#)  
 aguardável, [288](#)  
 allocfunc (*C type*), [277](#)  
 ambiente virtual, [301](#)  
 anotação, [287](#)  
 anotação de função, [292](#)  
 anotação de variável, [301](#)  
 apelido de tipo, [300](#)  
 API provisória, [298](#)  
 argumento, [287](#)  
 argumento nomeado, [295](#)  
 argumento posicional, [298](#)  
 argv (*in module sys*), [190](#)  
 arquivo binário, [289](#)  
 arquivo texto, [300](#)  
 ascii  
     função interna, [91](#)  
 aspas triplas, [300](#)  
 atributo, [288](#)

## B

BDFL, [288](#)  
 binaryfunc (*C type*), [278](#)  
 buffer interface  
     (see buffer protocol), [105](#)  
 buffer object  
     (see buffer protocol), [105](#)  
 buffer protocol, [105](#)  
 builtins  
     módulo, [12](#), [186](#), [198](#)  
 bytearray  
     objeto, [127](#)  
 bytecode, [289](#)  
 bytes

função interna, 91  
objeto, 125

## C

`calloc()`, 227  
caminho de importação, 294  
Capsule  
    objeto, 173  
carregador, 295  
C-contiguous, 109, 290  
chamável, 289  
classe, 289  
classe base abstrata, 287  
classe estilo novo, 297  
`classmethod`  
    função interna, 244  
cleanup functions, 70  
`close()` (*in module os*), 198  
`CO_FUTURE_DIVISION` (*C var*), 47  
code object, 159  
codificação da localidade, 295  
codificador de texto, 300  
coerção, 289  
coleta de lixo, 292  
compile  
    função interna, 71  
complex number  
    objeto, 124  
compreensão de conjunto, 299  
compreensão de dicionário, 291  
compreensão de lista, 295  
contagem de referências, 299  
contíguo, 290  
contiguous, 109  
copyright (*in module sys*), 189  
corrotina, 290  
CPython, 290

## D

decorador, 290  
`descrgetfunc` (*C type*), 278  
descriptor, 290  
`descrsetfunc` (*C type*), 278  
desligamento do interpretador, 294  
despacho único, 299  
destructor (*C type*), 277  
dica de tipo, 301  
dicionário, 290  
dictionary  
    objeto, 152  
divisão pelo piso, 292  
divmod  
    função interna, 99  
docstring, 291

## E

EAFP, 291  
entrada de caminho, 297  
`EOFError` (*built-in exception*), 161  
escopo aninhado, 297  
espaço de nomes, 296  
`exc_info()` (*in module sys*), 11  
`executable` (*in module sys*), 188  
`exit()`, 70  
expressão, 291  
expressão geradora, 293

## F

f-string, 291  
fatia, 300  
file  
    objeto, 160  
float  
    função interna, 101  
floating point  
    objeto, 123  
Fortran contiguous, 109, 290  
`free()`, 227  
`freefunc` (*C type*), 277  
freeze utility, 73  
frozenset  
    objeto, 155  
função, 292  
função chave, 295  
função de corrotina, 290  
função de retorno, 289  
função genérica, 293  
função interna  
    `__import__`, 70  
    abs, 99  
    ascii, 91  
    bytes, 91  
    `classmethod`, 244  
    compile, 71  
    divmod, 99  
    float, 101  
    hash, 92, 257  
    int, 101  
    len, 92, 101, 103, 151, 154, 156  
    pow, 99, 100  
    repr, 91, 256  
    `staticmethod`, 244  
    tuple, 102, 152  
    type, 92  
function  
    objeto, 157

## G

gancho de entrada de caminho, 298

generator, [292](#)  
 generator expression, [293](#)  
 gerador, [292](#)  
 gerador assíncrono, [288](#)  
 gerenciador de contexto, [290](#)  
 gerenciador de contexto assíncrono, [288](#)  
 getattrfunc (*C type*), [277](#)  
 getattrofunc (*C type*), [278](#)  
 getbufferproc (*C type*), [278](#)  
 getiterfunc (*C type*), [278](#)  
 GIL, [293](#)  
 global interpreter lock, [191](#)

## H

hash  
     função interna, [92](#), [257](#)  
 hasheável, [293](#)  
 hashfunc (*C type*), [278](#)

## I

IDLE, [293](#)  
 importação, [294](#)  
 importador, [294](#)  
 imutável, [293](#)  
 incr\_item(), [11](#), [12](#)  
 initproc (*C type*), [277](#)  
 inquiry (*C type*), [283](#)  
 instancemethod  
     objeto, [158](#)  
 instrução, [300](#)  
 int  
     função interna, [101](#)  
 integer  
     objeto, [119](#)  
 interativo, [294](#)  
 interpretado, [294](#)  
 interpreter lock, [191](#)  
 iterador, [294](#)  
 iterador assíncrono, [288](#)  
 iterador gerador, [292](#)  
 iterador gerador assíncrono, [288](#)  
 iterável, [294](#)  
 iterável assíncrono, [288](#)  
 iternextfunc (*C type*), [278](#)

## K

KeyboardInterrupt (*built-in exception*), [57](#), [58](#)

## L

lambda, [295](#)  
 LBYL, [295](#)  
 len  
     função interna, [92](#), [101](#), [103](#), [151](#), [154](#), [156](#)

lenfunc (*C type*), [278](#)  
 list  
     objeto, [151](#)  
 lista, [295](#)  
 localizador, [292](#)  
 localizador baseado no caminho, [298](#)  
 localizador de entrada de caminho, [297](#)  
 localizador de metacaminho, [295](#)  
 lock, interpreter, [191](#)  
 long integer  
     objeto, [119](#)  
 LONG\_MAX, [120](#)

## M

magic  
     method, [295](#)  
 main(), [187](#), [190](#)  
 malloc(), [227](#)  
 mapeamento, [295](#)  
 mapping  
     objeto, [152](#)  
 máquina virtual, [301](#)  
 memoryview  
     objeto, [172](#)  
 metaclasses, [295](#)  
 METH\_CLASS (*variável interna*), [244](#)  
 METH\_COEXIST (*variável interna*), [244](#)  
 METH\_FASTCALL (*variável interna*), [243](#)  
 METH\_NOARGS (*variável interna*), [244](#)  
 METH\_O (*variável interna*), [244](#)  
 METH\_STATIC (*variável interna*), [244](#)  
 METH\_VARARGS (*variável interna*), [243](#)  
 method  
     magic, [295](#)  
     objeto, [158](#)  
     special, [300](#)  
 MethodType (*in module types*), [157](#), [158](#)  
 método, [296](#)  
 método especial, [300](#)  
 método mágico, [295](#)  
 module  
     objeto, [162](#)  
     search path, [12](#), [186](#), [188](#), [189](#)  
 modules (*in module sys*), [70](#), [186](#)  
 ModuleType (*in module types*), [162](#)  
 módulo, [296](#)  
     \_\_main\_\_, [12](#), [186](#), [198](#)  
     \_thread, [193](#)  
     builtins, [12](#), [186](#), [198](#)  
     signal, [57](#), [58](#)  
     sys, [12](#), [186](#), [198](#)  
 módulo de extensão, [291](#)  
 MRO, [296](#)  
 mutável, [296](#)

## N

`newfunc` (*C type*), 277  
`nome qualificado`, 299  
`None`  
    objeto, 119  
`novas linhas universais`, 301  
`numeric`  
    objeto, 119  
`número complexo`, 289

## O

`object`  
    code, 159  
`objeto`, 297  
    bytearray, 127  
    bytes, 125  
    Capsule, 173  
    complex number, 124  
    dictionary, 152  
    file, 160  
    floating point, 123  
    frozenset, 155  
    function, 157  
    instancemethod, 158  
    integer, 119  
    list, 151  
    long integer, 119  
    mapping, 152  
    memoryview, 172  
    method, 158  
    module, 162  
    None, 119  
    numeric, 119  
    sequence, 125  
    set, 155  
    tuple, 148  
    type, 6, 115  
`objeto arquivo`, 291  
`objeto arquivo ou similar`, 291  
`objeto bytes ou similar`, 289  
`objeto caminho ou similar`, 298  
`objobjargproc` (*C type*), 278  
`objobjproc` (*C type*), 278  
`ordem de resolução de métodos`, 296  
`OverflowError` (*built-in exception*), 120, 121

## P

`package variable`  
    \_\_all\_\_, 70  
`pacote`, 297  
`pacote de espaço de nomes`, 296  
`pacote provisório`, 298  
`pacote regular`, 299

`parâmetro`, 297  
`PATH`, 12  
`path`  
    module search, 12, 186, 188, 189  
`path` (*in module sys*), 12, 186, 188, 189  
`PEP`, 298  
`platform` (*in module sys*), 189  
`porção`, 298  
`pow`  
    função interna, 99, 100  
`Propostas Estendidas Python`  
    PEP 1, 298  
    PEP 7, 4, 6  
    PEP 238, 47, 292  
    PEP 278, 301  
    PEP 302, 292, 295  
    PEP 343, 290  
    PEP 353, 10  
    PEP 362, 288, 297  
    PEP 383, 137, 138  
    PEP 387, 15  
    PEP 393, 128, 136  
    PEP 411, 298  
    PEP 420, 292, 296, 298  
    PEP 432, 224, 225  
    PEP 442, 271  
    PEP 443, 293  
    PEP 451, 165, 292  
    PEP 483, 293  
    PEP 484, 287, 292, 293, 300, 301  
    PEP 489, 166  
    PEP 492, 288, 290  
    PEP 498, 291  
    PEP 519, 298  
    PEP 523, 196  
    PEP 525, 288  
    PEP 526, 287, 301  
    PEP 528, 185, 216  
    PEP 529, 138, 185  
    PEP 538, 222  
    PEP 539, 202  
    PEP 540, 222  
    PEP 552, 213  
    PEP 578, 69  
    PEP 585, 293  
    PEP 587, 205  
    PEP 590, 94  
    PEP 623, 129  
    PEP 634, 261  
    PEP 3116, 301  
    PEP 3119, 92  
    PEP 3121, 163  
    PEP 3147, 72  
    PEP 3151, 63



- 
- PEP 3155, 299
  - Py\_ABS (*C macro*), 5
  - Py\_AddPendingCall (*C function*), 199
  - Py\_AddPendingCall(), 199
  - Py\_AtExit (*C function*), 70
  - Py\_BEGIN\_ALLOW\_THREADS, 191
  - Py\_BEGIN\_ALLOW\_THREADS (*C macro*), 194
  - Py\_BLOCK\_THREADS (*C macro*), 195
  - Py\_buffer (*C type*), 106
  - Py\_buffer.buf (*C member*), 106
  - Py\_buffer.format (*C member*), 107
  - Py\_buffer.internal (*C member*), 108
  - Py\_buffer.itemsize (*C member*), 107
  - Py\_buffer.len (*C member*), 106
  - Py\_buffer.ndim (*C member*), 107
  - Py\_buffer.obj (*C member*), 106
  - Py\_buffer.readonly (*C member*), 107
  - Py\_buffer.shape (*C member*), 107
  - Py\_buffer.strides (*C member*), 107
  - Py\_buffer.suboffsets (*C member*), 107
  - Py\_BuildValue (*C function*), 81
  - Py\_BytesMain (*C function*), 43
  - Py\_BytesWarningFlag (*C var*), 184
  - Py\_CHARMASK (*C macro*), 5
  - Py\_CLEAR (*C function*), 50
  - Py\_CompileString (*C function*), 45
  - Py\_CompileString(), 47
  - Py\_CompileStringExFlags (*C function*), 46
  - Py\_CompileStringFlags (*C function*), 46
  - Py\_CompileStringObject (*C function*), 46
  - Py\_complex (*C type*), 124
  - Py\_DebugFlag (*C var*), 184
  - Py\_DecodeLocale (*C function*), 66
  - Py\_DECREF (*C function*), 50
  - Py\_DecRef (*C function*), 50
  - Py\_DECREF(), 7
  - Py\_DEPRECATED (*C macro*), 5
  - Py\_DontWriteBytecodeFlag (*C var*), 184
  - Py\_Ellipsis (*C var*), 172
  - Py\_EncodeLocale (*C function*), 67
  - Py\_END\_ALLOW\_THREADS, 191
  - Py\_END\_ALLOW\_THREADS (*C macro*), 194
  - Py\_EndInterpreter (*C function*), 198
  - Py\_EnterRecursiveCall (*C function*), 61
  - Py\_eval\_input (*C var*), 47
  - Py\_Exit (*C function*), 70
  - Py\_False (*C var*), 122
  - Py\_FatalError (*C function*), 70
  - Py\_FatalError(), 190
  - Py\_FdIsInteractive (*C function*), 65
  - Py\_file\_input (*C var*), 47
  - Py\_Finalize (*C function*), 187
  - Py\_FinalizeEx (*C function*), 186
  - Py\_FinalizeEx(), 70, 186, 198
  - Py\_FrozenFlag (*C var*), 184
  - Py\_GenericAlias (*C function*), 181
  - Py\_GenericAliasType (*C var*), 181
  - Py\_GetArgcArgv (*C function*), 224
  - Py\_GetBuildInfo (*C function*), 189
  - Py\_GetCompiler (*C function*), 189
  - Py\_GetCopyright (*C function*), 189
  - Py\_GETENV (*C macro*), 5
  - Py\_GetExecPrefix (*C function*), 188
  - Py\_GetExecPrefix(), 12
  - Py\_GetPath (*C function*), 188
  - Py\_GetPath(), 12, 187, 189
  - Py\_GetPlatform (*C function*), 189
  - Py\_GetPrefix (*C function*), 188
  - Py\_GetPrefix(), 12
  - Py\_GetProgramFullPath (*C function*), 188
  - Py\_GetProgramFullPath(), 12
  - Py\_GetProgramName (*C function*), 187
  - Py\_GetPythonHome (*C function*), 190
  - Py\_GetVersion (*C function*), 189
  - Py\_HashRandomizationFlag (*C var*), 185
  - Py\_IgnoreEnvironmentFlag (*C var*), 185
  - Py\_INCREF (*C function*), 49
  - Py\_IncRef (*C function*), 50
  - Py\_INCREF(), 7
  - Py\_Initialize (*C function*), 186
  - Py\_Initialize(), 12, 187, 198
  - Py\_InitializeEx (*C function*), 186
  - Py\_InitializeFromConfig (*C function*), 220
  - Py\_InspectFlag (*C var*), 185
  - Py\_InteractiveFlag (*C var*), 185
  - Py\_Is (*C function*), 240
  - Py\_IS\_TYPE (*C function*), 241
  - Py\_IsFalse (*C function*), 241
  - Py\_IsInitialized (*C function*), 186
  - Py\_IsInitialized(), 12
  - Py\_IsNone (*C function*), 241
  - Py\_IsolatedFlag (*C var*), 185
  - Py\_IsTrue (*C function*), 241
  - Py\_LeaveRecursiveCall (*C function*), 61
  - Py\_LegacyWindowsFSEncodingFlag (*C var*), 185
  - Py\_LegacyWindowsStdioFlag (*C var*), 185
  - Py\_LIMITED\_API (*C macro*), 15
  - Py\_Main (*C function*), 43
  - PY\_MAJOR\_VERSION (*C macro*), 285
  - Py\_MAX (*C macro*), 5
  - Py\_MEMBER\_SIZE (*C macro*), 5
  - PY\_MICRO\_VERSION (*C macro*), 285
  - Py\_MIN (*C macro*), 5
  - PY\_MINOR\_VERSION (*C macro*), 285
  - Py\_mod\_create (*C macro*), 165
  - Py\_mod\_create.create\_module (*C function*), 165
  - Py\_mod\_exec (*C macro*), 166
  - Py\_mod\_exec.exec\_module (*C function*), 166

`Py_NewInterpreter` (*C function*), 198  
`Py_NewRef` (*C function*), 49  
`Py_None` (*C var*), 119  
`Py_NoSiteFlag` (*C var*), 185  
`Py_NotImplemented` (*C var*), 89  
`Py_NoUserSiteDirectory` (*C var*), 185  
`Py_OptimizeFlag` (*C var*), 186  
`Py_PreInitialize` (*C function*), 210  
`Py_PreInitializeFromArgs` (*C function*), 210  
`Py_PreInitializeFromBytesArgs` (*C function*), 210  
`Py_PRINT_RAW`, 161  
`Py_QuietFlag` (*C var*), 186  
`Py_REFCNT` (*C function*), 241  
`PY_RELEASE_LEVEL` (*C macro*), 285  
`PY_RELEASE_SERIAL` (*C macro*), 285  
`Py_ReprEnter` (*C function*), 61  
`Py_ReprLeave` (*C function*), 61  
`Py_RETURN_FALSE` (*C macro*), 122  
`Py_RETURN_NONE` (*C macro*), 119  
`Py_RETURN_NOTIMPLEMENTED` (*C macro*), 89  
`Py_RETURN_TRUE` (*C macro*), 122  
`Py_RunMain` (*C function*), 224  
`Py_SET_REFCNT` (*C function*), 241  
`Py_SET_SIZE` (*C function*), 241  
`Py_SET_TYPE` (*C function*), 241  
`Py_SetPath` (*C function*), 189  
`Py_SetPath()`, 188  
`Py_SetProgramName` (*C function*), 187  
`Py_SetProgramName()`, 12, 186, 188  
`Py_SetPythonHome` (*C function*), 190  
`Py_SetStandardStreamEncoding` (*C function*), 187  
`Py_single_input` (*C var*), 47  
`Py_SIZE` (*C function*), 241  
`Py_ssize_t` (*C type*), 10  
`PY_SSIZE_T_MAX`, 121  
`Py_STRINGIFY` (*C macro*), 5  
`Py_TPFLAGS_BASE_EXC_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_BASETYPE` (*variável interna*), 259  
`Py_TPFLAGS_BYTES_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_DEFAULT` (*variável interna*), 259  
`Py_TPFLAGS_DICT_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_DISALLOW_INSTANTIATION` (*variável interna*), 261  
`Py_TPFLAGS_HAVE_FINALIZE` (*variável interna*), 260  
`Py_TPFLAGS_HAVE_GC` (*variável interna*), 259  
`Py_TPFLAGS_HAVE_VECTORCALL` (*variável interna*), 260  
`Py_TPFLAGS_HEAPTYPE` (*variável interna*), 259  
`Py_TPFLAGS_IMMUTABLETYPE` (*variável interna*), 260  
`Py_TPFLAGS_LIST_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_LONG_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_MAPPING` (*variável interna*), 261  
`Py_TPFLAGS_METHOD_DESCRIPTOR` (*variável interna*), 260  
`Py_TPFLAGS_READY` (*variável interna*), 259  
`Py_TPFLAGS_READYING` (*variável interna*), 259  
`Py_TPFLAGS_SEQUENCE` (*variável interna*), 261  
`Py_TPFLAGS_TUPLE_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_TYPE_SUBCLASS` (*variável interna*), 260  
`Py_TPFLAGS_UNICODE_SUBCLASS` (*variável interna*), 260  
`Py_tracefunc` (*C type*), 200  
`Py_True` (*C var*), 122  
`Py_tss_NEEDS_INIT` (*C macro*), 202  
`Py_tss_t` (*C type*), 202  
`Py_TYPE` (*C function*), 241  
`Py_UCS1` (*C type*), 129  
`Py_UCS2` (*C type*), 129  
`Py_UCS4` (*C type*), 129  
`Py_UNBLOCK_THREADS` (*C macro*), 195  
`Py_UnbufferedStdioFlag` (*C var*), 186  
`Py_UNICODE` (*C type*), 129  
`Py_UNICODE_IS_HIGH_SURROGATE` (*C macro*), 132  
`Py_UNICODE_IS_LOW_SURROGATE` (*C macro*), 132  
`Py_UNICODE_IS_SURROGATE` (*C macro*), 132  
`Py_UNICODE_ISALNUM` (*C function*), 132  
`Py_UNICODE_ISALPHA` (*C function*), 132  
`Py_UNICODE_ISDECIMAL` (*C function*), 131  
`Py_UNICODE_ISDIGIT` (*C function*), 131  
`Py_UNICODE_ISLINEBREAK` (*C function*), 131  
`Py_UNICODE_ISLOWER` (*C function*), 131  
`Py_UNICODE_ISNUMERIC` (*C function*), 132  
`Py_UNICODE_ISPRINTABLE` (*C function*), 132  
`Py_UNICODE_ISSPACE` (*C function*), 131  
`Py_UNICODE_ISTITLE` (*C function*), 131  
`Py_UNICODE_ISUPPER` (*C function*), 131  
`Py_UNICODE_JOIN_SURROGATES` (*C macro*), 132  
`Py_UNICODE_TODECIMAL` (*C function*), 132  
`Py_UNICODE_TODIGIT` (*C function*), 132  
`Py_UNICODE_TOLOWER` (*C function*), 132  
`Py_UNICODE_TONUMERIC` (*C function*), 132  
`Py_UNICODE_TOTITLE` (*C function*), 132  
`Py_UNICODE_TOUPPER` (*C function*), 132  
`Py_UNREACHABLE` (*C macro*), 5  
`Py_UNUSED` (*C macro*), 5  
`Py_VaBuildValue` (*C function*), 83

- PY\_VECTORCALL\_ARGUMENTS\_OFFSET (*C macro*), 94  
 Py\_VerboseFlag (*C var*), 186  
 PY\_VERSION\_HEX (*C macro*), 285  
 Py\_VISIT (*C function*), 283  
 Py\_XDECREF (*C function*), 50  
 Py\_XDECREF (), 12  
 Py\_XINCRREF (*C function*), 49  
 Py\_XNewRef (*C function*), 49  
 PyAIter\_Check (*C function*), 104  
 PyAnySet\_Check (*C function*), 155  
 PyAnySet\_CheckExact (*C function*), 156  
 PyArg\_Parse (*C function*), 80  
 PyArg\_ParseTuple (*C function*), 80  
 PyArg\_ParseTupleAndKeywords (*C function*), 80  
 PyArg\_UnpackTuple (*C function*), 81  
 PyArg\_ValidateKeywordArguments (*C function*), 80  
 PyArg\_VaParse (*C function*), 80  
 PyArg\_VaParseTupleAndKeywords (*C function*), 80  
 PyASCIIObject (*C type*), 129  
 PyAsyncMethods (*C type*), 276  
 PyAsyncMethods.am\_aiter (*C member*), 277  
 PyAsyncMethods.am\_anext (*C member*), 277  
 PyAsyncMethods.am\_await (*C member*), 276  
 PyAsyncMethods.am\_send (*C member*), 277  
 PyBool\_Check (*C function*), 122  
 PyBool\_FromLong (*C function*), 123  
 PyBUF\_ANY\_CONTIGUOUS (*C macro*), 109  
 PyBUF\_C\_CONTIGUOUS (*C macro*), 109  
 PyBUF\_CONTIG (*C macro*), 110  
 PyBUF\_CONTIG\_RO (*C macro*), 110  
 PyBUF\_F\_CONTIGUOUS (*C macro*), 109  
 PyBUF\_FORMAT (*C macro*), 108  
 PyBUF\_FULL (*C macro*), 110  
 PyBUF\_FULL\_RO (*C macro*), 110  
 PyBUF\_INDIRECT (*C macro*), 109  
 PyBUF\_ND (*C macro*), 109  
 PyBUF\_RECORDS (*C macro*), 110  
 PyBUF\_RECORDS\_RO (*C macro*), 110  
 PyBUF\_SIMPLE (*C macro*), 109  
 PyBUF\_STRIDED (*C macro*), 110  
 PyBUF\_STRIDED\_RO (*C macro*), 110  
 PyBUF\_STRIDES (*C macro*), 109  
 PyBUF\_WRITABLE (*C macro*), 108  
 PyBuffer\_FillContiguousStrides (*C function*), 112  
 PyBuffer\_FillInfo (*C function*), 112  
 PyBuffer\_FromContiguous (*C function*), 112  
 PyBuffer\_GetPointer (*C function*), 112  
 PyBuffer\_IsContiguous (*C function*), 112  
 PyBuffer\_Release (*C function*), 112  
 PyBuffer\_SizeFromFormat (*C function*), 112  
 PyBuffer\_ToContiguous (*C function*), 112  
 PyBufferProcs, 105  
 PyBufferProcs (*C type*), 275  
 PyBufferProcs.bf\_getbuffer (*C member*), 275  
 PyBufferProcs.bf\_releasebuffer (*C member*), 276  
 PyByteArray\_AS\_STRING (*C function*), 128  
 PyByteArray\_AsString (*C function*), 128  
 PyByteArray\_Check (*C function*), 127  
 PyByteArray\_CheckExact (*C function*), 127  
 PyByteArray\_Concat (*C function*), 128  
 PyByteArray\_FromObject (*C function*), 128  
 PyByteArray\_FromStringAndSize (*C function*), 128  
 PyByteArray\_GET\_SIZE (*C function*), 128  
 PyByteArray\_Resize (*C function*), 128  
 PyByteArray\_Size (*C function*), 128  
 PyByteArray\_Type (*C var*), 127  
 PyByteArrayObject (*C type*), 127  
 PyBytes\_AS\_STRING (*C function*), 126  
 PyBytes\_AsString (*C function*), 126  
 PyBytes\_AsStringAndSize (*C function*), 126  
 PyBytes\_Check (*C function*), 125  
 PyBytes\_CheckExact (*C function*), 125  
 PyBytes\_Concat (*C function*), 127  
 PyBytes\_ConcatAndDel (*C function*), 127  
 PyBytes\_FromFormat (*C function*), 126  
 PyBytes\_FromFormatV (*C function*), 126  
 PyBytes\_FromObject (*C function*), 126  
 PyBytes\_FromString (*C function*), 125  
 PyBytes\_FromStringAndSize (*C function*), 125  
 PyBytes\_GET\_SIZE (*C function*), 126  
 PyBytes\_Size (*C function*), 126  
 PyBytes\_Type (*C var*), 125  
 PyBytesObject (*C type*), 125  
 pyc baseado em hash, 293  
 PyCallable\_Check (*C function*), 98  
 PyCallIter\_Check (*C function*), 169  
 PyCallIter\_New (*C function*), 170  
 PyCallIter\_Type (*C var*), 169  
 PyCapsule (*C type*), 173  
 PyCapsule\_CheckExact (*C function*), 173  
 PyCapsule\_Destructor (*C type*), 173  
 PyCapsule\_GetContext (*C function*), 174  
 PyCapsule\_GetDestructor (*C function*), 174  
 PyCapsule\_GetName (*C function*), 174  
 PyCapsule\_GetPointer (*C function*), 174  
 PyCapsule\_Import (*C function*), 174  
 PyCapsule\_IsValid (*C function*), 174  
 PyCapsule\_New (*C function*), 174  
 PyCapsule\_SetContext (*C function*), 175  
 PyCapsule\_SetDestructor (*C function*), 175  
 PyCapsule\_SetName (*C function*), 175  
 PyCapsule\_SetPointer (*C function*), 175

- PyCell\_Check (*C function*), 159
- PyCell\_GET (*C function*), 159
- PyCell\_Get (*C function*), 159
- PyCell\_New (*C function*), 159
- PyCell\_SET (*C function*), 159
- PyCell\_Set (*C function*), 159
- PyCell\_Type (*C var*), 159
- PyCellobject (*C type*), 159
- PyCFunction (*C type*), 242
- PyCFunctionWithKeywords (*C type*), 242
- PyCMethod (*C type*), 242
- PyCode\_Addr2Line (*C function*), 160
- PyCode\_Check (*C function*), 160
- PyCode\_GetNumFree (*C function*), 160
- PyCode\_New (*C function*), 160
- PyCode\_NewEmpty (*C function*), 160
- PyCode\_NewWithPosOnlyArgs (*C function*), 160
- PyCode\_Type (*C var*), 160
- PyCodec\_BackslashReplaceErrors (*C function*), 87
- PyCodec\_Decompile (*C function*), 86
- PyCodec\_Decoder (*C function*), 86
- PyCodec\_Encode (*C function*), 86
- PyCodec\_Encoder (*C function*), 86
- PyCodec\_IgnoreErrors (*C function*), 87
- PyCodec\_IncrementalDecoder (*C function*), 86
- PyCodec\_IncrementalEncoder (*C function*), 86
- PyCodec\_KnownEncoding (*C function*), 86
- PyCodec\_LookupError (*C function*), 87
- PyCodec\_NameReplaceErrors (*C function*), 87
- PyCodec\_Register (*C function*), 86
- PyCodec\_RegisterError (*C function*), 87
- PyCodec\_ReplaceErrors (*C function*), 87
- PyCodec\_StreamReader (*C function*), 86
- PyCodec\_StreamWriter (*C function*), 86
- PyCodec\_StrictErrors (*C function*), 87
- PyCodec\_Unregister (*C function*), 86
- PyCodec\_XMLCharRefReplaceErrors (*C function*), 87
- PyCodeObject (*C type*), 160
- PyCompactUnicodeObject (*C type*), 129
- PyCompilerFlags (*C struct*), 47
- PyCompilerFlags.cf\_feature\_version (*C member*), 47
- PyCompilerFlags.cf\_flags (*C member*), 47
- PyComplex\_AsCComplex (*C function*), 125
- PyComplex\_Check (*C function*), 124
- PyComplex\_CheckExact (*C function*), 124
- PyComplex\_FromCComplex (*C function*), 125
- PyComplex\_FromDoubles (*C function*), 125
- PyComplex\_ImagAsDouble (*C function*), 125
- PyComplex\_RealAsDouble (*C function*), 125
- PyComplex\_Type (*C var*), 124
- PyComplexObject (*C type*), 124
- PyConfig (*C type*), 211
- PyConfig.argv (*C member*), 212
- PyConfig.base\_exec\_prefix (*C member*), 212
- PyConfig.base\_executable (*C member*), 212
- PyConfig.base\_prefix (*C member*), 212
- PyConfig.buffered\_stdio (*C member*), 212
- PyConfig.bytes\_warning (*C member*), 213
- PyConfig.check\_hash\_pycs\_mode (*C member*), 213
- PyConfig.configure\_c\_stdio (*C member*), 213
- PyConfig.dev\_mode (*C member*), 213
- PyConfig.dump\_refs (*C member*), 213
- PyConfig.exec\_prefix (*C member*), 214
- PyConfig.executable (*C member*), 214
- PyConfig.faulthandler (*C member*), 214
- PyConfig.filesystem\_encoding (*C member*), 214
- PyConfig.filesystem\_errors (*C member*), 214
- PyConfig.hash\_seed (*C member*), 214
- PyConfig.home (*C member*), 215
- PyConfig.import\_time (*C member*), 215
- PyConfig.inspect (*C member*), 215
- PyConfig.install\_signal\_handlers (*C member*), 215
- PyConfig.interactive (*C member*), 215
- PyConfig.isolated (*C member*), 215
- PyConfig.legacy\_windows\_stdio (*C member*), 215
- PyConfig.malloc\_stats (*C member*), 216
- PyConfig.module\_search\_paths (*C member*), 216
- PyConfig.module\_search\_paths\_set (*C member*), 216
- PyConfig.optimization\_level (*C member*), 216
- PyConfig.orig\_argv (*C member*), 216
- PyConfig.parse\_argv (*C member*), 217
- PyConfig.parser\_debug (*C member*), 217
- PyConfig.pathconfig\_warnings (*C member*), 217
- PyConfig.platlibdir (*C member*), 216
- PyConfig.prefix (*C member*), 217
- PyConfig.program\_name (*C member*), 217
- PyConfig.pycache\_prefix (*C member*), 218
- PyConfig.PyConfig\_Clear (*C function*), 212
- PyConfig.PyConfig\_InitIsolatedConfig (*C function*), 211
- PyConfig.PyConfig\_InitPythonConfig (*C function*), 211
- PyConfig.PyConfig\_Read (*C function*), 211
- PyConfig.PyConfig\_SetArgv (*C function*), 211
- PyConfig.PyConfig\_SetBytesArgv (*C function*), 211
- PyConfig.PyConfig\_SetBytesString (*C function*), 211



- PyConfig.PyConfig\_SetString (*C function*), 211
- PyConfig.PyConfig\_SetWideStringList (*C function*), 211
- PyConfig.pythonpath\_env (*C member*), 216
- PyConfig.quiet (*C member*), 218
- PyConfig.run\_command (*C member*), 218
- PyConfig.run\_filename (*C member*), 218
- PyConfig.run\_module (*C member*), 218
- PyConfig.show\_ref\_count (*C member*), 218
- PyConfig.site\_import (*C member*), 218
- PyConfig.skip\_source\_first\_line (*C member*), 218
- PyConfig.stdio\_encoding (*C member*), 219
- PyConfig.stdio\_errors (*C member*), 219
- PyConfig.tracemalloc (*C member*), 219
- PyConfig.use\_environment (*C member*), 219
- PyConfig.use\_hash\_seed (*C member*), 215
- PyConfig.user\_site\_directory (*C member*), 219
- PyConfig.verbose (*C member*), 219
- PyConfig.warn\_default\_encoding (*C member*), 213
- PyConfig.warnoptions (*C member*), 220
- PyConfig.write\_bytecode (*C member*), 220
- PyConfig.xoptions (*C member*), 220
- PyContext (*C type*), 176
- PyContext\_CheckExact (*C function*), 176
- PyContext\_Copy (*C function*), 177
- PyContext\_CopyCurrent (*C function*), 177
- PyContext\_Enter (*C function*), 177
- PyContext\_Exit (*C function*), 177
- PyContext\_New (*C function*), 177
- PyContext\_Type (*C var*), 176
- PyContextToken (*C type*), 176
- PyContextToken\_CheckExact (*C function*), 177
- PyContextToken\_Type (*C var*), 176
- PyContextVar (*C type*), 176
- PyContextVar\_CheckExact (*C function*), 177
- PyContextVar\_Get (*C function*), 177
- PyContextVar\_New (*C function*), 177
- PyContextVar\_Reset (*C function*), 177
- PyContextVar\_Set (*C function*), 177
- PyContextVar\_Type (*C var*), 176
- PyCoro\_CheckExact (*C function*), 176
- PyCoro\_New (*C function*), 176
- PyCoro\_Type (*C var*), 176
- PyCoroObject (*C type*), 176
- PyDate\_Check (*C function*), 178
- PyDate\_CheckExact (*C function*), 178
- PyDate\_FromDate (*C function*), 178
- PyDate\_FromTimestamp (*C function*), 180
- PyDateTime\_Check (*C function*), 178
- PyDateTime\_CheckExact (*C function*), 178
- PyDateTime\_DATE\_GET\_FOLD (*C function*), 180
- PyDateTime\_DATE\_GET\_HOUR (*C function*), 179
- PyDateTime\_DATE\_GET\_MICROSECOND (*C function*), 179
- PyDateTime\_DATE\_GET\_MINUTE (*C function*), 179
- PyDateTime\_DATE\_GET\_SECOND (*C function*), 179
- PyDateTime\_DATE\_GET\_TZINFO (*C function*), 180
- PyDateTime\_DELTA\_GET\_DAYS (*C function*), 180
- PyDateTime\_DELTA\_GET\_MICROSECONDS (*C function*), 180
- PyDateTime\_DELTA\_GET\_SECONDS (*C function*), 180
- PyDateTime\_FromDateAndTime (*C function*), 178
- PyDateTime\_FromDateAndTimeAndFold (*C function*), 179
- PyDateTime\_FromTimestamp (*C function*), 180
- PyDateTime\_GET\_DAY (*C function*), 179
- PyDateTime\_GET\_MONTH (*C function*), 179
- PyDateTime\_GET\_YEAR (*C function*), 179
- PyDateTime\_TIME\_GET\_FOLD (*C function*), 180
- PyDateTime\_TIME\_GET\_HOUR (*C function*), 180
- PyDateTime\_TIME\_GET\_MICROSECOND (*C function*), 180
- PyDateTime\_TIME\_GET\_MINUTE (*C function*), 180
- PyDateTime\_TIME\_GET\_SECOND (*C function*), 180
- PyDateTime\_TIME\_GET\_TZINFO (*C function*), 180
- PyDateTime\_TimeZone\_UTC (*C var*), 178
- PyDelta\_Check (*C function*), 178
- PyDelta\_CheckExact (*C function*), 178
- PyDelta\_FromDSU (*C function*), 179
- PyDescr\_IsData (*C function*), 170
- PyDescr\_NewClassMethod (*C function*), 170
- PyDescr\_NewGetSet (*C function*), 170
- PyDescr\_NewMember (*C function*), 170
- PyDescr\_NewMethod (*C function*), 170
- PyDescr\_NewWrapper (*C function*), 170
- PyDict\_Check (*C function*), 152
- PyDict\_CheckExact (*C function*), 152
- PyDict\_Clear (*C function*), 153
- PyDict\_Contains (*C function*), 153
- PyDict\_Copy (*C function*), 153
- PyDict\_DelItem (*C function*), 153
- PyDict\_DelItemString (*C function*), 153
- PyDict\_GetItem (*C function*), 153
- PyDict\_GetItemString (*C function*), 153
- PyDict\_GetItemWithError (*C function*), 153
- PyDict\_Items (*C function*), 154
- PyDict\_Keys (*C function*), 154
- PyDict\_Merge (*C function*), 154
- PyDict\_MergeFromSeq2 (*C function*), 155
- PyDict\_New (*C function*), 152
- PyDict\_Next (*C function*), 154
- PyDict\_SetDefault (*C function*), 153
- PyDict\_SetItem (*C function*), 153
- PyDict\_SetItemString (*C function*), 153

- [PyDict\\_Size \(C function\), 154](#)
- [PyDict\\_Type \(C var\), 152](#)
- [PyDict\\_Update \(C function\), 155](#)
- [PyDict\\_Values \(C function\), 154](#)
- [PyDictObject \(C type\), 152](#)
- [PyDictProxy\\_New \(C function\), 152](#)
- [PyDoc\\_STR \(C macro\), 6](#)
- [PyDoc\\_STRVAR \(C macro\), 6](#)
- [PyErr\\_BadArgument \(C function\), 52](#)
- [PyErr\\_BadInternalCall \(C function\), 54](#)
- [PyErr\\_CheckSignals \(C function\), 57](#)
- [PyErr\\_Clear \(C function\), 52](#)
- [PyErr\\_Clear \(\), 10, 12](#)
- [PyErr\\_ExceptionMatches \(C function\), 56](#)
- [PyErr\\_ExceptionMatches \(\), 12](#)
- [PyErr\\_Fetch \(C function\), 56](#)
- [PyErr\\_Format \(C function\), 52](#)
- [PyErr\\_FormatV \(C function\), 52](#)
- [PyErr\\_GetExcInfo \(C function\), 57](#)
- [PyErr\\_GivenExceptionMatches \(C function\), 56](#)
- [PyErr\\_NewException \(C function\), 58](#)
- [PyErr\\_NewExceptionWithDoc \(C function\), 58](#)
- [PyErr\\_NoMemory \(C function\), 53](#)
- [PyErr\\_NormalizeException \(C function\), 56](#)
- [PyErr\\_Occurred \(C function\), 56](#)
- [PyErr\\_Occurred \(\), 10](#)
- [PyErr\\_Print \(C function\), 52](#)
- [PyErr\\_PrintEx \(C function\), 52](#)
- [PyErr\\_ResourceWarning \(C function\), 55](#)
- [PyErr\\_Restore \(C function\), 56](#)
- [PyErr\\_SetExcFromWindowsErr \(C function\), 53](#)
- [PyErr\\_SetExcFromWindowsErrWithFilename \(C function\), 54](#)
- [PyErr\\_SetExcFromWindowsErrWithFilenameObject \(C function\), 53](#)
- [PyErr\\_SetExcFromWindowsErrWithFilenameObjectEx \(C function\), 54](#)
- [PyErr\\_SetExcInfo \(C function\), 57](#)
- [PyErr\\_SetFromErrno \(C function\), 53](#)
- [PyErr\\_SetFromErrnoWithFilename \(C function\), 53](#)
- [PyErr\\_SetFromErrnoWithFilenameObject \(C function\), 53](#)
- [PyErr\\_SetFromErrnoWithFilenameObjects \(C function\), 53](#)
- [PyErr\\_SetFromWindowsErr \(C function\), 53](#)
- [PyErr\\_SetFromWindowsErrWithFilename \(C function\), 53](#)
- [PyErr\\_SetImportError \(C function\), 54](#)
- [PyErr\\_SetImportErrorSubclass \(C function\), 54](#)
- [PyErr\\_SetInterrupt \(C function\), 58](#)
- [PyErr\\_SetInterruptEx \(C function\), 58](#)
- [PyErr\\_SetNone \(C function\), 52](#)
- [PyErr\\_SetObject \(C function\), 52](#)
- [PyErr\\_SetString \(C function\), 52](#)
- [PyErr\\_SetString \(\), 10](#)
- [PyErr\\_SyntaxLocation \(C function\), 54](#)
- [PyErr\\_SyntaxLocationEx \(C function\), 54](#)
- [PyErr\\_SyntaxLocationObject \(C function\), 54](#)
- [PyErr\\_WarnEx \(C function\), 55](#)
- [PyErr\\_WarnExplicit \(C function\), 55](#)
- [PyErr\\_WarnExplicitObject \(C function\), 55](#)
- [PyErr\\_WarnFormat \(C function\), 55](#)
- [PyErr\\_WriteUnraisable \(C function\), 52](#)
- [PyEval\\_AcquireLock \(C function\), 197](#)
- [PyEval\\_AcquireThread \(C function\), 197](#)
- [PyEval\\_AcquireThread \(\), 193](#)
- [PyEval\\_EvalCode \(C function\), 46](#)
- [PyEval\\_EvalCodeEx \(C function\), 46](#)
- [PyEval\\_EvalFrame \(C function\), 46](#)
- [PyEval\\_EvalFrameEx \(C function\), 46](#)
- [PyEval\\_GetBuiltins \(C function\), 85](#)
- [PyEval\\_GetFrame \(C function\), 85](#)
- [PyEval\\_GetFuncDesc \(C function\), 85](#)
- [PyEval\\_GetFuncName \(C function\), 85](#)
- [PyEval\\_GetGlobals \(C function\), 85](#)
- [PyEval\\_GetLocals \(C function\), 85](#)
- [PyEval\\_InitThreads \(C function\), 193](#)
- [PyEval\\_InitThreads \(\), 186](#)
- [PyEval\\_MergeCompilerFlags \(C function\), 46](#)
- [PyEval\\_ReleaseLock \(C function\), 197](#)
- [PyEval\\_ReleaseThread \(C function\), 197](#)
- [PyEval\\_ReleaseThread \(\), 193](#)
- [PyEval\\_RestoreThread \(C function\), 193](#)
- [PyEval\\_RestoreThread \(\), 191, 193](#)
- [PyEval\\_SaveThread \(C function\), 193](#)
- [PyEval\\_SaveThread \(\), 191, 193](#)
- [PyEval\\_SetProfile \(C function\), 201](#)
- [PyEval\\_SetTrace \(C function\), 201](#)
- [PyEval\\_ThreadsInitialized \(C function\), 193](#)
- [PyExc\\_ArithmeticError, 61](#)
- [PyExc\\_AssertionError, 61](#)
- [PyExc\\_AttributeError, 61](#)
- [PyExc\\_BaseException, 61](#)
- [PyExc\\_BlockingIOError, 61](#)
- [PyExc\\_BrokenPipeError, 61](#)
- [PyExc\\_BufferError, 61](#)
- [PyExc\\_BytesWarning, 63](#)
- [PyExc\\_ChildProcessError, 61](#)
- [PyExc\\_ConnectionAbortedError, 61](#)
- [PyExc\\_ConnectionError, 61](#)
- [PyExc\\_ConnectionRefusedError, 61](#)
- [PyExc\\_ConnectionResetError, 61](#)
- [PyExc\\_DeprecationWarning, 63](#)
- [PyExc\\_EnvironmentError, 63](#)
- [PyExc\\_EOFError, 61](#)
- [PyExc\\_Exception, 61](#)

---

PyExc\_FileExistsError, 61  
 PyExc\_FileNotFoundError, 61  
 PyExc\_FloatingPointError, 61  
 PyExc\_FutureWarning, 63  
 PyExc\_GeneratorExit, 61  
 PyExc\_ImportError, 61  
 PyExc\_ImportWarning, 63  
 PyExc\_IndentationError, 61  
 PyExc\_IndexError, 61  
 PyExc\_InterruptedError, 61  
 PyExc\_IOError, 63  
 PyExc\_IsADirectoryError, 61  
 PyExc\_KeyboardInterrupt, 61  
 PyExc\_KeyError, 61  
 PyExc\_LookupError, 61  
 PyExc\_MemoryError, 61  
 PyExc\_ModuleNotFoundError, 61  
 PyExc\_NameError, 61  
 PyExc\_NotADirectoryError, 61  
 PyExc\_NotImplementedError, 61  
 PyExc\_OSError, 61  
 PyExc\_OverflowError, 61  
 PyExc\_PendingDeprecationWarning, 63  
 PyExc\_PermissionError, 61  
 PyExc\_ProcessLookupError, 61  
 PyExc\_RecursionError, 61  
 PyExc\_ReferenceError, 61  
 PyExc\_ResourceWarning, 63  
 PyExc\_RuntimeError, 61  
 PyExc\_RuntimeWarning, 63  
 PyExc\_StopAsyncIteration, 61  
 PyExc\_StopIteration, 61  
 PyExc\_SyntaxError, 61  
 PyExc\_SyntaxWarning, 63  
 PyExc\_SystemError, 61  
 PyExc\_SystemExit, 61  
 PyExc\_TabError, 61  
 PyExc\_TimeoutError, 61  
 PyExc\_TypeError, 61  
 PyExc\_UnboundLocalError, 61  
 PyExc\_UnicodeDecodeError, 61  
 PyExc\_UnicodeEncodeError, 61  
 PyExc\_UnicodeError, 61  
 PyExc\_UnicodeTranslateError, 61  
 PyExc\_UnicodeWarning, 63  
 PyExc\_UserWarning, 63  
 PyExc\_ValueError, 61  
 PyExc\_Warning, 63  
 PyExc\_WindowsError, 63  
 PyExc\_ZeroDivisionError, 61  
 PyException\_GetCause (C function), 59  
 PyException\_GetContext (C function), 59  
 PyException\_GetTraceback (C function), 59  
 PyException\_SetCause (C function), 59  
 PyException\_SetContext (C function), 59  
 PyException\_SetTraceback (C function), 59  
 PyFile\_FromFd (C function), 160  
 PyFile\_GetLine (C function), 161  
 PyFile\_SetOpenCodeHook (C function), 161  
 PyFile\_WriteObject (C function), 161  
 PyFile\_WriteString (C function), 161  
 PyFloat\_AS\_DOUBLE (C function), 123  
 PyFloat\_AsDouble (C function), 123  
 PyFloat\_Check (C function), 123  
 PyFloat\_CheckExact (C function), 123  
 PyFloat\_FromDouble (C function), 123  
 PyFloat\_FromString (C function), 123  
 PyFloat\_GetInfo (C function), 123  
 PyFloat\_GetMax (C function), 123  
 PyFloat\_GetMin (C function), 123  
 PyFloat\_Type (C var), 123  
 PyFloatObject (C type), 123  
 PyFrame\_GetBack (C function), 85  
 PyFrame\_GetCode (C function), 85  
 PyFrame\_GetLineNumber (C function), 85  
 PyFrameObject (C type), 46  
 PyFrozenSet\_Check (C function), 155  
 PyFrozenSet\_CheckExact (C function), 156  
 PyFrozenSet\_New (C function), 156  
 PyFrozenSet\_Type (C var), 155  
 PyFunction\_Check (C function), 157  
 PyFunction\_GetAnnotations (C function), 158  
 PyFunction\_GetClosure (C function), 158  
 PyFunction\_GetCode (C function), 157  
 PyFunction\_GetDefaults (C function), 157  
 PyFunction\_GetGlobals (C function), 157  
 PyFunction\_GetModule (C function), 157  
 PyFunction\_New (C function), 157  
 PyFunction\_NewWithQualName (C function), 157  
 PyFunction\_SetAnnotations (C function), 158  
 PyFunction\_SetClosure (C function), 158  
 PyFunction\_SetDefaults (C function), 157  
 PyFunction\_Type (C var), 157  
 PyFunctionObject (C type), 157  
 PyGC\_Collect (C function), 283  
 PyGC\_Disable (C function), 283  
 PyGC\_Enable (C function), 283  
 PyGC\_IsEnabled (C function), 283  
 PyGen\_Check (C function), 175  
 PyGen\_CheckExact (C function), 175  
 PyGen\_New (C function), 175  
 PyGen\_NewWithQualName (C function), 175  
 PyGen\_Type (C var), 175  
 PyGenObject (C type), 175  
 PyGetSetDef (C type), 245  
 PyGILState\_Check (C function), 194  
 PyGILState\_Ensure (C function), 194

- `PyGILState_GetThisThreadState` (*C function*), 194
- `PyGILState_Release` (*C function*), 194
- `PyImport_AddModule` (*C function*), 71
- `PyImport_AddModuleObject` (*C function*), 71
- `PyImport_AppendInittab` (*C function*), 73
- `PyImport_ExecCodeModule` (*C function*), 71
- `PyImport_ExecCodeModuleEx` (*C function*), 72
- `PyImport_ExecCodeModuleObject` (*C function*), 72
- `PyImport_ExecCodeModuleWithPathnames` (*C function*), 72
- `PyImport_ExtendInittab` (*C function*), 74
- `PyImport_FrozenModules` (*C var*), 73
- `PyImport_GetImporter` (*C function*), 73
- `PyImport_GetMagicNumber` (*C function*), 72
- `PyImport_GetMagicTag` (*C function*), 72
- `PyImport_GetModule` (*C function*), 72
- `PyImport_GetModuleDict` (*C function*), 72
- `PyImport_Import` (*C function*), 71
- `PyImport_ImportFrozenModule` (*C function*), 73
- `PyImport_ImportFrozenModuleObject` (*C function*), 73
- `PyImport_ImportModule` (*C function*), 70
- `PyImport_ImportModuleEx` (*C function*), 70
- `PyImport_ImportModuleLevel` (*C function*), 71
- `PyImport_ImportModuleLevelObject` (*C function*), 71
- `PyImport_ImportModuleNoBlock` (*C function*), 70
- `PyImport_ReloadModule` (*C function*), 71
- `PyIndex_Check` (*C function*), 101
- `PyInstanceMethod_Check` (*C function*), 158
- `PyInstanceMethod_Function` (*C function*), 158
- `PyInstanceMethod_GET_FUNCTION` (*C function*), 158
- `PyInstanceMethod_New` (*C function*), 158
- `PyInstanceMethod_Type` (*C var*), 158
- `PyInterpreterState` (*C type*), 193
- `PyInterpreterState_Clear` (*C function*), 195
- `PyInterpreterState_Delete` (*C function*), 195
- `PyInterpreterState_Get` (*C function*), 196
- `PyInterpreterState_GetDict` (*C function*), 196
- `PyInterpreterState_GetID` (*C function*), 196
- `PyInterpreterState_Head` (*C function*), 201
- `PyInterpreterState_Main` (*C function*), 201
- `PyInterpreterState_New` (*C function*), 195
- `PyInterpreterState_Next` (*C function*), 201
- `PyInterpreterState_ThreadHead` (*C function*), 201
- `PyIter_Check` (*C function*), 104
- `PyIter_Next` (*C function*), 104
- `PyIter_Send` (*C function*), 105
- `PyList_Append` (*C function*), 152
- `PyList_AsTuple` (*C function*), 152
- `PyList_Check` (*C function*), 151
- `PyList_CheckExact` (*C function*), 151
- `PyList_GET_ITEM` (*C function*), 151
- `PyList_GET_SIZE` (*C function*), 151
- `PyList_GetItem` (*C function*), 151
- `PyList_GetItem()`, 9
- `PyList_GetSlice` (*C function*), 152
- `PyList_Insert` (*C function*), 151
- `PyList_New` (*C function*), 151
- `PyList_Reverse` (*C function*), 152
- `PyList_SET_ITEM` (*C function*), 151
- `PyList_SetItem` (*C function*), 151
- `PyList_SetItem()`, 8
- `PyList_SetSlice` (*C function*), 152
- `PyList_Size` (*C function*), 151
- `PyList_Sort` (*C function*), 152
- `PyList_Type` (*C var*), 151
- `PyListObject` (*C type*), 151
- `PyLong_AsDouble` (*C function*), 122
- `PyLong_AsLong` (*C function*), 120
- `PyLong_AsLongAndOverflow` (*C function*), 120
- `PyLong_AsLongLong` (*C function*), 121
- `PyLong_AsLongLongAndOverflow` (*C function*), 121
- `PyLong_AsSize_t` (*C function*), 121
- `PyLong_AsSsize_t` (*C function*), 121
- `PyLong_AsUnsignedLong` (*C function*), 121
- `PyLong_AsUnsignedLongLong` (*C function*), 121
- `PyLong_AsUnsignedLongLongMask` (*C function*), 122
- `PyLong_AsUnsignedLongMask` (*C function*), 121
- `PyLong_AsVoidPtr` (*C function*), 122
- `PyLong_Check` (*C function*), 119
- `PyLong_CheckExact` (*C function*), 119
- `PyLong_FromDouble` (*C function*), 120
- `PyLong_FromLong` (*C function*), 119
- `PyLong_FromLongLong` (*C function*), 120
- `PyLong_FromSize_t` (*C function*), 119
- `PyLong_FromSsize_t` (*C function*), 119
- `PyLong_FromString` (*C function*), 120
- `PyLong_FromUnicodeObject` (*C function*), 120
- `PyLong_FromUnsignedLong` (*C function*), 119
- `PyLong_FromUnsignedLongLong` (*C function*), 120
- `PyLong_FromVoidPtr` (*C function*), 120
- `PyLong_Type` (*C var*), 119
- `PyLongObject` (*C type*), 119
- `PyMapping_Check` (*C function*), 103
- `PyMapping_DelItem` (*C function*), 103
- `PyMapping_DelItemString` (*C function*), 103
- `PyMapping_GetItemString` (*C function*), 103
- `PyMapping_HasKey` (*C function*), 104
- `PyMapping_HasKeyString` (*C function*), 104
- `PyMapping_Items` (*C function*), 104



- PyMapping\_Keys (*C function*), 104
- PyMapping\_Length (*C function*), 103
- PyMapping\_SetItemString (*C function*), 103
- PyMapping\_Size (*C function*), 103
- PyMapping\_Values (*C function*), 104
- PyMappingMethods (*C type*), 274
- PyMappingMethods.mp\_ass\_subscript (*C member*), 274
- PyMappingMethods.mp\_length (*C member*), 274
- PyMappingMethods.mp\_subscript (*C member*), 274
- PyMarshal\_ReadLastObjectFromFile (*C function*), 74
- PyMarshal\_ReadLongFromFile (*C function*), 74
- PyMarshal\_ReadObjectFromFile (*C function*), 74
- PyMarshal\_ReadObjectFromString (*C function*), 75
- PyMarshal\_ReadShortFromFile (*C function*), 74
- PyMarshal\_WriteLongToFile (*C function*), 74
- PyMarshal\_WriteObjectToFile (*C function*), 74
- PyMarshal\_WriteObjectToString (*C function*), 74
- PyMem\_Calloc (*C function*), 230
- PyMem\_Del (*C function*), 230
- PyMem\_Free (*C function*), 230
- PyMem\_GetAllocator (*C function*), 233
- PyMem\_Malloc (*C function*), 229
- PyMem\_New (*C function*), 230
- PyMem\_RawCalloc (*C function*), 229
- PyMem\_RawFree (*C function*), 229
- PyMem\_RawMalloc (*C function*), 229
- PyMem\_RawRealloc (*C function*), 229
- PyMem\_Realloc (*C function*), 230
- PyMem\_Resize (*C function*), 230
- PyMem\_SetAllocator (*C function*), 233
- PyMem\_SetupDebugHooks (*C function*), 233
- PyMemAllocatorDomain (*C type*), 232
- PyMemAllocatorDomain.PYMEM\_DOMAIN\_MEM (*C macro*), 233
- PyMemAllocatorDomain.PYMEM\_DOMAIN\_OBJ (*C macro*), 233
- PyMemAllocatorDomain.PYMEM\_DOMAIN\_RAW (*C macro*), 232
- PyMemAllocatorEx (*C type*), 232
- PyMember\_GetOne (*C function*), 245
- PyMember\_SetOne (*C function*), 245
- PyMemberDef (*C type*), 244
- PyMemoryView\_Check (*C function*), 172
- PyMemoryView\_FromBuffer (*C function*), 172
- PyMemoryView\_FromMemory (*C function*), 172
- PyMemoryView\_FromObject (*C function*), 172
- PyMemoryView\_GET\_BASE (*C function*), 172
- PyMemoryView\_GET\_BUFFER (*C function*), 172
- PyMemoryView\_GetContiguous (*C function*), 172
- PyMethod\_Check (*C function*), 158
- PyMethod\_Function (*C function*), 159
- PyMethod\_GET\_FUNCTION (*C function*), 159
- PyMethod\_GET\_SELF (*C function*), 159
- PyMethod\_New (*C function*), 158
- PyMethod\_Self (*C function*), 159
- PyMethod\_Type (*C var*), 158
- PyMethodDef (*C type*), 242
- PyMethodDef.ml\_doc (*C member*), 243
- PyMethodDef.ml\_flags (*C member*), 243
- PyMethodDef.ml\_meth (*C member*), 243
- PyMethodDef.ml\_name (*C member*), 243
- PyModule\_AddFunctions (*C function*), 166
- PyModule\_AddIntConstant (*C function*), 168
- PyModule\_AddIntMacro (*C function*), 168
- PyModule\_AddObject (*C function*), 167
- PyModule\_AddObjectRef (*C function*), 167
- PyModule\_AddStringConstant (*C function*), 168
- PyModule\_AddStringMacro (*C function*), 168
- PyModule\_AddType (*C function*), 168
- PyModule\_Check (*C function*), 162
- PyModule\_CheckExact (*C function*), 162
- PyModule\_Create (*C function*), 164
- PyModule\_Create2 (*C function*), 164
- PyModule\_ExecDef (*C function*), 166
- PyModule\_FromDefAndSpec (*C function*), 166
- PyModule\_FromDefAndSpec2 (*C function*), 166
- PyModule\_GetDef (*C function*), 162
- PyModule\_GetDict (*C function*), 162
- PyModule\_GetFilename (*C function*), 162
- PyModule\_GetFilenameObject (*C function*), 162
- PyModule\_GetName (*C function*), 162
- PyModule\_GetNameObject (*C function*), 162
- PyModule\_GetState (*C function*), 162
- PyModule\_New (*C function*), 162
- PyModule\_NewObject (*C function*), 162
- PyModule\_SetDocString (*C function*), 166
- PyModule\_Type (*C var*), 162
- PyModuleDef (*C type*), 163
- PyModuleDef\_Init (*C function*), 165
- PyModuleDef\_Slot (*C type*), 165
- PyModuleDef\_Slot.slot (*C member*), 165
- PyModuleDef\_Slot.value (*C member*), 165
- PyModuleDef.m\_base (*C member*), 163
- PyModuleDef.m\_clear (*C member*), 164
- PyModuleDef.m\_doc (*C member*), 163
- PyModuleDef.m\_free (*C member*), 164
- PyModuleDef.m\_methods (*C member*), 163
- PyModuleDef.m\_name (*C member*), 163
- PyModuleDef.m\_size (*C member*), 163
- PyModuleDef.m\_slots (*C member*), 163
- PyModuleDef.m\_slots.m\_reload (*C member*), 163

- `PyModuleDef.m_traverse` (*C member*), 164
- `PyNumber_Absolute` (*C function*), 99
- `PyNumber_Add` (*C function*), 98
- `PyNumber_And` (*C function*), 99
- `PyNumber_AsSsize_t` (*C function*), 101
- `PyNumber_Check` (*C function*), 98
- `PyNumber_Divmod` (*C function*), 99
- `PyNumber_Float` (*C function*), 101
- `PyNumber_FloorDivide` (*C function*), 98
- `PyNumber_Index` (*C function*), 101
- `PyNumber_InPlaceAdd` (*C function*), 99
- `PyNumber_InPlaceAnd` (*C function*), 100
- `PyNumber_InPlaceFloorDivide` (*C function*), 100
- `PyNumber_InPlaceLshift` (*C function*), 100
- `PyNumber_InPlaceMatrixMultiply` (*C function*), 100
- `PyNumber_InPlaceMultiply` (*C function*), 100
- `PyNumber_InPlaceOr` (*C function*), 100
- `PyNumber_InPlacePower` (*C function*), 100
- `PyNumber_InPlaceRemainder` (*C function*), 100
- `PyNumber_InPlaceRshift` (*C function*), 100
- `PyNumber_InPlaceSubtract` (*C function*), 99
- `PyNumber_InPlaceTrueDivide` (*C function*), 100
- `PyNumber_InPlaceXor` (*C function*), 100
- `PyNumber_Invert` (*C function*), 99
- `PyNumber_Long` (*C function*), 101
- `PyNumber_Lshift` (*C function*), 99
- `PyNumber_MatrixMultiply` (*C function*), 98
- `PyNumber_Multiply` (*C function*), 98
- `PyNumber_Negative` (*C function*), 99
- `PyNumber_Or` (*C function*), 99
- `PyNumber_Positive` (*C function*), 99
- `PyNumber_Power` (*C function*), 99
- `PyNumber_Remainder` (*C function*), 99
- `PyNumber_Rshift` (*C function*), 99
- `PyNumber_Subtract` (*C function*), 98
- `PyNumber_ToBase` (*C function*), 101
- `PyNumber_TrueDivide` (*C function*), 98
- `PyNumber_Xor` (*C function*), 99
- `PyNumberMethods` (*C type*), 272
- `PyNumberMethods.nb_absolute` (*C member*), 273
- `PyNumberMethods.nb_add` (*C member*), 273
- `PyNumberMethods.nb_and` (*C member*), 273
- `PyNumberMethods.nb_bool` (*C member*), 273
- `PyNumberMethods.nb_divmod` (*C member*), 273
- `PyNumberMethods.nb_float` (*C member*), 273
- `PyNumberMethods.nb_floor_divide` (*C member*), 274
- `PyNumberMethods.nb_index` (*C member*), 274
- `PyNumberMethods.nb_inplace_add` (*C member*), 273
- `PyNumberMethods.nb_inplace_and` (*C member*), 273
- `PyNumberMethods.nb_inplace_floor_divide` (*C member*), 274
- `PyNumberMethods.nb_inplace_lshift` (*C member*), 273
- `PyNumberMethods.nb_inplace_matrix_multiply` (*C member*), 274
- `PyNumberMethods.nb_inplace_multiply` (*C member*), 273
- `PyNumberMethods.nb_inplace_or` (*C member*), 274
- `PyNumberMethods.nb_inplace_power` (*C member*), 273
- `PyNumberMethods.nb_inplace_remainder` (*C member*), 273
- `PyNumberMethods.nb_inplace_rshift` (*C member*), 273
- `PyNumberMethods.nb_inplace_subtract` (*C member*), 273
- `PyNumberMethods.nb_inplace_true_divide` (*C member*), 274
- `PyNumberMethods.nb_inplace_xor` (*C member*), 274
- `PyNumberMethods.nb_int` (*C member*), 273
- `PyNumberMethods.nb_invert` (*C member*), 273
- `PyNumberMethods.nb_lshift` (*C member*), 273
- `PyNumberMethods.nb_matrix_multiply` (*C member*), 274
- `PyNumberMethods.nb_multiply` (*C member*), 273
- `PyNumberMethods.nb_negative` (*C member*), 273
- `PyNumberMethods.nb_or` (*C member*), 273
- `PyNumberMethods.nb_positive` (*C member*), 273
- `PyNumberMethods.nb_power` (*C member*), 273
- `PyNumberMethods.nb_remainder` (*C member*), 273
- `PyNumberMethods.nb_reserved` (*C member*), 273
- `PyNumberMethods.nb_rshift` (*C member*), 273
- `PyNumberMethods.nb_subtract` (*C member*), 273
- `PyNumberMethods.nb_true_divide` (*C member*), 274
- `PyNumberMethods.nb_xor` (*C member*), 273
- `PyObject` (*C type*), 240
- `PyObject_AsCharBuffer` (*C function*), 113
- `PyObject_ASCII` (*C function*), 91
- `PyObject_AsFileDescriptor` (*C function*), 161
- `PyObject_AsReadBuffer` (*C function*), 113
- `PyObject_AsWriteBuffer` (*C function*), 113
- `PyObject_Bytes` (*C function*), 91
- `PyObject_Call` (*C function*), 96
- `PyObject_CallFunction` (*C function*), 96
- `PyObject_CallFunctionObjArgs` (*C function*), 97
- `PyObject_CallMethod` (*C function*), 97
- `PyObject_CallMethodNoArgs` (*C function*), 97
- `PyObject_CallMethodObjArgs` (*C function*), 97

- `PyObject_CallMethodOneArg` (*C function*), 97
- `PyObject_CallNoArgs` (*C function*), 96
- `PyObject_CallObject` (*C function*), 96
- `PyObject_Calloc` (*C function*), 231
- `PyObject_CallOneArg` (*C function*), 96
- `PyObject_CheckBuffer` (*C function*), 111
- `PyObject_CheckReadBuffer` (*C function*), 113
- `PyObject_ClearWeakRefs` (*C function*), 173
- `PyObject_Del` (*C function*), 239
- `PyObject_DelAttr` (*C function*), 90
- `PyObject_DelAttrString` (*C function*), 90
- `PyObject_DelItem` (*C function*), 93
- `PyObject_Dir` (*C function*), 93
- `PyObject_Format` (*C function*), 91
- `PyObject_Free` (*C function*), 231
- `PyObject_GC_Del` (*C function*), 282
- `PyObject_GC_IsFinalized` (*C function*), 282
- `PyObject_GC_IsTracked` (*C function*), 282
- `PyObject_GC_New` (*C function*), 282
- `PyObject_GC_NewVar` (*C function*), 282
- `PyObject_GC_Resize` (*C function*), 282
- `PyObject_GC_Track` (*C function*), 282
- `PyObject_GC_UnTrack` (*C function*), 282
- `PyObject_GenericGetAttr` (*C function*), 90
- `PyObject_GenericGetDict` (*C function*), 90
- `PyObject_GenericSetAttr` (*C function*), 90
- `PyObject_GenericSetDict` (*C function*), 90
- `PyObject_GetAIter` (*C function*), 93
- `PyObject_GetArenaAllocator` (*C function*), 235
- `PyObject_GetAttr` (*C function*), 90
- `PyObject_GetAttrString` (*C function*), 90
- `PyObject_GetBuffer` (*C function*), 111
- `PyObject_GetItem` (*C function*), 93
- `PyObject_GetIter` (*C function*), 93
- `PyObject_HasAttr` (*C function*), 89
- `PyObject_HasAttrString` (*C function*), 89
- `PyObject_Hash` (*C function*), 92
- `PyObject_HashNotImplemented` (*C function*), 92
- `PyObject_HEAD` (*C macro*), 240
- `PyObject_HEAD_INIT` (*C macro*), 241
- `PyObject_Init` (*C function*), 239
- `PyObject_InitVar` (*C function*), 239
- `PyObject_IS_GC` (*C function*), 282
- `PyObject_IsInstance` (*C function*), 92
- `PyObject_IsSubclass` (*C function*), 91
- `PyObject_IsTrue` (*C function*), 92
- `PyObject_Length` (*C function*), 92
- `PyObject_LengthHint` (*C function*), 92
- `PyObject_Malloc` (*C function*), 231
- `PyObject_New` (*C function*), 239
- `PyObject_NewVar` (*C function*), 239
- `PyObject_Not` (*C function*), 92
- `PyObject._ob_next` (*C member*), 253
- `PyObject._ob_prev` (*C member*), 253
- `PyObject_Print` (*C function*), 89
- `PyObject_Realloc` (*C function*), 231
- `PyObject_Repr` (*C function*), 91
- `PyObject_RichCompare` (*C function*), 91
- `PyObject_RichCompareBool` (*C function*), 91
- `PyObject_SetArenaAllocator` (*C function*), 235
- `PyObject_SetAttr` (*C function*), 90
- `PyObject_SetAttrString` (*C function*), 90
- `PyObject_SetItem` (*C function*), 93
- `PyObject_Size` (*C function*), 92
- `PyObject_Str` (*C function*), 91
- `PyObject_Type` (*C function*), 92
- `PyObject_TypeCheck` (*C function*), 92
- `PyObject_VAR_HEAD` (*C macro*), 240
- `PyObject_Vectorcall` (*C function*), 97
- `PyObject_VectorcallDict` (*C function*), 97
- `PyObject_VectorcallMethod` (*C function*), 98
- `PyObjectArenaAllocator` (*C type*), 235
- `PyObject.ob_refcnt` (*C member*), 252
- `PyObject.ob_type` (*C member*), 252
- `PyOS_AfterFork` (*C function*), 66
- `PyOS_AfterFork_Child` (*C function*), 66
- `PyOS_AfterFork_Parent` (*C function*), 65
- `PyOS_BeforeFork` (*C function*), 65
- `PyOS_CheckStack` (*C function*), 66
- `PyOS_double_to_string` (*C function*), 84
- `PyOS_FSPath` (*C function*), 65
- `PyOS_getsig` (*C function*), 66
- `PyOS_InputHook` (*C var*), 45
- `PyOS_ReadlineFunctionPointer` (*C var*), 45
- `PyOS_setsig` (*C function*), 66
- `PyOS_snprintf` (*C function*), 83
- `PyOS_stricmp` (*C function*), 84
- `PyOS_string_to_double` (*C function*), 84
- `PyOS_strnicmp` (*C function*), 84
- `PyOS_vsnprintf` (*C function*), 83
- `PyPreConfig` (*C type*), 208
- `PyPreConfig.allocator` (*C member*), 208
- `PyPreConfig.coerce_c_locale` (*C member*), 209
- `PyPreConfig.coerce_c_locale_warn` (*C member*), 209
- `PyPreConfig.configure_locale` (*C member*), 208
- `PyPreConfig.dev_mode` (*C member*), 209
- `PyPreConfig.isolated` (*C member*), 209
- `PyPreConfig.legacy_windows_fs_encoding` (*C member*), 209
- `PyPreConfig.parse_argv` (*C member*), 209
- `PyPreConfig.PyPreConfig_InitIsolatedConfig` (*C function*), 208
- `PyPreConfig.PyPreConfig_InitPythonConfig` (*C function*), 208
- `PyPreConfig.use_environment` (*C member*), 209
- `PyPreConfig.utf8_mode` (*C member*), 209

- `PyProperty_Type` (*C var*), 170
- `PyRun_AnyFile` (*C function*), 43
- `PyRun_AnyFileEx` (*C function*), 43
- `PyRun_AnyFileExFlags` (*C function*), 44
- `PyRun_AnyFileFlags` (*C function*), 43
- `PyRun_File` (*C function*), 45
- `PyRun_FileEx` (*C function*), 45
- `PyRun_FileExFlags` (*C function*), 45
- `PyRun_FileFlags` (*C function*), 45
- `PyRun_InteractiveLoop` (*C function*), 44
- `PyRun_InteractiveLoopFlags` (*C function*), 44
- `PyRun_InteractiveOne` (*C function*), 44
- `PyRun_InteractiveOneFlags` (*C function*), 44
- `PyRun_SimpleFile` (*C function*), 44
- `PyRun_SimpleFileEx` (*C function*), 44
- `PyRun_SimpleFileExFlags` (*C function*), 44
- `PyRun_SimpleString` (*C function*), 44
- `PyRun_SimpleStringFlags` (*C function*), 44
- `PyRun_String` (*C function*), 45
- `PyRun_StringFlags` (*C function*), 45
- `PySendResult` (*C type*), 105
- `PySeqIter_Check` (*C function*), 169
- `PySeqIter_New` (*C function*), 169
- `PySeqIter_Type` (*C var*), 169
- `PySequence_Check` (*C function*), 101
- `PySequence_Concat` (*C function*), 101
- `PySequence_Contains` (*C function*), 102
- `PySequence_Count` (*C function*), 102
- `PySequence_DelItem` (*C function*), 102
- `PySequence_DelSlice` (*C function*), 102
- `PySequence_Fast` (*C function*), 102
- `PySequence_Fast_GET_ITEM` (*C function*), 103
- `PySequence_Fast_GET_SIZE` (*C function*), 103
- `PySequence_Fast_ITEMS` (*C function*), 103
- `PySequence_GetItem` (*C function*), 102
- `PySequence_GetItem()`, 9
- `PySequence_GetSlice` (*C function*), 102
- `PySequence_Index` (*C function*), 102
- `PySequence_InPlaceConcat` (*C function*), 101
- `PySequence_InPlaceRepeat` (*C function*), 102
- `PySequence_ITEM` (*C function*), 103
- `PySequence_Length` (*C function*), 101
- `PySequence_List` (*C function*), 102
- `PySequence_Repeat` (*C function*), 101
- `PySequence_SetItem` (*C function*), 102
- `PySequence_SetSlice` (*C function*), 102
- `PySequence_Size` (*C function*), 101
- `PySequence_Tuple` (*C function*), 102
- `PySequenceMethods` (*C type*), 274
- `PySequenceMethods.sq_ass_item` (*C member*), 275
- `PySequenceMethods.sq_concat` (*C member*), 274
- `PySequenceMethods.sq_contains` (*C member*), 275
- `PySequenceMethods.sq_inplace_concat` (*C member*), 275
- `PySequenceMethods.sq_inplace_repeat` (*C member*), 275
- `PySequenceMethods.sq_item` (*C member*), 274
- `PySequenceMethods.sq_length` (*C member*), 274
- `PySequenceMethods.sq_repeat` (*C member*), 274
- `PySet_Add` (*C function*), 156
- `PySet_Check` (*C function*), 155
- `PySet_CheckExact` (*C function*), 156
- `PySet_Clear` (*C function*), 157
- `PySet_Contains` (*C function*), 156
- `PySet_Discard` (*C function*), 156
- `PySet_GET_SIZE` (*C function*), 156
- `PySet_New` (*C function*), 156
- `PySet_Pop` (*C function*), 156
- `PySet_Size` (*C function*), 156
- `PySet_Type` (*C var*), 155
- `PySetObject` (*C type*), 155
- `PySignal_SetWakeupFd` (*C function*), 58
- `PySlice_AdjustIndices` (*C function*), 171
- `PySlice_Check` (*C function*), 170
- `PySlice_GetIndices` (*C function*), 170
- `PySlice_GetIndicesEx` (*C function*), 171
- `PySlice_New` (*C function*), 170
- `PySlice_Type` (*C var*), 170
- `PySlice_Unpack` (*C function*), 171
- `PyState_AddModule` (*C function*), 169
- `PyState_FindModule` (*C function*), 169
- `PyState_RemoveModule` (*C function*), 169
- `PyStatus` (*C type*), 207
- `PyStatus.err_msg` (*C member*), 207
- `PyStatus.exitcode` (*C member*), 207
- `PyStatus.func` (*C member*), 207
- `PyStatus.Py_ExitStatusException` (*C function*), 207
- `PyStatus.PyStatus_Error` (*C function*), 207
- `PyStatus.PyStatus_Exception` (*C function*), 207
- `PyStatus.PyStatus_Exit` (*C function*), 207
- `PyStatus.PyStatus_IsError` (*C function*), 207
- `PyStatus.PyStatus_IsExit` (*C function*), 207
- `PyStatus.PyStatus_NoMemory` (*C function*), 207
- `PyStatus.PyStatus_Ok` (*C function*), 207
- `PyStructSequence_Desc` (*C type*), 149
- `PyStructSequence_Field` (*C type*), 150
- `PyStructSequence_GET_ITEM` (*C function*), 150
- `PyStructSequence_GetItem` (*C function*), 150
- `PyStructSequence_InitType` (*C function*), 149
- `PyStructSequence_InitType2` (*C function*), 149
- `PyStructSequence_New` (*C function*), 150
- `PyStructSequence_NewType` (*C function*), 149
- `PyStructSequence_SET_ITEM` (*C function*), 150
- `PyStructSequence_SetItem` (*C function*), 150
- `PyStructSequence_UnnamedField` (*C var*), 150



- `PySys_AddAuditHook` (*C function*), 69
- `PySys_AddWarnOption` (*C function*), 68
- `PySys_AddWarnOptionUnicode` (*C function*), 68
- `PySys_AddXOption` (*C function*), 69
- `PySys_Audit` (*C function*), 69
- `PySys_FormatStderr` (*C function*), 68
- `PySys_FormatStdout` (*C function*), 68
- `PySys_GetObject` (*C function*), 68
- `PySys_GetXOptions` (*C function*), 69
- `PySys_ResetWarnOptions` (*C function*), 68
- `PySys_SetArgv` (*C function*), 190
- `PySys_SetArgv()`, 186
- `PySys_SetArgvEx` (*C function*), 190
- `PySys_SetArgvEx()`, 12, 186
- `PySys_SetObject` (*C function*), 68
- `PySys_SetPath` (*C function*), 68
- `PySys_WriteStderr` (*C function*), 68
- `PySys_WriteStdout` (*C function*), 68
- `Python 3000`, 298
- `PYTHON*`, 185
- `PYTHONCOERCECLOCALE`, 222
- `PYTHONDEBUG`, 184, 217
- `PYTHONDONTWRITEBYTECODE`, 184, 220
- `PYTHONDUMPREFS`, 213, 253
- `PYTHONEXECUTABLE`, 217
- `PYTHONFAULTHANDLER`, 214
- `PYTHONHASHSEED`, 185, 215
- `PYTHONHOME`, 12, 185, 190, 215
- `Pythônico`, 298
- `PYTHONINSPECT`, 185, 215
- `PYTHONIOENCODING`, 187, 219
- `PYTHONLEGACYWINDOWSFSENCODING`, 185, 209
- `PYTHONLEGACYWINDOWSTDIO`, 185, 216
- `PYTHONMALLOC`, 228, 232, 234, 235
- `PYTHONMALLOCSTATS`, 216, 228
- `PYTHONNOUSERSITE`, 186, 219
- `PYTHONOPTIMIZE`, 186, 216
- `PYTHONPATH`, 12, 185, 216
- `PYTHONPLATLIBDIR`, 216
- `PYTHONPROFILEIMPORTTIME`, 215
- `PYTHONPYCACHEPREFIX`, 218
- `PYTHONTRACEMALLOC`, 219
- `PYTHONUNBUFFERED`, 186, 213
- `PYTHONUTF8`, 209, 222
- `PYTHONVERBOSE`, 186, 220
- `PYTHONWARNINGS`, 220
- `PyThread_create_key` (*C function*), 203
- `PyThread_delete_key` (*C function*), 203
- `PyThread_delete_key_value` (*C function*), 203
- `PyThread_get_key_value` (*C function*), 203
- `PyThread_ReInitTLS` (*C function*), 203
- `PyThread_set_key_value` (*C function*), 203
- `PyThread_tss_alloc` (*C function*), 202
- `PyThread_tss_create` (*C function*), 202
- `PyThread_tss_delete` (*C function*), 203
- `PyThread_tss_free` (*C function*), 202
- `PyThread_tss_get` (*C function*), 203
- `PyThread_tss_is_created` (*C function*), 202
- `PyThread_tss_set` (*C function*), 203
- `PyThreadState`, 191
- `PyThreadState` (*C type*), 193
- `PyThreadState_Clear` (*C function*), 195
- `PyThreadState_Delete` (*C function*), 195
- `PyThreadState_DeleteCurrent` (*C function*), 195
- `PyThreadState_Get` (*C function*), 193
- `PyThreadState_GetDict` (*C function*), 196
- `PyThreadState_GetFrame` (*C function*), 195
- `PyThreadState_GetID` (*C function*), 196
- `PyThreadState_GetInterpreter` (*C function*), 196
- `PyThreadState_New` (*C function*), 195
- `PyThreadState_Next` (*C function*), 201
- `PyThreadState_SetAsyncExc` (*C function*), 197
- `PyThreadState_Swap` (*C function*), 193
- `PyTime_Check` (*C function*), 178
- `PyTime_CheckExact` (*C function*), 178
- `PyTime_FromTime` (*C function*), 179
- `PyTime_FromTimeAndFold` (*C function*), 179
- `PyTimeZone_FromOffset` (*C function*), 179
- `PyTimeZone_FromOffsetAndName` (*C function*), 179
- `PyTrace_C_CALL` (*C var*), 200
- `PyTrace_C_EXCEPTION` (*C var*), 200
- `PyTrace_C_RETURN` (*C var*), 200
- `PyTrace_CALL` (*C var*), 200
- `PyTrace_EXCEPTION` (*C var*), 200
- `PyTrace_LINE` (*C var*), 200
- `PyTrace_OPCODE` (*C var*), 200
- `PyTrace_RETURN` (*C var*), 200
- `PyTraceMalloc_Track` (*C function*), 236
- `PyTraceMalloc_Untrack` (*C function*), 236
- `PyTuple_Check` (*C function*), 148
- `PyTuple_CheckExact` (*C function*), 148
- `PyTuple_GET_ITEM` (*C function*), 148
- `PyTuple_GET_SIZE` (*C function*), 148
- `PyTuple_GetItem` (*C function*), 148
- `PyTuple_GetSlice` (*C function*), 149
- `PyTuple_New` (*C function*), 148
- `PyTuple_Pack` (*C function*), 148
- `PyTuple_SET_ITEM` (*C function*), 149
- `PyTuple_SetItem` (*C function*), 149
- `PyTuple_SetItem()`, 8
- `PyTuple_Size` (*C function*), 148
- `PyTuple_Type` (*C var*), 148
- `PyTupleObject` (*C type*), 148
- `PyType_Check` (*C function*), 115
- `PyType_CheckExact` (*C function*), 115
- `PyType_ClearCache` (*C function*), 115

- `PyType_FromModuleAndSpec` (*C function*), 117
- `PyType_FromSpec` (*C function*), 117
- `PyType_FromSpecWithBases` (*C function*), 117
- `PyType_GenericAlloc` (*C function*), 116
- `PyType_GenericNew` (*C function*), 116
- `PyType_GetFlags` (*C function*), 116
- `PyType_GetModule` (*C function*), 116
- `PyType_GetModuleState` (*C function*), 117
- `PyType_GetSlot` (*C function*), 116
- `PyType_HasFeature` (*C function*), 116
- `PyType_IS_GC` (*C function*), 116
- `PyType_IsSubtype` (*C function*), 116
- `PyType_Modified` (*C function*), 116
- `PyType_Ready` (*C function*), 116
- `PyType_Slot` (*C type*), 118
- `PyType_Slot.PyType_Slot.pfunc` (*C member*), 118
- `PyType_Slot.PyType_Slot.slot` (*C member*), 118
- `PyType_Spec` (*C type*), 117
- `PyType_Spec.PyType_Spec.basicsize` (*C member*), 117
- `PyType_Spec.PyType_Spec.flags` (*C member*), 118
- `PyType_Spec.PyType_Spec.itemsize` (*C member*), 118
- `PyType_Spec.PyType_Spec.name` (*C member*), 117
- `PyType_Spec.PyType_Spec.slots` (*C member*), 118
- `PyType_Type` (*C var*), 115
- `PyObject` (*C type*), 115
- `PyObject.tp_alloc` (*C member*), 268
- `PyObject.tp_as_async` (*C member*), 256
- `PyObject.tp_as_buffer` (*C member*), 258
- `PyObject.tp_as_mapping` (*C member*), 257
- `PyObject.tp_as_number` (*C member*), 256
- `PyObject.tp_as_sequence` (*C member*), 256
- `PyObject.tp_base` (*C member*), 266
- `PyObject.tp_bases` (*C member*), 269
- `PyObject.tp_basicsize` (*C member*), 254
- `PyObject.tp_cache` (*C member*), 270
- `PyObject.tp_call` (*C member*), 257
- `PyObject.tp_clear` (*C member*), 263
- `PyObject.tp_dealloc` (*C member*), 254
- `PyObject.tp_del` (*C member*), 270
- `PyObject.tp_descr_get` (*C member*), 266
- `PyObject.tp_descr_set` (*C member*), 266
- `PyObject.tp_dict` (*C member*), 266
- `PyObject.tp_dictoffset` (*C member*), 267
- `PyObject.tp_doc` (*C member*), 262
- `PyObject.tp_finalize` (*C member*), 270
- `PyObject.tp_flags` (*C member*), 258
- `PyObject.tp_free` (*C member*), 269
- `PyObject.tp_getattr` (*C member*), 255
- `PyObject.tp_getattro` (*C member*), 257
- `PyObject.tp_getset` (*C member*), 265
- `PyObject.tp_hash` (*C member*), 257
- `PyObject.tp_init` (*C member*), 267
- `PyObject.tp_is_gc` (*C member*), 269
- `PyObject.tp_itemsize` (*C member*), 254
- `PyObject.tp_iter` (*C member*), 265
- `PyObject.tp_iternext` (*C member*), 265
- `PyObject.tp_members` (*C member*), 265
- `PyObject.tp_methods` (*C member*), 265
- `PyObject.tp_mro` (*C member*), 270
- `PyObject.tp_name` (*C member*), 253
- `PyObject.tp_new` (*C member*), 268
- `PyObject.tp_repr` (*C member*), 256
- `PyObject.tp_richcompare` (*C member*), 263
- `PyObject.tp_richcompare.Py_RETURN_RICHCOMPARE` (*C macro*), 264
- `PyObject.tp_setattr` (*C member*), 256
- `PyObject.tp_setattro` (*C member*), 258
- `PyObject.tp_str` (*C member*), 257
- `PyObject.tp_subclasses` (*C member*), 270
- `PyObject.tp_traverse` (*C member*), 262
- `PyObject.tp_vectorcall` (*C member*), 271
- `PyObject.tp_vectorcall_offset` (*C member*), 255
- `PyObject.tp_version_tag` (*C member*), 270
- `PyObject.tp_weaklist` (*C member*), 270
- `PyObject.tp_weaklistoffset` (*C member*), 264
- `PyTZInfo_Check` (*C function*), 178
- `PyTZInfo_CheckExact` (*C function*), 178
- `PyUnicode_1BYTE_DATA` (*C function*), 130
- `PyUnicode_1BYTE_KIND` (*C macro*), 130
- `PyUnicode_2BYTE_DATA` (*C function*), 130
- `PyUnicode_2BYTE_KIND` (*C macro*), 130
- `PyUnicode_4BYTE_DATA` (*C function*), 130
- `PyUnicode_4BYTE_KIND` (*C macro*), 130
- `PyUnicode_AS_DATA` (*C function*), 131
- `PyUnicode_AS_UNICODE` (*C function*), 131
- `PyUnicode_AsASCIIString` (*C function*), 144
- `PyUnicode_AsCharmapString` (*C function*), 145
- `PyUnicode_AsEncodedString` (*C function*), 140
- `PyUnicode_AsLatin1String` (*C function*), 144
- `PyUnicode_AsMBCSString` (*C function*), 146
- `PyUnicode_AsRawUnicodeEscapeString` (*C function*), 144
- `PyUnicode_AsUCS4` (*C function*), 135
- `PyUnicode_AsUCS4Copy` (*C function*), 135
- `PyUnicode_AsUnicode` (*C function*), 136
- `PyUnicode_AsUnicodeAndSize` (*C function*), 136
- `PyUnicode_AsUnicodeEscapeString` (*C function*), 143
- `PyUnicode_AsUTF8` (*C function*), 141

- PyUnicode\_AsUTF8AndSize (*C function*), 140
- PyUnicode\_AsUTF8String (*C function*), 140
- PyUnicode\_AsUTF16String (*C function*), 142
- PyUnicode\_AsUTF32String (*C function*), 141
- PyUnicode\_AsWideChar (*C function*), 139
- PyUnicode\_AsWideCharString (*C function*), 139
- PyUnicode\_Check (*C function*), 129
- PyUnicode\_CheckExact (*C function*), 129
- PyUnicode\_Compare (*C function*), 147
- PyUnicode\_CompareWithASCIIString (*C function*), 147
- PyUnicode\_Concat (*C function*), 146
- PyUnicode\_Contains (*C function*), 148
- PyUnicode\_CopyCharacters (*C function*), 135
- PyUnicode\_Count (*C function*), 147
- PyUnicode\_DATA (*C function*), 130
- PyUnicode\_Decode (*C function*), 140
- PyUnicode\_DecodeASCII (*C function*), 144
- PyUnicode\_DecodeCharmap (*C function*), 145
- PyUnicode\_DecodeFSDefault (*C function*), 138
- PyUnicode\_DecodeFSDefaultAndSize (*C function*), 138
- PyUnicode\_DecodeLatin1 (*C function*), 144
- PyUnicode\_DecodeLocale (*C function*), 137
- PyUnicode\_DecodeLocaleAndSize (*C function*), 137
- PyUnicode\_DecodeMBCS (*C function*), 146
- PyUnicode\_DecodeMBCSStateful (*C function*), 146
- PyUnicode\_DecodeRawUnicodeEscape (*C function*), 144
- PyUnicode\_DecodeUnicodeEscape (*C function*), 143
- PyUnicode\_DecodeUTF7 (*C function*), 143
- PyUnicode\_DecodeUTF7Stateful (*C function*), 143
- PyUnicode\_DecodeUTF8 (*C function*), 140
- PyUnicode\_DecodeUTF8Stateful (*C function*), 140
- PyUnicode\_DecodeUTF16 (*C function*), 142
- PyUnicode\_DecodeUTF16Stateful (*C function*), 142
- PyUnicode\_DecodeUTF32 (*C function*), 141
- PyUnicode\_DecodeUTF32Stateful (*C function*), 141
- PyUnicode\_Encode (*C function*), 140
- PyUnicode\_EncodeASCII (*C function*), 144
- PyUnicode\_EncodeCharmap (*C function*), 145
- PyUnicode\_EncodeCodePage (*C function*), 146
- PyUnicode\_EncodeFSDefault (*C function*), 138
- PyUnicode\_EncodeLatin1 (*C function*), 144
- PyUnicode\_EncodeLocale (*C function*), 137
- PyUnicode\_EncodeMBCS (*C function*), 146
- PyUnicode\_EncodeRawUnicodeEscape (*C function*), 144
- PyUnicode\_EncodeUnicodeEscape (*C function*), 143
- PyUnicode\_EncodeUTF7 (*C function*), 143
- PyUnicode\_EncodeUTF8 (*C function*), 141
- PyUnicode\_EncodeUTF16 (*C function*), 142
- PyUnicode\_EncodeUTF32 (*C function*), 141
- PyUnicode\_Fill (*C function*), 135
- PyUnicode\_Find (*C function*), 147
- PyUnicode\_FindChar (*C function*), 147
- PyUnicode\_Format (*C function*), 147
- PyUnicode\_FromEncodedObject (*C function*), 134
- PyUnicode\_FromFormat (*C function*), 133
- PyUnicode\_FromFormatV (*C function*), 134
- PyUnicode\_FromKindAndData (*C function*), 133
- PyUnicode\_FromObject (*C function*), 136
- PyUnicode\_FromString (*C function*), 133
- PyUnicode\_FromString(), 153
- PyUnicode\_FromStringAndSize (*C function*), 133
- PyUnicode\_FromUnicode (*C function*), 136
- PyUnicode\_FromWideChar (*C function*), 139
- PyUnicode\_FSConverter (*C function*), 138
- PyUnicode\_FSDecoder (*C function*), 138
- PyUnicode\_GET\_DATA\_SIZE (*C function*), 131
- PyUnicode\_GET\_LENGTH (*C function*), 129
- PyUnicode\_GET\_SIZE (*C function*), 131
- PyUnicode\_GetLength (*C function*), 135
- PyUnicode\_GetSize (*C function*), 136
- PyUnicode\_InternFromString (*C function*), 148
- PyUnicode\_InternInPlace (*C function*), 148
- PyUnicode\_IsIdentifier (*C function*), 131
- PyUnicode\_Join (*C function*), 147
- PyUnicode\_KIND (*C function*), 130
- PyUnicode\_MAX\_CHAR\_VALUE (*C macro*), 130
- PyUnicode\_New (*C function*), 133
- PyUnicode\_READ (*C function*), 130
- PyUnicode\_READ\_CHAR (*C function*), 130
- PyUnicode\_ReadChar (*C function*), 135
- PyUnicode\_READY (*C function*), 129
- PyUnicode\_Replace (*C function*), 147
- PyUnicode\_RichCompare (*C function*), 147
- PyUnicode\_Split (*C function*), 146
- PyUnicode\_Splitlines (*C function*), 146
- PyUnicode\_Substring (*C function*), 135
- PyUnicode\_Tailmatch (*C function*), 147
- PyUnicode\_TransformDecimalToASCII (*C function*), 136
- PyUnicode\_Translate (*C function*), 145
- PyUnicode\_TranslateCharmap (*C function*), 145
- PyUnicode\_Type (*C var*), 129
- PyUnicode\_WCHAR\_KIND (*C macro*), 130
- PyUnicode\_WRITE (*C function*), 130
- PyUnicode\_WriteChar (*C function*), 135

- PyUnicodeDecodeError\_Create (*C function*), 59
  - PyUnicodeDecodeError\_GetEncoding (*C function*), 60
  - PyUnicodeDecodeError\_GetEnd (*C function*), 60
  - PyUnicodeDecodeError\_GetObject (*C function*), 60
  - PyUnicodeDecodeError\_GetReason (*C function*), 60
  - PyUnicodeDecodeError\_GetStart (*C function*), 60
  - PyUnicodeDecodeError\_SetEnd (*C function*), 60
  - PyUnicodeDecodeError\_SetReason (*C function*), 60
  - PyUnicodeDecodeError\_SetStart (*C function*), 60
  - PyUnicodeEncodeError\_Create (*C function*), 59
  - PyUnicodeEncodeError\_GetEncoding (*C function*), 60
  - PyUnicodeEncodeError\_GetEnd (*C function*), 60
  - PyUnicodeEncodeError\_GetObject (*C function*), 60
  - PyUnicodeEncodeError\_GetReason (*C function*), 60
  - PyUnicodeEncodeError\_GetStart (*C function*), 60
  - PyUnicodeEncodeError\_SetEnd (*C function*), 60
  - PyUnicodeEncodeError\_SetReason (*C function*), 60
  - PyUnicodeEncodeError\_SetStart (*C function*), 60
  - PyUnicodeObject (*C type*), 129
  - PyUnicodeTranslateError\_Create (*C function*), 60
  - PyUnicodeTranslateError\_GetEnd (*C function*), 60
  - PyUnicodeTranslateError\_GetObject (*C function*), 60
  - PyUnicodeTranslateError\_GetReason (*C function*), 60
  - PyUnicodeTranslateError\_GetStart (*C function*), 60
  - PyUnicodeTranslateError\_SetEnd (*C function*), 60
  - PyUnicodeTranslateError\_SetReason (*C function*), 60
  - PyUnicodeTranslateError\_SetStart (*C function*), 60
  - PyVarObject (*C type*), 240
  - PyVarObject\_HEAD\_INIT (*C macro*), 241
  - PyVarObject.ob\_size (*C member*), 253
  - PyVectorcall\_Call (*C function*), 95
  - PyVectorcall\_Function (*C function*), 95
  - PyVectorcall\_NARGS (*C function*), 95
  - PyWeakref\_Check (*C function*), 172
  - PyWeakref\_CheckProxy (*C function*), 172
  - PyWeakref\_CheckRef (*C function*), 172
  - PyWeakref\_GET\_OBJECT (*C function*), 173
  - PyWeakref\_GetObject (*C function*), 173
  - PyWeakref\_NewProxy (*C function*), 173
  - PyWeakref\_NewRef (*C function*), 173
  - PyWideStringList (*C type*), 206
  - PyWideStringList.items (*C member*), 206
  - PyWideStringList.length (*C member*), 206
  - PyWideStringList.PyWideStringList\_Append (*C function*), 206
  - PyWideStringList.PyWideStringList\_Insert (*C function*), 206
  - PyWrapper\_New (*C function*), 170
- ## R
- realloc(), 227
  - referência emprestada, 289
  - referência forte, 300
  - releasebufferproc (*C type*), 278
  - repr
    - função interna, 91, 256
  - reprfunc (*C type*), 277
  - richcmpfunc (*C type*), 278
- ## S
- sdtterr
    - stdin stdout, 187
  - search
    - path, module, 12, 186, 188, 189
  - sendfunc (*C type*), 278
  - sequence
    - objeto, 125
  - sequência, 299
  - set
    - objeto, 155
  - set\_all(), 9
  - setattrfunc (*C type*), 277
  - setattrofunc (*C type*), 278
  - setswitchinterval() (*in module sys*), 191
  - SIGINT, 57, 58
  - signal
    - módulo, 57, 58
  - SIZE\_MAX, 121
  - spec de módulo, 296
  - special
    - method, 300
  - ssizeargfunc (*C type*), 278
  - ssizeobjargproc (*C type*), 278
  - staticmethod
    - função interna, 244
  - stderr (*in module sys*), 198
  - stdin
    - stdout sdtterr, 187



stdin (*in module sys*), 198  
 stdout  
     sdterr, stdin, 187  
 stdout (*in module sys*), 198  
 strerror(), 53  
 string  
     PyObject\_Str (*C function*), 91  
 sum\_list(), 9  
 sum\_sequence(), 10, 11  
 sys  
     módulo, 12, 186, 198  
 SystemError (*built-in exception*), 162

## T

ternaryfunc (*C type*), 278  
 tipagem pato, 291  
 tipo, 300  
 tipo genérico, 293  
 tratador de erros e codificação do  
     sistema de arquivos, 291  
 trava global do interpretador, 293  
 traverseproc (*C type*), 283  
 tupla nomeada, 296  
 tuple  
     função interna, 102, 152  
     objeto, 148  
 type  
     função interna, 92  
     objeto, 6, 115

## U

ULONG\_MAX, 121  
 unaryfunc (*C type*), 278

## V

variável de ambiente  
     \_\_PYENV\_LAUNCHER\_\_, 212, 217  
     PATH, 12  
     PYTHON\*, 185  
     PYTHONCOERCECLOCALE, 222  
     PYTHONDEBUG, 184, 217  
     PYTHONDONTWRITEBYTECODE, 184, 220  
     PYTHONDUMPREFS, 213, 253  
     PYTHONEXECUTABLE, 217  
     PYTHONFAULTHANDLER, 214  
     PYTHONHASHSEED, 185, 215  
     PYTHONHOME, 12, 185, 190, 215  
     PYTHONINSPECT, 185, 215  
     PYTHONIOENCODING, 187, 219  
     PYTHONLEGACYWINDOWSFSENCODING, 185,  
         209  
     PYTHONLEGACYWINDOWSTDIO, 185, 216  
     PYTHONMALLOC, 228, 232, 234, 235  
     PYTHONMALLOCSTATS, 216, 228

    PYTHONNOUSERSITE, 186, 219  
     PYTHONOPTIMIZE, 186, 216  
     PYTHONPATH, 12, 185, 216  
     PYTHONPLATLIBDIR, 216  
     PYTHONPROFILEIMPORTTIME, 215  
     PYTHONPYCACHEPREFIX, 218  
     PYTHONTRACEMALLOC, 219  
     PYTHONUNBUFFERED, 186, 213  
     PYTHONUTF8, 209, 222  
     PYTHONVERBOSE, 186, 220  
     PYTHONWARNINGS, 220  
 variável de classe, 289  
 variável de contexto, 290  
 vectorcallfunc (*C type*), 94  
 version (*in module sys*), 189, 190  
 visão de dicionário, 291  
 visitproc (*C type*), 282

## Z

Zen do Python, 301