The Python/C API

Yayım 3.14.0rc3

Guido van Rossum and the Python development team

Ekim 01, 2025

Python Software Foundation
Email: docs@python.org

İçindekiler

1 Introduction **3**
- 1.1 Language version compatibility . . . 3
- 1.2 Coding standards . . . 3
- 1.3 Include Files . . . 3
- 1.4 Useful macros . . . 4
- 1.5 Objects, Types and Reference Counts . . . 6
  - 1.5.1 Reference Counts . . . 6
  - 1.5.2 Types . . . 10
- 1.6 Exceptions . . . 10
- 1.7 Embedding Python . . . 12
- 1.8 Debugging Builds . . . 12
- 1.9 Recommended third party tools . . . 13

2 C API Stability **15**
- 2.1 Unstable C API . . . 15
- 2.2 Stable Application Binary Interface . . . 15
  - 2.2.1 Limited C API . . . 16
  - 2.2.2 Stable ABI . . . 16
  - 2.2.3 Limited API Scope and Performance . . . 16
  - 2.2.4 Limited API Caveats . . . 17
- 2.3 Platform Considerations . . . 17
- 2.4 Contents of Limited API . . . 17

3 The Very High Level Layer **43**

4 Reference Counting **49**

5 Exception Handling **53**
- 5.1 Printing and clearing . . . 53
- 5.2 Raising exceptions . . . 54
- 5.3 Issuing warnings . . . 57
- 5.4 Querying the error indicator . . . 57
- 5.5 Signal Handling . . . 61
- 5.6 Exception Classes . . . 62
- 5.7 Exception Objects . . . 62
- 5.8 Unicode Exception Objects . . . 63
- 5.9 Recursion Control . . . 64
- 5.10 Exception and warning types . . . 65
  - 5.10.1 Exception types . . . 65
  - 5.10.2 OSError aliases . . . 70
  - 5.10.3 Warning types . . . 71

6 Defining extension modules **73**
6.1 Multiple module instances . . . 73
6.2 Initialization function . . . 74
6.3 Multi-phase initialization . . . 75
6.4 Legacy single-phase initialization . . . 75

7 Utilities **77**
7.1 Operating System Utilities . . . 77
7.2 System Functions . . . 80
7.3 Process Control . . . 82
7.4 Importing Modules . . . 82
7.5 Data marshalling support . . . 86
7.6 Parsing arguments and building values . . . 87
7.6.1 Parsing arguments . . . 87
7.6.2 Building values . . . 94
7.7 String conversion and formatting . . . 96
7.8 PyHash API . . . 98
7.9 Reflection . . . 99
7.10 Codec registry and support functions . . . 100
7.10.1 Codec lookup API . . . 101
7.10.2 Registry API for Unicode encoding error handlers . . . 101
7.11 PyTime C API . . . 102
7.11.1 Types . . . 102
7.11.2 Clock Functions . . . 102
7.11.3 Raw Clock Functions . . . 103
7.11.4 Conversion functions . . . 103
7.12 Support for Perf Maps . . . 103

8 Abstract Objects Layer **105**
8.1 Object Protocol . . . 105
8.2 Call Protocol . . . 115
8.2.1 The *tp_call* Protocol . . . 115
8.2.2 The Vectorcall Protocol . . . 115
8.2.3 Object Calling API . . . 117
8.2.4 Call Support API . . . 119
8.3 Number Protocol . . . 120
8.4 Sequence Protocol . . . 123
8.5 Mapping Protocol . . . 125
8.6 Iterator Protocol . . . 126
8.7 Buffer Protocol . . . 127
8.7.1 Buffer structure . . . 127
8.7.2 Buffer request types . . . 129
8.7.3 Complex arrays . . . 131
8.7.4 Buffer-related functions . . . 132

9 Concrete Objects Layer **135**
9.1 Fundamental Objects . . . 135
9.1.1 Type Objects . . . 135
9.1.2 The `None` Object . . . 142
9.2 Numeric Objects . . . 142
9.2.1 Integer Objects . . . 142
9.2.2 Boolean Objects . . . 152
9.2.3 Floating-Point Objects . . . 152
9.2.4 Complex Number Objects . . . 154
9.3 Sequence Objects . . . 156
9.3.1 Bytes Objects . . . 156
9.3.2 Byte Array Objects . . . 158
9.3.3 Unicode Objects and Codecs . . . 159
9.3.4 Tuple Objects . . . 181

9.3.5 Struct Sequence Objects . . . 182
9.3.6 List Objects . . . 184
9.4 Container Objects . . . 186
9.4.1 Dictionary Objects . . . 186
9.4.2 Set Objects . . . 191
9.5 Function Objects . . . 192
9.5.1 Function Objects . . . 192
9.5.2 Instance Method Objects . . . 195
9.5.3 Method Objects . . . 195
9.5.4 Cell Objects . . . 196
9.5.5 Code Objects . . . 196
9.5.6 Code Object Flags . . . 199
9.5.7 Extra information . . . 201
9.6 Other Objects . . . 202
9.6.1 File Objects . . . 202
9.6.2 Module Objects . . . 203
9.6.3 Module definitions . . . 204
9.6.4 Creating extension modules dynamically . . . 207
9.6.5 Support functions . . . 208
9.6.6 Iterator Objects . . . 211
9.6.7 Descriptor Objects . . . 211
9.6.8 Slice Objects . . . 212
9.6.9 MemoryView objects . . . 213
9.6.10 Weak Reference Objects . . . 214
9.6.11 Capsules . . . 215
9.6.12 Frame Objects . . . 217
9.6.13 Generator Objects . . . 220
9.6.14 Coroutine Objects . . . 220
9.6.15 Context Variables Objects . . . 220
9.6.16 DateTime Objects . . . 222
9.6.17 Objects for Type Hinting . . . 226

10 Initialization, Finalization, and Threads 227
10.1 Before Python Initialization . . . 227
10.2 Global configuration variables . . . 228
10.3 Initializing and finalizing the interpreter . . . 231
10.4 Process-wide parameters . . . 234
10.5 Thread State and the Global Interpreter Lock . . . 237
10.5.1 Detaching the thread state from extension code . . . 238
10.5.2 Non-Python created threads . . . 238
10.5.3 Supporting subinterpreters in non-Python threads . . . 239
10.5.4 Cautions about fork() . . . 239
10.5.5 Cautions regarding runtime finalization . . . 240
10.5.6 High-level API . . . 240
10.5.7 Low-level API . . . 243
10.6 Sub-interpreter support . . . 245
10.6.1 A Per-Interpreter GIL . . . 248
10.6.2 Bugs and caveats . . . 248
10.7 Asynchronous Notifications . . . 248
10.8 Profiling and Tracing . . . 249
10.9 Reference tracing . . . 251
10.10 Advanced Debugger Support . . . 251
10.11 Thread Local Storage Support . . . 252
10.11.1 Thread Specific Storage (TSS) API . . . 252
10.11.2 Thread Local Storage (TLS) API . . . 253
10.12 Synchronization Primitives . . . 254
10.12.1 Python Critical Section API . . . 254

11 Python Initialization Configuration **257**
11.1 PyInitConfig C API . . . 257
11.1.1 Example . . . 257
11.1.2 Create Config . . . 258
11.1.3 Error Handling . . . 258
11.1.4 Get Options . . . 259
11.1.5 Set Options . . . 259
11.1.6 Module . . . 260
11.1.7 Initialize Python . . . 260
11.2 Configuration Options . . . 260
11.3 Runtime Python configuration API . . . 261
11.4 PyConfig C API . . . 263
11.4.1 Example . . . 263
11.4.2 PyWideStringList . . . 264
11.4.3 PyStatus . . . 264
11.4.4 PyPreConfig . . . 265
11.4.5 Preinitialize Python with PyPreConfig . . . 267
11.4.6 PyConfig . . . 268
11.4.7 Initialization with PyConfig . . . 280
11.4.8 Isolated Configuration . . . 281
11.4.9 Python Configuration . . . 281
11.4.10 Python Path Configuration . . . 282
11.5 Py_GetArgcArgv() . . . 283
11.6 Delaying main module execution . . . 283

12 Memory Management **285**
12.1 Overview . . . 285
12.2 Allocator Domains . . . 286
12.3 Raw Memory Interface . . . 286
12.4 Memory Interface . . . 287
12.5 Object allocators . . . 288
12.6 Default Memory Allocators . . . 290
12.7 Customize Memory Allocators . . . 290
12.8 Debug hooks on the Python memory allocators . . . 292
12.9 The pymalloc allocator . . . 293
12.9.1 Customize pymalloc Arena Allocator . . . 293
12.10 The mimalloc allocator . . . 294
12.11 tracemalloc C API . . . 294
12.12 Examples . . . 294

13 Object Implementation Support **297**
13.1 Allocating Objects on the Heap . . . 297
13.2 Object Life Cycle . . . 299
13.2.1 Life Events . . . 299
13.2.2 Cyclic Isolate Destruction . . . 302
13.2.3 Functions . . . 303
13.3 Common Object Structures . . . 303
13.3.1 Base object types and macros . . . 303
13.3.2 Implementing functions and methods . . . 305
13.3.3 Accessing attributes of extension types . . . 308
13.4 Type Object Structures . . . 312
13.4.1 Quick Reference . . . 313
13.4.2 PyTypeObject Definition . . . 317
13.4.3 PyObject Slots . . . 318
13.4.4 PyVarObject Slots . . . 319
13.4.5 PyTypeObject Slots . . . 319
13.4.6 Static Types . . . 343
13.4.7 Heap Types . . . 343

13.4.8 Number Object Structures . . . 343
13.4.9 Mapping Object Structures . . . 345
13.4.10 Sequence Object Structures . . . 346
13.4.11 Buffer Object Structures . . . 347
13.4.12 Async Object Structures . . . 348
13.4.13 Slot Type typedefs . . . 348
13.4.14 Examples . . . 350
13.5 Supporting Cyclic Garbage Collection . . . 352
13.5.1 Controlling the Garbage Collector State . . . 356
13.5.2 Querying Garbage Collector State . . . 356

14 API and ABI Versioning **357**
14.1 Build-time version constants . . . 357
14.2 Run-time version . . . 357
14.3 Bit-packing macros . . . 358

15 Monitoring C API **359**

16 Generating Execution Events **361**
16.1 Managing the Monitoring State . . . 362

A Sözlük **367**

B About this documentation **385**
B.1 Contributors to the Python documentation . . . 385

C Tarihçe ve Lisans **387**
C.1 Yazılımın tarihçesi . . . 387
C.2 Python'a erişmek veya başka bir şekilde kullanmak için şartlar ve koşullar . . . 388
C.2.1 PYTHON SOFTWARE FOUNDATION LICENSE VERSION 2 . . . 388
C.2.2 PYTHON 2.0 İÇİN BEOPEN.COM LİSANS SÖZLEŞMESİ . . . 389
C.2.3 PYTHON 1.6.1 İÇİN CNRI LİSANS ANLAŞMASI . . . 390
C.2.4 0.9.0 ARASI 1.2 PYTHON İÇİN CWI LİSANS SÖZLEŞMESİ . . . 391
C.2.5 ZERO-CLAUSE BSD LICENSE FOR CODE IN THE PYTHON DOCUMENTATION . . . 391
C.3 Tüzel Yazılımlar için Lisanslar ve Onaylar . . . 391
C.3.1 Mersenne Twister'ı . . . 391
C.3.2 Soketler . . . 392
C.3.3 Asenkron soket hizmetleri . . . 393
C.3.4 Çerez yönetimi . . . 393
C.3.5 Çalıştırma izleme . . . 394
C.3.6 UUencode ve UUdecode fonksiyonları . . . 394
C.3.7 XML Uzaktan Yordam Çağrıları . . . 395
C.3.8 test_epoll . . . 395
C.3.9 kqueue seçin . . . 396
C.3.10 SipHash24 . . . 396
C.3.11 strtod ve dtoa . . . 397
C.3.12 OpenSSL . . . 397
C.3.13 expat . . . 401
C.3.14 libffi . . . 401
C.3.15 zlib . . . 402
C.3.16 cfuhash . . . 402
C.3.17 libmpdec . . . 403
C.3.18 W3C C14N test paketi . . . 403
C.3.19 mimalloc . . . 404
C.3.20 asyncio . . . 404
C.3.21 Global Unbounded Sequences (GUS) . . . 405
C.3.22 Zstandard bindings . . . 405

D Telif Hakkı **407**

Kaynakça **409**

Dizin **411**

Bu kılavuz, genişletme modülleri yazmak veya Python'u gömmek isteyen C ve C++ programcıları tarafından kullanılan API'yi belgelemektedir. Uzantı yazmanın genel ilkelerini açıklayan ancak API işlevlerini ayrıntılı olarak belgelemeyen extending-index'in tamamlayıcısıdır.

BÖLÜM 1

Introduction

The Application Programmer's Interface to Python gives C and C++ programmers access to the Python interpreter at a variety of levels. The API is equally usable from C++, but for brevity it is generally referred to as the Python/C API. There are two fundamentally different reasons for using the Python/C API. The first reason is to write *extension modules* for specific purposes; these are C modules that extend the Python interpreter. This is probably the most common use. The second reason is to use Python as a component in a larger application; this technique is generally referred to as *embedding* Python in an application.

Writing an extension module is a relatively well-understood process, where a "cookbook" approach works well. There are several tools that automate the process to some extent. While people have embedded Python in other applications since its early existence, the process of embedding Python is less straightforward than writing an extension.

Many API functions are useful independent of whether you're embedding or extending Python; moreover, most applications that embed Python will need to provide a custom extension as well, so it's probably a good idea to become familiar with writing an extension before attempting to embed Python in a real application.

1.1 Language version compatibility

Python's C API is compatible with C11 and C++11 versions of C and C++.

This is a lower limit: the C API does not require features from later C/C++ versions. You do *not* need to enable your compiler's "c11 mode".

1.2 Coding standards

If you're writing C code for inclusion in CPython, you **must** follow the guidelines and standards defined in **PEP 7**. These guidelines apply regardless of the version of Python you are contributing to. Following these conventions is not necessary for your own third party extension modules, unless you eventually expect to contribute them to Python.

1.3 Include Files

All function, type and macro definitions needed to use the Python/C API are included in your code by the following line:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

This implies inclusion of the following standard headers: <stdio.h>, <string.h>, <errno.h>, <limits.h>, <assert.h> and <stdlib.h> (if available).

> **Not**
>
> Since Python may define some pre-processor definitions which affect the standard headers on some systems, you *must* include Python.h before any standard headers are included.
>
> It is recommended to always define PY_SSIZE_T_CLEAN before including Python.h. See *Parsing arguments and building values* for a description of this macro.

All user visible names defined by Python.h (except those defined by the included standard headers) have one of the prefixes Py or _Py. Names beginning with _Py are for internal use by the Python implementation and should not be used by extension writers. Structure member names do not have a reserved prefix.

> **Not**
>
> User code should never define names that begin with Py or _Py. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

The header files are typically installed with Python. On Unix, these are located in the directories *prefix*/include/pythonversion/ and *exec_prefix*/include/pythonversion/, where prefix and exec_prefix are defined by the corresponding parameters to Python's **configure** script and *version* is '%d.%d' % sys.version_info[:2]. On Windows, the headers are installed in *prefix*/include, where prefix is the installation directory specified to the installer.

To include the headers, place both directories (if different) on your compiler's search path for includes. Do *not* place the parent directories on the search path and then use #include <pythonX.Y/Python.h>; this will break on multi-platform builds since the platform independent headers under prefix include the platform specific headers from exec_prefix.

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be extern "C". As a result, there is no need to do anything special to use the API from C++.

1.4 Useful macros

Several useful macros are defined in the Python header files. Many are defined closer to where they are useful (for example, *Py_RETURN_NONE*, *PyMODINIT_FUNC*). Others of a more general utility are defined here. This is not necessarily a complete listing.

Py_ABS(x)

Return the absolute value of x.

Added in version 3.3.

Py_ALWAYS_INLINE

Ask the compiler to always inline a static inline function. The compiler can ignore it and decide to not inline the function.

It can be used to inline performance critical static inline functions when building Python in debug mode with function inlining disabled. For example, MSC disables function inlining when building in debug mode.

Marking blindly a static inline function with Py_ALWAYS_INLINE can result in worse performances (due to increased code size for example). The compiler is usually smarter than the developer for the cost/benefit analysis.

If Python is built in debug mode (if the *Py_DEBUG* macro is defined), the *Py_ALWAYS_INLINE* macro does nothing.

It must be specified before the function return type. Usage:

```
static inline Py_ALWAYS_INLINE int random(void) { return 4; }
```

Added in version 3.11.

Py_CHARMASK(c)

Argument must be a character or an integer in the range [-128, 127] or [0, 255]. This macro returns `c` cast to an `unsigned char`.

Py_DEPRECATED(version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

Example:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

3.8 sürümünde değişti: MSVC support was added.

Py_GETENV(s)

Like `getenv(s)`, but returns `NULL` if `-E` was passed on the command line (see *PyConfig.use_environment*).

Py_MAX(x, y)

Return the maximum value between `x` and `y`.

Added in version 3.3.

Py_MEMBER_SIZE(type, member)

Return the size of a structure (`type`) `member` in bytes.

Added in version 3.6.

Py_MIN(x, y)

Return the minimum value between `x` and `y`.

Added in version 3.3.

Py_NO_INLINE

Disable inlining on a function. For example, it reduces the C stack consumption: useful on LTO+PGO builds which heavily inline code (see bpo-33720).

Usage:

```
Py_NO_INLINE static int random(void) { return 4; }
```

Added in version 3.11.

Py_STRINGIFY(x)

Convert `x` to a C string. E.g. `Py_STRINGIFY(123)` returns `"123"`.

Added in version 3.4.

Py_UNREACHABLE()

Use this when you have a code path that cannot be reached by design. For example, in the `default:` clause in a `switch` statement for which all possible values are covered in `case` statements. Use this in places where you might be tempted to put an `assert(0)` or `abort()` call.

In release mode, the macro helps the compiler to optimize the code, and avoids a warning about unreachable code. For example, the macro is implemented with `__builtin_unreachable()` on GCC in release mode.

A use for `Py_UNREACHABLE()` is following a call a function that never returns but that is not declared `_Py_NO_RETURN`.

If a code path is very unlikely code but can be reached under exceptional case, this macro must not be used. For example, under low memory condition or if a system call returns a value out of the expected range. In this

case, it's better to report the error to the caller. If the error cannot be reported to caller, *Py_FatalError()* can be used.

Added in version 3.7.

Py_UNUSED(arg)

Use this for unused arguments in a function definition to silence compiler warnings. Example: `int func(int a, int Py_UNUSED(b)) { return a; }`.

Added in version 3.4.

PyDoc_STRVAR(name, str)

Creates a variable with name `name` that can be used in docstrings. If Python is built without docstrings, the value will be empty.

Use *PyDoc_STRVAR* for docstrings to support building Python without docstrings, as specified in **PEP 7**.

Example:

```
PyDoc_STRVAR(pop_doc, "Remove and return the rightmost element.");

static PyMethodDef deque_methods[] = {
    // ...
    {"pop", (PyCFunction)deque_pop, METH_NOARGS, pop_doc},
    // ...
}
```

PyDoc_STR(str)

Creates a docstring for the given input string or an empty string if docstrings are disabled.

Use *PyDoc_STR* in specifying docstrings to support building Python without docstrings, as specified in **PEP 7**.

Example:

```
static PyMethodDef pysqlite_row_methods[] = {
    {"keys", (PyCFunction)pysqlite_row_keys, METH_NOARGS,
        PyDoc_STR("Returns the keys of the row.")},
    {NULL, NULL}
};
```

1.5 Objects, Types and Reference Counts

Most Python/C API functions have one or more arguments as well as a return value of type *PyObject**. This type is a pointer to an opaque data type representing an arbitrary Python object. Since all Python object types are treated the same way by the Python language in most situations (e.g., assignments, scope rules, and argument passing), it is only fitting that they should be represented by a single C type. Almost all Python objects live on the heap: you never declare an automatic or static variable of type *PyObject*, only pointer variables of type *PyObject** can be declared. The sole exception are the type objects; since these must never be deallocated, they are typically static *PyTypeObject* objects.

All Python objects (even Python integers) have a *type* and a *reference count*. An object's type determines what kind of object it is (e.g., an integer, a list, or a user-defined function; there are many more as explained in types). For each of the well-known types there is a macro to check whether an object is of that type; for instance, `PyList_Check(a)` is true if (and only if) the object pointed to by *a* is a Python list.

1.5.1 Reference Counts

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a *strong reference* to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When the last *strong reference* to an

object is released (i.e. its reference count becomes zero), the object is deallocated. If it contains references to other objects, those references are released. Those other objects may be deallocated in turn, if there are no more references to them, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is "don't do that.")

Reference counts are always manipulated explicitly. The normal way is to use the macro *Py_INCREF()* to take a new reference to an object (i.e. increment its reference count by one), and *Py_DECREF()* to release that reference (i.e. decrement the reference count by one). The *Py_DECREF()* macro is considerably more complex than the incref one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of releasing references for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming `sizeof(Py_ssize_t) > = sizeof(void*)`). Thus, the reference count increment is a simple operation.

It is not necessary to hold a *strong reference* (i.e. increment the reference count) for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to take a new *strong reference* (i.e. increment the reference count) temporarily. An important situation where this arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without taking a new reference. Some other operation might conceivably remove the object from the list, releasing that reference, and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a code path which allows control to flow back to the user from a *Py_DECREF()*, so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with `PyObject_`, `PyNumber_`, `PySequence_` or `PyMapping_`). These operations always create a new *strong reference* (i.e. increment the reference count) of the object they return. This leaves the caller with the responsibility to call *Py_DECREF()* when they are done with the result; this soon becomes second nature.

Reference Count Details

The reference count behavior of functions in the Python/C API is best explained in terms of *ownership of references*. Ownership pertains to references, never to objects (objects are not owned: they are always shared). "Owning a reference" means being responsible for calling Py_DECREF on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually releasing it by calling *Py_DECREF()* or *Py_XDECREF()* when it's no longer needed—or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a *new* reference. When no ownership is transferred, the caller is said to *borrow* the reference. Nothing needs to be done for a *borrowed reference*.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are *PyList_SetItem()* and *PyTuple_SetItem()*, which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple `(1, 2, "three")` could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here, *PyLong_FromLong()* returns a new reference which is immediately stolen by *PyTuple_SetItem()*. When you want to keep using an object although the reference to it will be stolen, use *Py_INCREF()* to grab another reference before calling the reference-stealing function.

Incidentally, *PyTuple_SetItem()* is the *only* way to set tuple items; *PySequence_SetItem()* and *PyObject_SetItem()* refuse to do this since tuples are an immutable data type. You should only use *PyTuple_SetItem()* for tuples that you are creating yourself.

Equivalent code for populating a list can be written using *PyList_New()* and *PyList_SetItem()*.

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function, *Py_BuildValue()*, that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

It is much more common to use *PyObject_SetItem()* and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding references is much saner, since you don't have to take a new reference just so you can give that reference away ("have it be stolen"). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;

    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {
            Py_DECREF(index);
            return -1;
        }
        Py_DECREF(index);
    }
    return 0;
}
```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the only reference to the object. Therefore, the generic functions that return object references, like *PyObject_GetItem()* and *PySequence_GetItem()*, always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only — *the plumage* (the type of the object passed as an argument to the function) *doesn't enter into it!* Thus, if you extract an item from a list using *PyList_GetItem()*, you don't own the reference — but if you obtain the same

item from the same list using *PySequence_GetItem()* (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using *PyList_GetItem()*, and once using *PySequence_GetItem()*.

```
long
sum_list(PyObject *list)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;

    n = PyList_Size(list);
    if (n < 0)
        return -1; /* Not a list */
    for (i = 0; i < n; i++) {
        item = PyList_GetItem(list, i); /* Can't fail */
        if (!PyLong_Check(item)) continue; /* Skip non-integers */
        value = PyLong_AsLong(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
    return total;
}
```

```
long
sum_sequence(PyObject *sequence)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;
    n = PySequence_Length(sequence);
    if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {
            value = PyLong_AsLong(item);
            Py_DECREF(item);
            if (value == -1 && PyErr_Occurred())
                /* Integer too big to fit in a C long, bail out */
                return -1;
            total += value;
        }
        else {
            Py_DECREF(item); /* Discard reference ownership */
        }
    }
    return total;
}
```

1.5.2 Types

There are few other data types that play a significant role in the Python/C API; most are simple C types such as `int`, `long`, `double` and `char*`. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

type **`Py_ssize_t`**

Bir parçası Kararlı ABI. A signed integral type such that `sizeof(Py_ssize_t) == sizeof(size_t)`. C99 doesn't define such a thing directly (size_t is an unsigned integral type). See **PEP 353** for details. `PY_SSIZE_T_MAX` is the largest positive value of type *`Py_ssize_t`*.

1.6 Exceptions

The Python programmer only needs to deal with exceptions if specific error handling is required; unhandled exceptions are automatically propagated to the caller, then to the caller's caller, and so on, until they reach the top-level interpreter, where they are reported to the user accompanied by a stack traceback.

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented otherwise, this indicator is either `NULL` or `-1`, depending on the function's return type. A few functions return a Boolean true/false result, with false indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with *`PyErr_Occurred()`*. These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function *`PyErr_Occurred()`* can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and `NULL` otherwise. There are a number of functions to set the exception state: *`PyErr_SetString()`* is the most common (though not the most general) function to set the exception state, and *`PyErr_Clear()`* clears the exception state.

The full exception state consists of three objects (all of which can be `NULL`): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of `sys.exc_info()`; however, they are not the same: the Python objects represent the last exception being handled by a Python `try` … `except` statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to `sys.exc_info()` and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function `sys.exc_info()`, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns, and return an error indicator, but it should *not* set another exception — that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the `sum_sequence()` example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
int
incr_item(PyObject *dict, PyObject *key)
{
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
    int rv = -1; /* Return value initialized to -1 (failure) */

    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;

        /* Clear the error and use zero: */
        PyErr_Clear();
        item = PyLong_FromLong(0L);
        if (item == NULL)
            goto error;
    }
    const_one = PyLong_FromLong(1L);
    if (const_one == NULL)
        goto error;

    incremented_item = PyNumber_Add(item, const_one);
    if (incremented_item == NULL)
        goto error;

    if (PyObject_SetItem(dict, key, incremented_item) < 0)
        goto error;
    rv = 0; /* Success */
    /* Continue with cleanup code */

 error:
    /* Cleanup code, shared by success and failure path */

    /* Use Py_XDECREF() to ignore NULL references */
    Py_XDECREF(item);
    Py_XDECREF(const_one);
    Py_XDECREF(incremented_item);

    return rv; /* -1 for error, 0 for success */
}
```

This example represents an endorsed use of the `goto` statement in C! It illustrates the use of *PyErr_ExceptionMatches()* and *PyErr_Clear()* to handle specific exceptions, and the use of *Py_XDECREF()* to dispose of owned references that may be `NULL` (note the `'X'` in the name; *Py_DECREF()* would crash when confronted with a `NULL` reference). It is important that the variables used to hold owned references are initialized to `NULL` for this to work; likewise, the proposed return value is initialized to `-1` (failure) and only set to success after the final call made is successful.

1.7 Embedding Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is *Py_Initialize()*. This initializes the table of loaded modules, and creates the fundamental modules `builtins`, `__main__`, and `sys`. It also initializes the module search path (`sys.path`).

Py_Initialize() does not set the "script argument list" (`sys.argv`). If this variable is needed by Python code that will be executed later, setting *PyConfig.argv* and *PyConfig.parse_argv* must be set: see *Python Initialization Configuration*.

On most systems (in particular, on Unix and Windows, although the details are slightly different), *Py_Initialize()* calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named `lib/python`*X.Y* relative to the parent directory where the executable named `python` is found on the shell command search path (the environment variable `PATH`).

For instance, if the Python executable is found in `/usr/local/bin/python`, it will assume that the libraries are in `/usr/local/lib/python`*X.Y*. (In fact, this particular path is also the "fallback" location, used when no executable file named `python` is found along `PATH`.) The user can override this behavior by setting the environment variable `PYTHONHOME`, or insert additional directories in front of the standard path by setting `PYTHONPATH`.

The embedding application can steer the search by setting *PyConfig.program_name* *before* calling *Py_InitializeFromConfig()*. Note that `PYTHONHOME` still overrides this and `PYTHONPATH` is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of *Py_GetPath()*, *Py_GetPrefix()*, *Py_GetExecPrefix()*, and *Py_GetProgramFullPath()* (all defined in `Modules/getpath.c`).

Sometimes, it is desirable to "uninitialize" Python. For instance, the application may want to start over (make another call to *Py_Initialize()*) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling *Py_FinalizeEx()*. The function *Py_IsInitialized()* returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that *Py_FinalizeEx()* does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

1.8 Debugging Builds

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file `Misc/SpecialBuilds.txt` in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently used builds will be described in the remainder of this section.

Py_DEBUG

Compiling the interpreter with the `Py_DEBUG` macro defined produces what is generally meant by a debug build of Python. `Py_DEBUG` is enabled in the Unix build by adding `--with-pydebug` to the `./configure` command. It is also implied by the presence of the not-Python-specific `_DEBUG` macro. When `Py_DEBUG` is enabled in the Unix build, compiler optimization is disabled.

In addition to the reference count debugging described below, extra checks are performed, see Python Debug Build.

Defining `Py_TRACE_REFS` enables reference tracing (see the `configure --with-trace-refs option`). When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every *PyObject*. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.)

Please refer to `Misc/SpecialBuilds.txt` in the Python source distribution for more detailed information.

1.9 Recommended third party tools

The following third party tools offer both simpler and more sophisticated approaches to creating C, C++ and Rust extensions for Python:

- Cython
- cffi
- HPy
- nanobind (C++)
- Numba
- pybind11 (C++)
- PyO3 (Rust)
- SWIG

Using tools such as these can help avoid writing code that is tightly bound to a particular version of CPython, avoid reference counting errors, and focus more on your own code than on using the CPython API. In general, new versions of Python can be supported by updating the tool, and your code will often use newer and more efficient APIs automatically. Some tools also support compiling for other implementations of Python from a single set of sources.

These projects are not supported by the same people who maintain Python, and issues need to be raised with the projects directly. Remember to check that the project is still maintained and supported, as the list above may become outdated.

Ayrıca bakınız

Python Packaging User Guide: Binary Extensions
The Python Packaging User Guide not only covers several available tools that simplify the creation of binary extensions, but also discusses the various reasons why creating an extension module may be desirable in the first place.

BÖLÜM 2

C API Stability

Unless documented otherwise, Python's C API is covered by the Backwards Compatibility Policy, **PEP 387**. Most changes to it are source-compatible (typically by only adding new API). Changing existing API or removing API is only done after a deprecation period or to fix serious issues.

CPython's Application Binary Interface (ABI) is forward- and backwards-compatible across a minor release (if these are compiled the same way; see *Platform Considerations* below). So, code compiled for Python 3.10.0 will work on 3.10.8 and vice versa, but will need to be compiled separately for 3.9.x and 3.11.x.

There are two tiers of C API with different stability expectations:

- *Unstable API*, may change in minor versions without a deprecation period. It is marked by the `PyUnstable` prefix in names.
- *Limited API*, is compatible across several minor releases. When `Py_LIMITED_API` is defined, only this subset is exposed from `Python.h`.

These are discussed in more detail below.

Names prefixed by an underscore, such as `_Py_InternalState`, are private API that can change without notice even in patch releases. If you need to use this API, consider reaching out to CPython developers to discuss adding public API for your use case.

2.1 Unstable C API

Any API named with the `PyUnstable` prefix exposes CPython implementation details, and may change in every minor release (e.g. from 3.9 to 3.10) without any deprecation warnings. However, it will not change in a bugfix release (e.g. from 3.10.0 to 3.10.1).

It is generally intended for specialized, low-level tools like debuggers.

Projects that use this API are expected to follow CPython development and spend extra effort adjusting to changes.

2.2 Stable Application Binary Interface

For simplicity, this document talks about *extensions*, but the Limited API and Stable ABI work the same way for all uses of the API – for example, embedding Python.

2.2.1 Limited C API

Python 3.2 introduced the *Limited API*, a subset of Python's C API. Extensions that only use the Limited API can be compiled once and be loaded on multiple versions of Python. Contents of the Limited API are *listed below*.

Py_LIMITED_API

Define this macro before including `Python.h` to opt in to only use the Limited API, and to select the Limited API version.

Define `Py_LIMITED_API` to the value of *PY_VERSION_HEX* corresponding to the lowest Python version your extension supports. The extension will be ABI-compatible with all Python 3 releases from the specified one onward, and can use Limited API introduced up to that version.

Rather than using the `PY_VERSION_HEX` macro directly, hardcode a minimum minor version (e.g. `0x030A0000` for Python 3.10) for stability when compiling with future Python versions.

You can also define `Py_LIMITED_API` to `3`. This works the same as `0x03020000` (Python 3.2, the version that introduced Limited API).

2.2.2 Stable ABI

To enable this, Python provides a *Stable ABI*: a set of symbols that will remain ABI-compatible across Python 3.x versions.

Not

The Stable ABI prevents ABI issues, like linker errors due to missing symbols or data corruption due to changes in structure layouts or function signatures. However, other changes in Python can change the *behavior* of extensions. See Python's Backwards Compatibility Policy (**PEP 387**) for details.

The Stable ABI contains symbols exposed in the *Limited API*, but also other ones – for example, functions necessary to support older versions of the Limited API.

On Windows, extensions that use the Stable ABI should be linked against `python3.dll` rather than a version-specific library such as `python39.dll`.

On some platforms, Python will look for and load shared library files named with the `abi3` tag (e.g. `mymodule.abi3.so`). It does not check if such extensions conform to a Stable ABI. The user (or their packaging tools) need to ensure that, for example, extensions built with the 3.10+ Limited API are not installed for lower versions of Python.

All functions in the Stable ABI are present as functions in Python's shared library, not solely as macros. This makes them usable from languages that don't use the C preprocessor.

2.2.3 Limited API Scope and Performance

The goal for the Limited API is to allow everything that is possible with the full C API, but possibly with a performance penalty.

For example, while *PyList_GetItem()* is available, its "unsafe" macro variant *PyList_GET_ITEM()* is not. The macro can be faster because it can rely on version-specific implementation details of the list object.

Without `Py_LIMITED_API` defined, some C API functions are inlined or replaced by macros. Defining `Py_LIMITED_API` disables this inlining, allowing stability as Python's data structures are improved, but possibly reducing performance.

By leaving out the `Py_LIMITED_API` definition, it is possible to compile a Limited API extension with a version-specific ABI. This can improve performance for that Python version, but will limit compatibility. Compiling with `Py_LIMITED_API` will then yield an extension that can be distributed where a version-specific one is not available – for example, for prereleases of an upcoming Python version.

2.2.4 Limited API Caveats

Note that compiling with `Py_LIMITED_API` is *not* a complete guarantee that code conforms to the *Limited API* or the *Stable ABI*. `Py_LIMITED_API` only covers definitions, but an API also includes other issues, such as expected semantics.

One issue that `Py_LIMITED_API` does not guard against is calling a function with arguments that are invalid in a lower Python version. For example, consider a function that starts accepting `NULL` for an argument. In Python 3.9, `NULL` now selects a default behavior, but in Python 3.8, the argument will be used directly, causing a `NULL` dereference and crash. A similar argument works for fields of structs.

Another issue is that some struct fields are currently not hidden when `Py_LIMITED_API` is defined, even though they're part of the Limited API.

For these reasons, we recommend testing an extension with *all* minor Python versions it supports, and preferably to build with the *lowest* such version.

We also recommend reviewing documentation of all used API to check if it is explicitly part of the Limited API. Even with `Py_LIMITED_API` defined, a few private declarations are exposed for technical reasons (or even unintentionally, as bugs).

Also note that the Limited API is not necessarily stable: compiling with `Py_LIMITED_API` with Python 3.8 means that the extension will run with Python 3.12, but it will not necessarily *compile* with Python 3.12. In particular, parts of the Limited API may be deprecated and removed, provided that the Stable ABI stays stable.

2.3 Platform Considerations

ABI stability depends not only on Python, but also on the compiler used, lower-level libraries and compiler options. For the purposes of the *Stable ABI*, these details define a "platform". They usually depend on the OS type and processor architecture

It is the responsibility of each particular distributor of Python to ensure that all Python versions on a particular platform are built in a way that does not break the Stable ABI. This is the case with Windows and macOS releases from `python.org` and many third-party distributors.

2.4 Contents of Limited API

Currently, the *Limited API* includes the following items:

- *PY_VECTORCALL_ARGUMENTS_OFFSET*
- *PyAIter_Check()*
- *PyArg_Parse()*
- *PyArg_ParseTuple()*
- *PyArg_ParseTupleAndKeywords()*
- *PyArg_UnpackTuple()*
- *PyArg_VaParse()*
- *PyArg_VaParseTupleAndKeywords()*
- *PyArg_ValidateKeywordArguments()*
- *PyBaseObject_Type*
- *PyBool_FromLong()*
- *PyBool_Type*
- *PyBuffer_FillContiguousStrides()*

- *PyBuffer_FillInfo()*
- *PyBuffer_FromContiguous()*
- *PyBuffer_GetPointer()*
- *PyBuffer_IsContiguous()*
- *PyBuffer_Release()*
- *PyBuffer_SizeFromFormat()*
- *PyBuffer_ToContiguous()*
- PyByteArrayIter_Type
- *PyByteArray_AsString()*
- *PyByteArray_Concat()*
- *PyByteArray_FromObject()*
- *PyByteArray_FromStringAndSize()*
- *PyByteArray_Resize()*
- *PyByteArray_Size()*
- *PyByteArray_Type*
- PyBytesIter_Type
- *PyBytes_AsString()*
- *PyBytes_AsStringAndSize()*
- *PyBytes_Concat()*
- *PyBytes_ConcatAndDel()*
- PyBytes_DecodeEscape()
- *PyBytes_FromFormat()*
- *PyBytes_FromFormatV()*
- *PyBytes_FromObject()*
- *PyBytes_FromString()*
- *PyBytes_FromStringAndSize()*
- PyBytes_Repr()
- *PyBytes_Size()*
- *PyBytes_Type*
- *PyCFunction*
- *PyCFunctionFast*
- *PyCFunctionFastWithKeywords*
- *PyCFunctionWithKeywords*
- PyCFunction_GetFlags()
- PyCFunction_GetFunction()
- PyCFunction_GetSelf()
- *PyCFunction_New()*
- *PyCFunction_NewEx()*
- PyCFunction_Type

- *PyCMethod_New()*
- *PyCallIter_New()*
- *PyCallIter_Type*
- *PyCallable_Check()*
- *PyCapsule_Destructor*
- *PyCapsule_GetContext()*
- *PyCapsule_GetDestructor()*
- *PyCapsule_GetName()*
- *PyCapsule_GetPointer()*
- *PyCapsule_Import()*
- *PyCapsule_IsValid()*
- *PyCapsule_New()*
- *PyCapsule_SetContext()*
- *PyCapsule_SetDestructor()*
- *PyCapsule_SetName()*
- *PyCapsule_SetPointer()*
- PyCapsule_Type
- PyClassMethodDescr_Type
- *PyCodec_BackslashReplaceErrors()*
- *PyCodec_Decode()*
- *PyCodec_Decoder()*
- *PyCodec_Encode()*
- *PyCodec_Encoder()*
- *PyCodec_IgnoreErrors()*
- *PyCodec_IncrementalDecoder()*
- *PyCodec_IncrementalEncoder()*
- *PyCodec_KnownEncoding()*
- *PyCodec_LookupError()*
- *PyCodec_NameReplaceErrors()*
- *PyCodec_Register()*
- *PyCodec_RegisterError()*
- *PyCodec_ReplaceErrors()*
- *PyCodec_StreamReader()*
- *PyCodec_StreamWriter()*
- *PyCodec_StrictErrors()*
- *PyCodec_Unregister()*
- *PyCodec_XMLCharRefReplaceErrors()*
- *PyComplex_FromDoubles()*
- *PyComplex_ImagAsDouble()*

- *PyComplex_RealAsDouble()*
- *PyComplex_Type*
- *PyDescr_NewClassMethod()*
- *PyDescr_NewGetSet()*
- *PyDescr_NewMember()*
- *PyDescr_NewMethod()*
- PyDictItems_Type
- PyDictIterItem_Type
- PyDictIterKey_Type
- PyDictIterValue_Type
- PyDictKeys_Type
- *PyDictProxy_New()*
- PyDictProxy_Type
- PyDictRevIterItem_Type
- PyDictRevIterKey_Type
- PyDictRevIterValue_Type
- PyDictValues_Type
- *PyDict_Clear()*
- *PyDict_Contains()*
- *PyDict_Copy()*
- *PyDict_DelItem()*
- *PyDict_DelItemString()*
- *PyDict_GetItem()*
- *PyDict_GetItemRef()*
- *PyDict_GetItemString()*
- *PyDict_GetItemStringRef()*
- *PyDict_GetItemWithError()*
- *PyDict_Items()*
- *PyDict_Keys()*
- *PyDict_Merge()*
- *PyDict_MergeFromSeq2()*
- *PyDict_New()*
- *PyDict_Next()*
- *PyDict_SetItem()*
- *PyDict_SetItemString()*
- *PyDict_Size()*
- *PyDict_Type*
- *PyDict_Update()*
- *PyDict_Values()*

- *PyEllipsis_Type*
- PyEnum_Type
- *PyErr_BadArgument()*
- *PyErr_BadInternalCall()*
- *PyErr_CheckSignals()*
- *PyErr_Clear()*
- PyErr_Display()
- *PyErr_DisplayException()*
- *PyErr_ExceptionMatches()*
- *PyErr_Fetch()*
- *PyErr_Format()*
- *PyErr_FormatV()*
- *PyErr_GetExcInfo()*
- *PyErr_GetHandledException()*
- *PyErr_GetRaisedException()*
- *PyErr_GivenExceptionMatches()*
- *PyErr_NewException()*
- *PyErr_NewExceptionWithDoc()*
- *PyErr_NoMemory()*
- *PyErr_NormalizeException()*
- *PyErr_Occurred()*
- *PyErr_Print()*
- *PyErr_PrintEx()*
- PyErr_ProgramText()
- *PyErr_ResourceWarning()*
- *PyErr_Restore()*
- *PyErr_SetExcFromWindowsErr()*
- *PyErr_SetExcFromWindowsErrWithFilename()*
- *PyErr_SetExcFromWindowsErrWithFilenameObject()*
- *PyErr_SetExcFromWindowsErrWithFilenameObjects()*
- *PyErr_SetExcInfo()*
- *PyErr_SetFromErrno()*
- *PyErr_SetFromErrnoWithFilename()*
- *PyErr_SetFromErrnoWithFilenameObject()*
- *PyErr_SetFromErrnoWithFilenameObjects()*
- *PyErr_SetFromWindowsErr()*
- *PyErr_SetFromWindowsErrWithFilename()*
- *PyErr_SetHandledException()*
- *PyErr_SetImportError()*

- *PyErr_SetImportErrorSubclass()*
- *PyErr_SetInterrupt()*
- *PyErr_SetInterruptEx()*
- *PyErr_SetNone()*
- *PyErr_SetObject()*
- *PyErr_SetRaisedException()*
- *PyErr_SetString()*
- *PyErr_SyntaxLocation()*
- *PyErr_SyntaxLocationEx()*
- *PyErr_WarnEx()*
- *PyErr_WarnExplicit()*
- *PyErr_WarnFormat()*
- *PyErr_WriteUnraisable()*
- *PyEval_AcquireThread()*
- *PyEval_EvalCode()*
- *PyEval_EvalCodeEx()*
- *PyEval_EvalFrame()*
- *PyEval_EvalFrameEx()*
- *PyEval_GetBuiltins()*
- *PyEval_GetFrame()*
- *PyEval_GetFrameBuiltins()*
- *PyEval_GetFrameGlobals()*
- *PyEval_GetFrameLocals()*
- *PyEval_GetFuncDesc()*
- *PyEval_GetFuncName()*
- *PyEval_GetGlobals()*
- *PyEval_GetLocals()*
- *PyEval_InitThreads()*
- *PyEval_ReleaseThread()*
- *PyEval_RestoreThread()*
- *PyEval_SaveThread()*
- *PyExc_ArithmeticError*
- *PyExc_AssertionError*
- *PyExc_AttributeError*
- *PyExc_BaseException*
- *PyExc_BaseExceptionGroup*
- *PyExc_BlockingIOError*
- *PyExc_BrokenPipeError*
- *PyExc_BufferError*

- *PyExc_BytesWarning*
- *PyExc_ChildProcessError*
- *PyExc_ConnectionAbortedError*
- *PyExc_ConnectionError*
- *PyExc_ConnectionRefusedError*
- *PyExc_ConnectionResetError*
- *PyExc_DeprecationWarning*
- *PyExc_EOFError*
- *PyExc_EncodingWarning*
- *PyExc_EnvironmentError*
- *PyExc_Exception*
- *PyExc_FileExistsError*
- *PyExc_FileNotFoundError*
- *PyExc_FloatingPointError*
- *PyExc_FutureWarning*
- *PyExc_GeneratorExit*
- *PyExc_IOError*
- *PyExc_ImportError*
- *PyExc_ImportWarning*
- *PyExc_IndentationError*
- *PyExc_IndexError*
- *PyExc_InterruptedError*
- *PyExc_IsADirectoryError*
- *PyExc_KeyError*
- *PyExc_KeyboardInterrupt*
- *PyExc_LookupError*
- *PyExc_MemoryError*
- *PyExc_ModuleNotFoundError*
- *PyExc_NameError*
- *PyExc_NotADirectoryError*
- *PyExc_NotImplementedError*
- *PyExc_OSError*
- *PyExc_OverflowError*
- *PyExc_PendingDeprecationWarning*
- *PyExc_PermissionError*
- *PyExc_ProcessLookupError*
- *PyExc_RecursionError*
- *PyExc_ReferenceError*
- *PyExc_ResourceWarning*

- *PyExc_RuntimeError*
- *PyExc_RuntimeWarning*
- *PyExc_StopAsyncIteration*
- *PyExc_StopIteration*
- *PyExc_SyntaxError*
- *PyExc_SyntaxWarning*
- *PyExc_SystemError*
- *PyExc_SystemExit*
- *PyExc_TabError*
- *PyExc_TimeoutError*
- *PyExc_TypeError*
- *PyExc_UnboundLocalError*
- *PyExc_UnicodeDecodeError*
- *PyExc_UnicodeEncodeError*
- *PyExc_UnicodeError*
- *PyExc_UnicodeTranslateError*
- *PyExc_UnicodeWarning*
- *PyExc_UserWarning*
- *PyExc_ValueError*
- *PyExc_Warning*
- *PyExc_WindowsError*
- *PyExc_ZeroDivisionError*
- *PyExceptionClass_Name()*
- *PyException_GetArgs()*
- *PyException_GetCause()*
- *PyException_GetContext()*
- *PyException_GetTraceback()*
- *PyException_SetArgs()*
- *PyException_SetCause()*
- *PyException_SetContext()*
- *PyException_SetTraceback()*
- *PyFile_FromFd()*
- *PyFile_GetLine()*
- *PyFile_WriteObject()*
- *PyFile_WriteString()*
- PyFilter_Type
- *PyFloat_AsDouble()*
- *PyFloat_FromDouble()*
- *PyFloat_FromString()*

- *PyFloat_GetInfo()*
- *PyFloat_GetMax()*
- *PyFloat_GetMin()*
- *PyFloat_Type*
- *PyFrameObject*
- *PyFrame_GetCode()*
- *PyFrame_GetLineNumber()*
- *PyFrozenSet_New()*
- *PyFrozenSet_Type*
- *PyGC_Collect()*
- *PyGC_Disable()*
- *PyGC_Enable()*
- *PyGC_IsEnabled()*
- *PyGILState_Ensure()*
- *PyGILState_GetThisThreadState()*
- *PyGILState_Release()*
- PyGILState_STATE
- *PyGetSetDef*
- PyGetSetDescr_Type
- *PyImport_AddModule()*
- *PyImport_AddModuleObject()*
- *PyImport_AddModuleRef()*
- *PyImport_AppendInittab()*
- *PyImport_ExecCodeModule()*
- *PyImport_ExecCodeModuleEx()*
- *PyImport_ExecCodeModuleObject()*
- *PyImport_ExecCodeModuleWithPathnames()*
- *PyImport_GetImporter()*
- *PyImport_GetMagicNumber()*
- *PyImport_GetMagicTag()*
- *PyImport_GetModule()*
- *PyImport_GetModuleDict()*
- *PyImport_Import()*
- *PyImport_ImportFrozenModule()*
- *PyImport_ImportFrozenModuleObject()*
- *PyImport_ImportModule()*
- *PyImport_ImportModuleLevel()*
- *PyImport_ImportModuleLevelObject()*
- *PyImport_ImportModuleNoBlock()*

- *PyImport_ReloadModule()*
- *PyIndex_Check()*
- *PyInterpreterState*
- *PyInterpreterState_Clear()*
- *PyInterpreterState_Delete()*
- *PyInterpreterState_Get()*
- *PyInterpreterState_GetDict()*
- *PyInterpreterState_GetID()*
- *PyInterpreterState_New()*
- *PyIter_Check()*
- *PyIter_Next()*
- *PyIter_NextItem()*
- *PyIter_Send()*
- PyListIter_Type
- PyListRevIter_Type
- *PyList_Append()*
- *PyList_AsTuple()*
- *PyList_GetItem()*
- *PyList_GetItemRef()*
- *PyList_GetSlice()*
- *PyList_Insert()*
- *PyList_New()*
- *PyList_Reverse()*
- *PyList_SetItem()*
- *PyList_SetSlice()*
- *PyList_Size()*
- *PyList_Sort()*
- *PyList_Type*
- *PyLongObject*
- PyLongRangeIter_Type
- *PyLong_AsDouble()*
- *PyLong_AsInt()*
- *PyLong_AsInt32()*
- *PyLong_AsInt64()*
- *PyLong_AsLong()*
- *PyLong_AsLongAndOverflow()*
- *PyLong_AsLongLong()*
- *PyLong_AsLongLongAndOverflow()*
- *PyLong_AsNativeBytes()*

- *PyLong_AsSize_t()*
- *PyLong_AsSsize_t()*
- *PyLong_AsUInt32()*
- *PyLong_AsUInt64()*
- *PyLong_AsUnsignedLong()*
- *PyLong_AsUnsignedLongLong()*
- *PyLong_AsUnsignedLongLongMask()*
- *PyLong_AsUnsignedLongMask()*
- *PyLong_AsVoidPtr()*
- *PyLong_FromDouble()*
- *PyLong_FromInt32()*
- *PyLong_FromInt64()*
- *PyLong_FromLong()*
- *PyLong_FromLongLong()*
- *PyLong_FromNativeBytes()*
- *PyLong_FromSize_t()*
- *PyLong_FromSsize_t()*
- *PyLong_FromString()*
- *PyLong_FromUInt32()*
- *PyLong_FromUInt64()*
- *PyLong_FromUnsignedLong()*
- *PyLong_FromUnsignedLongLong()*
- *PyLong_FromUnsignedNativeBytes()*
- *PyLong_FromVoidPtr()*
- *PyLong_GetInfo()*
- *PyLong_Type*
- PyMap_Type
- *PyMapping_Check()*
- *PyMapping_GetItemString()*
- *PyMapping_GetOptionalItem()*
- *PyMapping_GetOptionalItemString()*
- *PyMapping_HasKey()*
- *PyMapping_HasKeyString()*
- *PyMapping_HasKeyStringWithError()*
- *PyMapping_HasKeyWithError()*
- *PyMapping_Items()*
- *PyMapping_Keys()*
- *PyMapping_Length()*
- *PyMapping_SetItemString()*

- *PyMapping_Size()*
- *PyMapping_Values()*
- *PyMem_Calloc()*
- *PyMem_Free()*
- *PyMem_Malloc()*
- *PyMem_RawCalloc()*
- *PyMem_RawFree()*
- *PyMem_RawMalloc()*
- *PyMem_RawRealloc()*
- *PyMem_Realloc()*
- *PyMemberDef*
- PyMemberDescr_Type
- *PyMember_GetOne()*
- *PyMember_SetOne()*
- *PyMemoryView_FromBuffer()*
- *PyMemoryView_FromMemory()*
- *PyMemoryView_FromObject()*
- *PyMemoryView_GetContiguous()*
- PyMemoryView_Type
- *PyMethodDef*
- PyMethodDescr_Type
- *PyModuleDef*
- PyModuleDef_Base
- *PyModuleDef_Init()*
- PyModuleDef_Type
- *PyModule_Add()*
- *PyModule_AddFunctions()*
- *PyModule_AddIntConstant()*
- *PyModule_AddObject()*
- *PyModule_AddObjectRef()*
- *PyModule_AddStringConstant()*
- *PyModule_AddType()*
- *PyModule_Create2()*
- *PyModule_ExecDef()*
- *PyModule_FromDefAndSpec2()*
- *PyModule_GetDef()*
- *PyModule_GetDict()*
- *PyModule_GetFilename()*
- *PyModule_GetFilenameObject()*

- *PyModule_GetName()*
- *PyModule_GetNameObject()*
- *PyModule_GetState()*
- *PyModule_New()*
- *PyModule_NewObject()*
- *PyModule_SetDocString()*
- *PyModule_Type*
- *PyNumber_Absolute()*
- *PyNumber_Add()*
- *PyNumber_And()*
- *PyNumber_AsSsize_t()*
- *PyNumber_Check()*
- *PyNumber_Divmod()*
- *PyNumber_Float()*
- *PyNumber_FloorDivide()*
- *PyNumber_InPlaceAdd()*
- *PyNumber_InPlaceAnd()*
- *PyNumber_InPlaceFloorDivide()*
- *PyNumber_InPlaceLshift()*
- *PyNumber_InPlaceMatrixMultiply()*
- *PyNumber_InPlaceMultiply()*
- *PyNumber_InPlaceOr()*
- *PyNumber_InPlacePower()*
- *PyNumber_InPlaceRemainder()*
- *PyNumber_InPlaceRshift()*
- *PyNumber_InPlaceSubtract()*
- *PyNumber_InPlaceTrueDivide()*
- *PyNumber_InPlaceXor()*
- *PyNumber_Index()*
- *PyNumber_Invert()*
- *PyNumber_Long()*
- *PyNumber_Lshift()*
- *PyNumber_MatrixMultiply()*
- *PyNumber_Multiply()*
- *PyNumber_Negative()*
- *PyNumber_Or()*
- *PyNumber_Positive()*
- *PyNumber_Power()*
- *PyNumber_Remainder()*

- *PyNumber_Rshift()*
- *PyNumber_Subtract()*
- *PyNumber_ToBase()*
- *PyNumber_TrueDivide()*
- *PyNumber_Xor()*
- *PyOS_AfterFork()*
- *PyOS_AfterFork_Child()*
- *PyOS_AfterFork_Parent()*
- *PyOS_BeforeFork()*
- *PyOS_CheckStack()*
- *PyOS_FSPath()*
- *PyOS_InputHook*
- PyOS_InterruptOccurred()
- *PyOS_double_to_string()*
- *PyOS_getsig()*
- PyOS_mystricmp()
- PyOS_mystrnicmp()
- *PyOS_setsig()*
- *PyOS_sighandler_t*
- *PyOS_snprintf()*
- *PyOS_string_to_double()*
- *PyOS_strtol()*
- *PyOS_strtoul()*
- *PyOS_vsnprintf()*
- *PyObject*
- *PyObject.ob_refcnt*
- *PyObject.ob_type*
- *PyObject_ASCII()*
- *PyObject_AsFileDescriptor()*
- *PyObject_Bytes()*
- *PyObject_Call()*
- *PyObject_CallFunction()*
- *PyObject_CallFunctionObjArgs()*
- *PyObject_CallMethod()*
- *PyObject_CallMethodObjArgs()*
- *PyObject_CallNoArgs()*
- *PyObject_CallObject()*
- *PyObject_Calloc()*
- *PyObject_CheckBuffer()*

- *PyObject_ClearWeakRefs()*
- *PyObject_CopyData()*
- *PyObject_DelAttr()*
- *PyObject_DelAttrString()*
- *PyObject_DelItem()*
- *PyObject_DelItemString()*
- *PyObject_Dir()*
- *PyObject_Format()*
- *PyObject_Free()*
- *PyObject_GC_Del()*
- *PyObject_GC_IsFinalized()*
- *PyObject_GC_IsTracked()*
- *PyObject_GC_Track()*
- *PyObject_GC_UnTrack()*
- *PyObject_GenericGetAttr()*
- *PyObject_GenericGetDict()*
- *PyObject_GenericSetAttr()*
- *PyObject_GenericSetDict()*
- *PyObject_GetAIter()*
- *PyObject_GetAttr()*
- *PyObject_GetAttrString()*
- *PyObject_GetBuffer()*
- *PyObject_GetItem()*
- *PyObject_GetIter()*
- *PyObject_GetOptionalAttr()*
- *PyObject_GetOptionalAttrString()*
- *PyObject_GetTypeData()*
- *PyObject_HasAttr()*
- *PyObject_HasAttrString()*
- *PyObject_HasAttrStringWithError()*
- *PyObject_HasAttrWithError()*
- *PyObject_Hash()*
- *PyObject_HashNotImplemented()*
- *PyObject_Init()*
- *PyObject_InitVar()*
- *PyObject_IsInstance()*
- *PyObject_IsSubclass()*
- *PyObject_IsTrue()*
- *PyObject_Length()*

- *PyObject_Malloc()*
- *PyObject_Not()*
- *PyObject_Realloc()*
- *PyObject_Repr()*
- *PyObject_RichCompare()*
- *PyObject_RichCompareBool()*
- *PyObject_SelfIter()*
- *PyObject_SetAttr()*
- *PyObject_SetAttrString()*
- *PyObject_SetItem()*
- *PyObject_Size()*
- *PyObject_Str()*
- *PyObject_Type()*
- *PyObject_Vectorcall()*
- *PyObject_VectorcallMethod()*
- *PyProperty_Type*
- PyRangeIter_Type
- PyRange_Type
- PyReversed_Type
- *PySeqIter_New()*
- *PySeqIter_Type*
- *PySequence_Check()*
- *PySequence_Concat()*
- *PySequence_Contains()*
- *PySequence_Count()*
- *PySequence_DelItem()*
- *PySequence_DelSlice()*
- *PySequence_Fast()*
- *PySequence_GetItem()*
- *PySequence_GetSlice()*
- *PySequence_In()*
- *PySequence_InPlaceConcat()*
- *PySequence_InPlaceRepeat()*
- *PySequence_Index()*
- *PySequence_Length()*
- *PySequence_List()*
- *PySequence_Repeat()*
- *PySequence_SetItem()*
- *PySequence_SetSlice()*

- *PySequence_Size()*
- *PySequence_Tuple()*
- PySetIter_Type
- *PySet_Add()*
- *PySet_Clear()*
- *PySet_Contains()*
- *PySet_Discard()*
- *PySet_New()*
- *PySet_Pop()*
- *PySet_Size()*
- *PySet_Type*
- *PySlice_AdjustIndices()*
- *PySlice_GetIndices()*
- *PySlice_GetIndicesEx()*
- *PySlice_New()*
- *PySlice_Type*
- *PySlice_Unpack()*
- *PyState_AddModule()*
- *PyState_FindModule()*
- *PyState_RemoveModule()*
- *PyStructSequence_Desc*
- *PyStructSequence_Field*
- *PyStructSequence_GetItem()*
- *PyStructSequence_New()*
- *PyStructSequence_NewType()*
- *PyStructSequence_SetItem()*
- *PyStructSequence_UnnamedField*
- PySuper_Type
- *PySys_Audit()*
- *PySys_AuditTuple()*
- *PySys_FormatStderr()*
- *PySys_FormatStdout()*
- *PySys_GetObject()*
- *PySys_GetXOptions()*
- *PySys_ResetWarnOptions()*
- *PySys_SetArgv()*
- *PySys_SetArgvEx()*
- *PySys_SetObject()*
- *PySys_WriteStderr()*

- *PySys_WriteStdout()*
- *PyThreadState*
- *PyThreadState_Clear()*
- *PyThreadState_Delete()*
- *PyThreadState_Get()*
- *PyThreadState_GetDict()*
- *PyThreadState_GetFrame()*
- *PyThreadState_GetID()*
- *PyThreadState_GetInterpreter()*
- *PyThreadState_New()*
- *PyThreadState_SetAsyncExc()*
- *PyThreadState_Swap()*
- PyThread_GetInfo()
- *PyThread_ReInitTLS()*
- PyThread_acquire_lock()
- PyThread_acquire_lock_timed()
- PyThread_allocate_lock()
- *PyThread_create_key()*
- *PyThread_delete_key()*
- *PyThread_delete_key_value()*
- PyThread_exit_thread()
- PyThread_free_lock()
- *PyThread_get_key_value()*
- PyThread_get_stacksize()
- PyThread_get_thread_ident()
- PyThread_get_thread_native_id()
- PyThread_init_thread()
- PyThread_release_lock()
- *PyThread_set_key_value()*
- PyThread_set_stacksize()
- PyThread_start_new_thread()
- *PyThread_tss_alloc()*
- *PyThread_tss_create()*
- *PyThread_tss_delete()*
- *PyThread_tss_free()*
- *PyThread_tss_get()*
- *PyThread_tss_is_created()*
- *PyThread_tss_set()*
- PyTraceBack_Here()

- PyTraceBack_Print()
- PyTraceBack_Type
- PyTupleIter_Type
- *PyTuple_GetItem()*
- *PyTuple_GetSlice()*
- *PyTuple_New()*
- *PyTuple_Pack()*
- *PyTuple_SetItem()*
- *PyTuple_Size()*
- *PyTuple_Type*
- *PyTypeObject*
- *PyType_ClearCache()*
- *PyType_Freeze()*
- *PyType_FromMetaclass()*
- *PyType_FromModuleAndSpec()*
- *PyType_FromSpec()*
- *PyType_FromSpecWithBases()*
- *PyType_GenericAlloc()*
- *PyType_GenericNew()*
- *PyType_GetBaseByToken()*
- *PyType_GetFlags()*
- *PyType_GetFullyQualifiedName()*
- *PyType_GetModule()*
- *PyType_GetModuleByDef()*
- *PyType_GetModuleName()*
- *PyType_GetModuleState()*
- *PyType_GetName()*
- *PyType_GetQualName()*
- *PyType_GetSlot()*
- *PyType_GetTypeDataSize()*
- *PyType_IsSubtype()*
- *PyType_Modified()*
- *PyType_Ready()*
- *PyType_Slot*
- *PyType_Spec*
- *PyType_Type*
- *PyUnicodeDecodeError_Create()*
- *PyUnicodeDecodeError_GetEncoding()*
- *PyUnicodeDecodeError_GetEnd()*

- *PyUnicodeDecodeError_GetObject()*
- *PyUnicodeDecodeError_GetReason()*
- *PyUnicodeDecodeError_GetStart()*
- *PyUnicodeDecodeError_SetEnd()*
- *PyUnicodeDecodeError_SetReason()*
- *PyUnicodeDecodeError_SetStart()*
- *PyUnicodeEncodeError_GetEncoding()*
- *PyUnicodeEncodeError_GetEnd()*
- *PyUnicodeEncodeError_GetObject()*
- *PyUnicodeEncodeError_GetReason()*
- *PyUnicodeEncodeError_GetStart()*
- *PyUnicodeEncodeError_SetEnd()*
- *PyUnicodeEncodeError_SetReason()*
- *PyUnicodeEncodeError_SetStart()*
- *PyUnicodeIter_Type*
- *PyUnicodeTranslateError_GetEnd()*
- *PyUnicodeTranslateError_GetObject()*
- *PyUnicodeTranslateError_GetReason()*
- *PyUnicodeTranslateError_GetStart()*
- *PyUnicodeTranslateError_SetEnd()*
- *PyUnicodeTranslateError_SetReason()*
- *PyUnicodeTranslateError_SetStart()*
- *PyUnicode_Append()*
- *PyUnicode_AppendAndDel()*
- *PyUnicode_AsASCIIString()*
- *PyUnicode_AsCharmapString()*
- PyUnicode_AsDecodedObject()
- PyUnicode_AsDecodedUnicode()
- PyUnicode_AsEncodedObject()
- *PyUnicode_AsEncodedString()*
- PyUnicode_AsEncodedUnicode()
- *PyUnicode_AsLatin1String()*
- *PyUnicode_AsMBCSString()*
- *PyUnicode_AsRawUnicodeEscapeString()*
- *PyUnicode_AsUCS4()*
- *PyUnicode_AsUCS4Copy()*
- *PyUnicode_AsUTF16String()*
- *PyUnicode_AsUTF32String()*
- *PyUnicode_AsUTF8AndSize()*

- *PyUnicode_AsUTF8String()*
- *PyUnicode_AsUnicodeEscapeString()*
- *PyUnicode_AsWideChar()*
- *PyUnicode_AsWideCharString()*
- *PyUnicode_BuildEncodingMap()*
- *PyUnicode_Compare()*
- *PyUnicode_CompareWithASCIIString()*
- *PyUnicode_Concat()*
- *PyUnicode_Contains()*
- *PyUnicode_Count()*
- *PyUnicode_Decode()*
- *PyUnicode_DecodeASCII()*
- *PyUnicode_DecodeCharmap()*
- *PyUnicode_DecodeCodePageStateful()*
- *PyUnicode_DecodeFSDefault()*
- *PyUnicode_DecodeFSDefaultAndSize()*
- *PyUnicode_DecodeLatin1()*
- *PyUnicode_DecodeLocale()*
- *PyUnicode_DecodeLocaleAndSize()*
- *PyUnicode_DecodeMBCS()*
- *PyUnicode_DecodeMBCSStateful()*
- *PyUnicode_DecodeRawUnicodeEscape()*
- *PyUnicode_DecodeUTF16()*
- *PyUnicode_DecodeUTF16Stateful()*
- *PyUnicode_DecodeUTF32()*
- *PyUnicode_DecodeUTF32Stateful()*
- *PyUnicode_DecodeUTF7()*
- *PyUnicode_DecodeUTF7Stateful()*
- *PyUnicode_DecodeUTF8()*
- *PyUnicode_DecodeUTF8Stateful()*
- *PyUnicode_DecodeUnicodeEscape()*
- *PyUnicode_EncodeCodePage()*
- *PyUnicode_EncodeFSDefault()*
- *PyUnicode_EncodeLocale()*
- *PyUnicode_Equal()*
- *PyUnicode_EqualToUTF8()*
- *PyUnicode_EqualToUTF8AndSize()*
- *PyUnicode_FSConverter()*
- *PyUnicode_FSDecoder()*

- *PyUnicode_Find()*
- *PyUnicode_FindChar()*
- *PyUnicode_Format()*
- *PyUnicode_FromEncodedObject()*
- *PyUnicode_FromFormat()*
- *PyUnicode_FromFormatV()*
- *PyUnicode_FromObject()*
- *PyUnicode_FromOrdinal()*
- *PyUnicode_FromString()*
- *PyUnicode_FromStringAndSize()*
- *PyUnicode_FromWideChar()*
- *PyUnicode_GetDefaultEncoding()*
- *PyUnicode_GetLength()*
- *PyUnicode_InternFromString()*
- *PyUnicode_InternInPlace()*
- *PyUnicode_IsIdentifier()*
- *PyUnicode_Join()*
- *PyUnicode_Partition()*
- *PyUnicode_RPartition()*
- *PyUnicode_RSplit()*
- *PyUnicode_ReadChar()*
- *PyUnicode_Replace()*
- *PyUnicode_Resize()*
- *PyUnicode_RichCompare()*
- *PyUnicode_Split()*
- *PyUnicode_Splitlines()*
- *PyUnicode_Substring()*
- *PyUnicode_Tailmatch()*
- *PyUnicode_Translate()*
- *PyUnicode_Type*
- *PyUnicode_WriteChar()*
- *PyVarObject*
- PyVarObject.ob_base
- *PyVarObject.ob_size*
- *PyVectorcall_Call()*
- *PyVectorcall_NARGS()*
- PyWeakReference
- *PyWeakref_GetObject()*
- *PyWeakref_GetRef()*

- *PyWeakref_NewProxy()*
- *PyWeakref_NewRef()*
- PyWrapperDescr_Type
- *PyWrapper_New()*
- PyZip_Type
- *Py_AddPendingCall()*
- *Py_AtExit()*
- *Py_BEGIN_ALLOW_THREADS*
- *Py_BLOCK_THREADS*
- *Py_BuildValue()*
- *Py_BytesMain()*
- *Py_CompileString()*
- *Py_DecRef()*
- *Py_DecodeLocale()*
- *Py_END_ALLOW_THREADS*
- *Py_EncodeLocale()*
- *Py_EndInterpreter()*
- *Py_EnterRecursiveCall()*
- *Py_Exit()*
- *Py_FatalError()*
- Py_FileSystemDefaultEncodeErrors
- Py_FileSystemDefaultEncoding
- *Py_Finalize()*
- *Py_FinalizeEx()*
- *Py_GenericAlias()*
- *Py_GenericAliasType*
- *Py_GetBuildInfo()*
- *Py_GetCompiler()*
- *Py_GetConstant()*
- *Py_GetConstantBorrowed()*
- *Py_GetCopyright()*
- *Py_GetExecPrefix()*
- *Py_GetPath()*
- *Py_GetPlatform()*
- *Py_GetPrefix()*
- *Py_GetProgramFullPath()*
- *Py_GetProgramName()*
- *Py_GetPythonHome()*
- Py_GetRecursionLimit()

- *Py_GetVersion()*
- Py_HasFileSystemDefaultEncoding
- *Py_IncRef()*
- *Py_Initialize()*
- *Py_InitializeEx()*
- *Py_Is()*
- *Py_IsFalse()*
- *Py_IsFinalizing()*
- *Py_IsInitialized()*
- *Py_IsNone()*
- *Py_IsTrue()*
- *Py_LeaveRecursiveCall()*
- *Py_Main()*
- Py_MakePendingCalls()
- *Py_NewInterpreter()*
- *Py_NewRef()*
- *Py_PACK_FULL_VERSION()*
- *Py_PACK_VERSION()*
- *Py_REFCNT()*
- *Py_ReprEnter()*
- *Py_ReprLeave()*
- *Py_SetProgramName()*
- *Py_SetPythonHome()*
- Py_SetRecursionLimit()
- *Py_TYPE()*
- *Py_UCS4*
- *Py_UNBLOCK_THREADS*
- Py_UTF8Mode
- *Py_VaBuildValue()*
- *Py_Version*
- *Py_XNewRef()*
- *Py_buffer*
- Py_intptr_t
- *Py_ssize_t*
- Py_uintptr_t
- *allocfunc*
- *binaryfunc*
- *descrgetfunc*
- *descrsetfunc*

- *destructor*
- *getattrfunc*
- *getattrofunc*
- *getbufferproc*
- *getiterfunc*
- *getter*
- *hashfunc*
- *initproc*
- *inquiry*
- *iternextfunc*
- *lenfunc*
- *newfunc*
- *objobjargproc*
- *objobjproc*
- *releasebufferproc*
- *reprfunc*
- *richcmpfunc*
- *setattrfunc*
- *setattrofunc*
- *setter*
- *ssizeargfunc*
- *ssizeobjargproc*
- ssizessizeargfunc
- ssizessizeobjargproc
- symtable
- *ternaryfunc*
- *traverseproc*
- *unaryfunc*
- *vectorcallfunc*
- *visitproc*

BÖLÜM 3

The Very High Level Layer

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are `Py_eval_input`, `Py_file_input`, and `Py_single_input`. These are described following the functions which accept them as parameters.

Note also that several of these functions take `FILE*` parameters. One particular issue which needs to be handled carefully is that the `FILE` structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that `FILE*` parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

int **PyRun_AnyFile**(FILE *fp, const char *filename)

This is a simplified interface to `PyRun_AnyFileExFlags()` below, leaving *closeit* set to `0` and *flags* set to `NULL`.

int **PyRun_AnyFileFlags**(FILE *fp, const char *filename, *PyCompilerFlags* *flags)

This is a simplified interface to `PyRun_AnyFileExFlags()` below, leaving the *closeit* argument set to `0`.

int **PyRun_AnyFileEx**(FILE *fp, const char *filename, int closeit)

This is a simplified interface to `PyRun_AnyFileExFlags()` below, leaving the *flags* argument set to `NULL`.

int **PyRun_AnyFileExFlags**(FILE *fp, const char *filename, int closeit, *PyCompilerFlags* *flags)

If *fp* refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of `PyRun_InteractiveLoop()`, otherwise return the result of `PyRun_SimpleFile()`. *filename* is decoded from the filesystem encoding (`sys.getfilesystemencoding()`). If *filename* is `NULL`, this function uses `"???"` as the filename. If *closeit* is true, the file is closed before `PyRun_SimpleFileExFlags()` returns.

int **PyRun_SimpleString**(const char *command)

This is a simplified interface to `PyRun_SimpleStringFlags()` below, leaving the `PyCompilerFlags`* argument set to `NULL`.

int **PyRun_SimpleStringFlags**(const char *command, *PyCompilerFlags* *flags)

Executes the Python source code from *command* in the `__main__` module according to the *flags* argument. If `__main__` does not already exist, it is created. Returns `0` on success or `-1` if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled `SystemExit` is raised, this function will not return `-1`, but exit the process, as long as *`PyConfig.inspect`* is zero.

int **`PyRun_SimpleFile`**(FILE *fp, const char *filename)

This is a simplified interface to *`PyRun_SimpleFileExFlags()`* below, leaving *closeit* set to `0` and *flags* set to `NULL`.

int **`PyRun_SimpleFileEx`**(FILE *fp, const char *filename, int closeit)

This is a simplified interface to *`PyRun_SimpleFileExFlags()`* below, leaving *flags* set to `NULL`.

int **`PyRun_SimpleFileExFlags`**(FILE *fp, const char *filename, int closeit, *PyCompilerFlags* *flags)

Similar to *`PyRun_SimpleStringFlags()`*, but the Python source code is read from *fp* instead of an in-memory string. *filename* should be the name of the file, it is decoded from *filesystem encoding and error handler*. If *closeit* is true, the file is closed before `PyRun_SimpleFileExFlags()` returns.

Not

On Windows, *fp* should be opened as binary mode (e.g. `fopen(filename, "rb")`). Otherwise, Python may not handle script file with LF line ending correctly.

int **`PyRun_InteractiveOne`**(FILE *fp, const char *filename)

This is a simplified interface to *`PyRun_InteractiveOneFlags()`* below, leaving *flags* set to `NULL`.

int **`PyRun_InteractiveOneFlags`**(FILE *fp, const char *filename, *PyCompilerFlags* *flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using `sys.ps1` and `sys.ps2`. *filename* is decoded from the *filesystem encoding and error handler*.

Returns `0` when the input was executed successfully, `-1` if there was an exception, or an error code from the `errcode.h` include file distributed as part of Python if there was a parse error. (Note that `errcode.h` is not included by `Python.h`, so must be included specifically if needed.)

int **`PyRun_InteractiveLoop`**(FILE *fp, const char *filename)

This is a simplified interface to *`PyRun_InteractiveLoopFlags()`* below, leaving *flags* set to `NULL`.

int **`PyRun_InteractiveLoopFlags`**(FILE *fp, const char *filename, *PyCompilerFlags* *flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using `sys.ps1` and `sys.ps2`. *filename* is decoded from the *filesystem encoding and error handler*. Returns `0` at EOF or a negative number upon failure.

int (***`PyOS_InputHook`**)(void)

Bir parçası Kararlı ABI. Can be set to point to a function with the prototype `int func(void)`. The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the `Modules/_tkinter.c` in the Python source code.

3.12 sürümünde değişti: This function is only called from the *main interpreter*.

char *(***`PyOS_ReadlineFunctionPointer`**)(FILE*, FILE*, const char*)

Can be set to point to a function with the prototype `char *func(FILE *stdin, FILE *stdout, char *prompt)`, overriding the default function used to read a single line of input at the interpreter's prompt. The function is expected to output the string *prompt* if it's not `NULL`, and then read a line of input from the provided standard input file, returning the resulting string. For example, The `readline` module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by *`PyMem_RawMalloc()`* or *`PyMem_RawRealloc()`*, or `NULL` if an error occurred.

3.4 sürümünde değişti: The result must be allocated by *`PyMem_RawMalloc()`* or *`PyMem_RawRealloc()`*, instead of being allocated by *`PyMem_Malloc()`* or *`PyMem_Realloc()`*.

3.12 sürümünde değişti: This function is only called from the *main interpreter*.

PyObject ***PyRun_String**(const char *str, int start, *PyObject* *globals, *PyObject* *locals)

Döndürdüğü değer: Yeni referans. This is a simplified interface to `PyRun_StringFlags()` below, leaving *flags* set to `NULL`.

PyObject ***PyRun_StringFlags**(const char *str, int start, *PyObject* *globals, *PyObject* *locals, *PyCompilerFlags* *flags)

Döndürdüğü değer: Yeni referans. Execute Python source code from *str* in the context specified by the objects *globals* and *locals* with the compiler flags specified by *flags*. *globals* must be a dictionary; *locals* can be any object that implements the mapping protocol. The parameter *start* specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or `NULL` if an exception was raised.

PyObject ***PyRun_File**(FILE *fp, const char *filename, int start, *PyObject* *globals, *PyObject* *locals)

Döndürdüğü değer: Yeni referans. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *closeit* set to `0` and *flags* set to `NULL`.

PyObject ***PyRun_FileEx**(FILE *fp, const char *filename, int start, *PyObject* *globals, *PyObject* *locals, int closeit)

Döndürdüğü değer: Yeni referans. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *flags* set to `NULL`.

PyObject ***PyRun_FileFlags**(FILE *fp, const char *filename, int start, *PyObject* *globals, *PyObject* *locals, *PyCompilerFlags* *flags)

Döndürdüğü değer: Yeni referans. This is a simplified interface to `PyRun_FileExFlags()` below, leaving *closeit* set to `0`.

PyObject ***PyRun_FileExFlags**(FILE *fp, const char *filename, int start, *PyObject* *globals, *PyObject* *locals, int closeit, *PyCompilerFlags* *flags)

Döndürdüğü değer: Yeni referans. Similar to `PyRun_StringFlags()`, but the Python source code is read from *fp* instead of an in-memory string. *filename* should be the name of the file, it is decoded from the *filesystem encoding and error handler*. If *closeit* is true, the file is closed before `PyRun_FileExFlags()` returns.

PyObject ***Py_CompileString**(const char *str, const char *filename, int start)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is a simplified interface to `Py_CompileStringFlags()` below, leaving *flags* set to `NULL`.

PyObject ***Py_CompileStringFlags**(const char *str, const char *filename, int start, *PyCompilerFlags* *flags)

Döndürdüğü değer: Yeni referans. This is a simplified interface to `Py_CompileStringExFlags()` below, with *optimize* set to `-1`.

PyObject ***Py_CompileStringObject**(const char *str, *PyObject* *filename, int start, *PyCompilerFlags* *flags, int optimize)

Döndürdüğü değer: Yeni referans. Parse and compile the Python source code in *str*, returning the resulting code object. The start token is given by *start*; this can be used to constrain the code which can be compiled and should be `Py_eval_input`, `Py_file_input`, or `Py_single_input`. The filename specified by *filename* is used to construct the code object and may appear in tracebacks or `SyntaxError` exception messages. This returns `NULL` if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of `-1` selects the optimization level of the interpreter as given by `-O` options. Explicit levels are `0` (no optimization; `__debug__` is true), `1` (asserts are removed, `__debug__` is false) or `2` (docstrings are removed too).

Added in version 3.4.

PyObject ***Py_CompileStringExFlags**(const char *str, const char *filename, int start, *PyCompilerFlags* *flags, int optimize)

Döndürdüğü değer: Yeni referans. Like `Py_CompileStringObject()`, but *filename* is a byte string decoded from the *filesystem encoding and error handler*.

Added in version 3.2.

PyObject ***PyEval_EvalCode**(*PyObject* *co, *PyObject* *globals, *PyObject* *locals)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is a simplified interface to `PyEval_EvalCodeEx()`, with just the code object, and global and local variables. The other arguments are set to `NULL`.

PyObject ***PyEval_EvalCodeEx**(*PyObject* *co, *PyObject* *globals, *PyObject* *locals, *PyObject* *const *args, int argcount, *PyObject* *const *kws, int kwcount, *PyObject* *const *defs, int defcount, *PyObject* *kwdefs, *PyObject* *closure)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for *keyword-only* arguments and a closure tuple of cells.

PyObject ***PyEval_EvalFrame**(*PyFrameObject* *f)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Evaluate an execution frame. This is a simplified interface to `PyEval_EvalFrameEx()`, for backward compatibility.

PyObject ***PyEval_EvalFrameEx**(*PyFrameObject* *f, int throwflag)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame *f* is executed, interpreting bytecode and executing calls as needed. The additional *throwflag* parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the `throw()` methods of generator objects.

3.4 sürümünde değişti: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

int **PyEval_MergeCompilerFlags**(*PyCompilerFlags* *cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

int **Py_eval_input**

The start symbol from the Python grammar for isolated expressions; for use with `Py_CompileString()`.

int **Py_file_input**

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with `Py_CompileString()`. This is the symbol to use when compiling arbitrarily long Python source code.

int **Py_single_input**

The start symbol from the Python grammar for a single statement; for use with `Py_CompileString()`. This is the symbol used for the interactive interpreter loop.

struct **PyCompilerFlags**

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as `int flags`, and in cases where code is being executed, it is passed as `PyCompilerFlags *flags`. In this case, `from __future__ import` can modify *flags*.

Whenever `PyCompilerFlags *flags` is `NULL`, `cf_flags` is treated as equal to `0`, and any modification due to `from __future__ import` is discarded.

int **cf_flags**

Compiler flags.

int **cf_feature_version**

cf_feature_version is the minor Python version. It should be initialized to `PY_MINOR_VERSION`.

The field is ignored by default, it is used if and only if `PyCF_ONLY_AST` flag is set in `cf_flags`.

3.8 sürümünde değişti: Added *cf_feature_version* field.

The available compiler flags are accessible as macros:

PyCF_ALLOW_TOP_LEVEL_AWAIT

PyCF_ONLY_AST

PyCF_OPTIMIZED_AST

PyCF_TYPE_COMMENTS

See compiler flags in documentation of the `ast` Python module, which exports these constants under the same names.

The "`PyCF`" flags above can be combined with "`CO_FUTURE`" flags such as *`CO_FUTURE_ANNOTATIONS`* to enable features normally selectable using future statements. See *Code Object Flags* for a complete list.

BÖLÜM 4

Reference Counting

The functions and macros in this section are used for managing reference counts of Python objects.

Py_ssize_t **Py_REFCNT**(*PyObject* *o)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Get the reference count of the Python object *o*.

Note that the returned value may not actually reflect how many references to the object are actually held. For example, some objects are *immortal* and have a very high refcount that does not reflect the actual number of references. Consequently, do not rely on the returned value to be accurate, other than a value of 0 or 1.

Use the `Py_SET_REFCNT()` function to set an object reference count.

Not

On *free threaded* builds of Python, returning 1 isn't sufficient to determine if it's safe to treat *o* as having no access by other threads. Use `PyUnstable_Object_IsUniquelyReferenced()` for that instead.

See also the function `PyUnstable_Object_IsUniqueReferencedTemporary()`.

3.10 sürümünde değişti: `Py_REFCNT()` is changed to the inline static function.

3.11 sürümünde değişti: The parameter type is no longer `const PyObject*`.

void **Py_SET_REFCNT**(*PyObject* *o, *Py_ssize_t* refcnt)

Set the object *o* reference counter to *refcnt*.

On Python build with Free Threading, if *refcnt* is larger than `UINT32_MAX`, the object is made *immortal*.

This function has no effect on *immortal* objects.

Added in version 3.9.

3.12 sürümünde değişti: Immortal objects are not modified.

void **Py_INCREF**(*PyObject* *o)

Indicate taking a new *strong reference* to object *o*, indicating it is in use and should not be destroyed.

This function has no effect on *immortal* objects.

This function is usually used to convert a *borrowed reference* to a *strong reference* in-place. The `Py_NewRef()` function can be used to create a new *strong reference*.

When done using the object, release is by calling `Py_DECREF()`.

The object must not be `NULL`; if you aren't sure that it isn't `NULL`, use *Py_XINCREF()*.

Do not expect this function to actually modify *o* in any way. For at least **some objects**, this function has no effect.

3.12 sürümünde değişti: Immortal objects are not modified.

void **Py_XINCREF**(*PyObject* *o)

Similar to *Py_INCREF()*, but the object *o* can be `NULL`, in which case this has no effect.

See also *Py_XNewRef()*.

PyObject ***Py_NewRef**(*PyObject* *o)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Create a new *strong reference* to an object: call *Py_INCREF()* on *o* and return the object *o*.

When the *strong reference* is no longer needed, *Py_DECREF()* should be called on it to release the reference.

The object *o* must not be `NULL`; use *Py_XNewRef()* if *o* can be `NULL`.

For example:

```
Py_INCREF(obj);
self->attr = obj;
```

can be written as:

```
self->attr = Py_NewRef(obj);
```

See also *Py_INCREF()*.

Added in version 3.10.

PyObject ***Py_XNewRef**(*PyObject* *o)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Similar to *Py_NewRef()*, but the object *o* can be NULL.

If the object *o* is `NULL`, the function just returns `NULL`.

Added in version 3.10.

void **Py_DECREF**(*PyObject* *o)

Release a *strong reference* to object *o*, indicating the reference is no longer used.

This function has no effect on *immortal* objects.

Once the last *strong reference* is released (i.e. the object's reference count reaches 0), the object's type's deallocation function (which must not be `NULL`) is invoked.

This function is usually used to delete a *strong reference* before exiting its scope.

The object must not be `NULL`; if you aren't sure that it isn't `NULL`, use *Py_XDECREF()*.

Do not expect this function to actually modify *o* in any way. For at least **some objects**, this function has no effect.

Uyarı

The deallocation function can cause arbitrary Python code to be invoked (e.g. when a class instance with a `__del__()` method is deallocated). While exceptions in such code are not propagated, the executed code has free access to all Python global variables. This means that any object that is reachable from a global variable should be in a consistent state before *Py_DECREF()* is invoked. For example, code to delete an object from a list should copy a reference to the deleted object in a temporary variable, update the list data structure, and then call *Py_DECREF()* for the temporary variable.

3.12 sürümünde değişti: Immortal objects are not modified.

void **Py_XDECREF**(*PyObject* *o)

Similar to `Py_DECREF()`, but the object *o* can be `NULL`, in which case this has no effect. The same warning from `Py_DECREF()` applies here as well.

void **Py_CLEAR**(*PyObject* *o)

Release a *strong reference* for object *o*. The object may be `NULL`, in which case the macro has no effect; otherwise the effect is the same as for `Py_DECREF()`, except that the argument is also set to `NULL`. The warning for `Py_DECREF()` does not apply with respect to the object passed because the macro carefully uses a temporary variable and sets the argument to `NULL` before releasing the reference.

It is a good idea to use this macro whenever releasing a reference to an object that might be traversed during garbage collection.

3.12 sürümünde değişti: The macro argument is now only evaluated once. If the argument has side effects, these are no longer duplicated.

void **Py_IncRef**(*PyObject* *o)

Bir parçası Kararlı ABI. Indicate taking a new *strong reference* to object *o*. A function version of `Py_XINCREF()`. It can be used for runtime dynamic embedding of Python.

void **Py_DecRef**(*PyObject* *o)

Bir parçası Kararlı ABI. Release a *strong reference* to object *o*. A function version of `Py_XDECREF()`. It can be used for runtime dynamic embedding of Python.

Py_SETREF(dst, src)

Macro safely releasing a *strong reference* to object *dst* and setting *dst* to *src*.

As in case of `Py_CLEAR()`, "the obvious" code can be deadly:

```
Py_DECREF(dst);
dst = src;
```

The safe way is:

```
Py_SETREF(dst, src);
```

That arranges to set *dst* to *src before* releasing the reference to the old value of *dst*, so that any code triggered as a side-effect of *dst* getting torn down no longer believes *dst* points to a valid object.

Added in version 3.6.

3.12 sürümünde değişti: The macro arguments are now only evaluated once. If an argument has side effects, these are no longer duplicated.

Py_XSETREF(dst, src)

Variant of `Py_SETREF` macro that uses `Py_XDECREF()` instead of `Py_DECREF()`.

Added in version 3.6.

3.12 sürümünde değişti: The macro arguments are now only evaluated once. If an argument has side effects, these are no longer duplicated.

BÖLÜM 5

Exception Handling

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX `errno` variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually `NULL` if they are supposed to return a pointer, or `-1` if they return an integer (exception: the `PyArg_*` functions return `1` for success and `0` for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be `NULL` if non-set (although some combinations are forbidden, for example you can't have a non-`NULL` traceback if the exception type is `NULL`).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

Not

The error indicator is **not** the result of `sys.exc_info()`. The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

5.1 Printing and clearing

void **`PyErr_Clear`**()

Bir parçası Kararlı ABI. Clear the error indicator. If the error indicator is not set, there is no effect.

void **`PyErr_PrintEx`**(int set_sys_last_vars)

Bir parçası Kararlı ABI. Print a standard traceback to `sys.stderr` and clear the error indicator. **Unless** the error is a `SystemExit`, in that case no traceback is printed and the Python process will exit with the error code specified by the `SystemExit` instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If *set_sys_last_vars* is nonzero, the variable `sys.last_exc` is set to the printed exception. For backwards compatibility, the deprecated variables `sys.last_type`, `sys.last_value` and `sys.last_traceback` are also set to the type, value and traceback of this exception, respectively.

3.12 sürümünde değişti: The setting of `sys.last_exc` was added.

void **PyErr_Print**()

Bir parçası Kararlı ABI. Alias for `PyErr_PrintEx(1)`.

void **PyErr_WriteUnraisable**(*PyObject* *obj)

Bir parçası Kararlı ABI. Call `sys.unraisablehook()` using the current exception and *obj* argument.

This utility function prints a warning message to `sys.stderr` when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an `__del__()` method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message. If *obj* is `NULL`, only the traceback is printed.

An exception must be set when calling this function.

3.4 sürümünde değişti: Print a traceback. Print only traceback if *obj* is `NULL`.

3.8 sürümünde değişti: Use `sys.unraisablehook()`.

void **PyErr_FormatUnraisable**(const char *format, ...)

Similar to *PyErr_WriteUnraisable()*, but the *format* and subsequent parameters help format the warning message; they have the same meaning and values as in *PyUnicode_FromFormat()*. `PyErr_WriteUnraisable(obj)` is roughly equivalent to `PyErr_FormatUnraisable("Exception ignored in: %R", obj)`. If *format* is `NULL`, only the traceback is printed.

Added in version 3.13.

void **PyErr_DisplayException**(*PyObject* *exc)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Print the standard traceback display of `exc` to `sys.stderr`, including chained exceptions and notes.

Added in version 3.12.

5.2 Raising exceptions

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a `NULL` pointer for use in a `return` statement.

void **PyErr_SetString**(*PyObject* *type, const char *message)

Bir parçası Kararlı ABI. This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. *PyExc_RuntimeError*. You need not create a new *strong reference* to it (e.g. with *Py_INCREF()*). The second argument is an error message; it is decoded from `'utf-8'`.

void **PyErr_SetObject**(*PyObject* *type, *PyObject* *value)

Bir parçası Kararlı ABI. This function is similar to *PyErr_SetString()* but lets you specify an arbitrary Python object for the "value" of the exception.

PyObject ***PyErr_Format**(*PyObject* *exception, const char *format, ...)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. This function sets the error indicator and returns `NULL`. *exception* should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in *PyUnicode_FromFormat()*. *format* is an ASCII-encoded string.

PyObject ***PyErr_FormatV**(*PyObject* *exception, const char *format, va_list vargs)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *3.5 sürümünden beri.* Same as *PyErr_Format()*, but taking a `va_list` argument rather than a variable number of arguments.

Added in version 3.5.

void **PyErr_SetNone**(*PyObject* *type)

Bir parçası Kararlı ABI. This is a shorthand for `PyErr_SetObject(type, Py_None)`.

int **PyErr_BadArgument**()

Bir parçası Kararlı ABI. This is a shorthand for `PyErr_SetString(PyExc_TypeError, message)`, where *message* indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

PyObject ***PyErr_NoMemory**()

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. This is a shorthand for `PyErr_SetNone(PyExc_MemoryError)`; it returns `NULL` so an object allocation function can write `return PyErr_NoMemory();` when it runs out of memory.

PyObject ***PyErr_SetFromErrno**(*PyObject* *type)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable `errno`. It constructs a tuple object whose first item is the integer `errno` value and whose second item is the corresponding error message (gotten from `strerror()`), and then calls `PyErr_SetObject(type, object)`. On Unix, when the `errno` value is `EINTR`, indicating an interrupted system call, this calls *PyErr_CheckSignals()*, and if that set the error indicator, leaves it set to that. The function always returns `NULL`, so a wrapper function around a system call can write `return PyErr_SetFromErrno(type);` when the system call returns an error.

PyObject ***PyErr_SetFromErrnoWithFilenameObject**(*PyObject* *type, *PyObject* *filenameObject)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. Similar to *PyErr_SetFromErrno()*, with the additional behavior that if *filenameObject* is not `NULL`, it is passed to the constructor of *type* as a third parameter. In the case of `OSError` exception, this is used to define the `filename` attribute of the exception instance.

PyObject ***PyErr_SetFromErrnoWithFilenameObjects**(*PyObject* *type, *PyObject* *filenameObject, *PyObject* *filenameObject2)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Similar to *PyErr_SetFromErrnoWithFilenameObject()*, but takes a second filename object, for raising errors when a function that takes two filenames fails.

Added in version 3.4.

PyObject ***PyErr_SetFromErrnoWithFilename**(*PyObject* *type, const char *filename)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. Similar to *PyErr_SetFromErrnoWithFilenameObject()*, but the filename is given as a C string. *filename* is decoded from the *filesystem encoding and error handler*.

PyObject ***PyErr_SetFromWindowsErr**(int ierr)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* This is a convenience function to raise `OSError`. If called with *ierr* of `0`, the error code returned by a call to `GetLastError()` is used instead. It calls the Win32 function `FormatMessage()` to retrieve the Windows description of error code given by *ierr* or `GetLastError()`, then it constructs a `OSError` object with the `winerror` attribute set to the error code, the `strerror` attribute set to the corresponding error message (gotten from `FormatMessage()`), and then calls `PyErr_SetObject(PyExc_OSError, object)`. This function always returns `NULL`.

Availability: Windows.

PyObject ***PyErr_SetExcFromWindowsErr**(*PyObject* *type, int ierr)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to *PyErr_SetFromWindowsErr()*, with an additional parameter specifying the exception type to be raised.

Availability: Windows.

PyObject ***PyErr_SetFromWindowsErrWithFilename**(int ierr, const char *filename)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to `PyErr_SetFromWindowsErr()`, with the additional behavior that if *filename* is not `NULL`, it is decoded from the filesystem encoding (`os.fsdecode()`) and passed to the constructor of `OSError` as a third parameter to be used to define the `filename` attribute of the exception instance.

Availability: Windows.

PyObject ***PyErr_SetExcFromWindowsErrWithFilenameObject**(*PyObject* *type, int ierr, *PyObject* *filename)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to `PyErr_SetExcFromWindowsErr()`, with the additional behavior that if *filename* is not `NULL`, it is passed to the constructor of `OSError` as a third parameter to be used to define the `filename` attribute of the exception instance.

Availability: Windows.

PyObject ***PyErr_SetExcFromWindowsErrWithFilenameObjects**(*PyObject* *type, int ierr, *PyObject* *filename, *PyObject* *filename2)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to `PyErr_SetExcFromWindowsErrWithFilenameObject()`, but accepts a second filename object.

Availability: Windows.

Added in version 3.4.

PyObject ***PyErr_SetExcFromWindowsErrWithFilename**(*PyObject* *type, int ierr, const char *filename)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to `PyErr_SetFromWindowsErrWithFilename()`, with an additional parameter specifying the exception type to be raised.

Availability: Windows.

PyObject ***PyErr_SetImportError**(*PyObject* *msg, *PyObject* *name, *PyObject* *path)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *3.7 sürümünden beri.* This is a convenience function to raise `ImportError`. *msg* will be set as the exception's message string. *name* and *path*, both of which can be `NULL`, will be set as the `ImportError`'s respective `name` and `path` attributes.

Added in version 3.3.

PyObject ***PyErr_SetImportErrorSubclass**(*PyObject* *exception, *PyObject* *msg, *PyObject* *name, *PyObject* *path)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI *3.6 sürümünden beri.* Much like `PyErr_SetImportError()` but this function allows for specifying a subclass of `ImportError` to raise.

Added in version 3.6.

void **PyErr_SyntaxLocationObject**(*PyObject* *filename, int lineno, int col_offset)

Set file, line, and offset information for the current exception. If the current exception is not a `SyntaxError`, then it sets additional attributes, which make the exception printing subsystem think the exception is a `SyntaxError`.

Added in version 3.4.

void **PyErr_SyntaxLocationEx**(const char *filename, int lineno, int col_offset)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Like `PyErr_SyntaxLocationObject()`, but *filename* is a byte string decoded from the *filesystem encoding and error handler*.

Added in version 3.2.

void **PyErr_SyntaxLocation**(const char *filename, int lineno)

Bir parçası Kararlı ABI. Like `PyErr_SyntaxLocationEx()`, but the *col_offset* parameter is omitted.

void **PyErr_BadInternalCall**()

Bir parçası Kararlı ABI. This is a shorthand for `PyErr_SetString(PyExc_SystemError, message)`, where *message* indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python `warnings` module. They normally print a warning message to *sys.stderr*; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is `0` if no exception is raised, or `-1` if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example, *Py_DECREF()* owned references and return an error value).

int **PyErr_WarnEx**(*PyObject* *category, const char *message, *Py_ssize_t* stack_level)

Bir parçası Kararlı ABI. Issue a warning message. The *category* argument is a warning category (see below) or `NULL`; the *message* argument is a UTF-8 encoded string. *stack_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack_level* of 1 is the function calling *PyErr_WarnEx()*, 2 is the function above that, and so forth.

Warning categories must be subclasses of *PyExc_Warning*; *PyExc_Warning* is a subclass of *PyExc_Exception*; the default warning category is *PyExc_RuntimeWarning*. The standard Python warning categories are available as global variables whose names are enumerated at *Warning types*.

For information about warning control, see the documentation for the `warnings` module and the `-W` option in the command line documentation. There is no C API for warning control.

int **PyErr_WarnExplicitObject**(*PyObject* *category, *PyObject* *message, *PyObject* *filename, int lineno, *PyObject* *module, *PyObject* *registry)

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function `warnings.warn_explicit()`; see there for more information. The *module* and *registry* arguments may be set to `NULL` to get the default effect described there.

Added in version 3.4.

int **PyErr_WarnExplicit**(*PyObject* *category, const char *message, const char *filename, int lineno, const char *module, *PyObject* *registry)

Bir parçası Kararlı ABI. Similar to *PyErr_WarnExplicitObject()* except that *message* and *module* are UTF-8 encoded strings, and *filename* is decoded from the *filesystem encoding and error handler*.

int **PyErr_WarnFormat**(*PyObject* *category, *Py_ssize_t* stack_level, const char *format, ...)

Bir parçası Kararlı ABI. Function similar to *PyErr_WarnEx()*, but use *PyUnicode_FromFormat()* to format the warning message. *format* is an ASCII-encoded string.

Added in version 3.2.

int **PyErr_ResourceWarning**(*PyObject* *source, *Py_ssize_t* stack_level, const char *format, ...)

Bir parçası Kararlı ABI *3.6 sürümünden beri.* Function similar to *PyErr_WarnFormat()*, but *category* is `ResourceWarning` and it passes *source* to `warnings.WarningMessage`.

Added in version 3.6.

5.4 Querying the error indicator

PyObject ***PyErr_Occurred**()

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Test whether the error indicator is set. If set, return the exception *type* (the first argument to the last call to one of the `PyErr_Set*` functions or to *PyErr_Restore()*). If not set, return `NULL`. You do not own a reference to the return value, so you do not need to *Py_DECREF()* it.

The caller must have an *attached thread state*.

> **Not**
>
> Do not compare the return value to a specific exception; use `PyErr_ExceptionMatches()` instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

int **PyErr_ExceptionMatches**(*PyObject* *exc)

Bir parçası Kararlı ABI. Equivalent to `PyErr_GivenExceptionMatches(PyErr_Occurred(), exc)`. This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

int **PyErr_GivenExceptionMatches**(*PyObject* *given, *PyObject* *exc)

Bir parçası Kararlı ABI. Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

PyObject ***PyErr_GetRaisedException**(void)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.12 sürümünden beri.* Return the exception currently being raised, clearing the error indicator at the same time. Return `NULL` if the error indicator is not set.

This function is used by code that needs to catch exceptions, or code that needs to save and restore the error indicator temporarily.

For example:

```
{
   PyObject *exc = PyErr_GetRaisedException();

   /* ... code that might produce other errors ... */

   PyErr_SetRaisedException(exc);
}
```

> **Ayrıca bakınız**
>
> `PyErr_GetHandledException()`, to save the exception currently being handled.

Added in version 3.12.

void **PyErr_SetRaisedException**(*PyObject* *exc)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Set *exc* as the exception currently being raised, clearing the existing exception if one is set.

> **Uyarı**
>
> This call steals a reference to *exc*, which must be a valid exception.

Added in version 3.12.

void **PyErr_Fetch**(*PyObject* **ptype, *PyObject* **pvalue, *PyObject* **ptraceback)

Bir parçası Kararlı ABI. 3.12 sürümünden beri kullanım dışı: Use `PyErr_GetRaisedException()` instead.

Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to `NULL`. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be `NULL` even when the type object is not.

Not

This function is normally only used by legacy code that needs to catch exceptions or save and restore the error indicator temporarily.

For example:

```
{
   PyObject *type, *value, *traceback;
   PyErr_Fetch(&type, &value, &traceback);

   /* ... code that might produce other errors ... */

   PyErr_Restore(type, value, traceback);
}
```

void **PyErr_Restore**(*PyObject* *type, *PyObject* *value, *PyObject* *traceback)

Bir parçası Kararlı ABI. 3.12 sürümünden beri kullanım dışı: Use `PyErr_SetRaisedException()` instead.

Set the error indicator from the three objects, *type*, *value*, and *traceback*, clearing the existing exception if one is set. If the objects are `NULL`, the error indicator is cleared. Do not pass a `NULL` type and non-`NULL` value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

Not

This function is normally only used by legacy code that needs to save and restore the error indicator temporarily. Use `PyErr_Fetch()` to save the current error indicator.

void **PyErr_NormalizeException**(*PyObject* **exc, *PyObject* **val, *PyObject* **tb)

Bir parçası Kararlı ABI. 3.12 sürümünden beri kullanım dışı: Use `PyErr_GetRaisedException()` instead, to avoid any possible de-normalization.

Under certain circumstances, the values returned by `PyErr_Fetch()` below can be "unnormalized", meaning that `*exc` is a class object but `*val` is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

Not

This function *does not* implicitly set the `__traceback__` attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
  PyException_SetTraceback(val, tb);
}
```

PyObject ***PyErr_GetHandledException**(void)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Retrieve the active exception instance, as would be returned by `sys.exception()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns a new reference to the exception or `NULL`. Does not modify the interpreter's exception state.

> **Not**
>
> This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use *PyErr_SetHandledException()* to restore or clear the exception state.

Added in version 3.11.

void **PyErr_SetHandledException**(*PyObject* *exc)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Set the active exception, as known from `sys.exception()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. To clear the exception state, pass `NULL`.

> **Not**
>
> This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use *PyErr_GetHandledException()* to get the exception state.

Added in version 3.11.

void **PyErr_GetExcInfo**(*PyObject* **ptype, *PyObject* **pvalue, *PyObject* **ptraceback)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Retrieve the old-style representation of the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be `NULL`. Does not modify the exception info state. This function is kept for backwards compatibility. Prefer using *PyErr_GetHandledException()*.

> **Not**
>
> This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use *PyErr_SetExcInfo()* to restore or clear the exception state.

Added in version 3.3.

void **PyErr_SetExcInfo**(*PyObject* *type, *PyObject* *value, *PyObject* *traceback)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Set the exception info, as known from `sys.exc_info()`. This refers to an exception that was *already caught*, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass `NULL` for all three arguments. This function is kept for backwards compatibility. Prefer using *PyErr_SetHandledException()*.

> **Not**
>
> This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use *PyErr_GetExcInfo()* to read the exception state.

Added in version 3.3.

3.11 sürümünde değişti: The `type` and `traceback` arguments are no longer used and can be NULL. The interpreter now derives them from the exception instance (the `value` argument). The function still steals references of all three arguments.

5.5 Signal Handling

int **PyErr_CheckSignals**()

Bir parçası Kararlı ABI. This function interacts with Python's signal handling.

If the function is called from the main thread and under the main Python interpreter, it checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the `signal` module is supported, this can invoke a signal handler written in Python.

The function attempts to handle all pending signals, and then returns `0`. However, if a Python signal handler raises an exception, the error indicator is set and the function returns `-1` immediately (such that other pending signals may not have been handled yet: they will be on the next *PyErr_CheckSignals()* invocation).

If the function is called from a non-main thread, or under a non-main Python interpreter, it does nothing and returns `0`.

This function can be called by long-running C code that wants to be interruptible by user requests (such as by pressing Ctrl-C).

> **Not**
>
> The default Python signal handler for `SIGINT` raises the `KeyboardInterrupt` exception.

void **PyErr_SetInterrupt**()

Bir parçası Kararlı ABI. Simulate the effect of a `SIGINT` signal arriving. This is equivalent to `PyErr_SetInterruptEx(SIGINT)`.

> **Not**
>
> This function is async-signal-safe. It can be called without an *attached thread state* and from a C signal handler.

int **PyErr_SetInterruptEx**(int signum)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Simulate the effect of a signal arriving. The next time *PyErr_CheckSignals()* is called, the Python signal handler for the given signal number will be called.

This function can be called by C code that sets up its own signal handling and wants Python signal handlers to be invoked as expected when an interruption is requested (for example when the user presses Ctrl-C to interrupt an operation).

If the given signal isn't handled by Python (it was set to `signal.SIG_DFL` or `signal.SIG_IGN`), it will be ignored.

If *signum* is outside of the allowed range of signal numbers, `-1` is returned. Otherwise, `0` is returned. The error indicator is never changed by this function.

> **Not**
>
> This function is async-signal-safe. It can be called without an *attached thread state* and from a C signal handler.

Added in version 3.10.

int **PySignal_SetWakeupFd**(int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. *fd* must be non-blocking. It returns the previous such file descriptor.

The value `-1` disables the feature; this is the initial state. This is equivalent to `signal.set_wakeup_fd()` in Python, but without any error checking. *fd* should be a valid file descriptor. The function should only be called from the main thread.

3.5 sürümünde değişti: On Windows, the function now also supports socket handles.

5.6 Exception Classes

PyObject ***PyErr_NewException**(const char *name, *PyObject* *base, *PyObject* *dict)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This utility function creates and returns a new exception class. The *name* argument must be the name of the new exception, a C string of the form `module.classname`. The *base* and *dict* arguments are normally `NULL`. This creates a class object derived from `Exception` (accessible in C as `PyExc_Exception`).

The `__module__` attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

PyObject ***PyErr_NewExceptionWithDoc**(const char *name, const char *doc, *PyObject* *base, *PyObject* *dict)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Same as `PyErr_NewException()`, except that the new exception class can easily be given a docstring: If *doc* is non-`NULL`, it will be used as the docstring for the exception class.

Added in version 3.2.

int **PyExceptionClass_Check**(*PyObject* *ob)

Return non-zero if *ob* is an exception class, zero otherwise. This function always succeeds.

const char ***PyExceptionClass_Name**(*PyObject* *ob)

Bir parçası Kararlı ABI *3.8 sürümünden beri.* Return `tp_name` of the exception class *ob*.

5.7 Exception Objects

PyObject ***PyException_GetTraceback**(*PyObject* *ex)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the traceback associated with the exception as a new reference, as accessible from Python through the `__traceback__` attribute. If there is no traceback associated, this returns `NULL`.

int **PyException_SetTraceback**(*PyObject* *ex, *PyObject* *tb)

Bir parçası Kararlı ABI. Set the traceback associated with the exception to *tb*. Use `Py_None` to clear it.

PyObject ***PyException_GetContext**(*PyObject* *ex)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the context (another exception instance during whose handling *ex* was raised) associated with the exception as a new reference, as accessible from Python through the `__context__` attribute. If there is no context associated, this returns `NULL`.

void **PyException_SetContext**(*PyObject* *ex, *PyObject* *ctx)

Bir parçası Kararlı ABI. Set the context associated with the exception to *ctx*. Use `NULL` to clear it. There is no type check to make sure that *ctx* is an exception instance. This steals a reference to *ctx*.

PyObject ***PyException_GetCause**(*PyObject* *ex)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the cause (either an exception instance, or `None`, set by `raise ... from ...`) associated with the exception as a new reference, as accessible from Python through the `__cause__` attribute.

void **PyException_SetCause**(*PyObject* *ex, *PyObject* *cause)

Bir parçası Kararlı ABI. Set the cause associated with the exception to *cause*. Use `NULL` to clear it. There is no type check to make sure that *cause* is either an exception instance or `None`. This steals a reference to *cause*.

The `__suppress_context__` attribute is implicitly set to `True` by this function.

PyObject ***PyException_GetArgs**(*PyObject* *ex)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.12 sürümünden beri.* Return `args` of exception *ex*.

void ***PyException_SetArgs**(*PyObject* *ex, *PyObject* *args)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Set `args` of exception *ex* to *args*.

PyObject ***PyUnstable_Exc_PrepReraiseStar**(*PyObject* *orig, *PyObject* *excs)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Implement part of the interpreter's implementation of `except*`. *orig* is the original exception that was caught, and *excs* is the list of the exceptions that need to be raised. This list contains the unhandled part of *orig*, if any, as well as the exceptions that were raised from the `except*` clauses (so they have a different traceback from *orig*) and those that were reraised (and have the same traceback as *orig*). Return the `ExceptionGroup` that needs to be reraised in the end, or `None` if there is nothing to reraise.

Added in version 3.12.

5.8 Unicode Exception Objects

The following functions are used to create and modify Unicode exceptions from C.

PyObject ***PyUnicodeDecodeError_Create**(const char *encoding, const char *object, *Py_ssize_t* length, *Py_ssize_t* start, *Py_ssize_t* end, const char *reason)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a `UnicodeDecodeError` object with the attributes *encoding*, *object*, *length*, *start*, *end* and *reason*. *encoding* and *reason* are UTF-8 encoded strings.

PyObject ***PyUnicodeDecodeError_GetEncoding**(*PyObject* *exc)

PyObject ***PyUnicodeEncodeError_GetEncoding**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the *encoding* attribute of the given exception object.

PyObject ***PyUnicodeDecodeError_GetObject**(*PyObject* *exc)

PyObject ***PyUnicodeEncodeError_GetObject**(*PyObject* *exc)

PyObject ***PyUnicodeTranslateError_GetObject**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the *object* attribute of the given exception object.

int ***PyUnicodeDecodeError_GetStart**(*PyObject* *exc, *Py_ssize_t* *start)

int ***PyUnicodeEncodeError_GetStart**(*PyObject* *exc, *Py_ssize_t* *start)

int ***PyUnicodeTranslateError_GetStart**(*PyObject* *exc, *Py_ssize_t* *start)

Bir parçası Kararlı ABI. Get the *start* attribute of the given exception object and place it into **start*. *start* must not be `NULL`. Return `0` on success, `-1` on failure.

If the `UnicodeError.object` is an empty sequence, the resulting *start* is `0`. Otherwise, it is clipped to `[0, len(object) - 1]`.

Ayrıca bakınız

`UnicodeError.start`

int ***PyUnicodeDecodeError_SetStart**(*PyObject* *exc, *Py_ssize_t* start)

int ***PyUnicodeEncodeError_SetStart**(*PyObject* *exc, *Py_ssize_t* start)

int **PyUnicodeTranslateError_SetStart**(*PyObject* *exc, *Py_ssize_t* start)

Bir parçası Kararlı ABI. Set the *start* attribute of the given exception object to *start*. Return `0` on success, `-1` on failure.

> **Not**
>
> While passing a negative *start* does not raise an exception, the corresponding getters will not consider it as a relative offset.

int **PyUnicodeDecodeError_GetEnd**(*PyObject* *exc, *Py_ssize_t* *end)

int **PyUnicodeEncodeError_GetEnd**(*PyObject* *exc, *Py_ssize_t* *end)

int **PyUnicodeTranslateError_GetEnd**(*PyObject* *exc, *Py_ssize_t* *end)

Bir parçası Kararlı ABI. Get the *end* attribute of the given exception object and place it into **end*. *end* must not be `NULL`. Return `0` on success, `-1` on failure.

If the `UnicodeError.object` is an empty sequence, the resulting *end* is `0`. Otherwise, it is clipped to `[1, len(object)]`.

int **PyUnicodeDecodeError_SetEnd**(*PyObject* *exc, *Py_ssize_t* end)

int **PyUnicodeEncodeError_SetEnd**(*PyObject* *exc, *Py_ssize_t* end)

int **PyUnicodeTranslateError_SetEnd**(*PyObject* *exc, *Py_ssize_t* end)

Bir parçası Kararlı ABI. Set the *end* attribute of the given exception object to *end*. Return `0` on success, `-1` on failure.

> **Ayrıca bakınız**
>
> `UnicodeError.end`

PyObject ***PyUnicodeDecodeError_GetReason**(*PyObject* *exc)

PyObject ***PyUnicodeEncodeError_GetReason**(*PyObject* *exc)

PyObject ***PyUnicodeTranslateError_GetReason**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the *reason* attribute of the given exception object.

int **PyUnicodeDecodeError_SetReason**(*PyObject* *exc, const char *reason)

int **PyUnicodeEncodeError_SetReason**(*PyObject* *exc, const char *reason)

int **PyUnicodeTranslateError_SetReason**(*PyObject* *exc, const char *reason)

Bir parçası Kararlı ABI. Set the *reason* attribute of the given exception object to *reason*. Return `0` on success, `-1` on failure.

5.9 Recursion Control

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically). They are also not needed for *tp_call* implementations because the *call protocol* takes care of recursion handling.

int **Py_EnterRecursiveCall**(const char *where)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Marks a point where a recursive C-level call is about to be performed.

The function then checks if the stack limit is reached. If this is the case, a `RecursionError` is set and a nonzero value is returned. Otherwise, zero is returned.

where should be a UTF-8 encoded string such as `" in instance check"` to be concatenated to the `RecursionError` message caused by the recursion depth limit.

3.9 sürümünde değişti: This function is now also available in the *limited API*.

void **Py_LeaveRecursiveCall**(void)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Ends a `Py_EnterRecursiveCall()`. Must be called once for each *successful* invocation of `Py_EnterRecursiveCall()`.

3.9 sürümünde değişti: This function is now also available in the *limited API*.

Properly implementing `tp_repr` for container types requires special recursion handling. In addition to protecting the stack, `tp_repr` also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to `reprlib.recursive_repr()`.

int **Py_ReprEnter**(*PyObject* *object)

Bir parçası Kararlı ABI. Called at the beginning of the `tp_repr` implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the `tp_repr` implementation should return a string object indicating a cycle. As examples, `dict` objects return `{...}` and `list` objects return `[...]`.

The function will return a negative integer if the recursion limit is reached. In that case the `tp_repr` implementation should typically return `NULL`.

Otherwise, the function returns zero and the `tp_repr` implementation can continue normally.

void **Py_ReprLeave**(*PyObject* *object)

Bir parçası Kararlı ABI. Ends a `Py_ReprEnter()`. Must be called once for each invocation of `Py_ReprEnter()` that returns zero.

5.10 Exception and warning types

All standard Python exceptions and warning categories are available as global variables whose names are `PyExc_` followed by the Python exception name. These have the type `PyObject*`; they are all class objects.

For completeness, here are all the variables:

5.10.1 Exception types

C name	Python name
PyObject ***PyExc_BaseException** *Bir parçası* Kararlı ABI.	`BaseException`
PyObject ***PyExc_BaseExceptionGroup** *Bir parçası* Kararlı ABI *3.11 sürümünden beri.*	`BaseExceptionGroup`
PyObject ***PyExc_Exception** *Bir parçası* Kararlı ABI.	`Exception`
PyObject ***PyExc_ArithmeticError** *Bir parçası* Kararlı ABI.	`ArithmeticError`
PyObject ***PyExc_AssertionError** *Bir parçası* Kararlı ABI.	`AssertionError`

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

C name	Python name
PyObject ***PyExc_AttributeError** *Bir parçası Kararlı ABI.*	`AttributeError`
PyObject ***PyExc_BlockingIOError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`BlockingIOError`
PyObject ***PyExc_BrokenPipeError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`BrokenPipeError`
PyObject ***PyExc_BufferError** *Bir parçası Kararlı ABI.*	`BufferError`
PyObject ***PyExc_ChildProcessError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`ChildProcessError`
PyObject ***PyExc_ConnectionAbortedError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`ConnectionAbortedError`
PyObject ***PyExc_ConnectionError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`ConnectionError`
PyObject ***PyExc_ConnectionRefusedError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`ConnectionRefusedError`
PyObject ***PyExc_ConnectionResetError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`ConnectionResetError`
PyObject ***PyExc_EOFError** *Bir parçası Kararlı ABI.*	`EOFError`
PyObject ***PyExc_FileExistsError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`FileExistsError`
PyObject ***PyExc_FileNotFoundError** *Bir parçası Kararlı ABI 3.7 sürümünden beri.*	`FileNotFoundError`
PyObject ***PyExc_FloatingPointError** *Bir parçası Kararlı ABI.*	`FloatingPointError`

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

C name	Python name
PyObject ***PyExc_GeneratorExit** *Bir parçası* Kararlı ABI.	`GeneratorExit`
PyObject ***PyExc_ImportError** *Bir parçası* Kararlı ABI.	`ImportError`
PyObject ***PyExc_IndentationError** *Bir parçası* Kararlı ABI.	`IndentationError`
PyObject ***PyExc_IndexError** *Bir parçası* Kararlı ABI.	`IndexError`
PyObject ***PyExc_InterruptedError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`InterruptedError`
PyObject ***PyExc_IsADirectoryError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`IsADirectoryError`
PyObject ***PyExc_KeyError** *Bir parçası* Kararlı ABI.	`KeyError`
PyObject ***PyExc_KeyboardInterrupt** *Bir parçası* Kararlı ABI.	`KeyboardInterrupt`
PyObject ***PyExc_LookupError** *Bir parçası* Kararlı ABI.	`LookupError`
PyObject ***PyExc_MemoryError** *Bir parçası* Kararlı ABI.	`MemoryError`
PyObject ***PyExc_ModuleNotFoundError** *Bir parçası* Kararlı ABI *3.6 sürümünden beri.*	`ModuleNotFoundError`
PyObject ***PyExc_NameError** *Bir parçası* Kararlı ABI.	`NameError`
PyObject ***PyExc_NotADirectoryError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`NotADirectoryError`

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

C name	Python name
PyObject ***PyExc_NotImplementedError** *Bir parçası* Kararlı ABI.	`NotImplementedError`
PyObject ***PyExc_OSError** *Bir parçası* Kararlı ABI.	`OSError`
PyObject ***PyExc_OverflowError** *Bir parçası* Kararlı ABI.	`OverflowError`
PyObject ***PyExc_PermissionError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`PermissionError`
PyObject ***PyExc_ProcessLookupError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`ProcessLookupError`
PyObject ***PyExc_PythonFinalizationError**	`PythonFinalizationError`
PyObject ***PyExc_RecursionError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`RecursionError`
PyObject ***PyExc_ReferenceError** *Bir parçası* Kararlı ABI.	`ReferenceError`
PyObject ***PyExc_RuntimeError** *Bir parçası* Kararlı ABI.	`RuntimeError`
PyObject ***PyExc_StopAsyncIteration** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`StopAsyncIteration`
PyObject ***PyExc_StopIteration** *Bir parçası* Kararlı ABI.	`StopIteration`
PyObject ***PyExc_SyntaxError** *Bir parçası* Kararlı ABI.	`SyntaxError`
PyObject ***PyExc_SystemError** *Bir parçası* Kararlı ABI.	`SystemError`
PyObject ***PyExc_SystemExit** *Bir parçası* Kararlı ABI.	`SystemExit`

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

C name	Python name
PyObject ***PyExc_TabError** *Bir parçası* Kararlı ABI.	`TabError`
PyObject ***PyExc_TimeoutError** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`TimeoutError`
PyObject ***PyExc_TypeError** *Bir parçası* Kararlı ABI.	`TypeError`
PyObject ***PyExc_UnboundLocalError** *Bir parçası* Kararlı ABI.	`UnboundLocalError`
PyObject ***PyExc_UnicodeDecodeError** *Bir parçası* Kararlı ABI.	`UnicodeDecodeError`
PyObject ***PyExc_UnicodeEncodeError** *Bir parçası* Kararlı ABI.	`UnicodeEncodeError`
PyObject ***PyExc_UnicodeError** *Bir parçası* Kararlı ABI.	`UnicodeError`
PyObject ***PyExc_UnicodeTranslateError** *Bir parçası* Kararlı ABI.	`UnicodeTranslateError`
PyObject ***PyExc_ValueError** *Bir parçası* Kararlı ABI.	`ValueError`
PyObject ***PyExc_ZeroDivisionError** *Bir parçası* Kararlı ABI.	`ZeroDivisionError`

Added in version 3.3: *PyExc_BlockingIOError*, *PyExc_BrokenPipeError*, *PyExc_ChildProcessError*, *PyExc_ConnectionError*, *PyExc_ConnectionAbortedError*, *PyExc_ConnectionRefusedError*, *PyExc_ConnectionResetError*, *PyExc_FileExistsError*, *PyExc_FileNotFoundError*, *PyExc_InterruptedError*, *PyExc_IsADirectoryError*, *PyExc_NotADirectoryError*, *PyExc_PermissionError*, *PyExc_ProcessLookupError* and *PyExc_TimeoutError* were introduced following **PEP 3151**.

Added in version 3.5: *PyExc_StopAsyncIteration* and *PyExc_RecursionError*.

Added in version 3.6: *PyExc_ModuleNotFoundError*.

Added in version 3.11: *PyExc_BaseExceptionGroup*.

5.10.2 OSError aliases

The following are a compatibility aliases to *PyExc_OSError*.

3.3 sürümünde değişti: These aliases used to be separate exception types.

C name	Python name	Notes
PyObject ***PyExc_EnvironmentError** *Bir parçası* Kararlı ABI.	`OSError`	
PyObject ***PyExc_IOError** *Bir parçası* Kararlı ABI.	`OSError`	
PyObject ***PyExc_WindowsError** *Bir parçası* Kararlı ABI *on Windows 3.7 sürümünden beri.*	`OSError`	[win]

Notes:

5.10.3 Warning types

C name	Python name
PyObject ***PyExc_Warning** *Bir parçası* Kararlı ABI.	`Warning`
PyObject ***PyExc_BytesWarning** *Bir parçası* Kararlı ABI.	`BytesWarning`
PyObject ***PyExc_DeprecationWarning** *Bir parçası* Kararlı ABI.	`DeprecationWarning`
PyObject ***PyExc_EncodingWarning** *Bir parçası* Kararlı ABI *3.10 sürümünden beri.*	`EncodingWarning`
PyObject ***PyExc_FutureWarning** *Bir parçası* Kararlı ABI.	`FutureWarning`
PyObject ***PyExc_ImportWarning** *Bir parçası* Kararlı ABI.	`ImportWarning`
PyObject ***PyExc_PendingDeprecationWarning** *Bir parçası* Kararlı ABI.	`PendingDeprecationWarning`
PyObject ***PyExc_ResourceWarning** *Bir parçası* Kararlı ABI *3.7 sürümünden beri.*	`ResourceWarning`
PyObject ***PyExc_RuntimeWarning** *Bir parçası* Kararlı ABI.	`RuntimeWarning`
PyObject ***PyExc_SyntaxWarning** *Bir parçası* Kararlı ABI.	`SyntaxWarning`
PyObject ***PyExc_UnicodeWarning** *Bir parçası* Kararlı ABI.	`UnicodeWarning`
PyObject ***PyExc_UserWarning** *Bir parçası* Kararlı ABI.	`UserWarning`

Added in version 3.2: *PyExc_ResourceWarning*.

Added in version 3.10: *PyExc_EncodingWarning*.

BÖLÜM 6

Defining extension modules

A C extension for CPython is a shared library (for example, a `.so` file on Linux, `.pyd` DLL on Windows), which is loadable into the Python process (for example, it is compiled with compatible compiler settings), and which exports an *initialization function*.

To be importable by default (that is, by `importlib.machinery.ExtensionFileLoader`), the shared library must be available on `sys.path`, and must be named after the module name plus an extension listed in `importlib.machinery.EXTENSION_SUFFIXES`.

Not

Building, packaging and distributing extension modules is best done with third-party tools, and is out of scope of this document. One suitable tool is Setuptools, whose documentation can be found at https://setuptools.pypa.io/en/latest/setuptools.html.

Normally, the initialization function returns a module definition initialized using `PyModuleDef_Init()`. This allows splitting the creation process into several phases:

- Before any substantial code is executed, Python can determine which capabilities the module supports, and it can adjust the environment or refuse loading an incompatible extension.
- By default, Python itself creates the module object – that is, it does the equivalent of `object.__new__()` for classes. It also sets initial attributes like `__package__` and `__loader__`.
- Afterwards, the module object is initialized using extension-specific code – the equivalent of `__init__()` on classes.

This is called *multi-phase initialization* to distinguish it from the legacy (but still supported) *single-phase initialization* scheme, where the initialization function returns a fully constructed module. See the *single-phase-initialization section below* for details.

3.5 sürümünde değişti: Added support for multi-phase initialization (**PEP 489**).

6.1 Multiple module instances

By default, extension modules are not singletons. For example, if the `sys.modules` entry is removed and the module is re-imported, a new module object is created, and typically populated with fresh method and type objects. The old module is subject to normal garbage collection. This mirrors the behavior of pure-Python modules.

Additional module instances may be created in *sub-interpreters* or after Python runtime reinitialization (`Py_Finalize()` and `Py_Initialize()`). In these cases, sharing Python objects between module instances would likely cause crashes or undefined behavior.

To avoid such issues, each instance of an extension module should be *isolated*: changes to one instance should not implicitly affect the others, and all state owned by the module, including references to Python objects, should be specific to a particular module instance. See isolating-extensions-howto for more details and a practical guide.

A simpler way to avoid these issues is raising an error on repeated initialization.

All modules are expected to support *sub-interpreters*, or otherwise explicitly signal a lack of support. This is usually achieved by isolation or blocking repeated initialization, as above. A module may also be limited to the main interpreter using the `Py_mod_multiple_interpreters` slot.

6.2 Initialization function

The initialization function defined by an extension module has the following signature:

PyObject ***PyInit_modulename**(void)

Its name should be `PyInit_<name>`, with `<name>` replaced by the name of the module.

For modules with ASCII-only names, the function must instead be named `PyInit_<name>`, with `<name>` replaced by the name of the module. When using *Multi-phase initialization*, non-ASCII module names are allowed. In this case, the initialization function name is `PyInitU_<name>`, with `<name>` encoded using Python's *punycode* encoding with hyphens replaced by underscores. In Python:

```
def initfunc_name(name):
    try:
        suffix = b'_' + name.encode('ascii')
    except UnicodeEncodeError:
        suffix = b'U_' + name.encode('punycode').replace(b'-', b'_')
    return b'PyInit' + suffix
```

It is recommended to define the initialization function using a helper macro:

PyMODINIT_FUNC

Declare an extension module initialization function. This macro:

- specifies the `PyObject*` return type,
- adds any special linkage declarations required by the platform, and
- for C++, declares the function as `extern "C"`.

For example, a module called `spam` would be defined like this:

```
static struct PyModuleDef spam_module = {
    .m_base = PyModuleDef_HEAD_INIT,
    .m_name = "spam",
    ...
};

PyMODINIT_FUNC
PyInit_spam(void)
{
    return PyModuleDef_Init(&spam_module);
}
```

It is possible to export multiple modules from a single shared library by defining multiple initialization functions. However, importing them requires using symbolic links or a custom importer, because by default only the function corresponding to the filename is found. See the Multiple modules in one library section in **PEP 489** for details.

The initialization function is typically the only non-`static` item defined in the module's C source.

6.3 Multi-phase initialization

Normally, the *initialization function* (`PyInit_modulename`) returns a *`PyModuleDef`* instance with non-`NULL` *`m_slots`*. Before it is returned, the `PyModuleDef` instance must be initialized using the following function:

PyObject ***PyModuleDef_Init**(*PyModuleDef* *def)

Bir parçası Kararlı ABI *3.5 sürümünden beri.* Ensure a module definition is a properly initialized Python object that correctly reports its type and a reference count.

Return *def* cast to `PyObject*`, or `NULL` if an error occurred.

Calling this function is required for *Multi-phase initialization*. It should not be used in other contexts.

Note that Python assumes that `PyModuleDef` structures are statically allocated. This function may return either a new reference or a borrowed one; this reference must not be released.

Added in version 3.5.

6.4 Legacy single-phase initialization

Dikkat

Single-phase initialization is a legacy mechanism to initialize extension modules, with known drawbacks and design flaws. Extension module authors are encouraged to use multi-phase initialization instead.

In single-phase initialization, the *initialization function* (`PyInit_modulename`) should create, populate and return a module object. This is typically done using *`PyModule_Create()`* and functions like *`PyModule_AddObjectRef()`*.

Single-phase initialization differs from the *default* in the following ways:

- Single-phase modules are, or rather *contain*, "singletons".

  When the module is first initialized, Python saves the contents of the module's `__dict__` (that is, typically, the module's functions and types).

  For subsequent imports, Python does not call the initialization function again. Instead, it creates a new module object with a new `__dict__`, and copies the saved contents to it. For example, given a single-phase module `_testsinglephase`[1] that defines a function `sum` and an exception class `error`:

  ```
  >>> import sys
  >>> import _testsinglephase as one
  >>> del sys.modules['_testsinglephase']
  >>> import _testsinglephase as two
  >>> one is two
  False
  >>> one.__dict__ is two.__dict__
  False
  >>> one.sum is two.sum
  True
  >>> one.error is two.error
  True
  ```

  The exact behavior should be considered a CPython implementation detail.

- To work around the fact that `PyInit_modulename` does not take a *spec* argument, some state of the import machinery is saved and applied to the first suitable module created during the `PyInit_modulename` call. Specifically, when a sub-module is imported, this mechanism prepends the parent package name to the name of the module.

[1] `_testsinglephase` is an internal module used in CPython's self-test suite; your installation may or may not include it.

A single-phase `PyInit_modulename` function should create "its" module object as soon as possible, before any other module objects can be created.

- Non-ASCII module names (`PyInitU_modulename`) are not supported.
- Single-phase modules support module lookup functions like *PyState_FindModule()*.

BÖLÜM 7

Utilities

The functions in this chapter perform various utility tasks, ranging from helping C code be more portable across platforms, using Python modules from C, and parsing function arguments and constructing Python values from C values.

7.1 Operating System Utilities

PyObject ***PyOS_FSPath**(*PyObject* *path)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.6 sürümünden beri.* Return the file system representation for *path*. If the object is a `str` or `bytes` object, then a new *strong reference* is returned. If the object implements the `os.PathLike` interface, then `__fspath__()` is returned as long as it is a `str` or `bytes` object. Otherwise `TypeError` is raised and `NULL` is returned.

Added in version 3.6.

int **Py_FdIsInteractive**(FILE *fp, const char *filename)

Return true (nonzero) if the standard I/O file *fp* with name *filename* is deemed interactive. This is the case for files for which `isatty(fileno(fp))` is true. If the *PyConfig.interactive* is non-zero, this function also returns true if the *filename* pointer is `NULL` or if the name is equal to one of the strings `'<stdin>'` or `'???'`.

This function must not be called before Python is initialized.

void **PyOS_BeforeFork**()

Bir parçası Kararlı ABI *on platforms with fork() 3.7 sürümünden beri.* Function to prepare some internal state before a process fork. This should be called before calling `fork()` or any similar function that clones the current process. Only available on systems where `fork()` is defined.

> **Uyarı**
>
> The C `fork()` call should only be made from the *"main" thread* (of the *"main" interpreter*). The same is true for `PyOS_BeforeFork()`.

Added in version 3.7.

void **PyOS_AfterFork_Parent**()

Bir parçası Kararlı ABI *on platforms with fork() 3.7 sürümünden beri.* Function to update some internal state after a process fork. This should be called from the parent process after calling `fork()` or any similar function that clones the current process, regardless of whether process cloning was successful. Only available on systems where `fork()` is defined.

Uyarı

The C `fork()` call should only be made from the *"main" thread* (of the *"main" interpreter*). The same is true for `PyOS_AfterFork_Parent()`.

Added in version 3.7.

void **PyOS_AfterFork_Child**()

Bir parçası Kararlı ABI *on platforms with fork() 3.7 sürümünden beri.* Function to update internal interpreter state after a process fork. This must be called from the child process after calling `fork()`, or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where `fork()` is defined.

Uyarı

The C `fork()` call should only be made from the *"main" thread* (of the *"main" interpreter*). The same is true for `PyOS_AfterFork_Child()`.

Added in version 3.7.

Ayrıca bakınız

`os.register_at_fork()` allows registering custom Python functions to be called by *`PyOS_BeforeFork()`*, *`PyOS_AfterFork_Parent()`* and *`PyOS_AfterFork_Child()`*.

void **PyOS_AfterFork**()

Bir parçası Kararlı ABI *on platforms with fork().* Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

3.7 sürümünden beri kullanım dışı: This function is superseded by *`PyOS_AfterFork_Child()`*.

int **PyOS_CheckStack**()

Bir parçası Kararlı ABI *on platforms with USE_STACKCHECK 3.7 sürümünden beri.* Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when `USE_STACKCHECK` is defined (currently on certain versions of Windows using the Microsoft Visual C++ compiler). `USE_STACKCHECK` will be defined automatically; you should never change the definition in your own code.

typedef void (***PyOS_sighandler_t**)(int)

Bir parçası Kararlı ABI.

PyOS_sighandler_t **PyOS_getsig**(int i)

Bir parçası Kararlı ABI. Return the current signal handler for signal *i*. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly!

PyOS_sighandler_t **PyOS_setsig**(int i, *PyOS_sighandler_t* h)

Bir parçası Kararlı ABI. Set the signal handler for signal *i* to be *h*; return the old signal handler. This is a thin wrapper around either `sigaction()` or `signal()`. Do not call those functions directly!

wchar_t *`Py_DecodeLocale`(const char *arg, size_t *size)

Bir parçası Kararlı ABI *3.7 sürümünden beri.*

> **Uyarı**
>
> This function should not be called directly: use the `PyConfig` API with the `PyConfig_SetBytesString()` function which ensures that *Python is preinitialized*.
>
> This function must not be called before *Python is preinitialized* and so that the LC_CTYPE locale is properly configured: see the `Py_PreInitialize()` function.

Decode a byte string from the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, undecodable bytes are decoded as characters in range U+DC80..U+DCFF; and if a byte sequence can be decoded as a surrogate character, the bytes are escaped using the surrogateescape error handler instead of decoding them.

Return a pointer to a newly allocated wide character string, use `PyMem_RawFree()` to free the memory. If size is not `NULL`, write the number of wide characters excluding the null character into `*size`

Return `NULL` on decoding error or memory allocation error. If *size* is not `NULL`, `*size` is set to `(size_t)-1` on memory error or set to `(size_t)-2` on decoding error.

The *filesystem encoding and error handler* are selected by `PyConfig_Read()`: see `filesystem_encoding` and `filesystem_errors` members of `PyConfig`.

Decoding errors should never happen, unless there is a bug in the C library.

Use the `Py_EncodeLocale()` function to encode the character string back to a byte string.

> **Ayrıca bakınız**
>
> The `PyUnicode_DecodeFSDefaultAndSize()` and `PyUnicode_DecodeLocaleAndSize()` functions.

Added in version 3.5.

3.7 sürümünde değişti: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

3.8 sürümünde değişti: The function now uses the UTF-8 encoding on Windows if `PyPreConfig.legacy_windows_fs_encoding` is zero;

char *`Py_EncodeLocale`(const wchar_t *text, size_t *error_pos)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Encode a wide character string to the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Return a pointer to a newly allocated byte string, use `PyMem_Free()` to free the memory. Return `NULL` on encoding error or memory allocation error.

If error_pos is not `NULL`, `*error_pos` is set to `(size_t)-1` on success, or set to the index of the invalid character on encoding error.

The *filesystem encoding and error handler* are selected by `PyConfig_Read()`: see `filesystem_encoding` and `filesystem_errors` members of `PyConfig`.

Use the `Py_DecodeLocale()` function to decode the bytes string back to a wide character string.

> **Uyarı**
>
> This function must not be called before *Python is preinitialized* and so that the LC_CTYPE locale is properly configured: see the `Py_PreInitialize()` function.

> **Ayrıca bakınız**
>
> The `PyUnicode_EncodeFSDefault()` and `PyUnicode_EncodeLocale()` functions.

Added in version 3.5.

3.7 sürümünde değişti: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

3.8 sürümünde değişti: The function now uses the UTF-8 encoding on Windows if `PyPreConfig.legacy_windows_fs_encoding` is zero.

FILE *`Py_fopen`(*PyObject* *path, const char *mode)

Similar to `fopen()`, but *path* is a Python object and an exception is set on error.

path must be a `str` object, a `bytes` object, or a *path-like object*.

On success, return the new file pointer. On error, set an exception and return `NULL`.

The file must be closed by `Py_fclose()` rather than calling directly `fclose()`.

The file descriptor is created non-inheritable (**PEP 446**).

The caller must have an *attached thread state*.

Added in version 3.14.

int `Py_fclose`(FILE *file)

Close a file that was opened by `Py_fopen()`.

On success, return `0`. On error, return `EOF` and `errno` is set to indicate the error. In either case, any further access (including another call to `Py_fclose()`) to the stream results in undefined behavior.

Added in version 3.14.

7.2 System Functions

These are utility functions that make functionality from the `sys` module accessible to C code. They all work with the current interpreter thread's `sys` module's dict, which is contained in the internal thread state structure.

PyObject *`PySys_GetObject`(const char *name)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the object *name* from the `sys` module or `NULL` if it does not exist, without setting an exception.

int `PySys_SetObject`(const char *name, *PyObject* *v)

Bir parçası Kararlı ABI. Set *name* in the `sys` module to *v* unless *v* is `NULL`, in which case *name* is deleted from the sys module. Returns `0` on success, `-1` on error.

void `PySys_ResetWarnOptions`()

Bir parçası Kararlı ABI. Reset `sys.warnoptions` to an empty list. This function may be called prior to `Py_Initialize()`.

Deprecated since version 3.13, will be removed in version 3.15: Clear `sys.warnoptions` and `warnings.filters` instead.

void `PySys_WriteStdout`(const char *format, ...)

Bir parçası Kararlı ABI. Write the output string described by *format* to `sys.stdout`. No exceptions are raised, even if truncation occurs (see below).

format should limit the total size of the formatted output string to 1000 bytes or less – after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted "%s" formats should occur; these should be limited using "%.<N>s" where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for "%f", which can print hundreds of digits for very large numbers.

If a problem occurs, or `sys.stdout` is unset, the formatted message is written to the real (C level) *stdout*.

void **PySys_WriteStderr**(const char *format, ...)

Bir parçası Kararlı ABI. As *PySys_WriteStdout()*, but write to `sys.stderr` or *stderr* instead.

void **PySys_FormatStdout**(const char *format, ...)

Bir parçası Kararlı ABI. Function similar to PySys_WriteStdout() but format the message using *PyUnicode_FromFormatV()* and don't truncate the message to an arbitrary length.

Added in version 3.2.

void **PySys_FormatStderr**(const char *format, ...)

Bir parçası Kararlı ABI. As *PySys_FormatStdout()*, but write to `sys.stderr` or *stderr* instead.

Added in version 3.2.

PyObject ***PySys_GetXOptions**()

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return the current dictionary of `-X` options, similarly to `sys._xoptions`. On error, `NULL` is returned and an exception is set.

Added in version 3.2.

int **PySys_Audit**(const char *event, const char *format, ...)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure.

The *event* string argument must not be *NULL*.

If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from `N`, the same format characters as used in *Py_BuildValue()* are available. If the built value is not a tuple, it will be added into a single-element tuple.

The `N` format option must not be used. It consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.

Note that `#` format characters should always be treated as *Py_ssize_t*, regardless of whether `PY_SSIZE_T_CLEAN` was defined.

`sys.audit()` performs the same function from Python code.

See also *PySys_AuditTuple()*.

Added in version 3.8.

3.8.2 sürümünde değişti: Require *Py_ssize_t* for `#` format characters. Previously, an unavoidable deprecation warning was raised.

int **PySys_AuditTuple**(const char *event, *PyObject* *args)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to *PySys_Audit()*, but pass arguments as a Python object. *args* must be a `tuple`. To pass no arguments, *args* can be *NULL*.

Added in version 3.13.

int **PySys_AddAuditHook**(*Py_AuditHookFunction* hook, void *userData)

Append the callable *hook* to the list of active auditing hooks. Return zero on success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

This function is safe to call before *Py_Initialize()*. When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from `Exception` (other errors will not be silenced).

The hook function is always called with an *attached thread state* by the Python interpreter that raised the event.

See **PEP 578** for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

If the interpreter is initialized, this function raises an auditing event `sys.addaudithook` with no arguments. If any existing hooks raise an exception derived from `Exception`, the new hook will not be added and the exception is cleared. As a result, callers cannot assume that their hook has been added unless they control all existing hooks.

typedef int (***Py_AuditHookFunction**)(const char *event, *PyObject* *args, void *userData)

The type of the hook function. *event* is the C string event argument passed to `PySys_Audit()` or `PySys_AuditTuple()`. *args* is guaranteed to be a `PyTupleObject`. *userData* is the argument passed to PySys_AddAuditHook().

Added in version 3.8.

7.3 Process Control

void **Py_FatalError**(const char *message)

Bir parçası Kararlı ABI. Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function `abort()` is called which will attempt to produce a `core` file.

The `Py_FatalError()` function is replaced with a macro which logs automatically the name of the current function, unless the `Py_LIMITED_API` macro is defined.

3.9 sürümünde değişti: Log the function name automatically.

void **Py_Exit**(int status)

Bir parçası Kararlı ABI. Exit the current process. This calls `Py_FinalizeEx()` and then calls the standard C library function `exit(status)`. If `Py_FinalizeEx()` indicates an error, the exit status is set to 120.

3.6 sürümünde değişti: Errors from finalization no longer ignored.

int **Py_AtExit**(void (*func)())

Bir parçası Kararlı ABI. Register a cleanup function to be called by `Py_FinalizeEx()`. The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful, `Py_AtExit()` returns `0`; on failure, it returns `-1`. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

Ayrıca bakınız

`PyUnstable_AtExit()` for passing a `void *data` argument.

7.4 Importing Modules

PyObject ***PyImport_ImportModule**(const char *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is a wrapper around `PyImport_Import()` which takes a `const char*` as an argument instead of a `PyObject*`.

PyObject ***PyImport_ImportModuleNoBlock**(const char *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This function is a deprecated alias of `PyImport_ImportModule()`.

3.3 sürümünde değişti: This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

Deprecated since version 3.13, will be removed in version 3.15: Use `PyImport_ImportModule()` instead.

PyObject ***PyImport_ImportModuleEx**(const char *name, *PyObject* *globals, *PyObject* *locals, *PyObject* *fromlist)

Döndürdüğü değer: Yeni referans. Import a module. This is best described by referring to the built-in Python function `__import__()`.

The return value is a new reference to the imported module or top-level package, or `NULL` with an exception set on failure. Like for `__import__()`, the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with *PyImport_ImportModule()*.

PyObject ***PyImport_ImportModuleLevelObject**(*PyObject* *name, *PyObject* *globals, *PyObject* *locals, *PyObject* *fromlist, int level)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Import a module. This is best described by referring to the built-in Python function `__import__()`, as the standard `__import__()` function calls this function directly.

The return value is a new reference to the imported module or top-level package, or `NULL` with an exception set on failure. Like for `__import__()`, the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Added in version 3.3.

PyObject ***PyImport_ImportModuleLevel**(const char *name, *PyObject* *globals, *PyObject* *locals, *PyObject* *fromlist, int level)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Similar to *PyImport_ImportModuleLevelObject()*, but the name is a UTF-8 encoded string instead of a Unicode object.

3.3 sürümünde değişti: Negative values for *level* are no longer accepted.

PyObject ***PyImport_Import**(*PyObject* *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is a higher-level interface that calls the current "import hook function" (with an explicit *level* of 0, meaning absolute import). It invokes the `__import__()` function from the `__builtins__` of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

This function always uses absolute imports.

PyObject ***PyImport_ReloadModule**(*PyObject* *m)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Reload a module. Return a new reference to the reloaded module, or `NULL` with an exception set on failure (the module still exists in this case).

PyObject ***PyImport_AddModuleRef**(const char *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return the module object corresponding to a module name.

The *name* argument may be of the form `package.module`. First check the modules dictionary if there's one there, and if not, create a new one and insert it in the modules dictionary.

Return a *strong reference* to the module on success. Return `NULL` with an exception set on failure.

The module name *name* is decoded from UTF-8.

This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use *PyImport_ImportModule()* or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

Added in version 3.13.

PyObject ***PyImport_AddModuleObject**(*PyObject* *name)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Similar to *PyImport_AddModuleRef()*, but return a *borrowed reference* and *name* is a Python `str` object.

Added in version 3.3.

PyObject ***PyImport_AddModule**(const char *name)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Similar to `PyImport_AddModuleRef()`, but return a *borrowed reference*.

PyObject ***PyImport_ExecCodeModule**(const char *name, *PyObject* *co)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Given a module name (possibly of the form `package.module`) and a code object read from a Python bytecode file or obtained from the built-in function `compile()`, load the module. Return a new reference to the module object, or `NULL` with an exception set if an error occurred. *name* is removed from `sys.modules` in error cases, even if *name* was already in `sys.modules` on entry to `PyImport_ExecCodeModule()`. Leaving incompletely initialized modules in `sys.modules` is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's `__spec__` and `__loader__` will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's `__loader__` (if set) and to an instance of `SourceFileLoader` otherwise.

The module's `__file__` attribute will be set to the code object's `co_filename`. If applicable, `__cached__` will also be set.

This function will reload the module if it was already imported. See `PyImport_ReloadModule()` for the intended way to reload a module.

If *name* points to a dotted name of the form `package.module`, any package structures not already created will still not be created.

See also `PyImport_ExecCodeModuleEx()` and `PyImport_ExecCodeModuleWithPathnames()`.

3.12 sürümünde değişti: The setting of `__cached__` and `__loader__` is deprecated. See `ModuleSpec` for alternatives.

PyObject ***PyImport_ExecCodeModuleEx**(const char *name, *PyObject* *co, const char *pathname)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Like `PyImport_ExecCodeModule()`, but the `__file__` attribute of the module object is set to *pathname* if it is non-`NULL`.

See also `PyImport_ExecCodeModuleWithPathnames()`.

PyObject ***PyImport_ExecCodeModuleObject**(*PyObject* *name, *PyObject* *co, *PyObject* *pathname, *PyObject* *cpathname)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI 3.7 sürümünden beri. Like `PyImport_ExecCodeModuleEx()`, but the `__cached__` attribute of the module object is set to *cpathname* if it is non-`NULL`. Of the three functions, this is the preferred one to use.

Added in version 3.3.

3.12 sürümünde değişti: Setting `__cached__` is deprecated. See `ModuleSpec` for alternatives.

PyObject ***PyImport_ExecCodeModuleWithPathnames**(const char *name, *PyObject* *co, const char *pathname, const char *cpathname)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Like `PyImport_ExecCodeModuleObject()`, but *name*, *pathname* and *cpathname* are UTF-8 encoded strings. Attempts are also made to figure out what the value for *pathname* should be from *cpathname* if the former is set to `NULL`.

Added in version 3.2.

3.3 sürümünde değişti: Uses `imp.source_from_cache()` in calculating the source path if only the bytecode path is provided.

3.12 sürümünde değişti: No longer uses the removed `imp` module.

long **PyImport_GetMagicNumber**()

Bir parçası Kararlı ABI. Return the magic number for Python bytecode files (a.k.a. `.pyc` file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns `-1` on error.

3.3 sürümünde değişti: Return value of `-1` upon failure.

const char *__PyImport_GetMagicTag__()

Bir parçası Kararlı ABI. Return the magic tag string for **PEP 3147** format Python bytecode file names. Keep in mind that the value at `sys.implementation.cache_tag` is authoritative and should be used instead of this function.

Added in version 3.2.

PyObject *__PyImport_GetModuleDict__()

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the dictionary used for the module administration (a.k.a. `sys.modules`). Note that this is a per-interpreter variable.

PyObject *__PyImport_GetModule__(*PyObject* *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.8 sürümünden beri.* Return the already imported module with the given name. If the module has not been imported yet then returns `NULL` but does not set an error. Returns `NULL` and sets an error if the lookup failed.

Added in version 3.7.

PyObject *__PyImport_GetImporter__(*PyObject* *path)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a finder object for a `sys.path`/`pkg.__path__` item *path*, possibly by fetching it from the `sys.path_importer_cache` dict. If it wasn't yet cached, traverse `sys.path_hooks` until a hook is found that can handle the path item. Return `None` if no hook could; this tells our caller that the *path based finder* could not find a finder for this path item. Cache the result in `sys.path_importer_cache`. Return a new reference to the finder object.

int __PyImport_ImportFrozenModuleObject__(*PyObject* *name)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Load a frozen module named *name*. Return `1` for success, `0` if the module is not found, and `-1` with an exception set if the initialization failed. To access the imported module on a successful load, use *`PyImport_ImportModule()`*. (Note the misnomer — this function would reload the module if it was already imported.)

Added in version 3.3.

3.4 sürümünde değişti: The `__file__` attribute is no longer set on the module.

int __PyImport_ImportFrozenModule__(const char *name)

Bir parçası Kararlı ABI. Similar to *`PyImport_ImportFrozenModuleObject()`*, but the name is a UTF-8 encoded string instead of a Unicode object.

struct ___frozen__

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see `Tools/freeze/` in the Python source distribution). Its definition, found in `Include/import.h`, is:

```
struct _frozen {
    const char *name;
    const unsigned char *code;
    int size;
    bool is_package;
};
```

3.11 sürümünde değişti: The new `is_package` field indicates whether the module is a package or not. This replaces setting the `size` field to a negative value.

const struct *_frozen* *__PyImport_FrozenModules__

This pointer is initialized to point to an array of *`_frozen`* records, terminated by one whose members are all `NULL` or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

int __PyImport_AppendInittab__(const char *name, *PyObject* *(*initfunc)(void))

Bir parçası Kararlı ABI. Add a single module to the existing table of built-in modules. This is a convenience wrapper around *`PyImport_ExtendInittab()`*, returning `-1` if the table could not be extended. The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import. This should be called before *`Py_Initialize()`*.

struct **_inittab**

Structure describing a single entry in the list of built-in modules. Programs which embed Python may use an array of these structures in conjunction with *PyImport_ExtendInittab()* to provide additional built-in modules. The structure consists of two members:

const char ***name**

The module name, as an ASCII encoded string.

PyObject *(***initfunc**)(void)

Initialization function for a module built into the interpreter.

int **PyImport_ExtendInittab**(struct *_inittab* *newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains `NULL` for the *name* field; failure to provide the sentinel value can result in a memory fault. Returns `0` on success or `-1` if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This must be called before *Py_Initialize()*.

If Python is initialized multiple times, *PyImport_AppendInittab()* or *PyImport_ExtendInittab()* must be called before each Python initialization.

PyObject ***PyImport_ImportModuleAttr**(*PyObject* *mod_name, *PyObject* *attr_name)

Döndürdüğü değer: Yeni referans. Import the module *mod_name* and get its attribute *attr_name*.

Names must be Python `str` objects.

Helper function combining *PyImport_Import()* and *PyObject_GetAttr()*. For example, it can raise `ImportError` if the module is not found, and `AttributeError` if the attribute doesn't exist.

Added in version 3.14.

PyObject ***PyImport_ImportModuleAttrString**(const char *mod_name, const char *attr_name)

Döndürdüğü değer: Yeni referans. Similar to *PyImport_ImportModuleAttr()*, but names are UTF-8 encoded strings instead of Python `str` objects.

Added in version 3.14.

7.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the `marshal` module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports several versions of the data format; see the `Python module documentation` for details.

Py_MARSHAL_VERSION

The current format version. See `marshal.version`.

void **PyMarshal_WriteLongToFile**(long value, FILE *file, int version)

Marshal a `long` integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native `long` type. *version* indicates the file format.

This function can fail, in which case it sets the error indicator. Use *PyErr_Occurred()* to check for that.

void **PyMarshal_WriteObjectToFile**(*PyObject* *value, FILE *file, int version)

Marshal a Python object, *value*, to *file*. *version* indicates the file format.

This function can fail, in which case it sets the error indicator. Use *PyErr_Occurred()* to check for that.

PyObject ***PyMarshal_WriteObjectToString**(*PyObject* *value, int version)

Döndürdüğü değer: Yeni referans. Return a bytes object containing the marshalled representation of *value*. *version* indicates the file format.

The following functions allow marshalled values to be read back in.

long **PyMarshal_ReadLongFromFile**(FILE *file)

Return a C `long` from the data stream in a `FILE*` opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of `long`.

On error, sets the appropriate exception (`EOFError`) and returns `-1`.

int **PyMarshal_ReadShortFromFile**(FILE *file)

Return a C `short` from the data stream in a `FILE*` opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of `short`.

On error, sets the appropriate exception (`EOFError`) and returns `-1`.

PyObject ***PyMarshal_ReadObjectFromFile**(FILE *file)

Döndürdüğü değer: Yeni referans. Return a Python object from the data stream in a `FILE*` opened for reading.

On error, sets the appropriate exception (`EOFError`, `ValueError` or `TypeError`) and returns `NULL`.

PyObject ***PyMarshal_ReadLastObjectFromFile**(FILE *file)

Döndürdüğü değer: Yeni referans. Return a Python object from the data stream in a `FILE*` opened for reading. Unlike *PyMarshal_ReadObjectFromFile()*, this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (`EOFError`, `ValueError` or `TypeError`) and returns `NULL`.

PyObject ***PyMarshal_ReadObjectFromString**(const char *data, *Py_ssize_t* len)

Döndürdüğü değer: Yeni referans. Return a Python object from the data stream in a byte buffer containing *len* bytes pointed to by *data*.

On error, sets the appropriate exception (`EOFError`, `ValueError` or `TypeError`) and returns `NULL`.

7.6 Parsing arguments and building values

These functions are useful when creating your own extension functions and methods. Additional information and examples are available in extending-index.

The first three of these functions described, *PyArg_ParseTuple()*, *PyArg_ParseTupleAndKeywords()*, and *PyArg_Parse()*, all use *format strings* which are used to tell the function about the expected arguments. The format strings use the same syntax for each of these functions.

7.6.1 Parsing arguments

A format string consists of zero or more "format units." A format unit describes one Python object; it is usually a single character or a parenthesized sequence of format units. With a few exceptions, a format unit that is not a parenthesized sequence normally corresponds to a single address argument to these functions. In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that matches the format unit; and the entry in [square] brackets is the type of the C variable(s) whose address should be passed.

Strings and buffers

Not

On Python 3.12 and older, the macro `PY_SSIZE_T_CLEAN` must be defined before including `Python.h` to use all `#` variants of formats (`s#`, `y#`, etc.) explained below. This is not necessary on Python 3.13 and later.

These formats allow accessing an object as a contiguous chunk of memory. You don't have to provide raw storage for the returned unicode or bytes area.

Unless otherwise stated, buffers are not NUL-terminated.

There are three ways strings and buffers can be converted to C:

- Formats such as `y*` and `s*` fill a *Py_buffer* structure. This locks the underlying buffer so that the caller can subsequently use the buffer even inside a *Py_BEGIN_ALLOW_THREADS* block without the risk of mutable data being resized or destroyed. As a result, **you have to call** *PyBuffer_Release()* after you have finished processing the data (or in any early abort case).
- The `es`, `es#`, `et` and `et#` formats allocate the result buffer. **You have to call** *PyMem_Free()* after you have finished processing the data (or in any early abort case).
- Other formats take a `str` or a read-only *bytes-like object*, such as `bytes`, and provide a `const char *` pointer to its buffer. In this case the buffer is "borrowed": it is managed by the corresponding Python object, and shares the lifetime of this object. You won't have to release any memory yourself.

  To ensure that the underlying buffer may be safely borrowed, the object's *PyBufferProcs.bf_releasebuffer* field must be `NULL`. This disallows common mutable objects such as `bytearray`, but also some read-only objects such as `memoryview` of `bytes`.

  Besides this `bf_releasebuffer` requirement, there is no check to verify whether the input object is immutable (e.g. whether it would honor a request for a writable buffer, or whether another thread can mutate the data).

`s` (`str`) [const char *]
Convert a Unicode object to a C pointer to a character string. A pointer to an existing string is stored in the character pointer variable whose address you pass. The C string is NUL-terminated. The Python string must not contain embedded null code points; if it does, a `ValueError` exception is raised. Unicode objects are converted to C strings using `'utf-8'` encoding. If this conversion fails, a `UnicodeError` is raised.

> **Not**
>
> This format does not accept *bytes-like objects*. If you want to accept filesystem paths and convert them to C character strings, it is preferable to use the `O&` format with *PyUnicode_FSConverter()* as *converter*.

3.5 sürümünde değişti: Previously, `TypeError` was raised when embedded null code points were encountered in the Python string.

`s*` (`str` or *bytes-like object*) [Py_buffer]
This format accepts Unicode objects as well as bytes-like objects. It fills a *Py_buffer* structure provided by the caller. In this case the resulting C string may contain embedded NUL bytes. Unicode objects are converted to C strings using `'utf-8'` encoding.

`s#` (`str`, read-only *bytes-like object*) [const char *, *Py_ssize_t*]
Like `s*`, except that it provides a *borrowed buffer*. The result is stored into two C variables, the first one a pointer to a C string, the second one its length. The string may contain embedded null bytes. Unicode objects are converted to C strings using `'utf-8'` encoding.

`z` (`str` or `None`) [const char *]
Like `s`, but the Python object may also be `None`, in which case the C pointer is set to `NULL`.

`z*` (`str`, *bytes-like object* or `None`) [Py_buffer]
Like `s*`, but the Python object may also be `None`, in which case the `buf` member of the *Py_buffer* structure is set to `NULL`.

`z#` (`str`, read-only *bytes-like object* or `None`) [const char *, *Py_ssize_t*]
Like `s#`, but the Python object may also be `None`, in which case the C pointer is set to `NULL`.

`y` (read-only *bytes-like object*) [const char *]
This format converts a bytes-like object to a C pointer to a *borrowed* character string; it does not accept Unicode objects. The bytes buffer must not contain embedded null bytes; if it does, a `ValueError` exception is raised.

3.5 sürümünde değişti: Previously, `TypeError` was raised when embedded null bytes were encountered in the bytes buffer.

y* (*bytes-like object*) **[Py_buffer]**
This variant on `s*` doesn't accept Unicode objects, only bytes-like objects. **This is the recommended way to accept binary data.**

y# (**read-only** *bytes-like object*) **[const char *, Py_ssize_t]**
This variant on `s#` doesn't accept Unicode objects, only bytes-like objects.

S (`bytes`) **[PyBytesObject *]**
Requires that the Python object is a `bytes` object, without attempting any conversion. Raises `TypeError` if the object is not a bytes object. The C variable may also be declared as *PyObject**.

Y (`bytearray`) **[PyByteArrayObject *]**
Requires that the Python object is a `bytearray` object, without attempting any conversion. Raises `TypeError` if the object is not a `bytearray` object. The C variable may also be declared as *PyObject**.

U (`str`) **[PyObject *]**
Requires that the Python object is a Unicode object, without attempting any conversion. Raises `TypeError` if the object is not a Unicode object. The C variable may also be declared as *PyObject**.

w* (**read-write** *bytes-like object*) **[Py_buffer]**
This format accepts any object which implements the read-write buffer interface. It fills a *Py_buffer* structure provided by the caller. The buffer may contain embedded null bytes. The caller have to call *PyBuffer_Release()* when it is done with the buffer.

es (`str`) **[const char *encoding, char **buffer]**
This variant on `s` is used for encoding Unicode into a character buffer. It only works for encoded data without embedded NUL bytes.

This format requires two arguments. The first is only used as input, and must be a `const char*` which points to the name of an encoding as a NUL-terminated string, or `NULL`, in which case `'utf-8'` encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a `char**`; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument.

PyArg_ParseTuple() will allocate a buffer of the needed size, copy the encoded data into this buffer and adjust **buffer* to reference the newly allocated storage. The caller is responsible for calling *PyMem_Free()* to free the allocated buffer after use.

et (`str`, `bytes` or `bytearray`) **[const char *encoding, char **buffer]**
Same as `es` except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

es# (`str`) **[const char *encoding, char **buffer, Py_ssize_t *buffer_length]**
This variant on `s#` is used for encoding Unicode into a character buffer. Unlike the `es` format, this variant allows input data which contains NUL characters.

It requires three arguments. The first is only used as input, and must be a `const char*` which points to the name of an encoding as a NUL-terminated string, or `NULL`, in which case `'utf-8'` encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a `char**`; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument. The third argument must be a pointer to an integer; the referenced integer will be set to the number of bytes in the output buffer.

There are two modes of operation:

If **buffer* points a `NULL` pointer, the function will allocate a buffer of the needed size, copy the encoded data into this buffer and set **buffer* to reference the newly allocated storage. The caller is responsible for calling *PyMem_Free()* to free the allocated buffer after usage.

If **buffer* points to a non-`NULL` pointer (an already allocated buffer), *PyArg_ParseTuple()* will use this location as the buffer and interpret the initial value of **buffer_length* as the buffer size. It will then copy the encoded data into the buffer and NUL-terminate it. If the buffer is not large enough, a `ValueError` will be set.

In both cases, **buffer_length* is set to the length of the encoded data without the trailing NUL byte.

et# (str, bytes or bytearray) [const char *encoding, char **buffer, *Py_ssize_t* *buffer_length]
Same as `es#` except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

3.12 sürümünde değişti: `u`, `u#`, `Z`, and `Z#` are removed because they used a legacy `Py_UNICODE*` representation.

Numbers

These formats allow representing Python numbers or single characters as C numbers. Formats that require `int`, `float` or `complex` can also use the corresponding special methods `__index__()`, `__float__()` or `__complex__()` to convert the Python object to the required type.

For signed integer formats, `OverflowError` is raised if the value is out of range for the C type. For unsigned integer formats, no range checking is done — the most significant bits are silently truncated when the receiving field is too small to receive the value.

b (int) [unsigned char]
Convert a nonnegative Python integer to an unsigned tiny integer, stored in a C `unsigned char`.

B (int) [unsigned char]
Convert a Python integer to a tiny integer without overflow checking, stored in a C `unsigned char`.

h (int) [short int]
Convert a Python integer to a C `short int`.

H (int) [unsigned short int]
Convert a Python integer to a C `unsigned short int`, without overflow checking.

i (int) [int]
Convert a Python integer to a plain C `int`.

I (int) [unsigned int]
Convert a Python integer to a C `unsigned int`, without overflow checking.

l (int) [long int]
Convert a Python integer to a C `long int`.

k (int) [unsigned long]
Convert a Python integer to a C `unsigned long` without overflow checking.

3.14 sürümünde değişti: Use `__index__()` if available.

L (int) [long long]
Convert a Python integer to a C `long long`.

K (int) [unsigned long long]
Convert a Python integer to a C `unsigned long long` without overflow checking.

3.14 sürümünde değişti: Use `__index__()` if available.

n (int) [*Py_ssize_t*]
Convert a Python integer to a C *Py_ssize_t*.

c (bytes or bytearray of length 1) [char]
Convert a Python byte, represented as a `bytes` or `bytearray` object of length 1, to a C `char`.

3.3 sürümünde değişti: Allow `bytearray` objects.

C (str of length 1) [int]
Convert a Python character, represented as a `str` object of length 1, to a C `int`.

f (float) [float]
Convert a Python floating-point number to a C `float`.

d (float) [double]
Convert a Python floating-point number to a C `double`.

D (complex) [Py_complex]
Convert a Python complex number to a C *Py_complex* structure.

Other objects

o (object) [PyObject *]
Store a Python object (without any conversion) in a C object pointer. The C program thus receives the actual object that was passed. A new *strong reference* to the object is not created (i.e. its reference count is not increased). The pointer stored is not NULL.

O! (object) [*typeobject*, PyObject *]
Store a Python object in a C object pointer. This is similar to O, but takes two C arguments: the first is the address of a Python type object, the second is the address of the C variable (of type *PyObject**) into which the object pointer is stored. If the Python object does not have the required type, TypeError is raised.

O& (object) [*converter*, *address*]
Convert a Python object to a C variable through a *converter* function. This takes two arguments: the first is a function, the second is the address of a C variable (of arbitrary type), converted to void*. The *converter* function in turn is called as follows:

```
status = converter(object, address);
```

where *object* is the Python object to be converted and *address* is the void* argument that was passed to the PyArg_Parse* function. The returned *status* should be 1 for a successful conversion and 0 if the conversion has failed. When the conversion fails, the *converter* function should raise an exception and leave the content of *address* unmodified. If the *converter* returns Py_CLEANUP_SUPPORTED, it may get called a second time if the argument parsing eventually fails, giving the converter a chance to release any memory that it had already allocated. In this second call, the *object* parameter will be NULL; *address* will have the same value as in the original call.

Examples of converters: *PyUnicode_FSConverter()* and *PyUnicode_FSDecoder()*.

3.1 sürümünde değişti: Py_CLEANUP_SUPPORTED was added.

p (bool) [int]
Tests the value passed in for truth (a boolean **p**redicate) and converts the result to its equivalent C true/false integer value. Sets the int to 1 if the expression was true and 0 if it was false. This accepts any valid Python value. See truth for more information about how Python tests values for truth.

Added in version 3.3.

(items) (sequence) [*matching-items*]
The object must be a Python sequence (except str, bytes or bytearray) whose length is the number of format units in *items*. The C arguments must correspond to the individual format units in *items*. Format units for sequences may be nested.

If *items* contains format units which store a *borrowed buffer* (s, s#, z, z#, y, or y#) or a *borrowed reference* (S, Y, U, O, or O!), the object must be a Python tuple. The *converter* for the O& format unit in *items* must not store a borrowed buffer or a borrowed reference.

3.14 sürümünde değişti: str and bytearray objects no longer accepted as a sequence.

3.14 sürümünden beri kullanım dışı: Non-tuple sequences are deprecated if *items* contains format units which store a borrowed buffer or a borrowed reference.

A few other characters have a meaning in a format string. These may not occur inside nested parentheses. They are:

|
Indicates that the remaining arguments in the Python argument list are optional. The C variables corresponding to optional arguments should be initialized to their default value — when an optional argument is not specified, *PyArg_ParseTuple()* does not touch the contents of the corresponding C variable(s).

$
PyArg_ParseTupleAndKeywords() only: Indicates that the remaining arguments in the Python argument list are keyword-only. Currently, all keyword-only arguments must also be optional arguments, so | must always be specified before $ in the format string.

Added in version 3.3.

`:`
: The list of format units ends here; the string after the colon is used as the function name in error messages (the "associated value" of the exception that `PyArg_ParseTuple()` raises).

`;`
: The list of format units ends here; the string after the semicolon is used as the error message *instead* of the default error message. `:` and `;` mutually exclude each other.

Note that any Python object references which are provided to the caller are *borrowed* references; do not release them (i.e. do not decrement their reference count)!

Additional arguments passed to these functions must be addresses of variables whose type is determined by the format string; these are used to store values from the input tuple. There are a few cases, as described in the list of format units above, where these parameters are used as input values; they should match what is specified for the corresponding format unit in that case.

For the conversion to succeed, the *arg* object must match the format and the format must be exhausted. On success, the `PyArg_Parse*` functions return true, otherwise they return false and raise an appropriate exception. When the `PyArg_Parse*` functions fail due to conversion failure in one of the format units, the variables at the addresses corresponding to that and the following format units are left untouched.

API Functions

int **PyArg_ParseTuple**(*PyObject* *args, const char *format, ...)

Bir parçası Kararlı ABI. Parse the parameters of a function that takes only positional parameters into local variables. Returns true on success; on failure, it returns false and raises the appropriate exception.

int **PyArg_VaParse**(*PyObject* *args, const char *format, va_list vargs)

Bir parçası Kararlı ABI. Identical to `PyArg_ParseTuple()`, except that it accepts a va_list rather than a variable number of arguments.

int **PyArg_ParseTupleAndKeywords**(*PyObject* *args, *PyObject* *kw, const char *format, char *const *keywords, ...)

Bir parçası Kararlı ABI. Parse the parameters of a function that takes both positional and keyword parameters into local variables. The *keywords* argument is a `NULL`-terminated array of keyword parameter names specified as null-terminated ASCII or UTF-8 encoded C strings. Empty names denote *positional-only parameters*. Returns true on success; on failure, it returns false and raises the appropriate exception.

> **Not**
>
> The *keywords* parameter declaration is `char *const*` in C and `const char *const*` in C++. This can be overridden with the `PY_CXX_CONST` macro.

3.6 sürümünde değişti: Added support for *positional-only parameters*.

3.13 sürümünde değişti: The *keywords* parameter has now type `char *const*` in C and `const char *const*` in C++, instead of `char**`. Added support for non-ASCII keyword parameter names.

int **PyArg_VaParseTupleAndKeywords**(*PyObject* *args, *PyObject* *kw, const char *format, char *const *keywords, va_list vargs)

Bir parçası Kararlı ABI. Identical to `PyArg_ParseTupleAndKeywords()`, except that it accepts a va_list rather than a variable number of arguments.

int **PyArg_ValidateKeywordArguments**(*PyObject**)

Bir parçası Kararlı ABI. Ensure that the keys in the keywords argument dictionary are strings. This is only needed if `PyArg_ParseTupleAndKeywords()` is not used, since the latter already does this check.

Added in version 3.2.

int **PyArg_Parse**(*PyObject* *args, const char *format, ...)

Bir parçası Kararlı ABI. Parse the parameter of a function that takes a single positional parameter into a local variable. Returns true on success; on failure, it returns false and raises the appropriate exception.

Example:

```
// Function using METH_O calling convention
static PyObject*
my_function(PyObject *module, PyObject *arg)
{
    int value;
    if (!PyArg_Parse(arg, "i:my_function", &value)) {
        return NULL;
    }
    // ... use value ...
}
```

int **PyArg_UnpackTuple**(*PyObject* *args, const char *name, *Py_ssize_t* min, *Py_ssize_t* max, ...)

Bir parçası Kararlı ABI. A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as *METH_VARARGS* in function or method tables. The tuple containing the actual parameters should be passed as *args*; it must actually be a tuple. The length of the tuple must be at least *min* and no more than *max*; *min* and *max* may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a *PyObject** variable; these will be filled in with the values from *args*; they will contain *borrowed references*. The variables which correspond to optional parameters not given by *args* will not be filled in; these should be initialized by the caller. This function returns true on success and false if *args* is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

This is an example of the use of this function, taken from the sources for the `_weakref` helper module for weak references:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

The call to *PyArg_UnpackTuple()* in this example is entirely equivalent to this call to *PyArg_ParseTuple()*:

```
PyArg_ParseTuple(args, "O|O:ref", &object, &callback)
```

PY_CXX_CONST

The value to be inserted, if any, before `char *const*` in the *keywords* parameter declaration of *PyArg_ParseTupleAndKeywords()* and *PyArg_VaParseTupleAndKeywords()*. Default empty for C and `const` for C++ (`const char *const*`). To override, define it to the desired value before including `Python.h`.

Added in version 3.13.

7.6.2 Building values

PyObject ***Py_BuildValue**(const char *format, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a new value based on a format string similar to those accepted by the `PyArg_Parse*` family of functions and a sequence of values. Returns the value or `NULL` in the case of an error; an exception will be raised if `NULL` is returned.

Py_BuildValue() does not always build a tuple. It builds a tuple only if its format string contains two or more format units. If the format string is empty, it returns `None`; if it contains exactly one format unit, it returns whatever object is described by that format unit. To force it to return a tuple of size 0 or one, parenthesize the format string.

When memory buffers are passed as parameters to supply data to build objects, as for the `s` and `s#` formats, the required data is copied. Buffers provided by the caller are never referenced by the objects created by *Py_BuildValue()*. In other words, if your code invokes `malloc()` and passes the allocated memory to *Py_BuildValue()*, your code is responsible for calling `free()` for that memory once *Py_BuildValue()* returns.

In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that the format unit will return; and the entry in [square] brackets is the type of the C value(s) to be passed.

The characters space, tab, colon and comma are ignored in format strings (but not within format units such as `s#`). This can be used to make long format strings a tad more readable.

s (str or None) [const char *]
Convert a null-terminated C string to a Python `str` object using `'utf-8'` encoding. If the C string pointer is `NULL`, `None` is used.

s# (str or None) [const char *, *Py_ssize_t*]
Convert a C string and its length to a Python `str` object using `'utf-8'` encoding. If the C string pointer is `NULL`, the length is ignored and `None` is returned.

y (bytes) [const char *]
This converts a C string to a Python `bytes` object. If the C string pointer is `NULL`, `None` is returned.

y# (bytes) [const char *, *Py_ssize_t*]
This converts a C string and its lengths to a Python object. If the C string pointer is `NULL`, `None` is returned.

z (str or None) [const char *]
Same as `s`.

z# (str or None) [const char *, *Py_ssize_t*]
Same as `s#`.

u (str) [const wchar_t *]
Convert a null-terminated `wchar_t` buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is `NULL`, `None` is returned.

u# (str) [const wchar_t *, *Py_ssize_t*]
Convert a Unicode (UTF-16 or UCS-4) data buffer and its length to a Python Unicode object. If the Unicode buffer pointer is `NULL`, the length is ignored and `None` is returned.

U (str or None) [const char *]
Same as `s`.

U# (str or None) [const char *, *Py_ssize_t*]
Same as `s#`.

i (int) [int]
Convert a plain C `int` to a Python integer object.

b (int) [char]
Convert a plain C `char` to a Python integer object.

h (int) [short int]
Convert a plain C `short int` to a Python integer object.

l (int) [long int]
Convert a C `long int` to a Python integer object.

B (int) [unsigned char]
Convert a C `unsigned char` to a Python integer object.

H (int) [unsigned short int]
Convert a C `unsigned short int` to a Python integer object.

I (int) [unsigned int]
Convert a C `unsigned int` to a Python integer object.

k (int) [unsigned long]
Convert a C `unsigned long` to a Python integer object.

L (int) [long long]
Convert a C `long long` to a Python integer object.

K (int) [unsigned long long]
Convert a C `unsigned long long` to a Python integer object.

n (int) [*Py_ssize_t*]
Convert a C *Py_ssize_t* to a Python integer.

p (bool) [int]
Convert a C `int` to a Python `bool` object.

Be aware that this format requires an `int` argument. Unlike most other contexts in C, variadic arguments are not coerced to a suitable type automatically. You can convert another type (for example, a pointer or a float) to a suitable `int` value using `(x) ? 1 : 0` or `!!x`.

Added in version 3.14.

c (bytes of length 1) [char]
Convert a C `int` representing a byte to a Python `bytes` object of length 1.

C (str of length 1) [int]
Convert a C `int` representing a character to Python `str` object of length 1.

d (float) [double]
Convert a C `double` to a Python floating-point number.

f (float) [float]
Convert a C `float` to a Python floating-point number.

D (complex) [Py_complex *]
Convert a C *Py_complex* structure to a Python complex number.

O (object) [PyObject *]
Pass a Python object untouched but create a new *strong reference* to it (i.e. its reference count is incremented by one). If the object passed in is a `NULL` pointer, it is assumed that this was caused because the call producing the argument found an error and set an exception. Therefore, *Py_BuildValue()* will return `NULL` but won't raise an exception. If no exception has been raised yet, `SystemError` is set.

S (object) [PyObject *]
Same as `O`.

N (object) [PyObject *]
Same as `O`, except it doesn't create a new *strong reference*. Useful when the object is created by a call to an object constructor in the argument list.

O& (object) [*converter*, *anything*]
Convert *anything* to a Python object through a *converter* function. The function is called with *anything* (which should be compatible with `void*`) as its argument and should return a "new" Python object, or `NULL` if an error occurred.

(items) (tuple) [*matching-items*]
Convert a sequence of C values to a Python tuple with the same number of items.

[items] (list) [*matching-items*]
Convert a sequence of C values to a Python list with the same number of items.

{items} (dict) [*matching-items*]
Convert a sequence of C values to a Python dictionary. Each pair of consecutive C values adds one item to the dictionary, serving as key and value, respectively.

If there is an error in the format string, the `SystemError` exception is set and `NULL` returned.

PyObject ***Py_VaBuildValue**(const char *format, va_list vargs)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Identical to *Py_BuildValue()*, except that it accepts a va_list rather than a variable number of arguments.

7.7 String conversion and formatting

Functions for number conversion and formatted string output.

int **PyOS_snprintf**(char *str, size_t size, const char *format, ...)

Bir parçası Kararlı ABI. Output not more than *size* bytes to *str* according to the format string *format* and the extra arguments. See the Unix man page *snprintf(3)*.

int **PyOS_vsnprintf**(char *str, size_t size, const char *format, va_list va)

Bir parçası Kararlı ABI. Output not more than *size* bytes to *str* according to the format string *format* and the variable argument list *va*. Unix man page *vsnprintf(3)*.

PyOS_snprintf() and *PyOS_vsnprintf()* wrap the Standard C library functions `snprintf()` and `vsnprintf()`. Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

The wrappers ensure that `str[size-1]` is always `'\0'` upon return. They never write more than *size* bytes (including the trailing `'\0'`) into str. Both functions require that `str != NULL`, `size > 0`, `format != NULL` and `size < INT_MAX`. Note that this means there is no equivalent to the C99 `n = snprintf(NULL, 0, ...)` which would determine the necessary buffer size.

The return value (*rv*) for these functions should be interpreted as follows:

- When `0 < = rv < size`, the output conversion was successful and *rv* characters were written to *str* (excluding the trailing `'\0'` byte at `str[rv]`).
- When `rv > = size`, the output conversion was truncated and a buffer with `rv + 1` bytes would have been needed to succeed. `str[size-1]` is `'\0'` in this case.
- When `rv < 0`, “something bad happened.” `str[size-1]` is `'\0'` in this case too, but the rest of *str* is undefined. The exact cause of the error depends on the underlying platform.

The following functions provide locale-independent string to number conversions.

unsigned long **PyOS_strtoul**(const char *str, char **ptr, int base)

Bir parçası Kararlı ABI. Convert the initial part of the string in `str` to an `unsigned long` value according to the given `base`, which must be between `2` and `36` inclusive, or be the special value `0`.

Leading white space and case of characters are ignored. If `base` is zero it looks for a leading `0b`, `0o` or `0x` to tell which base. If these are absent it defaults to `10`. Base must be 0 or between 2 and 36 (inclusive). If `ptr` is non-`NULL` it will contain a pointer to the end of the scan.

If the converted value falls out of range of corresponding return type, range error occurs (`errno` is set to `ERANGE`) and `ULONG_MAX` is returned. If no conversion can be performed, `0` is returned.

See also the Unix man page *strtoul(3)*.

Added in version 3.2.

long **PyOS_strtol**(const char *str, char **ptr, int base)

Bir parçası Kararlı ABI. Convert the initial part of the string in `str` to an `long` value according to the given `base`, which must be between `2` and `36` inclusive, or be the special value `0`.

Same as *PyOS_strtoul()*, but return a `long` value instead and `LONG_MAX` on overflows.

See also the Unix man page *strtol(3)*.

Added in version 3.2.

double **PyOS_string_to_double**(const char *s, char **endptr, *PyObject* *overflow_exception)

Bir parçası Kararlı ABI. Convert a string `s` to a `double`, raising a Python exception on failure. The set of accepted strings corresponds to the set of strings accepted by Python's `float()` constructor, except that `s` must not have leading or trailing whitespace. The conversion is independent of the current locale.

If `endptr` is `NULL`, convert the whole string. Raise `ValueError` and return `-1.0` if the string is not a valid representation of a floating-point number.

If endptr is not `NULL`, convert as much of the string as possible and set `*endptr` to point to the first unconverted character. If no initial segment of the string is the valid representation of a floating-point number, set `*endptr` to point to the beginning of the string, raise ValueError, and return `-1.0`.

If `s` represents a value that is too large to store in a float (for example, `"1e500"` is such a string on many platforms) then if `overflow_exception` is `NULL` return `Py_INFINITY` (with an appropriate sign) and don't set any exception. Otherwise, `overflow_exception` must point to a Python exception object; raise that exception and return `-1.0`. In both cases, set `*endptr` to point to the first character after the converted value.

If any other error occurs during the conversion (for example an out-of-memory error), set the appropriate Python exception and return `-1.0`.

Added in version 3.1.

char ***PyOS_double_to_string**(double val, char format_code, int precision, int flags, int *ptype)

Bir parçası Kararlı ABI. Convert a `double` *val* to a string using supplied *format_code*, *precision*, and *flags*.

format_code must be one of `'e'`, `'E'`, `'f'`, `'F'`, `'g'`, `'G'` or `'r'`. For `'r'`, the supplied *precision* must be 0 and is ignored. The `'r'` format code specifies the standard `repr()` format.

flags can be zero or more of the values `Py_DTSF_SIGN`, `Py_DTSF_ADD_DOT_0`, or `Py_DTSF_ALT`, or-ed together:

- `Py_DTSF_SIGN` means to always precede the returned string with a sign character, even if *val* is non-negative.
- `Py_DTSF_ADD_DOT_0` means to ensure that the returned string will not look like an integer.
- `Py_DTSF_ALT` means to apply "alternate" formatting rules. See the documentation for the *PyOS_snprintf()* `'#'` specifier for details.

If *ptype* is non-`NULL`, then the value it points to will be set to one of `Py_DTST_FINITE`, `Py_DTST_INFINITE`, or `Py_DTST_NAN`, signifying that *val* is a finite number, an infinite number, or not a number, respectively.

The return value is a pointer to *buffer* with the converted string or `NULL` if the conversion failed. The caller is responsible for freeing the returned string by calling *PyMem_Free()*.

Added in version 3.1.

int **PyOS_stricmp**(const char *s1, const char *s2)

Case insensitive comparison of strings. The function works almost identically to `strcmp()` except that it ignores the case.

int **PyOS_strnicmp**(const char *s1, const char *s2, *Py_ssize_t* size)

Case insensitive comparison of strings. The function works almost identically to `strncmp()` except that it ignores the case.

7.8 PyHash API

See also the *PyTypeObject.tp_hash* member and numeric-hash.

type **Py_hash_t**

Hash value type: signed integer.

Added in version 3.2.

type **Py_uhash_t**

Hash value type: unsigned integer.

Added in version 3.2.

PyHASH_MODULUS

The Mersenne prime `P = 2**n -1`, used for numeric hash scheme.

Added in version 3.13.

PyHASH_BITS

The exponent `n` of `P` in *PyHASH_MODULUS*.

Added in version 3.13.

PyHASH_MULTIPLIER

Prime multiplier used in string and various other hashes.

Added in version 3.13.

PyHASH_INF

The hash value returned for a positive infinity.

Added in version 3.13.

PyHASH_IMAG

The multiplier used for the imaginary part of a complex number.

Added in version 3.13.

type **PyHash_FuncDef**

Hash function definition used by *PyHash_GetFuncDef()*.

Py_hash_t (*const **hash**)(const void*, *Py_ssize_t*)

Hash function.

const char ***name**

Hash function name (UTF-8 encoded string).

const int **hash_bits**

Internal size of the hash value in bits.

const int **seed_bits**

Size of seed input in bits.

Added in version 3.4.

PyHash_FuncDef ***PyHash_GetFuncDef**(void)

Get the hash function definition.

> **Ayrıca bakınız**
>
> **PEP 456** "Secure and interchangeable hash algorithm".

Added in version 3.4.

Py_hash_t **Py_HashPointer**(const void *ptr)

Hash a pointer value: process the pointer value as an integer (cast it to `uintptr_t` internally). The pointer is not dereferenced.

The function cannot fail: it cannot return `-1`.

Added in version 3.13.

Py_hash_t **Py_HashBuffer**(const void *ptr, *Py_ssize_t* len)

Compute and return the hash value of a buffer of *len* bytes starting at address *ptr*. The hash is guaranteed to match that of `bytes`, `memoryview`, and other built-in objects that implement the *buffer protocol*.

Use this function to implement hashing for immutable objects whose *`tp_richcompare`* function compares to another object's buffer.

len must be greater than or equal to `0`.

This function always succeeds.

Added in version 3.14.

Py_hash_t **PyObject_GenericHash**(*PyObject* *obj)

Generic hashing function that is meant to be put into a type object's `tp_hash` slot. Its result only depends on the object's identity.

CPython uygulama ayrıntısı: In CPython, it is equivalent to *`Py_HashPointer()`*.

Added in version 3.13.

7.9 Reflection

PyObject ***PyEval_GetBuiltins**(void)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. 3.13 sürümünden beri kullanım dışı: Use *`PyEval_GetFrameBuiltins()`* instead.

Return a dictionary of the builtins in the current execution frame, or the interpreter of the thread state if no frame is currently executing.

PyObject ***PyEval_GetLocals**(void)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. 3.13 sürümünden beri kullanım dışı: Use either *`PyEval_GetFrameLocals()`* to obtain the same behaviour as calling `locals()` in Python code, or else call *`PyFrame_GetLocals()`* on the result of *`PyEval_GetFrame()`* to access the `f_locals` attribute of the currently executing frame.

Return a mapping providing access to the local variables in the current execution frame, or `NULL` if no frame is currently executing.

Refer to `locals()` for details of the mapping returned at different scopes.

As this function returns a *borrowed reference*, the dictionary returned for *optimized scopes* is cached on the frame object and will remain alive as long as the frame object does. Unlike *`PyEval_GetFrameLocals()`* and `locals()`, subsequent calls to this function in the same frame will update the contents of the cached dictionary to reflect changes in the state of the local variables rather than returning a new snapshot.

3.13 sürümünde değişti: As part of **PEP 667**, *`PyFrame_GetLocals()`*, `locals()`, and `FrameType.f_locals` no longer make use of the shared cache dictionary. Refer to the What's New entry for additional details.

PyObject ***PyEval_GetGlobals**(void)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. 3.13 sürümünden beri kullanım dışı: Use *`PyEval_GetFrameGlobals()`* instead.

Return a dictionary of the global variables in the current execution frame, or `NULL` if no frame is currently executing.

PyFrameObject ***PyEval_GetFrame**(void)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the *attached thread state*'s frame, which is `NULL` if no frame is currently executing.

See also `PyThreadState_GetFrame()`.

PyObject ***PyEval_GetFrameBuiltins**(void)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return a dictionary of the builtins in the current execution frame, or the interpreter of the thread state if no frame is currently executing.

Added in version 3.13.

PyObject ***PyEval_GetFrameLocals**(void)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return a dictionary of the local variables in the current execution frame, or `NULL` if no frame is currently executing. Equivalent to calling `locals()` in Python code.

To access `f_locals` on the current frame without making an independent snapshot in *optimized scopes*, call `PyFrame_GetLocals()` on the result of `PyEval_GetFrame()`.

Added in version 3.13.

PyObject ***PyEval_GetFrameGlobals**(void)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return a dictionary of the global variables in the current execution frame, or `NULL` if no frame is currently executing. Equivalent to calling `globals()` in Python code.

Added in version 3.13.

const char ***PyEval_GetFuncName**(*PyObject* *func)

Bir parçası Kararlı ABI. Return the name of *func* if it is a function, class or instance object, else the name of *func*s type.

const char ***PyEval_GetFuncDesc**(*PyObject* *func)

Bir parçası Kararlı ABI. Return a description string, depending on the type of *func*. Return values include "()" for functions and methods, " constructor", " instance", and " object". Concatenated with the result of `PyEval_GetFuncName()`, the result will be a description of *func*.

7.10 Codec registry and support functions

int **PyCodec_Register**(*PyObject* *search_function)

Bir parçası Kararlı ABI. Register a new codec search function.

As side effect, this tries to load the `encodings` package, if not yet done, to make sure that it is always first in the list of search functions.

int **PyCodec_Unregister**(*PyObject* *search_function)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Unregister a codec search function and clear the registry's cache. If the search function is not registered, do nothing. Return 0 on success. Raise an exception and return -1 on error.

Added in version 3.10.

int **PyCodec_KnownEncoding**(const char *encoding)

Bir parçası Kararlı ABI. Return `1` or `0` depending on whether there is a registered codec for the given *encoding*. This function always succeeds.

PyObject ***PyCodec_Encode**(*PyObject* *object, const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Generic codec based encoding API.

object is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be `NULL` to use the default method defined for the codec. Raises a `LookupError` if no encoder can be found.

PyObject ***PyCodec_Decode**(*PyObject* *object, const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Generic codec based decoding API.

object is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be `NULL` to use the default method defined for the codec. Raises a `LookupError` if no encoder can be found.

7.10.1 Codec lookup API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a `KeyError` is set and `NULL` returned.

PyObject ***PyCodec_Encoder**(const char *encoding)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get an encoder function for the given *encoding*.

PyObject ***PyCodec_Decoder**(const char *encoding)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get a decoder function for the given *encoding*.

PyObject ***PyCodec_IncrementalEncoder**(const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get an `IncrementalEncoder` object for the given *encoding*.

PyObject ***PyCodec_IncrementalDecoder**(const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get an `IncrementalDecoder` object for the given *encoding*.

PyObject ***PyCodec_StreamReader**(const char *encoding, *PyObject* *stream, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get a `StreamReader` factory function for the given *encoding*.

PyObject ***PyCodec_StreamWriter**(const char *encoding, *PyObject* *stream, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Get a `StreamWriter` factory function for the given *encoding*.

7.10.2 Registry API for Unicode encoding error handlers

int **PyCodec_RegisterError**(const char *name, *PyObject* *error)

Bir parçası Kararlı ABI. Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of `UnicodeEncodeError`, `UnicodeDecodeError` or `UnicodeTranslateError` that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Unicode Exception Objects* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

Return `0` on success, `-1` on error.

PyObject ***PyCodec_LookupError**(const char *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Lookup the error handling callback function registered under *name*. As a special case `NULL` can be passed, in which case the error handling callback for “strict” will be returned.

PyObject ***PyCodec_StrictErrors**(*PyObject* *exc)

Döndürdüğü değer: Her zaman NULL. Bir parçası Kararlı ABI. Raise *exc* as an exception.

PyObject ***PyCodec_IgnoreErrors**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Ignore the unicode error, skipping the faulty input.

PyObject ***PyCodec_ReplaceErrors**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Replace the unicode encode error with `?` or `U+FFFD`.

PyObject ***PyCodec_XMLCharRefReplaceErrors**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Replace the unicode encode error with XML character references.

PyObject ***PyCodec_BackslashReplaceErrors**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Replace the unicode encode error with backslash escapes (`\x`, `\u` and `\U`).

PyObject ***PyCodec_NameReplaceErrors**(*PyObject* *exc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Replace the unicode encode error with `\N{...}` escapes.

Added in version 3.5.

7.11 PyTime C API

Added in version 3.13.

The clock C API provides access to system clocks. It is similar to the Python `time` module.

For C API related to the `datetime` module, see *DateTime Objects*.

7.11.1 Types

type **PyTime_t**

A timestamp or duration in nanoseconds, represented as a signed 64-bit integer.

The reference point for timestamps depends on the clock used. For example, *PyTime_Time()* returns timestamps relative to the UNIX epoch.

The supported range is around [-292.3 years; +292.3 years]. Using the Unix epoch (January 1st, 1970) as reference, the supported date range is around [1677-09-21; 2262-04-11]. The exact limits are exposed as constants:

PyTime_t **PyTime_MIN**

Minimum value of *PyTime_t*.

PyTime_t **PyTime_MAX**

Maximum value of *PyTime_t*.

7.11.2 Clock Functions

The following functions take a pointer to a *PyTime_t* that they set to the value of a particular clock. Details of each clock are given in the documentation of the corresponding Python function.

The functions return `0` on success, or `-1` (with an exception set) on failure.

On integer overflow, they set the *PyExc_OverflowError* exception and set `*result` to the value clamped to the `[PyTime_MIN; PyTime_MAX]` range. (On current systems, integer overflows are likely caused by misconfigured system time.)

As any other C API (unless otherwise specified), the functions must be called with an *attached thread state*.

int **PyTime_Monotonic**(*PyTime_t* *result)

Read the monotonic clock. See `time.monotonic()` for important details on this clock.

int **PyTime_PerfCounter**(*PyTime_t* *result)

Read the performance counter. See `time.perf_counter()` for important details on this clock.

int **PyTime_Time**(*PyTime_t* *result)

Read the “wall clock” time. See `time.time()` for details important on this clock.

7.11.3 Raw Clock Functions

Similar to clock functions, but don't set an exception on error and don't require the caller to have an *attached thread state*.

On success, the functions return `0`.

On failure, they set `*result` to `0` and return `-1`, *without* setting an exception. To get the cause of the error, *attach* a *thread state*, and call the regular (non-`Raw`) function. Note that the regular function may succeed after the `Raw` one failed.

int **PyTime_MonotonicRaw**(*PyTime_t* *result)

Similar to `PyTime_Monotonic()`, but don't set an exception on error and don't require an *attached thread state*.

int **PyTime_PerfCounterRaw**(*PyTime_t* *result)

Similar to `PyTime_PerfCounter()`, but don't set an exception on error and don't require an *attached thread state*.

int **PyTime_TimeRaw**(*PyTime_t* *result)

Similar to `PyTime_Time()`, but don't set an exception on error and don't require an *attached thread state*.

7.11.4 Conversion functions

double **PyTime_AsSecondsDouble**(*PyTime_t* t)

Convert a timestamp to a number of seconds as a C `double`.

The function cannot fail, but note that `double` has limited accuracy for large values.

7.12 Support for Perf Maps

On supported platforms (as of this writing, only Linux), the runtime can take advantage of *perf map files* to make Python functions visible to an external profiling tool (such as perf). A running process may create a file in the `/tmp` directory, which contains entries that can map a section of executable code to a name. This interface is described in the documentation of the Linux Perf tool.

In Python, these helper APIs can be used by libraries and features that rely on generating machine code on the fly.

Note that holding an *attached thread state* is not required for these APIs.

int **PyUnstable_PerfMapState_Init**(void)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Open the `/tmp/perf-$pid.map` file, unless it's already opened, and create a lock to ensure thread-safe writes to the file (provided the writes are done through `PyUnstable_WritePerfMapEntry()`). Normally, there's no need to call this explicitly; just use `PyUnstable_WritePerfMapEntry()` and it will initialize the state on first call.

Returns `0` on success, `-1` on failure to create/open the perf map file, or `-2` on failure to create a lock. Check `errno` for more information about the cause of a failure.

int **PyUnstable_WritePerfMapEntry**(const void *code_addr, unsigned int code_size, const char *entry_name)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Write one single entry to the `/tmp/perf-$pid.map` file. This function is thread safe. Here is what an example entry looks like:

```
# address      size  name
7f3529fcf759 b     py::bar:/run/t.py
```

Will call *`PyUnstable_PerfMapState_Init()`* before writing the entry, if the perf map file is not already opened. Returns `0` on success, or the same error codes as *`PyUnstable_PerfMapState_Init()`* on failure.

void **`PyUnstable_PerfMapState_Fini`**(void)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Close the perf map file opened by *`PyUnstable_PerfMapState_Init()`*. This is called by the runtime itself during interpreter shut-down. In general, there shouldn't be a reason to explicitly call this, except to handle specific scenarios such as forking.

BÖLÜM 8

Abstract Objects Layer

The functions in this chapter interact with Python objects regardless of their type, or with wide classes of object types (e.g. all numerical types, or all sequence types). When used on object types for which they do not apply, they will raise a Python exception.

It is not possible to use these functions on objects that are not properly initialized, such as a list object that has been created by `PyList_New()`, but whose items have not been set to some non-`NULL` value yet.

8.1 Object Protocol

PyObject ***Py_GetConstant**(unsigned int constant_id)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Get a *strong reference* to a constant.

Set an exception and return `NULL` if *constant_id* is invalid.

constant_id must be one of these constant identifiers:

Constant Identifier	Value	Returned object
Py_CONSTANT_NONE	0	None
Py_CONSTANT_FALSE	1	False
Py_CONSTANT_TRUE	2	True
Py_CONSTANT_ELLIPSIS	3	Ellipsis
Py_CONSTANT_NOT_IMPLEMENTED	4	NotImplemented
Py_CONSTANT_ZERO	5	0
Py_CONSTANT_ONE	6	1
Py_CONSTANT_EMPTY_STR	7	''
Py_CONSTANT_EMPTY_BYTES	8	b''
Py_CONSTANT_EMPTY_TUPLE	9	()

Numeric values are only given for projects which cannot use the constant identifiers.

Added in version 3.13.

CPython uygulama ayrıntısı: In CPython, all of these constants are *immortal*.

PyObject ***Py_GetConstantBorrowed**(unsigned int constant_id)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to `Py_GetConstant()`, but return a *borrowed reference*.

This function is primarily intended for backwards compatibility: using `Py_GetConstant()` is recommended for new code.

The reference is borrowed from the interpreter, and is valid until the interpreter finalization.

Added in version 3.13.

PyObject ***Py_NotImplemented**

The `NotImplemented` singleton, used to signal that an operation is not implemented for the given type combination.

Py_RETURN_NOTIMPLEMENTED

Properly handle returning `Py_NotImplemented` from within a C function (that is, create a new *strong reference* to `NotImplemented` and return it).

Py_PRINT_RAW

Flag to be used with multiple functions that print the object (like `PyObject_Print()` and `PyFile_WriteObject()`). If passed, these function would use the `str()` of the object instead of the `repr()`.

int **PyObject_Print**(*PyObject* *o, FILE *fp, int flags)

Print an object *o*, on file *fp*. Returns `-1` on error. The flags argument is used to enable certain printing options. The only option currently supported is *Py_PRINT_RAW*; if given, the `str()` of the object is written instead of the `repr()`.

int **PyObject_HasAttrWithError**(*PyObject* *o, *PyObject* *attr_name)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Returns `1` if *o* has the attribute *attr_name*, and `0` otherwise. This is equivalent to the Python expression `hasattr(o, attr_name)`. On failure, return `-1`.

Added in version 3.13.

int **PyObject_HasAttrStringWithError**(*PyObject* *o, const char *attr_name)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* This is the same as *PyObject_HasAttrWithError()*, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

Added in version 3.13.

int **PyObject_HasAttr**(*PyObject* *o, *PyObject* *attr_name)

Bir parçası Kararlı ABI. Returns `1` if *o* has the attribute *attr_name*, and `0` otherwise. This function always succeeds.

> **Not**
>
> Exceptions that occur when this calls `__getattr__()` and `__getattribute__()` methods aren't propagated, but instead given to `sys.unraisablehook()`. For proper error handling, use *PyObject_HasAttrWithError()*, *PyObject_GetOptionalAttr()* or *PyObject_GetAttr()* instead.

int **PyObject_HasAttrString**(*PyObject* *o, const char *attr_name)

Bir parçası Kararlı ABI. This is the same as *PyObject_HasAttr()*, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

> **Not**
>
> Exceptions that occur when this calls `__getattr__()` and `__getattribute__()` methods or while creating the temporary `str` object are silently ignored. For proper error handling, use *PyObject_HasAttrStringWithError()*, *PyObject_GetOptionalAttrString()* or *PyObject_GetAttrString()* instead.

PyObject ***PyObject_GetAttr**(*PyObject* *o, *PyObject* *attr_name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Retrieve an attribute named *attr_name* from object *o*. Returns the attribute value on success, or `NULL` on failure. This is the equivalent of the Python expression `o.attr_name`.

If the missing attribute should not be treated as a failure, you can use *PyObject_GetOptionalAttr()* instead.

PyObject ***PyObject_GetAttrString**(*PyObject* *o, const char *attr_name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is the same as *PyObject_GetAttr()*, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

If the missing attribute should not be treated as a failure, you can use *PyObject_GetOptionalAttrString()* instead.

int **PyObject_GetOptionalAttr**(*PyObject* *obj, *PyObject* *attr_name, *PyObject* **result);

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Variant of *PyObject_GetAttr()* which doesn't raise `AttributeError` if the attribute is not found.

If the attribute is found, return `1` and set **result* to a new *strong reference* to the attribute. If the attribute is not found, return `0` and set **result* to `NULL`; the `AttributeError` is silenced. If an error other than `AttributeError` is raised, return `-1` and set **result* to `NULL`.

Added in version 3.13.

int **PyObject_GetOptionalAttrString**(*PyObject* *obj, const char *attr_name, *PyObject* **result);

Bir parçası Kararlı ABI *3.13 sürümünden beri.* This is the same as `PyObject_GetOptionalAttr()`, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

Added in version 3.13.

PyObject ***PyObject_GenericGetAttr**(*PyObject* *o, *PyObject* *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Generic attribute getter function that is meant to be put into a type object's `tp_getattro` slot. It looks for a descriptor in the dictionary of classes in the object's MRO as well as an attribute in the object's `__dict__` (if present). As outlined in descriptors, data descriptors take preference over instance attributes, while non-data descriptors don't. Otherwise, an `AttributeError` is raised.

int **PyObject_SetAttr**(*PyObject* *o, *PyObject* *attr_name, *PyObject* *v)

Bir parçası Kararlı ABI. Set the value of the attribute named *attr_name*, for object *o*, to the value *v*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o.attr_name = v`.

If *v* is `NULL`, the attribute is deleted. This behaviour is deprecated in favour of using `PyObject_DelAttr()`, but there are currently no plans to remove it.

int **PyObject_SetAttrString**(*PyObject* *o, const char *attr_name, *PyObject* *v)

Bir parçası Kararlı ABI. This is the same as `PyObject_SetAttr()`, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

If *v* is `NULL`, the attribute is deleted, but this feature is deprecated in favour of using `PyObject_DelAttrString()`.

The number of different attribute names passed to this function should be kept small, usually by using a statically allocated string as *attr_name*. For attribute names that aren't known at compile time, prefer calling `PyUnicode_FromString()` and `PyObject_SetAttr()` directly. For more details, see `PyUnicode_InternFromString()`, which may be used internally to create a key object.

int **PyObject_GenericSetAttr**(*PyObject* *o, *PyObject* *name, *PyObject* *value)

Bir parçası Kararlı ABI. Generic attribute setter and deleter function that is meant to be put into a type object's `tp_setattro` slot. It looks for a data descriptor in the dictionary of classes in the object's MRO, and if found it takes preference over setting or deleting the attribute in the instance dictionary. Otherwise, the attribute is set or deleted in the object's `__dict__` (if present). On success, `0` is returned, otherwise an `AttributeError` is raised and `-1` is returned.

int **PyObject_DelAttr**(*PyObject* *o, *PyObject* *attr_name)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Delete attribute named *attr_name*, for object *o*. Returns `-1` on failure. This is the equivalent of the Python statement `del o.attr_name`.

int **PyObject_DelAttrString**(*PyObject* *o, const char *attr_name)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* This is the same as `PyObject_DelAttr()`, but *attr_name* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

The number of different attribute names passed to this function should be kept small, usually by using a statically allocated string as *attr_name*. For attribute names that aren't known at compile time, prefer calling `PyUnicode_FromString()` and `PyObject_DelAttr()` directly. For more details, see `PyUnicode_InternFromString()`, which may be used internally to create a key object for lookup.

PyObject ***PyObject_GenericGetDict**(*PyObject* *o, void *context)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.10 sürümünden beri.* A generic implementation for the getter of a `__dict__` descriptor. It creates the dictionary if necessary.

This function may also be called to get the `__dict__` of the object *o*. Pass `NULL` for *context* when calling it. Since this function may need to allocate memory for the dictionary, it may be more efficient to call `PyObject_GetAttr()` when accessing an attribute on the object.

On failure, returns `NULL` with an exception set.

Added in version 3.3.

int **PyObject_GenericSetDict**(*PyObject* *o, *PyObject* *value, void *context)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* A generic implementation for the setter of a `__dict__` descriptor. This implementation does not allow the dictionary to be deleted.

Added in version 3.3.

PyObject ****_PyObject_GetDictPtr**(*PyObject* *obj)

Return a pointer to `__dict__` of the object *obj*. If there is no `__dict__`, return `NULL` without setting an exception.

This function may need to allocate memory for the dictionary, so it may be more efficient to call `PyObject_GetAttr()` when accessing an attribute on the object.

PyObject ***PyObject_RichCompare**(*PyObject* *o1, *PyObject* *o2, int opid)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Compare the values of *o1* and *o2* using the operation specified by *opid*, which must be one of `Py_LT`, `Py_LE`, `Py_EQ`, `Py_NE`, `Py_GT`, or `Py_GE`, corresponding to `<`, `<=`, `==`, `!=`, `>`, or `>=` respectively. This is the equivalent of the Python expression `o1 op o2`, where `op` is the operator corresponding to *opid*. Returns the value of the comparison on success, or `NULL` on failure.

int **PyObject_RichCompareBool**(*PyObject* *o1, *PyObject* *o2, int opid)

Bir parçası Kararlı ABI. Compare the values of *o1* and *o2* using the operation specified by *opid*, like `PyObject_RichCompare()`, but returns `-1` on error, `0` if the result is false, `1` otherwise.

Not

If *o1* and *o2* are the same object, `PyObject_RichCompareBool()` will always return `1` for `Py_EQ` and `0` for `Py_NE`.

PyObject ***PyObject_Format**(*PyObject* *obj, *PyObject* *format_spec)

Bir parçası Kararlı ABI. Format *obj* using *format_spec*. This is equivalent to the Python expression `format(obj, format_spec)`.

format_spec may be `NULL`. In this case the call is equivalent to `format(obj)`. Returns the formatted string on success, `NULL` on failure.

PyObject ***PyObject_Repr**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `repr(o)`. Called by the `repr()` built-in function.

3.4 sürümünde değişti: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

PyObject ***PyObject_ASCII**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. As `PyObject_Repr()`, compute a string representation of object *o*, but escape the non-ASCII characters in the string returned by `PyObject_Repr()` with `\x`, `\u` or `\U` escapes. This generates a string similar to that returned by `PyObject_Repr()` in Python 2. Called by the `ascii()` built-in function.

PyObject ***PyObject_Str**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Compute a string representation of object *o*. Returns the string representation on success, `NULL` on failure. This is the equivalent of the Python expression `str(o)`. Called by the `str()` built-in function and, therefore, by the `print()` function.

3.4 sürümünde değişti: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

PyObject ***PyObject_Bytes**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Compute a bytes representation of object *o*. `NULL` is returned on failure and a bytes object on success. This is equivalent to the Python expression `bytes(o)`, when *o* is not an integer. Unlike `bytes(o)`, a TypeError is raised when *o* is an integer instead of a zero-initialized bytes object.

int **PyObject_IsSubclass**(*PyObject* *derived, *PyObject* *cls)

Bir parçası Kararlı ABI. Return `1` if the class *derived* is identical to or derived from the class *cls*, otherwise return `0`. In case of an error, return `-1`.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be `1` when at least one of the checks returns `1`, otherwise it will be `0`.

If *cls* has a `__subclasscheck__()` method, it will be called to determine the subclass status as described in **PEP 3119**. Otherwise, *derived* is a subclass of *cls* if it is a direct or indirect subclass, i.e. contained in `cls.__mro__`.

Normally only class objects, i.e. instances of `type` or a derived class, are considered classes. However, objects can override this by having a `__bases__` attribute (which must be a tuple of base classes).

int **PyObject_IsInstance**(*PyObject* *inst, *PyObject* *cls)

Bir parçası Kararlı ABI. Return `1` if *inst* is an instance of the class *cls* or a subclass of *cls*, or `0` if not. On error, returns `-1` and sets an exception.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be `1` when at least one of the checks returns `1`, otherwise it will be `0`.

If *cls* has a `__instancecheck__()` method, it will be called to determine the subclass status as described in **PEP 3119**. Otherwise, *inst* is an instance of *cls* if its class is a subclass of *cls*.

An instance *inst* can override what is considered its class by having a `__class__` attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a `__bases__` attribute (which must be a tuple of base classes).

Py_hash_t **PyObject_Hash**(*PyObject* *o)

Bir parçası Kararlı ABI. Compute and return the hash value of an object *o*. On failure, return `-1`. This is the equivalent of the Python expression `hash(o)`.

3.2 sürümünde değişti: The return type is now Py_hash_t. This is a signed integer the same size as *Py_ssize_t*.

Py_hash_t **PyObject_HashNotImplemented**(*PyObject* *o)

Bir parçası Kararlı ABI. Set a `TypeError` indicating that `type(o)` is not *hashable* and return `-1`. This function receives special treatment when stored in a `tp_hash` slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

int **PyObject_IsTrue**(*PyObject* *o)

Bir parçası Kararlı ABI. Returns `1` if the object *o* is considered to be true, and `0` otherwise. This is equivalent to the Python expression `not not o`. On failure, return `-1`.

int **PyObject_Not**(*PyObject* *o)

Bir parçası Kararlı ABI. Returns `0` if the object *o* is considered to be true, and `1` otherwise. This is equivalent to the Python expression `not o`. On failure, return `-1`.

PyObject ***PyObject_Type**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. When *o* is non-`NULL`, returns a type object corresponding to the object type of object *o*. On failure, raises `SystemError` and returns `NULL`. This is equivalent to the Python expression `type(o)`. This function creates a new *strong reference* to the return value. There's really no reason to use this function instead of the *Py_TYPE()* function, which returns a pointer of type *PyTypeObject**, except when a new *strong reference* is needed.

int **PyObject_TypeCheck**(*PyObject* *o, *PyTypeObject* *type)

Return non-zero if the object *o* is of type *type* or a subtype of *type*, and `0` otherwise. Both parameters must be non-`NULL`.

Py_ssize_t **PyObject_Size**(*PyObject* *o)

Py_ssize_t **PyObject_Length**(*PyObject* *o)

Bir parçası Kararlı ABI. Return the length of object *o*. If the object *o* provides either the sequence and mapping protocols, the sequence length is returned. On error, `-1` is returned. This is the equivalent to the Python expression `len(o)`.

Py_ssize_t **PyObject_LengthHint**(*PyObject* *o, *Py_ssize_t* defaultvalue)

Return an estimated length for the object *o*. First try to return its actual length, then an estimate using `__length_hint__()`, and finally return the default value. On error return `-1`. This is the equivalent to the Python expression `operator.length_hint(o, defaultvalue)`.

Added in version 3.4.

PyObject ***PyObject_GetItem**(*PyObject* *o, *PyObject* *key)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return element of *o* corresponding to the object *key* or `NULL` on failure. This is the equivalent of the Python expression `o[key]`.

int **PyObject_SetItem**(*PyObject* *o, *PyObject* *key, *PyObject* *v)

Bir parçası Kararlı ABI. Map the object *key* to the value *v*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o[key] = v`. This function *does not* steal a reference to *v*.

int **PyObject_DelItem**(*PyObject* *o, *PyObject* *key)

Bir parçası Kararlı ABI. Remove the mapping for the object *key* from the object *o*. Return `-1` on failure. This is equivalent to the Python statement `del o[key]`.

int **PyObject_DelItemString**(*PyObject* *o, const char *key)

Bir parçası Kararlı ABI. This is the same as *PyObject_DelItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

PyObject ***PyObject_Dir**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is equivalent to the Python expression `dir(o)`, returning a (possibly empty) list of strings appropriate for the object argument, or `NULL` if there was an error. If the argument is `NULL`, this is like the Python `dir()`, returning the names of the current locals; in this case, if no execution frame is active then `NULL` is returned but *PyErr_Occurred()* will return false.

PyObject ***PyObject_GetIter**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is equivalent to the Python expression `iter(o)`. It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises `TypeError` and returns `NULL` if the object cannot be iterated.

PyObject ***PyObject_SelfIter**(*PyObject* *obj)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is equivalent to the Python `__iter__(self): return self` method. It is intended for *iterator* types, to be used in the *PyTypeObject.tp_iter* slot.

PyObject ***PyObject_GetAIter**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.10 sürümünden beri.* This is the equivalent to the Python expression `aiter(o)`. Takes an `AsyncIterable` object and returns an `AsyncIterator` for it. This is typically a new iterator but if the argument is an `AsyncIterator`, this returns itself. Raises `TypeError` and returns `NULL` if the object cannot be iterated.

Added in version 3.10.

void ***PyObject_GetTypeData**(*PyObject* *o, *PyTypeObject* *cls)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Get a pointer to subclass-specific data reserved for *cls*.

The object *o* must be an instance of *cls*, and *cls* must have been created using negative *PyType_Spec.basicsize*. Python does not check this.

On error, set an exception and return `NULL`.

Added in version 3.12.

Py_ssize_t **PyType_GetTypeDataSize**(*PyTypeObject* *cls)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Return the size of the instance memory space reserved for *cls*, i.e. the size of the memory `PyObject_GetTypeData()` returns.

This may be larger than requested using `-PyType_Spec.basicsize`; it is safe to use this larger size (e.g. with `memset()`).

The type *cls* **must** have been created using negative `PyType_Spec.basicsize`. Python does not check this.

On error, set an exception and return a negative value.

Added in version 3.12.

void ***PyObject_GetItemData**(*PyObject* *o)

Get a pointer to per-item data for a class with `Py_TPFLAGS_ITEMS_AT_END`.

On error, set an exception and return `NULL`. `TypeError` is raised if *o* does not have `Py_TPFLAGS_ITEMS_AT_END` set.

Added in version 3.12.

int **PyObject_VisitManagedDict**(*PyObject* *obj, *visitproc* visit, void *arg)

Visit the managed dictionary of *obj*.

This function must only be called in a traverse function of the type which has the `Py_TPFLAGS_MANAGED_DICT` flag set.

Added in version 3.13.

void **PyObject_ClearManagedDict**(*PyObject* *obj)

Clear the managed dictionary of *obj*.

This function must only be called in a traverse function of the type which has the `Py_TPFLAGS_MANAGED_DICT` flag set.

Added in version 3.13.

int **PyUnstable_Object_EnableDeferredRefcount**(*PyObject* *obj)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Enable deferred reference counting on *obj*, if supported by the runtime. In the *free-threaded* build, this allows the interpreter to avoid reference count adjustments to *obj*, which may improve multi-threaded performance. The tradeoff is that *obj* will only be deallocated by the tracing garbage collector, and not when the interpreter no longer has any references to it.

This function returns `1` if deferred reference counting is enabled on *obj*, and `0` if deferred reference counting is not supported or if the hint was ignored by the interpreter, such as when deferred reference counting is already enabled on *obj*. This function is thread-safe, and cannot fail.

This function does nothing on builds with the *GIL* enabled, which do not support deferred reference counting. This also does nothing if *obj* is not an object tracked by the garbage collector (see `gc.is_tracked()` and `PyObject_GC_IsTracked()`).

This function is intended to be used soon after *obj* is created, by the code that creates it, such as in the object's `tp_new` slot.

Added in version 3.14.

int **PyUnstable_Object_IsUniqueReferencedTemporary**(*PyObject* *obj)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Check if *obj* is a unique temporary object. Returns `1` if *obj* is known to be a unique temporary object, and `0` otherwise. This function cannot fail, but the check is conservative, and may return `0` in some cases even if *obj* is a unique temporary object.

If an object is a unique temporary, it is guaranteed that the current code has the only reference to the object. For arguments to C functions, this should be used instead of checking if the reference count is `1`. Starting with Python 3.14, the interpreter internally avoids some reference count modifications when loading objects onto the operands stack by *borrowing* references when possible, which means that a reference count of `1` by itself does not guarantee that a function argument uniquely referenced.

In the example below, `my_func` is called with a unique temporary object as its argument:

```
my_func([1, 2, 3])
```

In the example below, `my_func` is **not** called with a unique temporary object as its argument, even if its refcount is `1`:

```
my_list = [1, 2, 3]
my_func(my_list)
```

See also the function *Py_REFCNT()*.

Added in version 3.14.

int **PyUnstable_IsImmortal**(*PyObject* *obj)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

This function returns non-zero if *obj* is *immortal*, and zero otherwise. This function cannot fail.

Not

Objects that are immortal in one CPython version are not guaranteed to be immortal in another.

Added in version 3.14.

int **PyUnstable_TryIncRef**(*PyObject* *obj)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Increments the reference count of *obj* if it is not zero. Returns `1` if the object's reference count was successfully incremented. Otherwise, this function returns `0`.

PyUnstable_EnableTryIncRef() must have been called earlier on *obj* or this function may spuriously return `0` in the *free threading* build.

This function is logically equivalent to the following C code, except that it behaves atomically in the *free threading* build:

```
if (Py_REFCNT(op) > 0) {
   Py_INCREF(op);
   return 1;
}
return 0;
```

This is intended as a building block for managing weak references without the overhead of a Python *weak reference object*.

Typically, correct use of this function requires support from *obj*'s deallocator (`tp_dealloc`). For example, the following sketch could be adapted to implement a "weakmap" that works like a `WeakValueDictionary` for a specific type:

```
PyMutex mutex;

PyObject *
add_entry(weakmap_key_type *key, PyObject *value)
{
    PyUnstable_EnableTryIncRef(value);
    weakmap_type weakmap = ...;
    PyMutex_Lock(&mutex);
    weakmap_add_entry(weakmap, key, value);
    PyMutex_Unlock(&mutex);
    Py_RETURN_NONE;
}

PyObject *
get_value(weakmap_key_type *key)
{
    weakmap_type weakmap = ...;
    PyMutex_Lock(&mutex);
    PyObject *result = weakmap_find(weakmap, key);
    if (PyUnstable_TryIncRef(result)) {
        // `result` is safe to use
        PyMutex_Unlock(&mutex);
        return result;
    }
    // if we get here, `result` is starting to be garbage-collected,
    // but has not been removed from the weakmap yet
    PyMutex_Unlock(&mutex);
    return NULL;
}

// tp_dealloc function for weakmap values
void
value_dealloc(PyObject *value)
{
    weakmap_type weakmap = ...;
    PyMutex_Lock(&mutex);
    weakmap_remove_value(weakmap, value);

    ...
    PyMutex_Unlock(&mutex);
}
```

Added in version 3.14.

void **PyUnstable_EnableTryIncRef**(*PyObject* *obj)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Enables subsequent uses of `PyUnstable_TryIncRef()` on *obj*. The caller must hold a *strong reference* to *obj* when calling this.

Added in version 3.14.

int **PyUnstable_Object_IsUniquelyReferenced**(*PyObject* *op)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Determine if *op* only has one reference.

On GIL-enabled builds, this function is equivalent to `Py_REFCNT(op) == 1`.

On a *free threaded* build, this checks if *op*'s *reference count* is equal to one and additionally checks if *op* is only used by this thread. `Py_REFCNT(op) == 1` is **not** thread-safe on free threaded builds; prefer this function.

The caller must hold an *attached thread state*, despite the fact that this function doesn't call into the Python interpreter. This function cannot fail.

Added in version 3.14.

8.2 Call Protocol

CPython supports two different calling protocols: *tp_call* and vectorcall.

8.2.1 The *tp_call* Protocol

Instances of classes that set `tp_call` are callable. The signature of the slot is:

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

A call is made using a tuple for the positional arguments and a dict for the keyword arguments, similarly to `callable(*args, **kwargs)` in Python code. *args* must be non-NULL (use an empty tuple if there are no arguments) but *kwargs* may be *NULL* if there are no keyword arguments.

This convention is not only used by *tp_call*: `tp_new` and `tp_init` also pass arguments this way.

To call an object, use `PyObject_Call()` or another *call API*.

8.2.2 The Vectorcall Protocol

Added in version 3.9.

The vectorcall protocol was introduced in **PEP 590** as an additional protocol for making calls more efficient.

As rule of thumb, CPython will prefer the vectorcall for internal calls if the callable supports it. However, this is not a hard rule. Additionally, some third-party extensions use *tp_call* directly (rather than using `PyObject_Call()`). Therefore, a class supporting vectorcall must also implement `tp_call`. Moreover, the callable must behave the same regardless of which protocol is used. The recommended way to achieve this is by setting `tp_call` to `PyVectorcall_Call()`. This bears repeating:

Uyarı

A class supporting vectorcall **must** also implement *tp_call* with the same semantics.

3.12 sürümünde değişti: The *Py_TPFLAGS_HAVE_VECTORCALL* flag is now removed from a class when the class's `__call__()` method is reassigned. (This internally sets *tp_call* only, and thus may make it behave differently than the vectorcall function.) In earlier Python versions, vectorcall should only be used with *immutable* or static types.

A class should not implement vectorcall if that would be slower than *tp_call*. For example, if the callee needs to convert the arguments to an args tuple and kwargs dict anyway, then there is no point in implementing vectorcall.

Classes can implement the vectorcall protocol by enabling the *Py_TPFLAGS_HAVE_VECTORCALL* flag and setting *tp_vectorcall_offset* to the offset inside the object structure where a *vectorcallfunc* appears. This is a pointer to a function with the following signature:

typedef *PyObject* *(***vectorcallfunc**)(*PyObject* *callable, *PyObject* *const *args, size_t nargsf, *PyObject* *kwnames)

Bir parçası Kararlı ABI *3.12 sürümünden beri.*

- *callable* is the object being called.
- ***args* is a C array consisting of the positional arguments followed by the** values of the keyword arguments. This can be *NULL* if there are no arguments.
- ***nargsf* is the number of positional arguments plus possibly the** *PY_VECTORCALL_ARGUMENTS_OFFSET* flag. To get the actual number of positional arguments from *nargsf*, use *PyVectorcall_NARGS()*.
- ***kwnames* is a tuple containing the names of the keyword arguments;** in other words, the keys of the kwargs dict. These names must be strings (instances of `str` or a subclass) and they must be unique. If there are no keyword arguments, then *kwnames* can instead be *NULL*.

PY_VECTORCALL_ARGUMENTS_OFFSET

Bir parçası Kararlı ABI *3.12 sürümünden beri.* If this flag is set in a vectorcall *nargsf* argument, the callee is allowed to temporarily change `args[-1]`. In other words, *args* points to argument 1 (not 0) in the allocated vector. The callee must restore the value of `args[-1]` before returning.

For *PyObject_VectorcallMethod()*, this flag means instead that `args[0]` may be changed.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use *PY_VECTORCALL_ARGUMENTS_OFFSET*. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) very efficiently.

Added in version 3.8.

To call an object that implements vectorcall, use a *call API* function as with any other callable. *PyObject_Vectorcall()* will usually be most efficient.

Recursion Control

When using *tp_call*, callees do not need to worry about *recursion*: CPython uses *Py_EnterRecursiveCall()* and *Py_LeaveRecursiveCall()* for calls made using *tp_call*.

For efficiency, this is not the case for calls done using vectorcall: the callee should use *Py_EnterRecursiveCall* and *Py_LeaveRecursiveCall* if needed.

Vectorcall Support API

Py_ssize_t **PyVectorcall_NARGS**(size_t nargsf)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Given a vectorcall *nargsf* argument, return the actual number of arguments. Currently equivalent to:

```
(Py_ssize_t)(nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET)
```

However, the function `PyVectorcall_NARGS` should be used to allow for future extensions.

Added in version 3.8.

vectorcallfunc **PyVectorcall_Function**(*PyObject* *op)

If *op* does not support the vectorcall protocol (either because the type does not or because the specific instance does not), return *NULL*. Otherwise, return the vectorcall function pointer stored in *op*. This function never raises an exception.

This is mostly useful to check whether or not *op* supports vectorcall, which can be done by checking `PyVectorcall_Function(op) != NULL`.

Added in version 3.9.

PyObject ***PyVectorcall_Call**(*PyObject* *callable, *PyObject* *tuple, *PyObject* *dict)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Call *callable*'s *vectorcallfunc* with positional and keyword arguments given in a tuple and dict, respectively.

This is a specialized function, intended to be put in the *tp_call* slot or be used in an implementation of `tp_call`. It does not check the *Py_TPFLAGS_HAVE_VECTORCALL* flag and it does not fall back to `tp_call`.

Added in version 3.8.

8.2.3 Object Calling API

Various functions are available for calling a Python object. Each converts its arguments to a convention supported by the called object – either *tp_call* or vectorcall. In order to do as little conversion as possible, pick one that best fits the format of data you have available.

The following table summarizes the available functions; please see individual documentation for details.

Function	callable	args	kwargs
PyObject_Call()	`PyObject *`	tuple	dict/`NULL`
PyObject_CallNoArgs()	`PyObject *`	—	—
PyObject_CallOneArg()	`PyObject *`	1 object	—
PyObject_CallObject()	`PyObject *`	tuple/`NULL`	—
PyObject_CallFunction()	`PyObject *`	format	—
PyObject_CallMethod()	obj + `char*`	format	—
PyObject_CallFunctionObjArgs()	`PyObject *`	variadic	—
PyObject_CallMethodObjArgs()	obj + name	variadic	—
PyObject_CallMethodNoArgs()	obj + name	—	—
PyObject_CallMethodOneArg()	obj + name	1 object	—
PyObject_Vectorcall()	`PyObject *`	vectorcall	vectorcall
PyObject_VectorcallDict()	`PyObject *`	vectorcall	dict/`NULL`
PyObject_VectorcallMethod()	arg + name	vectorcall	vectorcall

PyObject ***PyObject_Call**(*PyObject* *callable, *PyObject* *args, *PyObject* *kwargs)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call a callable Python object *callable*, with arguments given by the tuple *args*, and named arguments given by the dictionary *kwargs*.

args must not be *NULL*; use an empty tuple if no arguments are needed. If no named arguments are needed, *kwargs* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args, **kwargs)`.

PyObject ***PyObject_CallNoArgs**(*PyObject* *callable)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.10 sürümünden beri.* Call a callable Python object *callable* without any arguments. It is the most efficient way to call a callable Python object without any argument.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

PyObject ***PyObject_CallOneArg**(*PyObject* *callable, *PyObject* *arg)

Döndürdüğü değer: Yeni referans. Call a callable Python object *callable* with exactly 1 positional argument *arg* and no keyword arguments.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

PyObject ***PyObject_CallObject**(*PyObject* *callable, *PyObject* *args)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call a callable Python object *callable*, with arguments given by the tuple *args*. If no arguments are needed, then *args* can be *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args)`.

PyObject ***PyObject_CallFunction**(*PyObject* *callable, const char *format, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call a callable Python object *callable*, with a variable number of C arguments. The C arguments are described using a *Py_BuildValue()* style format string. The format can be *NULL*, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(*args)`.

Note that if you only pass *PyObject** args, *PyObject_CallFunctionObjArgs()* is a faster alternative.

3.4 sürümünde değişti: The type of *format* was changed from `char *`.

PyObject ***PyObject_CallMethod**(*PyObject* *obj, const char *name, const char *format, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call the method named *name* of object *obj* with a variable number of C arguments. The C arguments are described by a *Py_BuildValue()* format string that should produce a tuple.

The format can be *NULL*, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `obj.name(arg1, arg2, ...)`.

Note that if you only pass *PyObject** args, *PyObject_CallMethodObjArgs()* is a faster alternative.

3.4 sürümünde değişti: The types of *name* and *format* were changed from `char *`.

PyObject ***PyObject_CallFunctionObjArgs**(*PyObject* *callable, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call a callable Python object *callable*, with a variable number of *PyObject** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

This is the equivalent of the Python expression: `callable(arg1, arg2, ...)`.

PyObject ***PyObject_CallMethodObjArgs**(*PyObject* *obj, *PyObject* *name, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Call a method of the Python object *obj*, where the name of the method is given as a Python string object in *name*. It is called with a variable number of *PyObject** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

PyObject ***PyObject_CallMethodNoArgs**(*PyObject* *obj, *PyObject* *name)

Call a method of the Python object *obj* without arguments, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

PyObject ***PyObject_CallMethodOneArg**(*PyObject* *obj, *PyObject* *name, *PyObject* *arg)

Call a method of the Python object *obj* with a single positional argument *arg*, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

PyObject ***PyObject_Vectorcall**(*PyObject* *callable, *PyObject* *const *args, size_t nargsf, *PyObject* *kwnames)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Call a callable Python object *callable*. The arguments are the same as for `vectorcallfunc`. If *callable* supports *vectorcall*, this directly calls the vectorcall function stored in *callable*.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

PyObject ***PyObject_VectorcallDict**(*PyObject* *callable, *PyObject* *const *args, size_t nargsf, *PyObject* *kwdict)

Call *callable* with positional arguments passed exactly as in the *vectorcall* protocol, but with keyword arguments passed as a dictionary *kwdict*. The *args* array contains only the positional arguments.

Regardless of which protocol is used internally, a conversion of arguments needs to be done. Therefore, this function should only be used if the caller already has a dictionary ready to use for the keyword arguments, but not a tuple for the positional arguments.

Added in version 3.9.

PyObject ***PyObject_VectorcallMethod**(*PyObject* *name, *PyObject* *const *args, size_t nargsf, *PyObject* *kwnames)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Call a method using the vectorcall calling convention. The name of the method is given as a Python string *name*. The object whose method is called is *args[0]*, and the *args* array starting at *args[1]* represents the arguments of the call. There must be at least one positional argument. *nargsf* is the number of positional arguments including *args[0]*, plus `PY_VECTORCALL_ARGUMENTS_OFFSET` if the value of `args[0]` may temporarily be changed. Keyword arguments can be passed just like in `PyObject_Vectorcall()`.

If the object has the `Py_TPFLAGS_METHOD_DESCRIPTOR` feature, this will call the unbound method object with the full *args* vector as arguments.

Return the result of the call on success, or raise an exception and return *NULL* on failure.

Added in version 3.9.

8.2.4 Call Support API

int **PyCallable_Check**(*PyObject* *o)

Bir parçası Kararlı ABI. Determine if the object *o* is callable. Return `1` if the object is callable and `0` otherwise. This function always succeeds.

8.3 Number Protocol

int **PyNumber_Check**(*PyObject* *o)

Bir parçası Kararlı ABI. Returns `1` if the object *o* provides numeric protocols, and false otherwise. This function always succeeds.

3.8 sürümünde değişti: Returns `1` if *o* is an index integer.

PyObject ***PyNumber_Add**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of adding *o1* and *o2*, or `NULL` on failure. This is the equivalent of the Python expression `o1 + o2`.

PyObject ***PyNumber_Subtract**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of subtracting *o2* from *o1*, or `NULL` on failure. This is the equivalent of the Python expression `o1 - o2`.

PyObject ***PyNumber_Multiply**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of multiplying *o1* and *o2*, or `NULL` on failure. This is the equivalent of the Python expression `o1 * o2`.

PyObject ***PyNumber_MatrixMultiply**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Returns the result of matrix multiplication on *o1* and *o2*, or `NULL` on failure. This is the equivalent of the Python expression `o1 @ o2`.

Added in version 3.5.

PyObject ***PyNumber_FloorDivide**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the floor of *o1* divided by *o2*, or `NULL` on failure. This is the equivalent of the Python expression `o1 // o2`.

PyObject ***PyNumber_TrueDivide**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or `NULL` on failure. The return value is "approximate" because binary floating-point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating-point value when passed two integers. This is the equivalent of the Python expression `o1 / o2`.

PyObject ***PyNumber_Remainder**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the remainder of dividing *o1* by *o2*, or `NULL` on failure. This is the equivalent of the Python expression `o1 % o2`.

PyObject ***PyNumber_Divmod**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. See the built-in function `divmod()`. Returns `NULL` on failure. This is the equivalent of the Python expression `divmod(o1, o2)`.

PyObject ***PyNumber_Power**(*PyObject* *o1, *PyObject* *o2, *PyObject* *o3)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. See the built-in function `pow()`. Returns `NULL` on failure. This is the equivalent of the Python expression `pow(o1, o2, o3)`, where *o3* is optional. If *o3* is to be ignored, pass *Py_None* in its place (passing `NULL` for *o3* would cause an illegal memory access).

PyObject ***PyNumber_Negative**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the negation of *o* on success, or `NULL` on failure. This is the equivalent of the Python expression `-o`.

PyObject ***PyNumber_Positive**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns *o* on success, or `NULL` on failure. This is the equivalent of the Python expression `+o`.

PyObject ***PyNumber_Absolute**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the absolute value of *o*, or `NULL` on failure. This is the equivalent of the Python expression `abs(o)`.

PyObject ***PyNumber_Invert**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the bitwise negation of *o* on success, or `NULL` on failure. This is the equivalent of the Python expression `~o`.

PyObject ***PyNumber_Lshift**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of left shifting *o1* by *o2* on success, or `NULL` on failure. This is the equivalent of the Python expression `o1 << o2`.

PyObject ***PyNumber_Rshift**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of right shifting *o1* by *o2* on success, or `NULL` on failure. This is the equivalent of the Python expression `o1 >> o2`.

PyObject ***PyNumber_And**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise and" of *o1* and *o2* on success and `NULL` on failure. This is the equivalent of the Python expression `o1 & o2`.

PyObject ***PyNumber_Xor**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise exclusive or" of *o1* by *o2* on success, or `NULL` on failure. This is the equivalent of the Python expression `o1 ^ o2`.

PyObject ***PyNumber_Or**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise or" of *o1* and *o2* on success, or `NULL` on failure. This is the equivalent of the Python expression `o1 | o2`.

PyObject ***PyNumber_InPlaceAdd**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of adding *o1* and *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 += o2`.

PyObject ***PyNumber_InPlaceSubtract**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of subtracting *o2* from *o1*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 -= o2`.

PyObject ***PyNumber_InPlaceMultiply**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of multiplying *o1* and *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 *= o2`.

PyObject ***PyNumber_InPlaceMatrixMultiply**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Returns the result of matrix multiplication on *o1* and *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 @= o2`.

Added in version 3.5.

PyObject ***PyNumber_InPlaceFloorDivide**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the mathematical floor of dividing *o1* by *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 //= o2`.

PyObject ***PyNumber_InPlaceTrueDivide**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or `NULL` on failure. The return value is "approximate" because binary floating-point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating-point value when passed two integers. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 /= o2`.

PyObject ***PyNumber_InPlaceRemainder**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the remainder of dividing *o1* by *o2*, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 %= o2`.

PyObject ***PyNumber_InPlacePower**(*PyObject* *o1, *PyObject* *o2, *PyObject* *o3)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. See the built-in function `pow()`. Returns `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 ** = o2` when o3 is `Py_None`, or an in-place variant of `pow(o1, o2, o3)` otherwise. If *o3* is to be ignored, pass `Py_None` in its place (passing `NULL` for *o3* would cause an illegal memory access).

PyObject ***PyNumber_InPlaceLshift**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of left shifting *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 << = o2`.

PyObject ***PyNumber_InPlaceRshift**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the result of right shifting *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 >> = o2`.

PyObject ***PyNumber_InPlaceAnd**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise and" of *o1* and *o2* on success and `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 & = o2`.

PyObject ***PyNumber_InPlaceXor**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise exclusive or" of *o1* by *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 ^= o2`.

PyObject ***PyNumber_InPlaceOr**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the "bitwise or" of *o1* and *o2* on success, or `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement `o1 | = o2`.

PyObject ***PyNumber_Long**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the *o* converted to an integer object on success, or `NULL` on failure. This is the equivalent of the Python expression `int(o)`.

PyObject ***PyNumber_Float**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the *o* converted to a float object on success, or `NULL` on failure. This is the equivalent of the Python expression `float(o)`.

PyObject ***PyNumber_Index**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the *o* converted to a Python int on success or `NULL` with a `TypeError` exception raised on failure.

3.10 sürümünde değişti: The result always has exact type `int`. Previously, the result could have been an instance of a subclass of `int`.

PyObject ***PyNumber_ToBase**(*PyObject* *n, int base)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Returns the integer *n* converted to base *base* as a string. The *base* argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of `'0b'`, `'0o'`, or `'0x'`, respectively. If *n* is not a Python int, it is converted with `PyNumber_Index()` first.

Py_ssize_t **PyNumber_AsSsize_t**(*PyObject* *o, *PyObject* *exc)

Bir parçası Kararlı ABI. Returns *o* converted to a `Py_ssize_t` value if *o* can be interpreted as an integer. If the call fails, an exception is raised and `-1` is returned.

If *o* can be converted to a Python int but the attempt to convert to a `Py_ssize_t` value would raise an `OverflowError`, then the *exc* argument is the type of exception that will be raised (usually `IndexError` or `OverflowError`). If *exc* is `NULL`, then the exception is cleared and the value is clipped to `PY_SSIZE_T_MIN` for a negative integer or `PY_SSIZE_T_MAX` for a positive integer.

int **PyIndex_Check**(*PyObject* *o)

Bir parçası Kararlı ABI *3.8 sürümünden beri.* Returns `1` if *o* is an index integer (has the `nb_index` slot of the `tp_as_number` structure filled in), and `0` otherwise. This function always succeeds.

8.4 Sequence Protocol

int **PySequence_Check**(*PyObject* *o)

Bir parçası Kararlı ABI. Return `1` if the object provides the sequence protocol, and `0` otherwise. Note that it returns `1` for Python classes with a `__getitem__()` method, unless they are `dict` subclasses, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

Py_ssize_t **PySequence_Size**(*PyObject* *o)

Py_ssize_t **PySequence_Length**(*PyObject* *o)

Bir parçası Kararlı ABI. Returns the number of objects in sequence *o* on success, and `-1` on failure. This is equivalent to the Python expression `len(o)`.

PyObject ***PySequence_Concat**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the concatenation of *o1* and *o2* on success, and `NULL` on failure. This is the equivalent of the Python expression `o1 + o2`.

PyObject ***PySequence_Repeat**(*PyObject* *o, *Py_ssize_t* count)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the result of repeating sequence object *o* *count* times, or `NULL` on failure. This is the equivalent of the Python expression `o * count`.

PyObject ***PySequence_InPlaceConcat**(*PyObject* *o1, *PyObject* *o2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the concatenation of *o1* and *o2* on success, and `NULL` on failure. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python expression `o1 += o2`.

PyObject ***PySequence_InPlaceRepeat**(*PyObject* *o, *Py_ssize_t* count)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the result of repeating sequence object *o* *count* times, or `NULL` on failure. The operation is done *in-place* when *o* supports it. This is the equivalent of the Python expression `o *= count`.

PyObject ***PySequence_GetItem**(*PyObject* *o, *Py_ssize_t* i)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the *i*th element of *o*, or `NULL` on failure. This is the equivalent of the Python expression `o[i]`.

PyObject ***PySequence_GetSlice**(*PyObject* *o, *Py_ssize_t* i1, *Py_ssize_t* i2)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the slice of sequence object *o* between *i1* and *i2*, or `NULL` on failure. This is the equivalent of the Python expression `o[i1:i2]`.

int **PySequence_SetItem**(*PyObject* *o, *Py_ssize_t* i, *PyObject* *v)

Bir parçası Kararlı ABI. Assign object *v* to the *i*th element of *o*. Raise an exception and return `-1` on failure; return `0` on success. This is the equivalent of the Python statement `o[i] = v`. This function *does not* steal a reference to *v*.

If *v* is `NULL`, the element is deleted, but this feature is deprecated in favour of using *PySequence_DelItem()*.

int **PySequence_DelItem**(*PyObject* *o, *Py_ssize_t* i)

Bir parçası Kararlı ABI. Delete the *i*th element of object *o*. Returns `-1` on failure. This is the equivalent of the Python statement `del o[i]`.

int **PySequence_SetSlice**(*PyObject* *o, *Py_ssize_t* i1, *Py_ssize_t* i2, *PyObject* *v)

Bir parçası Kararlı ABI. Assign the sequence object *v* to the slice in sequence object *o* from *i1* to *i2*. This is the equivalent of the Python statement `o[i1:i2] = v`.

int **PySequence_DelSlice**(*PyObject* *o, *Py_ssize_t* i1, *Py_ssize_t* i2)

Bir parçası Kararlı ABI. Delete the slice in sequence object *o* from *i1* to *i2*. Returns `-1` on failure. This is the equivalent of the Python statement `del o[i1:i2]`.

Py_ssize_t **PySequence_Count**(*PyObject* *o, *PyObject* *value)

Bir parçası Kararlı ABI. Return the number of occurrences of *value* in *o*, that is, return the number of keys for which `o[key] == value`. On failure, return `-1`. This is equivalent to the Python expression `o.count(value)`.

int **PySequence_Contains**(*PyObject* *o, *PyObject* *value)

Bir parçası Kararlı ABI. Determine if *o* contains *value*. If an item in *o* is equal to *value*, return `1`, otherwise return `0`. On error, return `-1`. This is equivalent to the Python expression `value in o`.

int **PySequence_In**(*PyObject* *o, *PyObject* *value)

Bir parçası Kararlı ABI. Alias for *PySequence_Contains()*.

3.14 sürümünden beri kullanım dışı: The function is *soft deprecated* and should no longer be used to write new code.

Py_ssize_t **PySequence_Index**(*PyObject* *o, *PyObject* *value)

Bir parçası Kararlı ABI. Return the first index *i* for which `o[i] == value`. On error, return `-1`. This is equivalent to the Python expression `o.index(value)`.

PyObject ***PySequence_List**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a list object with the same contents as the sequence or iterable *o*, or `NULL` on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression `list(o)`.

PyObject ***PySequence_Tuple**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a tuple object with the same contents as the sequence or iterable *o*, or `NULL` on failure. If *o* is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression `tuple(o)`.

PyObject ***PySequence_Fast**(*PyObject* *o, const char *m)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the sequence or iterable *o* as an object usable by the other `PySequence_Fast*` family of functions. If the object is not a sequence or iterable, raises `TypeError` with *m* as the message text. Returns `NULL` on failure.

The `PySequence_Fast*` functions are thus named because they assume *o* is a *PyTupleObject* or a *PyListObject* and access the data fields of *o* directly.

As a CPython implementation detail, if *o* is already a sequence or list, it will be returned.

Py_ssize_t **PySequence_Fast_GET_SIZE**(*PyObject* *o)

Returns the length of *o*, assuming that *o* was returned by *PySequence_Fast()* and that *o* is not `NULL`. The size can also be retrieved by calling *PySequence_Size()* on *o*, but *PySequence_Fast_GET_SIZE()* is faster because it can assume *o* is a list or tuple.

PyObject ***PySequence_Fast_GET_ITEM**(*PyObject* *o, *Py_ssize_t* i)

Döndürdüğü değer: Ödünç alınmış referans. Return the *i*th element of *o*, assuming that *o* was returned by *PySequence_Fast()*, *o* is not `NULL`, and that *i* is within bounds.

PyObject ****PySequence_Fast_ITEMS**(*PyObject* *o)

Return the underlying array of PyObject pointers. Assumes that *o* was returned by *PySequence_Fast()* and *o* is not `NULL`.

Note, if a list gets resized, the reallocation may relocate the items array. So, only use the underlying array pointer in contexts where the sequence cannot change.

PyObject ***PySequence_ITEM**(*PyObject* *o, *Py_ssize_t* i)

Döndürdüğü değer: Yeni referans. Return the *i*th element of *o* or `NULL` on failure. Faster form of *PySequence_GetItem()* but without checking that *PySequence_Check()* on *o* is true and without adjustment for negative indices.

8.5 Mapping Protocol

See also *PyObject_GetItem()*, *PyObject_SetItem()* and *PyObject_DelItem()*.

int **PyMapping_Check**(*PyObject* *o)

Bir parçası Kararlı ABI. Return `1` if the object provides the mapping protocol or supports slicing, and `0` otherwise. Note that it returns `1` for Python classes with a `__getitem__()` method, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

Py_ssize_t **PyMapping_Size**(*PyObject* *o)

Py_ssize_t **PyMapping_Length**(*PyObject* *o)

Bir parçası Kararlı ABI. Returns the number of keys in object *o* on success, and `-1` on failure. This is equivalent to the Python expression `len(o)`.

PyObject ***PyMapping_GetItemString**(*PyObject* *o, const char *key)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is the same as *PyObject_GetItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

int **PyMapping_GetOptionalItem**(*PyObject* *obj, *PyObject* *key, *PyObject* **result)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Variant of *PyObject_GetItem()* which doesn't raise `KeyError` if the key is not found.

If the key is found, return `1` and set **result* to a new *strong reference* to the corresponding value. If the key is not found, return `0` and set **result* to `NULL`; the `KeyError` is silenced. If an error other than `KeyError` is raised, return `-1` and set **result* to `NULL`.

Added in version 3.13.

int **PyMapping_GetOptionalItemString**(*PyObject* *obj, const char *key, *PyObject* **result)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* This is the same as *PyMapping_GetOptionalItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

Added in version 3.13.

int **PyMapping_SetItemString**(*PyObject* *o, const char *key, *PyObject* *v)

Bir parçası Kararlı ABI. This is the same as *PyObject_SetItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

int **PyMapping_DelItem**(*PyObject* *o, *PyObject* *key)

This is an alias of *PyObject_DelItem()*.

int **PyMapping_DelItemString**(*PyObject* *o, const char *key)

This is the same as *PyObject_DelItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

int **PyMapping_HasKeyWithError**(*PyObject* *o, *PyObject* *key)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return `1` if the mapping object has the key *key* and `0` otherwise. This is equivalent to the Python expression `key in o`. On failure, return `-1`.

Added in version 3.13.

int **PyMapping_HasKeyStringWithError**(*PyObject* *o, const char *key)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* This is the same as *PyMapping_HasKeyWithError()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

Added in version 3.13.

int **PyMapping_HasKey**(*PyObject* *o, *PyObject* *key)

Bir parçası Kararlı ABI. Return `1` if the mapping object has the key *key* and `0` otherwise. This is equivalent to the Python expression `key in o`. This function always succeeds.

> **Not**
>
> Exceptions which occur when this calls `__getitem__()` method are silently ignored. For proper error handling, use *PyMapping_HasKeyWithError()*, *PyMapping_GetOptionalItem()* or *PyObject_GetItem()* instead.

int **PyMapping_HasKeyString**(*PyObject* *o, const char *key)

Bir parçası Kararlı ABI. This is the same as *PyMapping_HasKey()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

> **Not**
>
> Exceptions that occur when this calls `__getitem__()` method or while creating the temporary `str` object are silently ignored. For proper error handling, use *PyMapping_HasKeyStringWithError()*, *PyMapping_GetOptionalItemString()* or *PyMapping_GetItemString()* instead.

PyObject ***PyMapping_Keys**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. On success, return a list of the keys in object *o*. On failure, return `NULL`.

3.7 sürümünde değişti: Previously, the function returned a list or a tuple.

PyObject ***PyMapping_Values**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. On success, return a list of the values in object *o*. On failure, return `NULL`.

3.7 sürümünde değişti: Previously, the function returned a list or a tuple.

PyObject ***PyMapping_Items**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. On success, return a list of the items in object *o*, where each item is a tuple containing a key-value pair. On failure, return `NULL`.

3.7 sürümünde değişti: Previously, the function returned a list or a tuple.

8.6 Iterator Protocol

There are two functions specifically for working with iterators.

int **PyIter_Check**(*PyObject* *o)

Bir parçası Kararlı ABI *3.8 sürümünden beri.* Return non-zero if the object *o* can be safely passed to *PyIter_NextItem()* and `0` otherwise. This function always succeeds.

int **PyAIter_Check**(*PyObject* *o)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Return non-zero if the object *o* provides the `AsyncIterator` protocol, and `0` otherwise. This function always succeeds.

Added in version 3.10.

int **PyIter_NextItem**(*PyObject* *iter, *PyObject* **item)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Return `1` and set *item* to a *strong reference* of the next value of the iterator *iter* on success. Return `0` and set *item* to `NULL` if there are no remaining values. Return `-1`, set *item* to `NULL` and set an exception on error.

Added in version 3.14.

PyObject ***PyIter_Next**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. This is an older version of `PyIter_NextItem()`, which is retained for backwards compatibility. Prefer *PyIter_NextItem()*.

Return the next value from the iterator *o*. The object must be an iterator according to *PyIter_Check()* (it is up to the caller to check this). If there are no remaining values, returns NULL with no exception set. If an error occurs while retrieving the item, returns NULL and passes along the exception.

type **PySendResult**

The enum value used to represent different results of *PyIter_Send()*.

Added in version 3.10.

PySendResult **PyIter_Send**(*PyObject* *iter, *PyObject* *arg, *PyObject* **presult)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Sends the *arg* value into the iterator *iter*. Returns:

- PYGEN_RETURN if iterator returns. Return value is returned via *presult*.
- PYGEN_NEXT if iterator yields. Yielded value is returned via *presult*.
- PYGEN_ERROR if iterator has raised and exception. *presult* is set to NULL.

Added in version 3.10.

8.7 Buffer Protocol

Certain objects available in Python wrap access to an underlying memory array or *buffer*. Such objects include the built-in bytes and bytearray, and some extension types like array.array. Third-party libraries may define their own types for special purposes, such as image processing or numeric analysis.

While each of these types have their own semantics, they share the common characteristic of being backed by a possibly large memory buffer. It is then desirable, in some situations, to access that buffer directly and without intermediate copying.

Python provides such a facility at the C and Python level in the form of the *buffer protocol*. This protocol has two sides:

- on the producer side, a type can export a "buffer interface" which allows objects of that type to expose information about their underlying buffer. This interface is described in the section *Buffer Object Structures*; for Python see python-buffer-protocol.
- on the consumer side, several means are available to obtain a pointer to the raw underlying data of an object (for example a method parameter). For Python see memoryview.

Simple objects such as bytes and bytearray expose their underlying buffer in byte-oriented form. Other forms are possible; for example, the elements exposed by an array.array can be multi-byte values.

An example consumer of the buffer interface is the write() method of file objects: any object that can export a series of bytes through the buffer interface can be written to a file. While write() only needs read-only access to the internal contents of the object passed to it, other methods such as readinto() need write access to the contents of their argument. The buffer interface allows objects to selectively allow or reject exporting of read-write and read-only buffers.

There are two ways for a consumer of the buffer interface to acquire a buffer over a target object:

- call *PyObject_GetBuffer()* with the right parameters;
- call *PyArg_ParseTuple()* (or one of its siblings) with one of the y*, w* or s* *format codes*.

In both cases, *PyBuffer_Release()* must be called when the buffer isn't needed anymore. Failure to do so could lead to various issues such as resource leaks.

Added in version 3.12: The buffer protocol is now accessible in Python, see python-buffer-protocol and memoryview.

8.7.1 Buffer structure

Buffer structures (or simply "buffers") are useful as a way to expose the binary data from another object to the Python programmer. They can also be used as a zero-copy slicing mechanism. Using their ability to reference a block of memory, it is possible to expose any data to the Python programmer quite easily. The memory could be a large,

constant array in a C extension, it could be a raw block of memory for manipulation before passing to an operating system library, or it could be used to pass around structured data in its native, in-memory format.

Contrary to most data types exposed by the Python interpreter, buffers are not *PyObject* pointers but rather simple C structures. This allows them to be created and copied very simply. When a generic wrapper around a buffer is needed, a *memoryview* object can be created.

For short instructions how to write an exporting object, see *Buffer Object Structures*. For obtaining a buffer, see *PyObject_GetBuffer()*.

type **Py_buffer**

Bir parçası Kararlı ABI *(tüm üyeler dahil) 3.11 sürümünden beri.*

void ***buf**

A pointer to the start of the logical structure described by the buffer fields. This can be any location within the underlying physical memory block of the exporter. For example, with negative *strides* the value may point to the end of the memory block.

For *contiguous* arrays, the value points to the beginning of the memory block.

PyObject ***obj**

A new reference to the exporting object. The reference is owned by the consumer and automatically released (i.e. reference count decremented) and set to NULL by *PyBuffer_Release()*. The field is the equivalent of the return value of any standard C-API function.

As a special case, for *temporary* buffers that are wrapped by *PyMemoryView_FromBuffer()* or *PyBuffer_FillInfo()* this field is NULL. In general, exporting objects MUST NOT use this scheme.

Py_ssize_t **len**

`product(shape) * itemsize`. For contiguous arrays, this is the length of the underlying memory block. For non-contiguous arrays, it is the length that the logical structure would have if it were copied to a contiguous representation.

Accessing `((char *)buf)[0] up to ((char *)buf)[len-1]` is only valid if the buffer has been obtained by a request that guarantees contiguity. In most cases such a request will be *PyBUF_SIMPLE* or *PyBUF_WRITABLE*.

int **readonly**

An indicator of whether the buffer is read-only. This field is controlled by the *PyBUF_WRITABLE* flag.

Py_ssize_t **itemsize**

Item size in bytes of a single element. Same as the value of `struct.calcsize()` called on non-NULL *format* values.

Important exception: If a consumer requests a buffer without the *PyBUF_FORMAT* flag, *format* will be set to NULL, but *itemsize* still has the value for the original format.

If *shape* is present, the equality `product(shape) * itemsize == len` still holds and the consumer can use *itemsize* to navigate the buffer.

If *shape* is NULL as a result of a *PyBUF_SIMPLE* or a *PyBUF_WRITABLE* request, the consumer must disregard *itemsize* and assume `itemsize == 1`.

char ***format**

A *NULL* terminated string in `struct` module style syntax describing the contents of a single item. If this is NULL, `"B"` (unsigned bytes) is assumed.

This field is controlled by the *PyBUF_FORMAT* flag.

int **ndim**

The number of dimensions the memory represents as an n-dimensional array. If it is `0`, *buf* points to a single item representing a scalar. In this case, *shape*, *strides* and *suboffsets* MUST be NULL. The maximum number of dimensions is given by *PyBUF_MAX_NDIM*.

Py_ssize_t ***shape**

An array of *Py_ssize_t* of length *ndim* indicating the shape of the memory as an n-dimensional array. Note that `shape[0] * ... * shape[ndim-1] * itemsize` MUST be equal to *len*.

Shape values are restricted to `shape[n] >= 0`. The case `shape[n] == 0` requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

Py_ssize_t ***strides**

An array of *Py_ssize_t* of length *ndim* giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case `strides[n] <= 0`. See *complex arrays* for further information.

The strides array is read-only for the consumer.

Py_ssize_t ***suboffsets**

An array of *Py_ssize_t* of length *ndim*. If `suboffsets[n] >= 0`, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after de-referencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be `NULL` (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

void ***internal**

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

Constants:

PyBUF_MAX_NDIM

The maximum number of dimensions the memory represents. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to `PyBUF_MAX_NDIM` dimensions. Currently set to 64.

8.7.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via *PyObject_GetBuffer()*. Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the *flags* argument to specify the exact buffer type it can handle.

All *Py_buffer* fields are unambiguously defined by the request type.

request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values: *obj*, *buf*, *len*, *itemsize*, *ndim*.

readonly, format

PyBUF_WRITABLE

Controls the *readonly* field. If set, the exporter MUST provide a writable buffer or else report failure. Otherwise, the exporter MAY provide either a read-only or writable buffer, but the choice MUST be consistent for all consumers. For example, *PyBUF_SIMPLE* | *PyBUF_WRITABLE* can be used to request a simple writable buffer.

PyBUF_FORMAT

Controls the *format* field. If set, this field MUST be filled in correctly. Otherwise, this field MUST be NULL.

PyBUF_WRITABLE can be |'d to any of the flags in the next section. Since *PyBUF_SIMPLE* is defined as 0, *PyBUF_WRITABLE* can be used as a stand-alone flag to request a simple writable buffer.

PyBUF_FORMAT must be |'d to any of the flags except *PyBUF_SIMPLE*, because the latter already implies format B (unsigned bytes). PyBUF_FORMAT cannot be used on its own.

shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

Request	shape	strides	suboffsets
PyBUF_INDIRECT	yes	yes	if needed
PyBUF_STRIDES	yes	yes	NULL
PyBUF_ND	yes	NULL	NULL
PyBUF_SIMPLE	NULL	NULL	NULL

contiguity requests

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

Request	shape	strides	suboffsets	contig
PyBUF_C_CONTIGUOUS	yes	yes	NULL	C
PyBUF_F_CONTIGUOUS	yes	yes	NULL	F
PyBUF_ANY_CONTIGUOUS	yes	yes	NULL	C or F
PyBUF_ND	yes	NULL	NULL	C

compound requests

All possible requests are fully defined by some combination of the flags in the previous section. For convenience, the buffer protocol provides frequently used combinations as single flags.

In the following table *U* stands for undefined contiguity. The consumer would have to call *PyBuffer_IsContiguous()* to determine contiguity.

Request	shape	strides	suboffsets	contig	readonly	format
PyBUF_FULL	yes	yes	if needed	U	0	yes
PyBUF_FULL_RO	yes	yes	if needed	U	1 or 0	yes
PyBUF_RECORDS	yes	yes	NULL	U	0	yes
PyBUF_RECORDS_RO	yes	yes	NULL	U	1 or 0	yes
PyBUF_STRIDED	yes	yes	NULL	U	0	NULL
PyBUF_STRIDED_RO	yes	yes	NULL	U	1 or 0	NULL
PyBUF_CONTIG	yes	NULL	NULL	C	0	NULL
PyBUF_CONTIG_RO	yes	NULL	NULL	C	1 or 0	NULL

8.7.3 Complex arrays

NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by *itemsize*, *ndim*, *shape* and *strides*.

If `ndim == 0`, the memory location pointed to by *buf* is interpreted as a scalar of size *itemsize*. In that case, both *shape* and *strides* are `NULL`.

If *strides* is `NULL`, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, *buf* can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
       the bounds of the allocated memory:
           char *mem: start of the physical memory block
           memlen: length of the physical memory block
           offset: (char *)buf - mem
    """
    if offset % itemsize:
        return False
    if offset < 0 or offset+itemsize > memlen:
        return False
    if any(v % itemsize for v in strides):
        return False
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    if ndim <= 0:
        return ndim == 0 and not shape and not strides
    if 0 in shape:
        return True

    imin = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] <= 0)
    imax = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] > 0)

    return 0 <= offset+imin and offset+imax+itemsize <= memlen
```

PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array `char v[2][2][3]` can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: `char (*v[2])[2][3]`. In suboffsets representation, those two pointers can be embedded at the start of *buf*, pointing to two `char x[2][3]` arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-`NULL` strides and suboffsets:

```
void *get_item_pointer(int ndim, void *buf, Py_ssize_t *strides,
                       Py_ssize_t *suboffsets, Py_ssize_t *indices) {
    char *pointer = (char*)buf;
    int i;
    for (i = 0; i < ndim; i++) {
        pointer += strides[i] * indices[i];
        if (suboffsets[i] >=0 ) {
            pointer = *((char**)pointer) + suboffsets[i];
        }
    }
    return (void*)pointer;
}
```

8.7.4 Buffer-related functions

int **PyObject_CheckBuffer**(*PyObject* *obj)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Return `1` if *obj* supports the buffer interface otherwise `0`. When `1` is returned, it doesn't guarantee that *PyObject_GetBuffer()* will succeed. This function always succeeds.

int **PyObject_GetBuffer**(*PyObject* *exporter, *Py_buffer* *view, int flags)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Send a request to *exporter* to fill in *view* as specified by *flags*. If the exporter cannot provide a buffer of the exact type, it MUST raise `BufferError`, set `view->obj` to `NULL` and return `-1`.

On success, fill in *view*, set `view->obj` to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, `view->obj` MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to *PyObject_GetBuffer()* must be paired with calls to *PyBuffer_Release()*, similar to `malloc()` and `free()`. Thus, after the consumer is done with the buffer, *PyBuffer_Release()* must be called exactly once.

void **PyBuffer_Release**(*Py_buffer* *view)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Release the buffer *view* and release the *strong reference* (i.e.

decrement the reference count) to the view's supporting object, `view->obj`. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via *PyObject_GetBuffer()*.

Py_ssize_t **PyBuffer_SizeFromFormat**(const char *format)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Return the implied *itemsize* from *format*. On error, raise an exception and return -1.

Added in version 3.9.

int **PyBuffer_IsContiguous**(const *Py_buffer* *view, char order)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Return `1` if the memory defined by the *view* is C-style (*order* is `'C'`) or Fortran-style (*order* is `'F'`) *contiguous* or either one (*order* is `'A'`). Return `0` otherwise. This function always succeeds.

void ***PyBuffer_GetPointer**(const *Py_buffer* *view, const *Py_ssize_t* *indices)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Get the memory area pointed to by the *indices* inside the given *view*. *indices* must point to an array of `view->ndim` indices.

int **PyBuffer_FromContiguous**(const *Py_buffer* *view, const void *buf, *Py_ssize_t* len, char fort)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Copy contiguous *len* bytes from *buf* to *view*. *fort* can be `'C'` or `'F'` (for C-style or Fortran-style ordering). `0` is returned on success, `-1` on error.

int **PyBuffer_ToContiguous**(void *buf, const *Py_buffer* *src, *Py_ssize_t* len, char order)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Copy *len* bytes from *src* to its contiguous representation in *buf*. *order* can be `'C'` or `'F'` or `'A'` (for C-style or Fortran-style ordering or either one). `0` is returned on success, `-1` on error.

This function fails if *len* != *src->len*.

int **PyObject_CopyData**(*PyObject* *dest, *PyObject* *src)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Copy data from *src* to *dest* buffer. Can convert between C-style and or Fortran-style buffers.

`0` is returned on success, `-1` on error.

void **PyBuffer_FillContiguousStrides**(int ndims, *Py_ssize_t* *shape, *Py_ssize_t* *strides, int itemsize, char order)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Fill the *strides* array with byte-strides of a *contiguous* (C-style if *order* is `'C'` or Fortran-style if *order* is `'F'`) array of the given shape with the given number of bytes per element.

int **PyBuffer_FillInfo**(*Py_buffer* *view, *PyObject* *exporter, void *buf, *Py_ssize_t* len, int readonly, int flags)

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Handle buffer requests for an exporter that wants to expose *buf* of size *len* with writability set according to *readonly*. *buf* is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and *PyBUF_WRITABLE* is set in *flags*.

On success, set `view->obj` to a new reference to *exporter* and return 0. Otherwise, raise `BufferError`, set `view->obj` to `NULL` and return `-1`;

If this function is used as part of a *getbufferproc*, *exporter* MUST be set to the exporting object and *flags* must be passed unmodified. Otherwise, *exporter* MUST be `NULL`.

BÖLÜM 9

Concrete Objects Layer

The functions in this chapter are specific to certain Python object types. Passing them an object of the wrong type is not a good idea; if you receive an object from a Python program and you are not sure that it has the right type, you must perform a type check first; for example, to check that an object is a dictionary, use *PyDict_Check()*. The chapter is structured like the "family tree" of Python object types.

Uyarı

While the functions described in this chapter carefully check the type of the objects which are passed in, many of them do not check for `NULL` being passed instead of a valid object. Allowing `NULL` to be passed in can cause memory access violations and immediate termination of the interpreter.

9.1 Fundamental Objects

This section describes Python type objects and the singleton object `None`.

9.1.1 Type Objects

type **PyTypeObject**

Bir parçası Sınırlı API *(bir opak yapı olarak).* The C structure of the objects used to describe built-in types.

PyTypeObject **PyType_Type**

Bir parçası Kararlı ABI. This is the type object for type objects; it is the same object as `type` in the Python layer.

int **PyType_Check**(*PyObject* *o)

Return non-zero if the object *o* is a type object, including instances of types derived from the standard type object. Return 0 in all other cases. This function always succeeds.

int **PyType_CheckExact**(*PyObject* *o)

Return non-zero if the object *o* is a type object, but not a subtype of the standard type object. Return 0 in all other cases. This function always succeeds.

unsigned int **PyType_ClearCache**()

Bir parçası Kararlı ABI. Clear the internal lookup cache. Return the current version tag.

unsigned long **PyType_GetFlags**(*PyTypeObject* *type)

Bir parçası Kararlı ABI. Return the `tp_flags` member of *type*. This function is primarily meant for use with `Py_LIMITED_API`; the individual flag bits are guaranteed to be stable across Python releases, but access to `tp_flags` itself is not part of the *limited API*.

Added in version 3.2.

3.4 sürümünde değişti: The return type is now `unsigned long` rather than `long`.

PyObject ***PyType_GetDict**(*PyTypeObject* *type)

Return the type object's internal namespace, which is otherwise only exposed via a read-only proxy (`cls.__dict__`). This is a replacement for accessing `tp_dict` directly. The returned dictionary must be treated as read-only.

This function is meant for specific embedding and language-binding cases, where direct access to the dict is necessary and indirect access (e.g. via the proxy or `PyObject_GetAttr()`) isn't adequate.

Extension modules should continue to use `tp_dict`, directly or indirectly, when setting up their own types.

Added in version 3.12.

void **PyType_Modified**(*PyTypeObject* *type)

Bir parçası Kararlı ABI. Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

int **PyType_AddWatcher**(*PyType_WatchCallback* callback)

Register *callback* as a type watcher. Return a non-negative integer ID which must be passed to future calls to `PyType_Watch()`. In case of error (e.g. no more watcher IDs available), return `-1` and set an exception.

In free-threaded builds, `PyType_AddWatcher()` is not thread-safe, so it must be called at start up (before spawning the first thread).

Added in version 3.12.

int **PyType_ClearWatcher**(int watcher_id)

Clear watcher identified by *watcher_id* (previously returned from `PyType_AddWatcher()`). Return `0` on success, `-1` on error (e.g. if *watcher_id* was never registered.)

An extension should never call `PyType_ClearWatcher` with a *watcher_id* that was not returned to it by a previous call to `PyType_AddWatcher()`.

Added in version 3.12.

int **PyType_Watch**(int watcher_id, *PyObject* *type)

Mark *type* as watched. The callback granted *watcher_id* by `PyType_AddWatcher()` will be called whenever `PyType_Modified()` reports a change to *type*. (The callback may be called only once for a series of consecutive modifications to *type*, if `_PyType_Lookup()` is not called on *type* between the modifications; this is an implementation detail and subject to change.)

An extension should never call `PyType_Watch` with a *watcher_id* that was not returned to it by a previous call to `PyType_AddWatcher()`.

Added in version 3.12.

typedef int (***PyType_WatchCallback**)(*PyObject* *type)

Type of a type-watcher callback function.

The callback must not modify *type* or cause `PyType_Modified()` to be called on *type* or any type in its MRO; violating this rule could cause infinite recursion.

Added in version 3.12.

int **PyType_HasFeature**(*PyTypeObject* *o, int feature)

Return non-zero if the type object *o* sets the feature *feature*. Type features are denoted by single bit flags.

int **PyType_IS_GC**(*PyTypeObject* *o)

Return true if the type object includes support for the cycle detector; this tests the type flag `Py_TPFLAGS_HAVE_GC`.

int **PyType_IsSubtype**(*PyTypeObject* *a, *PyTypeObject* *b)

Bir parçası Kararlı ABI. Return true if *a* is a subtype of *b*.

This function only checks for actual subtypes, which means that `__subclasscheck__()` is not called on *b*. Call `PyObject_IsSubclass()` to do the same check that `issubclass()` would do.

PyObject ***PyType_GenericAlloc**(*PyTypeObject* *type, *Py_ssize_t* nitems)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Generic handler for the `tp_alloc` slot of a type object. Uses Python's default memory allocation mechanism to allocate memory for a new instance, zeros the memory, then initializes the memory as if by calling `PyObject_Init()` or `PyObject_InitVar()`.

Do not call this directly to allocate memory for an object; call the type's `tp_alloc` slot instead.

For types that support garbage collection (i.e., the `Py_TPFLAGS_HAVE_GC` flag is set), this function behaves like `PyObject_GC_New` or `PyObject_GC_NewVar` (except the memory is guaranteed to be zeroed before initialization), and should be paired with `PyObject_GC_Del()` in `tp_free`. Otherwise, it behaves like `PyObject_New` or `PyObject_NewVar` (except the memory is guaranteed to be zeroed before initialization) and should be paired with `PyObject_Free()` in `tp_free`.

PyObject ***PyType_GenericNew**(*PyTypeObject* *type, *PyObject* *args, *PyObject* *kwds)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Generic handler for the `tp_new` slot of a type object. Creates a new instance using the type's `tp_alloc` slot and returns the resulting object.

int **PyType_Ready**(*PyTypeObject* *type)

Bir parçası Kararlı ABI. Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return `0` on success, or return `-1` and sets an exception on error.

> **Not**
>
> If some of the base classes implements the GC protocol and the provided type does not include the `Py_TPFLAGS_HAVE_GC` in its flags, then the GC protocol will be automatically implemented from its parents. On the contrary, if the type being created does include `Py_TPFLAGS_HAVE_GC` in its flags then it **must** implement the GC protocol itself by at least implementing the `tp_traverse` handle.

PyObject ***PyType_GetName**(*PyTypeObject* *type)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.11 sürümünden beri.* Return the type's name. Equivalent to getting the type's `__name__` attribute.

Added in version 3.11.

PyObject ***PyType_GetQualName**(*PyTypeObject* *type)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.11 sürümünden beri.* Return the type's qualified name. Equivalent to getting the type's `__qualname__` attribute.

Added in version 3.11.

PyObject ***PyType_GetFullyQualifiedName**(*PyTypeObject* *type)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return the type's fully qualified name. Equivalent to `f"{type.__module__}.{type.__qualname__}"`, or `type.__qualname__` if `type.__module__` is not a string or is equal to `"builtins"`.

Added in version 3.13.

PyObject ***PyType_GetModuleName**(*PyTypeObject* *type)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return the type's module name. Equivalent to getting the `type.__module__` attribute.

Added in version 3.13.

void *__PyType_GetSlot__(*PyTypeObject* *type, int slot)

Bir parçası Kararlı ABI *3.4 sürümünden beri.* Return the function pointer stored in the given slot. If the result is `NULL`, this indicates that either the slot is `NULL`, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See `PyType_Slot.slot` for possible values of the *slot* argument.

Added in version 3.4.

3.10 sürümünde değişti: `PyType_GetSlot()` can now accept all types. Previously, it was limited to *heap types*.

PyObject *__PyType_GetModule__(*PyTypeObject* *type)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Return the module object associated with the given type when the type was created using `PyType_FromModuleAndSpec()`.

If no module is associated with the given type, sets `TypeError` and returns `NULL`.

This function is usually used to get the module in which a method is defined. Note that in such a method, `PyType_GetModule(Py_TYPE(self))` may not return the intended result. `Py_TYPE(self)` may be a *subclass* of the intended class, and subclasses are not necessarily defined in the same module as their superclass. See `PyCMethod` to get the class that defines the method. See `PyType_GetModuleByDef()` for cases when `PyCMethod` cannot be used.

Added in version 3.9.

void *__PyType_GetModuleState__(*PyTypeObject* *type)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Return the state of the module object associated with the given type. This is a shortcut for calling `PyModule_GetState()` on the result of `PyType_GetModule()`.

If no module is associated with the given type, sets `TypeError` and returns `NULL`.

If the *type* has an associated module but its state is `NULL`, returns `NULL` without setting an exception.

Added in version 3.9.

PyObject *__PyType_GetModuleByDef__(*PyTypeObject* *type, struct *PyModuleDef* *def)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Find the first superclass whose module was created from the given `PyModuleDef` *def*, and return that module.

If no module is found, raises a `TypeError` and returns `NULL`.

This function is intended to be used together with `PyModule_GetState()` to get module state from slot methods (such as `tp_init` or `nb_add`) and other places where a method's defining class cannot be passed using the `PyCMethod` calling convention.

The returned reference is *borrowed* from *type*, and will be valid as long as you hold a reference to *type*. Do not release it with `Py_DECREF()` or similar.

Added in version 3.11.

int __PyType_GetBaseByToken__(*PyTypeObject* *type, void *token, *PyTypeObject* **result)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Find the first superclass in *type*'s *method resolution order* whose `Py_tp_token` token is equal to the given one.

- If found, set **result* to a new *strong reference* to it and return `1`.
- If not found, set **result* to `NULL` and return `0`.
- On error, set **result* to `NULL` and return `-1` with an exception set.

The *result* argument may be `NULL`, in which case **result* is not set. Use this if you need only the return value.

The *token* argument may not be `NULL`.

Added in version 3.14.

int **PyUnstable_Type_AssignVersionTag**(*PyTypeObject* *type)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Attempt to assign a version tag to the given type.

Returns 1 if the type already had a valid version tag or a new one was assigned, or 0 if a new tag could not be assigned.

Added in version 3.12.

Creating Heap-Allocated Types

The following functions and structs are used to create *heap types*.

PyObject ***PyType_FromMetaclass**(*PyTypeObject* *metaclass, *PyObject* *module, *PyType_Spec* *spec, *PyObject* *bases)

Bir parçası Kararlı ABI *3.12 sürümünden beri.* Create and return a *heap type* from the *spec* (see `Py_TPFLAGS_HEAPTYPE`).

The metaclass *metaclass* is used to construct the resulting type object. When *metaclass* is `NULL`, the metaclass is derived from *bases* (or *Py_tp_base[s]* slots if *bases* is `NULL`, see below).

Metaclasses that override `tp_new` are not supported, except if `tp_new` is `NULL`.

The *bases* argument can be used to specify base classes; it can either be only one class or a tuple of classes. If *bases* is `NULL`, the *Py_tp_bases* slot is used instead. If that also is `NULL`, the *Py_tp_base* slot is used instead. If that also is `NULL`, the new type derives from `object`.

The *module* argument can be used to record the module in which the new class is defined. It must be a module object or `NULL`. If not `NULL`, the module is associated with the new type and can later be retrieved with `PyType_GetModule()`. The associated module is not inherited by subclasses; it must be specified for each class individually.

This function calls `PyType_Ready()` on the new type.

Note that this function does *not* fully match the behavior of calling `type()` or using the `class` statement. With user-provided base types or metaclasses, prefer *calling* `type` (or the metaclass) over `PyType_From*` functions. Specifically:

- `__new__()` is not called on the new class (and it must be set to `type.__new__`).
- `__init__()` is not called on the new class.
- `__init_subclass__()` is not called on any bases.
- `__set_name__()` is not called on new descriptors.

Added in version 3.12.

PyObject ***PyType_FromModuleAndSpec**(*PyObject* *module, *PyType_Spec* *spec, *PyObject* *bases)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.10 sürümünden beri.* Equivalent to `PyType_FromMetaclass(NULL, module, spec, bases)`.

Added in version 3.9.

3.10 sürümünde değişti: The function now accepts a single class as the *bases* argument and `NULL` as the `tp_doc` slot.

3.12 sürümünde değişti: The function now finds and uses a metaclass corresponding to the provided base classes. Previously, only `type` instances were returned.

The `tp_new` of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides `tp_new` is deprecated.

3.14 sürümünde değişti: Creating classes whose metaclass overrides *tp_new* is no longer allowed.

PyObject ***PyType_FromSpecWithBases**(*PyType_Spec* *spec, *PyObject* *bases)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.3 sürümünden beri.* Equivalent to `PyType_FromMetaclass(NULL, NULL, spec, bases)`.

Added in version 3.3.

3.12 sürümünde değişti: The function now finds and uses a metaclass corresponding to the provided base classes. Previously, only `type` instances were returned.

The *tp_new* of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides *tp_new* is deprecated.

3.14 sürümünde değişti: Creating classes whose metaclass overrides *tp_new* is no longer allowed.

PyObject ***PyType_FromSpec**(*PyType_Spec* *spec)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Equivalent to `PyType_FromMetaclass(NULL, NULL, spec, NULL)`.

3.12 sürümünde değişti: The function now finds and uses a metaclass corresponding to the base classes provided in *Py_tp_base[s]* slots. Previously, only `type` instances were returned.

The *tp_new* of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides *tp_new* is deprecated.

3.14 sürümünde değişti: Creating classes whose metaclass overrides *tp_new* is no longer allowed.

int **PyType_Freeze**(*PyTypeObject* *type)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Make a type immutable: set the *Py_TPFLAGS_IMMUTABLETYPE* flag.

All base classes of *type* must be immutable.

On success, return `0`. On error, set an exception and return `-1`.

The type must not be used before it's made immutable. For example, type instances must not be created before the type is made immutable.

Added in version 3.14.

type **PyType_Spec**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Structure defining a type's behavior.

const char ***name**

Name of the type, used to set *PyTypeObject.tp_name*.

int **basicsize**

If positive, specifies the size of the instance in bytes. It is used to set *PyTypeObject.tp_basicsize*.

If zero, specifies that *tp_basicsize* should be inherited.

If negative, the absolute value specifies how much space instances of the class need *in addition* to the superclass. Use *PyObject_GetTypeData()* to get a pointer to subclass-specific memory reserved this way. For negative `basicsize`, Python will insert padding when needed to meet *tp_basicsize*'s alignment requirements.

3.12 sürümünde değişti: Previously, this field could not be negative.

int **itemsize**

Size of one element of a variable-size type, in bytes. Used to set *PyTypeObject.tp_itemsize*. See `tp_itemsize` documentation for caveats.

If zero, *tp_itemsize* is inherited. Extending arbitrary variable-sized classes is dangerous, since some types use a fixed offset for variable-sized memory, which can then overlap fixed-sized memory used by a subclass. To help prevent mistakes, inheriting `itemsize` is only possible in the following situations:

- The base is not variable-sized (its *tp_itemsize*).

- The requested *PyType_Spec.basicsize* is positive, suggesting that the memory layout of the base class is known.
- The requested *PyType_Spec.basicsize* is zero, suggesting that the subclass does not access the instance's memory directly.
- With the *Py_TPFLAGS_ITEMS_AT_END* flag.

unsigned int **flags**

Type flags, used to set *PyTypeObject.tp_flags*.

If the `Py_TPFLAGS_HEAPTYPE` flag is not set, *PyType_FromSpecWithBases()* sets it automatically.

PyType_Slot ***slots**

Array of *PyType_Slot* structures. Terminated by the special slot value `{0, NULL}`.

Each slot ID should be specified at most once.

type **PyType_Slot**

Bir parçası Kararlı ABI *(tüm üyeler dahil)*. Structure defining optional functionality of a type, containing a slot ID and a value pointer.

int **slot**

A slot ID.

Slot IDs are named like the field names of the structures *PyTypeObject*, *PyNumberMethods*, *PySequenceMethods*, *PyMappingMethods* and *PyAsyncMethods* with an added `Py_` prefix. For example, use:

- `Py_tp_dealloc` to set *PyTypeObject.tp_dealloc*
- `Py_nb_add` to set *PyNumberMethods.nb_add*
- `Py_sq_length` to set *PySequenceMethods.sq_length*

An additional slot is supported that does not correspond to a `PyTypeObject` struct field:

- *Py_tp_token*

The following "offset" fields cannot be set using *PyType_Slot*:

- *tp_weaklistoffset* (use *Py_TPFLAGS_MANAGED_WEAKREF* instead if possible)
- *tp_dictoffset* (use *Py_TPFLAGS_MANAGED_DICT* instead if possible)
- *tp_vectorcall_offset* (use `"__vectorcalloffset__"` in *PyMemberDef*)

If it is not possible to switch to a `MANAGED` flag (for example, for vectorcall or to support Python older than 3.12), specify the offset in *Py_tp_members*. See *PyMemberDef documentation* for details.

The following internal fields cannot be set at all when creating a heap type:

- *tp_dict*, *tp_mro*, *tp_cache*, *tp_subclasses*, and *tp_weaklist*.

Setting `Py_tp_bases` or `Py_tp_base` may be problematic on some platforms. To avoid issues, use the *bases* argument of *PyType_FromSpecWithBases()* instead.

3.9 sürümünde değişti: Slots in *PyBufferProcs* may be set in the unlimited API.

3.11 sürümünde değişti: *bf_getbuffer* and *bf_releasebuffer* are now available under the *limited API*.

3.14 sürümünde değişti: The field *tp_vectorcall* can now set using `Py_tp_vectorcall`. See the field's documentation for details.

void ***pfunc**

The desired value of the slot. In most cases, this is a pointer to a function.

pfunc values may not be `NULL`, except for the following slots:

- `Py_tp_doc`

- *Py_tp_token* (for clarity, prefer *Py_TP_USE_SPEC* rather than NULL)

Py_tp_token

A *slot* that records a static memory layout ID for a class.

If the *PyType_Spec* of the class is statically allocated, the token can be set to the spec using the special value *Py_TP_USE_SPEC*:

```
static PyType_Slot foo_slots[] = {
   {Py_tp_token, Py_TP_USE_SPEC},
```

It can also be set to an arbitrary pointer, but you must ensure that:

- The pointer outlives the class, so it's not reused for something else while the class exists.
- It "belongs" to the extension module where the class lives, so it will not clash with other extensions.

Use *PyType_GetBaseByToken()* to check if a class's superclass has a given token – that is, check whether the memory layout is compatible.

To get the token for a given class (without considering superclasses), use *PyType_GetSlot()* with Py_tp_token.

Added in version 3.14.

Py_TP_USE_SPEC

Used as a value with *Py_tp_token* to set the token to the class's *PyType_Spec*. Expands to NULL.

Added in version 3.14.

9.1.2 The None Object

Note that the *PyTypeObject* for None is not directly exposed in the Python/C API. Since None is a singleton, testing for object identity (using == in C) is sufficient. There is no PyNone_Check() function for the same reason.

PyObject ***Py_None**

The Python None object, denoting lack of value. This object has no methods and is *immortal*.

3.12 sürümünde değişti: *Py_None* is *immortal*.

Py_RETURN_NONE

Return *Py_None* from a function.

9.2 Numeric Objects

9.2.1 Integer Objects

All integers are implemented as "long" integer objects of arbitrary size.

On error, most PyLong_As* APIs return (return type)-1 which cannot be distinguished from a number. Use *PyErr_Occurred()* to disambiguate.

type **PyLongObject**

Bir parçası Sınırlı API *(bir opak yapı olarak).* This subtype of *PyObject* represents a Python integer object.

PyTypeObject **PyLong_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python integer type. This is the same object as int in the Python layer.

int **PyLong_Check**(*PyObject* *p)

Return true if its argument is a *PyLongObject* or a subtype of *PyLongObject*. This function always succeeds.

int **PyLong_CheckExact**(*PyObject* *p)

Return true if its argument is a `PyLongObject`, but not a subtype of `PyLongObject`. This function always succeeds.

PyObject ***PyLong_FromLong**(long v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from *v*, or `NULL` on failure.

CPython uygulama ayrıntısı: CPython keeps an array of integer objects for all integers between `-5` and `256`. When you create an int in that range you actually just get back a reference to the existing object.

PyObject ***PyLong_FromUnsignedLong**(unsigned long v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from a C `unsigned long`, or `NULL` on failure.

PyObject ***PyLong_FromSsize_t**(*Py_ssize_t* v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from a C `Py_ssize_t`, or `NULL` on failure.

PyObject ***PyLong_FromSize_t**(size_t v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from a C `size_t`, or `NULL` on failure.

PyObject ***PyLong_FromLongLong**(long long v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from a C `long long`, or `NULL` on failure.

PyObject ***PyLong_FromInt32**(int32_t value)

PyObject ***PyLong_FromInt64**(int64_t value)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Return a new `PyLongObject` object from a signed C `int32_t` or `int64_t`, or `NULL` with an exception set on failure.

Added in version 3.14.

PyObject ***PyLong_FromUnsignedLongLong**(unsigned long long v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from a C `unsigned long long`, or `NULL` on failure.

PyObject ***PyLong_FromUInt32**(uint32_t value)

PyObject ***PyLong_FromUInt64**(uint64_t value)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Return a new `PyLongObject` object from an unsigned C `uint32_t` or `uint64_t`, or `NULL` with an exception set on failure.

Added in version 3.14.

PyObject ***PyLong_FromDouble**(double v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` object from the integer part of *v*, or `NULL` on failure.

PyObject ***PyLong_FromString**(const char *str, char **pend, int base)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `PyLongObject` based on the string value in *str*, which is interpreted according to the radix in *base*, or `NULL` on failure. If *pend* is non-`NULL`, **pend* will point to the end of *str* on success or to the first character that could not be processed on error. If *base* is `0`, *str* is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a `ValueError`. If *base* is not `0`, it must be between `2` and `36`, inclusive. Leading and trailing whitespace and single underscores after a base specifier and between digits are ignored. If there are no digits or *str* is not NULL-terminated following the digits and trailing whitespace, `ValueError` will be raised.

Ayrıca bakınız

`PyLong_AsNativeBytes()` and `PyLong_FromNativeBytes()` functions can be used to convert a `PyLongObject` to/from an array of bytes in base `256`.

PyObject ***PyLong_FromUnicodeObject**(*PyObject* *u, int base)

Döndürdüğü değer: Yeni referans. Convert a sequence of Unicode digits in the string *u* to a Python integer value.

Added in version 3.3.

PyObject ***PyLong_FromVoidPtr**(void *p)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Python integer from the pointer *p*. The pointer value can be retrieved from the resulting value using `PyLong_AsVoidPtr()`.

PyObject ***PyLong_FromNativeBytes**(const void *buffer, size_t n_bytes, int flags)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Create a Python integer from the value contained in the first *n_bytes* of *buffer*, interpreted as a two's-complement signed number.

flags are as for `PyLong_AsNativeBytes()`. Passing `-1` will select the native endian that CPython was compiled with and assume that the most-significant bit is a sign bit. Passing `Py_ASNATIVEBYTES_UNSIGNED_BUFFER` will produce the same result as calling `PyLong_FromUnsignedNativeBytes()`. Other flags are ignored.

Added in version 3.13.

PyObject ***PyLong_FromUnsignedNativeBytes**(const void *buffer, size_t n_bytes, int flags)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Create a Python integer from the value contained in the first *n_bytes* of *buffer*, interpreted as an unsigned number.

flags are as for `PyLong_AsNativeBytes()`. Passing `-1` will select the native endian that CPython was compiled with and assume that the most-significant bit is not a sign bit. Flags other than endian are ignored.

Added in version 3.13.

long **PyLong_AsLong**(*PyObject* *obj)

Bir parçası Kararlı ABI. Return a C `long` representation of *obj*. If *obj* is not an instance of `PyLongObject`, first call its `__index__()` method (if present) to convert it to a `PyLongObject`.

Raise `OverflowError` if the value of *obj* is out of range for a `long`.

Returns `-1` on error. Use `PyErr_Occurred()` to disambiguate.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

long **PyLong_AS_LONG**(*PyObject* *obj)

A *soft deprecated* alias. Exactly equivalent to the preferred `PyLong_AsLong`. In particular, it can fail with `OverflowError` or another exception.

3.14 sürümünden beri kullanım dışı: The function is soft deprecated.

int **PyLong_AsInt**(*PyObject* *obj)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to `PyLong_AsLong()`, but store the result in a C `int` instead of a C `long`.

Added in version 3.13.

long **PyLong_AsLongAndOverflow**(*PyObject* *obj, int *overflow)

Bir parçası Kararlı ABI. Return a C `long` representation of *obj*. If *obj* is not an instance of `PyLongObject`, first call its `__index__()` method (if present) to convert it to a `PyLongObject`.

If the value of *obj* is greater than `LONG_MAX` or less than `LONG_MIN`, set **overflow* to `1` or `-1`, respectively, and return `-1`; otherwise, set **overflow* to `0`. If any other exception occurs set **overflow* to `0` and return `-1` as usual.

Returns `-1` on error. Use *PyErr_Occurred()* to disambiguate.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

long long **PyLong_AsLongLong**(*PyObject* *obj)

Bir parçası Kararlı ABI. Return a C `long long` representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

Raise `OverflowError` if the value of *obj* is out of range for a `long long`.

Returns `-1` on error. Use *PyErr_Occurred()* to disambiguate.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

long long **PyLong_AsLongLongAndOverflow**(*PyObject* *obj, int *overflow)

Bir parçası Kararlı ABI. Return a C `long long` representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than `LLONG_MAX` or less than `LLONG_MIN`, set **overflow* to `1` or `-1`, respectively, and return `-1`; otherwise, set **overflow* to `0`. If any other exception occurs set **overflow* to `0` and return `-1` as usual.

Returns `-1` on error. Use *PyErr_Occurred()* to disambiguate.

Added in version 3.2.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

Py_ssize_t **PyLong_AsSsize_t**(*PyObject* *pylong)

Bir parçası Kararlı ABI. Return a C *Py_ssize_t* representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for a *Py_ssize_t*.

Returns `-1` on error. Use *PyErr_Occurred()* to disambiguate.

unsigned long **PyLong_AsUnsignedLong**(*PyObject* *pylong)

Bir parçası Kararlı ABI. Return a C `unsigned long` representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for a `unsigned long`.

Returns `(unsigned long)-1` on error. Use *PyErr_Occurred()* to disambiguate.

size_t **PyLong_AsSize_t**(*PyObject* *pylong)

Bir parçası Kararlı ABI. Return a C `size_t` representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for a `size_t`.

Returns `(size_t)-1` on error. Use *PyErr_Occurred()* to disambiguate.

unsigned long long **PyLong_AsUnsignedLongLong**(*PyObject* *pylong)

Bir parçası Kararlı ABI. Return a C `unsigned long long` representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for an `unsigned long long`.

Returns `(unsigned long long)-1` on error. Use *PyErr_Occurred()* to disambiguate.

3.1 sürümünde değişti: A negative *pylong* now raises `OverflowError`, not `TypeError`.

unsigned long **PyLong_AsUnsignedLongMask**(*PyObject* *obj)

Bir parçası Kararlı ABI. Return a C `unsigned long` representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an `unsigned long`, return the reduction of that value modulo `ULONG_MAX + 1`.

Returns `(unsigned long)-1` on error. Use *PyErr_Occurred()* to disambiguate.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

unsigned long long **PyLong_AsUnsignedLongLongMask**(*PyObject* *obj)

Bir parçası Kararlı ABI. Return a C `unsigned long long` representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an `unsigned long long`, return the reduction of that value modulo `ULLONG_MAX + 1`.

Returns `(unsigned long long)-1` on error. Use *PyErr_Occurred()* to disambiguate.

3.8 sürümünde değişti: Use `__index__()` if available.

3.10 sürümünde değişti: This function will no longer use `__int__()`.

int **PyLong_AsInt32**(*PyObject* *obj, int32_t *value)

int **PyLong_AsInt64**(*PyObject* *obj, int64_t *value)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Set **value* to a signed C `int32_t` or `int64_t` representation of *obj*.

If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

If the *obj* value is out of range, raise an `OverflowError`.

Set **value* and return `0` on success. Set an exception and return `-1` on error.

value must not be `NULL`.

Added in version 3.14.

int **PyLong_AsUInt32**(*PyObject* *obj, uint32_t *value)

int **PyLong_AsUInt64**(*PyObject* *obj, uint64_t *value)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Set **value* to an unsigned C `uint32_t` or `uint64_t` representation of *obj*.

If *obj* is not an instance of *PyLongObject*, first call its `__index__()` method (if present) to convert it to a *PyLongObject*.

- If *obj* is negative, raise a `ValueError`.
- If the *obj* value is out of range, raise an `OverflowError`.

Set **value* and return `0` on success. Set an exception and return `-1` on error.

value must not be `NULL`.

Added in version 3.14.

double **PyLong_AsDouble**(*PyObject* *pylong)

Bir parçası Kararlı ABI. Return a C `double` representation of *pylong*. *pylong* must be an instance of *PyLongObject*.

Raise `OverflowError` if the value of *pylong* is out of range for a `double`.

Returns `-1.0` on error. Use *PyErr_Occurred()* to disambiguate.

void *__PyLong_AsVoidPtr__(*PyObject* *pylong)

Bir parçası Kararlı ABI. Convert a Python integer *pylong* to a C `void` pointer. If *pylong* cannot be converted, an `OverflowError` will be raised. This is only assured to produce a usable `void` pointer for values created with *PyLong_FromVoidPtr()*.

Returns `NULL` on error. Use *PyErr_Occurred()* to disambiguate.

Py_ssize_t __PyLong_AsNativeBytes__(*PyObject* *pylong, void *buffer, *Py_ssize_t* n_bytes, int flags)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Copy the Python integer value *pylong* to a native *buffer* of size *n_bytes*. The *flags* can be set to `-1` to behave similarly to a C cast, or to values documented below to control the behavior.

Returns `-1` with an exception raised on error. This may happen if *pylong* cannot be interpreted as an integer, or if *pylong* was negative and the `Py_ASNATIVEBYTES_REJECT_NEGATIVE` flag was set.

Otherwise, returns the number of bytes required to store the value. If this is equal to or less than *n_bytes*, the entire value was copied. All *n_bytes* of the buffer are written: large buffers are padded with zeroes.

If the returned value is greater than *n_bytes*, the value was truncated: as many of the lowest bits of the value as could fit are written, and the higher bits are ignored. This matches the typical behavior of a C-style downcast.

> **Not**
>
> Overflow is not considered an error. If the returned value is larger than *n_bytes*, most significant bits were discarded.

`0` will never be returned.

Values are always copied as two's-complement.

Usage example:

```
int32_t value;
Py_ssize_t bytes = PyLong_AsNativeBytes(pylong, &value, sizeof(value), -1);
if (bytes < 0) {
    // Failed. A Python exception was set with the reason.
    return NULL;
}
else if (bytes <= (Py_ssize_t)sizeof(value)) {
    // Success!
}
else {
    // Overflow occurred, but 'value' contains the truncated
    // lowest bits of pylong.
}
```

Passing zero to *n_bytes* will return the size of a buffer that would be large enough to hold the value. This may be larger than technically necessary, but not unreasonably so. If *n_bytes =0*, *buffer* may be `NULL`.

> **Not**
>
> Passing *n_bytes =0* to this function is not an accurate way to determine the bit length of the value.

To get at the entire Python value of an unknown size, the function can be called twice: first to determine the buffer size, then to fill it:

```
// Ask how much space we need.
Py_ssize_t expected = PyLong_AsNativeBytes(pylong, NULL, 0, -1);
if (expected < 0) {
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    // Failed. A Python exception was set with the reason.
    return NULL;
}
assert(expected != 0);  // Impossible per the API definition.
uint8_t *bignum = malloc(expected);
if (!bignum) {
    PyErr_SetString(PyExc_MemoryError, "bignum malloc failed.");
    return NULL;
}
// Safely get the entire value.
Py_ssize_t bytes = PyLong_AsNativeBytes(pylong, bignum, expected, -1);
if (bytes < 0) {  // Exception has been set.
    free(bignum);
    return NULL;
}
else if (bytes > expected) {  // This should not be possible.
    PyErr_SetString(PyExc_RuntimeError,
        "Unexpected bignum truncation after a size check.");
    free(bignum);
    return NULL;
}
// The expected success given the above pre-check.
// ... use bignum ...
free(bignum);
```

flags is either `-1` (`Py_ASNATIVEBYTES_DEFAULTS`) to select defaults that behave most like a C cast, or a combination of the other flags in the table below. Note that `-1` cannot be combined with other flags.

Currently, `-1` corresponds to `Py_ASNATIVEBYTES_NATIVE_ENDIAN | Py_ASNATIVEBYTES_UNSIGNED_BUFFER`.

Flag	Value
Py_ASNATIVEBYTES_DEFAULTS	-1
Py_ASNATIVEBYTES_BIG_ENDIAN	0
Py_ASNATIVEBYTES_LITTLE_ENDIAN	1
Py_ASNATIVEBYTES_NATIVE_ENDIAN	3
Py_ASNATIVEBYTES_UNSIGNED_BUFFER	4
Py_ASNATIVEBYTES_REJECT_NEGATIVE	8
Py_ASNATIVEBYTES_ALLOW_INDEX	16

Specifying `Py_ASNATIVEBYTES_NATIVE_ENDIAN` will override any other endian flags. Passing `2` is reserved.

By default, sufficient buffer will be requested to include a sign bit. For example, when converting 128 with

n_bytes =*1*, the function will return 2 (or more) in order to store a zero sign bit.

If `Py_ASNATIVEBYTES_UNSIGNED_BUFFER` is specified, a zero sign bit will be omitted from size calculations. This allows, for example, 128 to fit in a single-byte buffer. If the destination buffer is later treated as signed, a positive input value may become negative. Note that the flag does not affect handling of negative values: for those, space for a sign bit is always requested.

Specifying `Py_ASNATIVEBYTES_REJECT_NEGATIVE` causes an exception to be set if *pylong* is negative. Without this flag, negative values will be copied provided there is enough space for at least one sign bit, regardless of whether `Py_ASNATIVEBYTES_UNSIGNED_BUFFER` was specified.

If `Py_ASNATIVEBYTES_ALLOW_INDEX` is specified and a non-integer value is passed, its `__index__()` method will be called first. This may result in Python code executing and other threads being allowed to run, which could cause changes to other objects or values in use. When *flags* is `-1`, this option is not set, and non-integer values will raise `TypeError`.

Not

With the default *flags* (`-1`, or *UNSIGNED_BUFFER* without *REJECT_NEGATIVE*), multiple Python integers can map to a single value without overflow. For example, both `255` and `-1` fit a single-byte buffer and set all its bits. This matches typical C cast behavior.

Added in version 3.13.

int **PyLong_GetSign**(*PyObject* *obj, int *sign)

Get the sign of the integer object *obj*.

On success, set **sign* to the integer sign (0, -1 or +1 for zero, negative or positive integer, respectively) and return 0.

On failure, return -1 with an exception set. This function always succeeds if *obj* is a `PyLongObject` or its subtype.

Added in version 3.14.

int **PyLong_IsPositive**(*PyObject* *obj)

Check if the integer object *obj* is positive (`obj > 0`).

If *obj* is an instance of `PyLongObject` or its subtype, return `1` when it's positive and `0` otherwise. Else set an exception and return `-1`.

Added in version 3.14.

int **PyLong_IsNegative**(*PyObject* *obj)

Check if the integer object *obj* is negative (`obj < 0`).

If *obj* is an instance of `PyLongObject` or its subtype, return `1` when it's negative and `0` otherwise. Else set an exception and return `-1`.

Added in version 3.14.

int **PyLong_IsZero**(*PyObject* *obj)

Check if the integer object *obj* is zero.

If *obj* is an instance of `PyLongObject` or its subtype, return `1` when it's zero and `0` otherwise. Else set an exception and return `-1`.

Added in version 3.14.

PyObject ***PyLong_GetInfo**(void)

Bir parçası Kararlı ABI. On success, return a read only *named tuple*, that holds information about Python's internal representation of integers. See `sys.int_info` for description of individual fields.

On failure, return `NULL` with an exception set.

Added in version 3.1.

int **PyUnstable_Long_IsCompact**(const *PyLongObject* *op)

> Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return 1 if *op* is compact, 0 otherwise.

This function makes it possible for performance-critical code to implement a "fast path" for small integers. For compact values use `PyUnstable_Long_CompactValue()`; for others fall back to a `PyLong_As*` function or `PyLong_AsNativeBytes()`.

The speedup is expected to be negligible for most users.

Exactly what values are considered compact is an implementation detail and is subject to change.

Added in version 3.12.

Py_ssize_t **PyUnstable_Long_CompactValue**(const *PyLongObject* *op)

> Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

If *op* is compact, as determined by `PyUnstable_Long_IsCompact()`, return its value.

Otherwise, the return value is undefined.

Added in version 3.12.

Export API

Added in version 3.14.

struct **PyLongLayout**

Layout of an array of "digits" ("limbs" in the GMP terminology), used to represent absolute value for arbitrary precision integers.

Use `PyLong_GetNativeLayout()` to get the native layout of Python `int` objects, used internally for integers with "big enough" absolute value.

See also `sys.int_info` which exposes similar information in Python.

uint8_t **bits_per_digit**

Bits per digit. For example, a 15 bit digit means that bits 0-14 contain meaningful information.

uint8_t **digit_size**

Digit size in bytes. For example, a 15 bit digit will require at least 2 bytes.

int8_t **digits_order**

Digits order:

- `1` for most significant digit first
- `-1` for least significant digit first

int8_t **digit_endianness**

Digit endianness:

- `1` for most significant byte first (big endian)
- `-1` for least significant byte first (little endian)

const *PyLongLayout* ***PyLong_GetNativeLayout**(void)

Get the native layout of Python `int` objects.

See the *PyLongLayout* structure.

The function must not be called before Python initialization nor after Python finalization. The returned layout is valid until Python is finalized. The layout is the same for all Python sub-interpreters in a process, and so it can be cached.

struct **PyLongExport**

Export of a Python `int` object.

There are two cases:

- If *digits* is `NULL`, only use the *value* member.
- If *digits* is not `NULL`, use *negative*, *ndigits* and *digits* members.

int64_t **value**

The native integer value of the exported `int` object. Only valid if *digits* is `NULL`.

uint8_t **negative**

`1` if the number is negative, `0` otherwise. Only valid if *digits* is not `NULL`.

Py_ssize_t **ndigits**

Number of digits in *digits* array. Only valid if *digits* is not `NULL`.

const void ***digits**

Read-only array of unsigned digits. Can be `NULL`.

int **PyLong_Export**(*PyObject* *obj, *PyLongExport* *export_long)

Export a Python `int` object.

export_long must point to a *PyLongExport* structure allocated by the caller. It must not be `NULL`.

On success, fill in **export_long* and return `0`. On error, set an exception and return `-1`.

PyLong_FreeExport() must be called when the export is no longer needed.

CPython uygulama ayrıntısı: This function always succeeds if *obj* is a Python `int` object or a subclass.

void **PyLong_FreeExport**(*PyLongExport* *export_long)

Release the export *export_long* created by *PyLong_Export()*.

CPython uygulama ayrıntısı: Calling *PyLong_FreeExport()* is optional if *export_long->digits* is `NULL`.

PyLongWriter API

The *PyLongWriter* API can be used to import an integer.

Added in version 3.14.

struct **PyLongWriter**

A Python `int` writer instance.

The instance must be destroyed by *PyLongWriter_Finish()* or *PyLongWriter_Discard()*.

PyLongWriter ***PyLongWriter_Create**(int negative, *Py_ssize_t* ndigits, void **digits)

Create a *PyLongWriter*.

On success, allocate **digits* and return a writer. On error, set an exception and return `NULL`.

negative is `1` if the number is negative, or `0` otherwise.

ndigits is the number of digits in the *digits* array. It must be greater than 0.

digits must not be NULL.

After a successful call to this function, the caller should fill in the array of digits *digits* and then call `PyLongWriter_Finish()` to get a Python `int`. The layout of *digits* is described by `PyLong_GetNativeLayout()`.

Digits must be in the range `[0; (1 << bits_per_digit) - 1]` (where the `bits_per_digit` is the number of bits per digit). Any unused most significant digits must be set to `0`.

Alternately, call `PyLongWriter_Discard()` to destroy the writer instance without creating an `int` object.

PyObject ***PyLongWriter_Finish**(*PyLongWriter* *writer)

Döndürdüğü değer: Yeni referans. Finish a `PyLongWriter` created by `PyLongWriter_Create()`.

On success, return a Python `int` object. On error, set an exception and return `NULL`.

The function takes care of normalizing the digits and converts the object to a compact integer if needed.

The writer instance and the *digits* array are invalid after the call.

void **PyLongWriter_Discard**(*PyLongWriter* *writer)

Discard a `PyLongWriter` created by `PyLongWriter_Create()`.

If *writer* is `NULL`, no operation is performed.

The writer instance and the *digits* array are invalid after the call.

9.2.2 Boolean Objects

Booleans in Python are implemented as a subclass of integers. There are only two booleans, `Py_False` and `Py_True`. As such, the normal creation and deletion functions don't apply to booleans. The following macros are available, however.

PyTypeObject **PyBool_Type**

Bir parçası Kararlı ABI. This instance of `PyTypeObject` represents the Python boolean type; it is the same object as `bool` in the Python layer.

int **PyBool_Check**(*PyObject* *o)

Return true if *o* is of type `PyBool_Type`. This function always succeeds.

PyObject ***Py_False**

The Python `False` object. This object has no methods and is *immortal*.

3.12 sürümünde değişti: `Py_False` is *immortal*.

PyObject ***Py_True**

The Python `True` object. This object has no methods and is *immortal*.

3.12 sürümünde değişti: `Py_True` is *immortal*.

Py_RETURN_FALSE

Return `Py_False` from a function.

Py_RETURN_TRUE

Return `Py_True` from a function.

PyObject ***PyBool_FromLong**(long v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return `Py_True` or `Py_False`, depending on the truth value of *v*.

9.2.3 Floating-Point Objects

type **PyFloatObject**

This subtype of `PyObject` represents a Python floating-point object.

PyTypeObject **PyFloat_Type**

Bir parçası Kararlı ABI. This instance of `PyTypeObject` represents the Python floating-point type. This is the same object as `float` in the Python layer.

int **PyFloat_Check**(*PyObject* *p)

Return true if its argument is a `PyFloatObject` or a subtype of `PyFloatObject`. This function always succeeds.

int **PyFloat_CheckExact**(*PyObject* *p)

Return true if its argument is a `PyFloatObject`, but not a subtype of `PyFloatObject`. This function always succeeds.

PyObject ***PyFloat_FromString**(*PyObject* *str)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a `PyFloatObject` object based on the string value in *str*, or `NULL` on failure.

PyObject ***PyFloat_FromDouble**(double v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a `PyFloatObject` object from *v*, or `NULL` on failure.

double **PyFloat_AsDouble**(*PyObject* *pyfloat)

Bir parçası Kararlı ABI. Return a C `double` representation of the contents of *pyfloat*. If *pyfloat* is not a Python floating-point object but has a `__float__()` method, this method will first be called to convert *pyfloat* into a float. If `__float__()` is not defined then it falls back to `__index__()`. This method returns `-1.0` upon failure, so one should call `PyErr_Occurred()` to check for errors.

3.8 sürümünde değişti: Use `__index__()` if available.

double **PyFloat_AS_DOUBLE**(*PyObject* *pyfloat)

Return a C `double` representation of the contents of *pyfloat*, but without error checking.

PyObject ***PyFloat_GetInfo**(void)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a structseq instance which contains information about the precision, minimum and maximum values of a float. It's a thin wrapper around the header file `float.h`.

double **PyFloat_GetMax**()

Bir parçası Kararlı ABI. Return the maximum representable finite float *DBL_MAX* as C `double`.

double **PyFloat_GetMin**()

Bir parçası Kararlı ABI. Return the minimum normalized positive float *DBL_MIN* as C `double`.

Pack and Unpack functions

The pack and unpack functions provide an efficient platform-independent way to store floating-point values as byte strings. The Pack routines produce a bytes string from a C `double`, and the Unpack routines produce a C `double` from such a bytes string. The suffix (2, 4 or 8) specifies the number of bytes in the bytes string.

On platforms that appear to use IEEE 754 formats these functions work by copying bits. On other platforms, the 2-byte format is identical to the IEEE 754 binary16 half-precision format, the 4-byte format (32-bit) is identical to the IEEE 754 binary32 single precision format, and the 8-byte format to the IEEE 754 binary64 double precision format, although the packing of INFs and NaNs (if such things exist on the platform) isn't handled correctly, and attempting to unpack a bytes string containing an IEEE INF or NaN will raise an exception.

Note that NaNs type may not be preserved on IEEE platforms (silent NaN become quiet), for example on x86 systems in 32-bit mode.

On non-IEEE platforms with more precision, or larger dynamic range, than IEEE 754 supports, not all values can be packed; on non-IEEE platforms with less precision, or smaller dynamic range, not all values can be unpacked. What happens in such cases is partly accidental (alas).

Added in version 3.11.

Pack functions

The pack routines write 2, 4 or 8 bytes, starting at *p*. *le* is an `int` argument, non-zero if you want the bytes string in little-endian format (exponent last, at `p+1`, `p+3`, or `p+6` `p+7`), zero if you want big-endian format (exponent first, at *p*). The `PY_BIG_ENDIAN` constant can be used to use the native endian: it is equal to `1` on big endian processor, or `0` on little endian processor.

Return value: `0` if all is OK, `-1` if error (and an exception is set, most likely `OverflowError`).

There are two problems on non-IEEE platforms:

- What this does is undefined if *x* is a NaN or infinity.
- `-0.0` and `+0.0` produce the same bytes string.

int **PyFloat_Pack2**(double x, char *p, int le)

Pack a C double as the IEEE 754 binary16 half-precision format.

int **PyFloat_Pack4**(double x, char *p, int le)

Pack a C double as the IEEE 754 binary32 single precision format.

int **PyFloat_Pack8**(double x, char *p, int le)

Pack a C double as the IEEE 754 binary64 double precision format.

Unpack functions

The unpack routines read 2, 4 or 8 bytes, starting at *p*. *le* is an `int` argument, non-zero if the bytes string is in little-endian format (exponent last, at `p+1`, `p+3` or `p+6` and `p+7`), zero if big-endian (exponent first, at *p*). The `PY_BIG_ENDIAN` constant can be used to use the native endian: it is equal to `1` on big endian processor, or `0` on little endian processor.

Return value: The unpacked double. On error, this is `-1.0` and *`PyErr_Occurred()`* is true (and an exception is set, most likely `OverflowError`).

Note that on a non-IEEE platform this will refuse to unpack a bytes string that represents a NaN or infinity.

double **PyFloat_Unpack2**(const char *p, int le)

Unpack the IEEE 754 binary16 half-precision format as a C double.

double **PyFloat_Unpack4**(const char *p, int le)

Unpack the IEEE 754 binary32 single precision format as a C double.

double **PyFloat_Unpack8**(const char *p, int le)

Unpack the IEEE 754 binary64 double precision format as a C double.

9.2.4 Complex Number Objects

Python's complex number objects are implemented as two distinct types when viewed from the C API: one is the Python object exposed to Python programs, and the other is a C structure which represents the actual complex number value. The API provides functions for working with both.

Complex Numbers as C Structures

Note that the functions which accept these structures as parameters and return them as results do so *by value* rather than dereferencing them through pointers. This is consistent throughout the API.

type **Py_complex**

The C structure which corresponds to the value portion of a Python complex number object. Most of the functions for dealing with complex number objects use structures of this type as input or output values, as appropriate.

double **real**

double **imag**

The structure is defined as:

```
typedef struct {
    double real;
    double imag;
} Py_complex;
```

Py_complex **_Py_c_sum**(*Py_complex* left, *Py_complex* right)

Return the sum of two complex numbers, using the C *Py_complex* representation.

Py_complex **_Py_c_diff**(*Py_complex* left, *Py_complex* right)

Return the difference between two complex numbers, using the C *Py_complex* representation.

Py_complex **_Py_c_neg**(*Py_complex* num)

Return the negation of the complex number *num*, using the C *Py_complex* representation.

Py_complex **_Py_c_prod**(*Py_complex* left, *Py_complex* right)

Return the product of two complex numbers, using the C *Py_complex* representation.

Py_complex **_Py_c_quot**(*Py_complex* dividend, *Py_complex* divisor)

Return the quotient of two complex numbers, using the C *Py_complex* representation.

If *divisor* is null, this method returns zero and sets `errno` to `EDOM`.

Py_complex **_Py_c_pow**(*Py_complex* num, *Py_complex* exp)

Return the exponentiation of *num* by *exp*, using the C *Py_complex* representation.

If *num* is null and *exp* is not a positive real number, this method returns zero and sets `errno` to `EDOM`.

Set `errno` to `ERANGE` on overflows.

Complex Numbers as Python Objects

type **PyComplexObject**

This subtype of *PyObject* represents a Python complex number object.

PyTypeObject **PyComplex_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python complex number type. It is the same object as `complex` in the Python layer.

int **PyComplex_Check**(*PyObject* *p)

Return true if its argument is a *PyComplexObject* or a subtype of *PyComplexObject*. This function always succeeds.

int **PyComplex_CheckExact**(*PyObject* *p)

Return true if its argument is a *PyComplexObject*, but not a subtype of *PyComplexObject*. This function always succeeds.

PyObject ***PyComplex_FromCComplex**(*Py_complex* v)

Döndürdüğü değer: Yeni referans. Create a new Python complex number object from a C *Py_complex* value. Return `NULL` with an exception set on error.

PyObject ***PyComplex_FromDoubles**(double real, double imag)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new *PyComplexObject* object from *real* and *imag*. Return `NULL` with an exception set on error.

double **PyComplex_RealAsDouble**(*PyObject* *op)

Bir parçası Kararlı ABI. Return the real part of *op* as a C `double`.

If *op* is not a Python complex number object but has a `__complex__()` method, this method will first be called to convert *op* to a Python complex number object. If `__complex__()` is not defined then it falls back to call *PyFloat_AsDouble()* and returns its result.

Upon failure, this method returns `-1.0` with an exception set, so one should call *PyErr_Occurred()* to check for errors.

3.13 sürümünde değişti: Use `__complex__()` if available.

double **PyComplex_ImagAsDouble**(*PyObject* *op)

Bir parçası Kararlı ABI. Return the imaginary part of *op* as a C `double`.

If *op* is not a Python complex number object but has a `__complex__()` method, this method will first be called to convert *op* to a Python complex number object. If `__complex__()` is not defined then it falls back to call *PyFloat_AsDouble()* and returns `0.0` on success.

Upon failure, this method returns `-1.0` with an exception set, so one should call *PyErr_Occurred()* to check for errors.

3.13 sürümünde değişti: Use `__complex__()` if available.

Py_complex **PyComplex_AsCComplex**(*PyObject* *op)

Return the *Py_complex* value of the complex number *op*.

If *op* is not a Python complex number object but has a `__complex__()` method, this method will first be called to convert *op* to a Python complex number object. If `__complex__()` is not defined then it falls back to `__float__()`. If `__float__()` is not defined then it falls back to `__index__()`.

Upon failure, this method returns *Py_complex* with *real* set to `-1.0` and with an exception set, so one should call *PyErr_Occurred()* to check for errors.

3.8 sürümünde değişti: Use `__index__()` if available.

9.3 Sequence Objects

Generic operations on sequence objects were discussed in the previous chapter; this section deals with the specific kinds of sequence objects that are intrinsic to the Python language.

9.3.1 Bytes Objects

These functions raise `TypeError` when expecting a bytes parameter and called with a non-bytes parameter.

type **PyBytesObject**

This subtype of *PyObject* represents a Python bytes object.

PyTypeObject **PyBytes_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python bytes type; it is the same object as `bytes` in the Python layer.

int **PyBytes_Check**(*PyObject* *o)

Return true if the object *o* is a bytes object or an instance of a subtype of the bytes type. This function always succeeds.

int **PyBytes_CheckExact**(*PyObject* *o)

Return true if the object *o* is a bytes object, but not an instance of a subtype of the bytes type. This function always succeeds.

PyObject ***PyBytes_FromString**(const char *v)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new bytes object with a copy of the string *v* as value on success, and `NULL` on failure. The parameter *v* must not be `NULL`; it will not be checked.

PyObject ***PyBytes_FromStringAndSize**(const char *v, *Py_ssize_t* len)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new bytes object with a copy of the string *v* as value and length *len* on success, and `NULL` on failure. If *v* is `NULL`, the contents of the bytes object are uninitialized.

PyObject ***PyBytes_FromFormat**(const char *format, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Take a C `printf()`-style *format* string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the *format* string. The following format characters are allowed:

Format Characters	Type	Comment
`%%`	*n/a*	The literal % character.
`%c`	int	A single byte, represented as a C int.
`%d`	int	Equivalent to `printf("%d")`.[1]
`%u`	unsigned int	Equivalent to `printf("%u")`.[1]
`%ld`	long	Equivalent to `printf("%ld")`.[1]
`%lu`	unsigned long	Equivalent to `printf("%lu")`.[1]
`%zd`	*Py_ssize_t*	Equivalent to `printf("%zd")`.[1]
`%zu`	size_t	Equivalent to `printf("%zu")`.[1]
`%i`	int	Equivalent to `printf("%i")`.[1]
`%x`	int	Equivalent to `printf("%x")`.[1]
`%s`	const char*	A null-terminated C character array.
`%p`	const void*	The hex representation of a C pointer. Mostly equivalent to `printf("%p")` except that it is guaranteed to start with the literal `0x` regardless of what the platform's `printf` yields.

An unrecognized format character causes all the rest of the format string to be copied as-is to the result object, and any extra arguments discarded.

PyObject ***PyBytes_FromFormatV**(const char *format, va_list vargs)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Identical to *PyBytes_FromFormat()* except that it takes exactly two arguments.

PyObject ***PyBytes_FromObject**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the bytes representation of object *o* that implements the buffer protocol.

Py_ssize_t **PyBytes_Size**(*PyObject* *o)

Bir parçası Kararlı ABI. Return the length of the bytes in bytes object *o*.

Py_ssize_t **PyBytes_GET_SIZE**(*PyObject* *o)

Similar to *PyBytes_Size()*, but without error checking.

char ***PyBytes_AsString**(*PyObject* *o)

Bir parçası Kararlı ABI. Return a pointer to the contents of *o*. The pointer refers to the internal buffer of *o*, which consists of `len(o) + 1` bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using `PyBytes_FromStringAndSize(NULL, size)`. It must not be deallocated. If *o* is not a bytes object at all, *PyBytes_AsString()* returns `NULL` and raises `TypeError`.

char ***PyBytes_AS_STRING**(*PyObject* *string)

Similar to *PyBytes_AsString()*, but without error checking.

int **PyBytes_AsStringAndSize**(*PyObject* *obj, char **buffer, *Py_ssize_t* *length)

Bir parçası Kararlı ABI. Return the null-terminated contents of the object *obj* through the output variables *buffer* and *length*. Returns `0` on success.

If *length* is `NULL`, the bytes object may not contain embedded null bytes; if it does, the function returns `-1` and a `ValueError` is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using

[1] For integer specifiers (d, u, ld, lu, zd, zu, i, x): the 0-conversion flag has effect even when a precision is given.

`PyBytes_FromStringAndSize(NULL, size)`. It must not be deallocated. If *obj* is not a bytes object at all, *PyBytes_AsStringAndSize()* returns `-1` and raises `TypeError`.

3.5 sürümünde değişti: Previously, `TypeError` was raised when embedded null bytes were encountered in the bytes object.

void **PyBytes_Concat**(*PyObject* **bytes, *PyObject* *newpart)

Bir parçası Kararlı ABI. Create a new bytes object in **bytes* containing the contents of *newpart* appended to *bytes*; the caller will own the new reference. The reference to the old value of *bytes* will be stolen. If the new object cannot be created, the old reference to *bytes* will still be discarded and the value of **bytes* will be set to `NULL`; the appropriate exception will be set.

void **PyBytes_ConcatAndDel**(*PyObject* **bytes, *PyObject* *newpart)

Bir parçası Kararlı ABI. Create a new bytes object in **bytes* containing the contents of *newpart* appended to *bytes*. This version releases the *strong reference* to *newpart* (i.e. decrements its reference count).

PyObject ***PyBytes_Join**(*PyObject* *sep, *PyObject* *iterable)

Similar to `sep.join(iterable)` in Python.

sep must be Python `bytes` object. (Note that *PyUnicode_Join()* accepts `NULL` separator and treats it as a space, whereas *PyBytes_Join()* doesn't accept `NULL` separator.)

iterable must be an iterable object yielding objects that implement the *buffer protocol*.

On success, return a new `bytes` object. On error, set an exception and return `NULL`.

Added in version 3.14.

int **_PyBytes_Resize**(*PyObject* **bytes, *Py_ssize_t* newsize)

Resize a bytes object. *newsize* will be the new length of the bytes object. You can think of it as creating a new bytes object and destroying the old one, only more efficiently. Pass the address of an existing bytes object as an lvalue (it may be written into), and the new size desired. On success, **bytes* holds the resized bytes object and `0` is returned; the address in **bytes* may differ from its input value. If the reallocation fails, the original bytes object at **bytes* is deallocated, **bytes* is set to `NULL`, `MemoryError` is set, and `-1` is returned.

9.3.2 Byte Array Objects

type **PyByteArrayObject**

This subtype of *PyObject* represents a Python bytearray object.

PyTypeObject **PyByteArray_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python bytearray type; it is the same object as `bytearray` in the Python layer.

Type check macros

int **PyByteArray_Check**(*PyObject* *o)

Return true if the object *o* is a bytearray object or an instance of a subtype of the bytearray type. This function always succeeds.

int **PyByteArray_CheckExact**(*PyObject* *o)

Return true if the object *o* is a bytearray object, but not an instance of a subtype of the bytearray type. This function always succeeds.

Direct API functions

PyObject ***PyByteArray_FromObject**(*PyObject* *o)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new bytearray object from any object, *o*, that implements the *buffer protocol*.

On failure, return `NULL` with an exception set.

PyObject ***PyByteArray_FromStringAndSize**(const char *string, *Py_ssize_t* len)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a new bytearray object from *string* and its length, *len*.

On failure, return `NULL` with an exception set.

PyObject ***PyByteArray_Concat**(*PyObject* *a, *PyObject* *b)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Concat bytearrays *a* and *b* and return a new bytearray with the result.

On failure, return `NULL` with an exception set.

Py_ssize_t **PyByteArray_Size**(*PyObject* *bytearray)

Bir parçası Kararlı ABI. Return the size of *bytearray* after checking for a `NULL` pointer.

char ***PyByteArray_AsString**(*PyObject* *bytearray)

Bir parçası Kararlı ABI. Return the contents of *bytearray* as a char array after checking for a `NULL` pointer. The returned array always has an extra null byte appended.

int **PyByteArray_Resize**(*PyObject* *bytearray, *Py_ssize_t* len)

Bir parçası Kararlı ABI. Resize the internal buffer of *bytearray* to *len*. Failure is a `-1` return with an exception set.

3.14 sürümünde değişti: A negative *len* will now result in an exception being set and -1 returned.

Macros

These macros trade safety for speed and they don't check pointers.

char ***PyByteArray_AS_STRING**(*PyObject* *bytearray)

Similar to *PyByteArray_AsString()*, but without error checking.

Py_ssize_t **PyByteArray_GET_SIZE**(*PyObject* *bytearray)

Similar to *PyByteArray_Size()*, but without error checking.

9.3.3 Unicode Objects and Codecs

Unicode Objects

Since the implementation of **PEP 393** in Python 3.3, Unicode objects internally use a variety of representations, in order to allow handling the complete range of Unicode characters while staying memory efficient. There are special cases for strings where all code points are below 128, 256, or 65536; otherwise, code points must be below 1114112 (which is the full Unicode range).

UTF-8 representation is created on demand and cached in the Unicode object.

Not

The *Py_UNICODE* representation has been removed since Python 3.12 with deprecated APIs. See **PEP 623** for more information.

Unicode Type

These are the basic Unicode object types used for the Unicode implementation in Python:

PyTypeObject **PyUnicode_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python Unicode type. It is exposed to Python code as `str`.

PyTypeObject **PyUnicodeIter_Type**

Bir parçası Kararlı ABI. This instance of `PyTypeObject` represents the Python Unicode iterator type. It is used to iterate over Unicode string objects.

type **Py_UCS4**

type **Py_UCS2**

type **Py_UCS1**

Bir parçası Kararlı ABI. These types are typedefs for unsigned integer types wide enough to contain characters of 32 bits, 16 bits and 8 bits, respectively. When dealing with single Unicode characters, use `Py_UCS4`.

Added in version 3.3.

type **PyASCIIObject**

type **PyCompactUnicodeObject**

type **PyUnicodeObject**

These subtypes of `PyObject` represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return `PyObject` pointers.

Added in version 3.3.

The following APIs are C macros and static inlined functions for fast checks and access to internal read-only data of Unicode objects:

int **PyUnicode_Check**(*PyObject* *obj)

Return true if the object *obj* is a Unicode object or an instance of a Unicode subtype. This function always succeeds.

int **PyUnicode_CheckExact**(*PyObject* *obj)

Return true if the object *obj* is a Unicode object, but not an instance of a subtype. This function always succeeds.

Py_ssize_t **PyUnicode_GET_LENGTH**(*PyObject* *unicode)

Return the length of the Unicode string, in code points. *unicode* has to be a Unicode object in the "canonical" representation (not checked).

Added in version 3.3.

Py_UCS1 ***PyUnicode_1BYTE_DATA**(*PyObject* *unicode)

Py_UCS2 ***PyUnicode_2BYTE_DATA**(*PyObject* *unicode)

Py_UCS4 ***PyUnicode_4BYTE_DATA**(*PyObject* *unicode)

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use `PyUnicode_KIND()` to select the right function.

Added in version 3.3.

PyUnicode_1BYTE_KIND

PyUnicode_2BYTE_KIND

PyUnicode_4BYTE_KIND

Return values of the `PyUnicode_KIND()` macro.

Added in version 3.3.

3.12 sürümünde değişti: `PyUnicode_WCHAR_KIND` has been removed.

int **PyUnicode_KIND**(*PyObject* *unicode)

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. *unicode* has to be a Unicode object in the "canonical" representation (not checked).

Added in version 3.3.

void *__PyUnicode_DATA__(*PyObject* *unicode)

Return a void pointer to the raw Unicode buffer. *unicode* has to be a Unicode object in the "canonical" representation (not checked).

Added in version 3.3.

void __PyUnicode_WRITE__(int kind, void *data, *Py_ssize_t* index, *Py_UCS4* value)

Write the code point *value* to the given zero-based *index* in a string.

The *kind* value and *data* pointer must have been obtained from a string using `PyUnicode_KIND()` and `PyUnicode_DATA()` respectively. You must hold a reference to that string while calling `PyUnicode_WRITE()`. All requirements of `PyUnicode_WriteChar()` also apply.

The function performs no checks for any of its requirements, and is intended for usage in loops.

Added in version 3.3.

Py_UCS4 __PyUnicode_READ__(int kind, void *data, *Py_ssize_t* index)

Read a code point from a canonical representation *data* (as obtained with `PyUnicode_DATA()`). No checks or ready calls are performed.

Added in version 3.3.

Py_UCS4 __PyUnicode_READ_CHAR__(*PyObject* *unicode, *Py_ssize_t* index)

Read a character from a Unicode object *unicode*, which must be in the "canonical" representation. This is less efficient than `PyUnicode_READ()` if you do multiple consecutive reads.

Added in version 3.3.

Py_UCS4 __PyUnicode_MAX_CHAR_VALUE__(*PyObject* *unicode)

Return the maximum code point that is suitable for creating another string based on *unicode*, which must be in the "canonical" representation. This is always an approximation but more efficient than iterating over the string.

Added in version 3.3.

int __PyUnicode_IsIdentifier__(*PyObject* *unicode)

Bir parçası Kararlı ABI. Return `1` if the string is a valid identifier according to the language definition, section identifiers. Return `0` otherwise.

3.9 sürümünde değişti: The function does not call `Py_FatalError()` anymore if the string is not ready.

unsigned int __PyUnicode_IS_ASCII__(*PyObject* *unicode)

Return true if the string only contains ASCII characters. Equivalent to `str.isascii()`.

Added in version 3.2.

Unicode Character Properties

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

int __Py_UNICODE_ISSPACE__(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a whitespace character.

int __Py_UNICODE_ISLOWER__(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a lowercase character.

int __Py_UNICODE_ISUPPER__(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is an uppercase character.

int __Py_UNICODE_ISTITLE__(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a titlecase character.

int **Py_UNICODE_ISLINEBREAK**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a linebreak character.

int **Py_UNICODE_ISDECIMAL**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a decimal character.

int **Py_UNICODE_ISDIGIT**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a digit character.

int **Py_UNICODE_ISNUMERIC**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a numeric character.

int **Py_UNICODE_ISALPHA**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is an alphabetic character.

int **Py_UNICODE_ISALNUM**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is an alphanumeric character.

int **Py_UNICODE_ISPRINTABLE**(*Py_UCS4* ch)

Return `1` or `0` depending on whether *ch* is a printable character, in the sense of `str.isprintable()`.

These APIs can be used for fast direct character conversions:

Py_UCS4 **Py_UNICODE_TOLOWER**(*Py_UCS4* ch)

Return the character *ch* converted to lower case.

Py_UCS4 **Py_UNICODE_TOUPPER**(*Py_UCS4* ch)

Return the character *ch* converted to upper case.

Py_UCS4 **Py_UNICODE_TOTITLE**(*Py_UCS4* ch)

Return the character *ch* converted to title case.

int **Py_UNICODE_TODECIMAL**(*Py_UCS4* ch)

Return the character *ch* converted to a decimal positive integer. Return `-1` if this is not possible. This function does not raise exceptions.

int **Py_UNICODE_TODIGIT**(*Py_UCS4* ch)

Return the character *ch* converted to a single digit integer. Return `-1` if this is not possible. This function does not raise exceptions.

double **Py_UNICODE_TONUMERIC**(*Py_UCS4* ch)

Return the character *ch* converted to a double. Return `-1.0` if this is not possible. This function does not raise exceptions.

These APIs can be used to work with surrogates:

int **Py_UNICODE_IS_SURROGATE**(*Py_UCS4* ch)

Check if *ch* is a surrogate (`0xD800 <= ch <= 0xDFFF`).

int **Py_UNICODE_IS_HIGH_SURROGATE**(*Py_UCS4* ch)

Check if *ch* is a high surrogate (`0xD800 <= ch <= 0xDBFF`).

int **Py_UNICODE_IS_LOW_SURROGATE**(*Py_UCS4* ch)

Check if *ch* is a low surrogate (`0xDC00 <= ch <= 0xDFFF`).

Py_UCS4 **Py_UNICODE_JOIN_SURROGATES**(*Py_UCS4* high, *Py_UCS4* low)

Join two surrogate code points and return a single *Py_UCS4* value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair. *high* must be in the range [0xD800; 0xDBFF] and *low* must be in the range [0xDC00; 0xDFFF].

Creating and accessing Unicode strings

To create Unicode objects and access their basic sequence properties, use these APIs:

PyObject ***PyUnicode_New**(*Py_ssize_t* size, *Py_UCS4* maxchar)

Döndürdüğü değer: Yeni referans. Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

On error, set an exception and return `NULL`.

After creation, the string can be filled by *PyUnicode_WriteChar()*, *PyUnicode_CopyCharacters()*, *PyUnicode_Fill()*, *PyUnicode_WRITE()* or similar. Since strings are supposed to be immutable, take care to not "use" the result while it is being modified. In particular, before it's filled with its final contents, a string:

- must not be hashed,
- must not be *converted to UTF-8*, or another non-"canonical" representation,
- must not have its reference count changed,
- must not be shared with code that might do one of the above.

This list is not exhaustive. Avoiding these uses is your responsibility; Python does not always check these requirements.

To avoid accidentally exposing a partially-written string object, prefer using the *PyUnicodeWriter* API, or one of the `PyUnicode_From*` functions below.

Added in version 3.3.

PyObject ***PyUnicode_FromKindAndData**(int kind, const void *buffer, *Py_ssize_t* size)

Döndürdüğü değer: Yeni referans. Create a new Unicode object with the given *kind* (possible values are *PyUnicode_1BYTE_KIND* etc., as returned by *PyUnicode_KIND()*). The *buffer* must point to an array of *size* units of 1, 2 or 4 bytes per character, as given by the kind.

If necessary, the input *buffer* is copied and transformed into the canonical representation. For example, if the *buffer* is a UCS4 string (*PyUnicode_4BYTE_KIND*) and it consists only of codepoints in the UCS1 range, it will be transformed into UCS1 (*PyUnicode_1BYTE_KIND*).

Added in version 3.3.

PyObject ***PyUnicode_FromStringAndSize**(const char *str, *Py_ssize_t* size)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object from the char buffer *str*. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. The return value might be a shared object, i.e. modification of the data is not allowed.

This function raises `SystemError` when:

- *size* < 0,
- *str* is `NULL` and *size* > 0

3.12 sürümünde değişti: *str* == `NULL` with *size* > 0 is not allowed anymore.

PyObject ***PyUnicode_FromString**(const char *str)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object from a UTF-8 encoded null-terminated char buffer *str*.

PyObject ***PyUnicode_FromFormat**(const char *format, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Take a C `printf()`-style *format* string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the *format* ASCII-encoded string.

A conversion specifier contains two or more characters and has the following components, which must occur in this order:

1. The `'%'` character, which marks the start of the specifier.
2. Conversion flags (optional), which affect the result of some conversion types.
3. Minimum field width (optional). If specified as an `'*'` (asterisk), the actual width is given in the next argument, which must be of type `int`, and the object to convert comes after the minimum field width and optional precision.
4. Precision (optional), given as a `'.'` (dot) followed by the precision. If specified as `'*'` (an asterisk), the actual precision is given in the next argument, which must be of type `int`, and the value to convert comes after the precision.
5. Length modifier (optional).
6. Conversion type.

The conversion flag characters are:

Flag	Meaning
`0`	The conversion will be zero padded for numeric values.
`-`	The converted value is left adjusted (overrides the `0` flag if both are given).

The length modifiers for following integer conversions (`d`, `i`, `o`, `u`, `x`, or `X`) specify the type of the argument (`int` by default):

Modifier	Types
`l`	`long` or `unsigned long`
`ll`	`long long` or `unsigned long long`
`j`	`intmax_t` or `uintmax_t`
`z`	`size_t` or `ssize_t`
`t`	`ptrdiff_t`

The length modifier `l` for following conversions `s` or `V` specify that the type of the argument is `const wchar_t*`.

The conversion specifiers are:

Conversion Specifier	Type	Comment
`%`	*n/a*	The literal `%` character.
`d`, `i`	Specified by the length modifier	The decimal representation of a signed C integer.
`u`	Specified by the length modifier	The decimal representation of an unsigned C integer.
`o`	Specified by the length modifier	The octal representation of an unsigned C integer.
`x`	Specified by the length modifier	The hexadecimal representation of an unsigned C integer (lowercase).
`X`	Specified by the length modifier	The hexadecimal representation of an unsigned C integer (uppercase).
`c`	`int`	A single character.
`s`	`const char*` or `const wchar_t*`	A null-terminated C character array.
`p`	`const void*`	The hex representation of a C pointer. Mostly equivalent to `printf("%p")` except that it is guaranteed to start with the literal `0x` regardless of what the platform's `printf` yields.
`A`	*`PyObject`*`*`	The result of calling `ascii()`.
`U`	*`PyObject`*`*`	A Unicode object.
`V`	*`PyObject`*`*`, `const char*` or `const wchar_t*`	A Unicode object (which may be `NULL`) and a null-terminated C character array as a second parameter (which will be used, if the first parameter is `NULL`).
`S`	*`PyObject`*`*`	The result of calling *`PyObject_Str()`*.
`R`	*`PyObject`*`*`	The result of calling *`PyObject_Repr()`*.
`T`	*`PyObject`*`*`	Get the fully qualified name of an object type; call *`PyType_GetFullyQualifiedName()`*.
`#T`	*`PyObject`*`*`	Similar to `T` format, but use a colon (`:`) as separator between the module name and the qualified name.
`N`	*`PyTypeObject`*`*`	Get the fully qualified name of a type; call *`PyType_GetFullyQualifiedName()`*.
`#N`	*`PyTypeObject`*`*`	Similar to `N` format, but use a colon (`:`) as separator between the module name and the qualified name.

Not

The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes or `wchar_t` items (if the length modifier `l` is used) for `"%s"` and `"%V"` (if the `PyObject*` argument is `NULL`), and a number of characters for `"%A"`, `"%U"`, `"%S"`, `"%R"` and `"%V"` (if the `PyObject*` argument is not `NULL`).

Not

Unlike to C `printf()` the `0` flag has effect even when a precision is given for integer conversions (`d`, `i`, `u`, `o`, `x`, or `X`).

3.2 sürümünde değişti: Support for `"%lld"` and `"%llu"` added.

3.3 sürümünde değişti: Support for `"%li"`, `"%lli"` and `"%zi"` added.

3.4 sürümünde değişti: Support width and precision formatter for `"%s"`, `"%A"`, `"%U"`, `"%V"`, `"%S"`, `"%R"`

added.

3.12 sürümünde değişti: Support for conversion specifiers `o` and `X`. Support for length modifiers `j` and `t`. Length modifiers are now applied to all integer conversions. Length modifier `l` is now applied to conversion specifiers `s` and `V`. Support for variable width and precision `*`. Support for flag `-`.

An unrecognized format character now sets a `SystemError`. In previous versions it caused all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

3.13 sürümünde değişti: Support for `%T`, `%#T`, `%N` and `%#N` formats added.

PyObject ***PyUnicode_FromFormatV**(const char *format, va_list vargs)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Identical to *`PyUnicode_FromFormat()`* except that it takes exactly two arguments.

PyObject ***PyUnicode_FromObject**(*PyObject* *obj)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If *obj* is already a true Unicode object (not a subtype), return a new *strong reference* to the object.

Objects other than Unicode or its subtypes will cause a `TypeError`.

PyObject ***PyUnicode_FromOrdinal**(int ordinal)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode Object from the given Unicode code point *ordinal*.

The ordinal must be in `range(0x110000)`. A `ValueError` is raised in the case it is not.

PyObject ***PyUnicode_FromEncodedObject**(*PyObject* *obj, const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Decode an encoded object *obj* to a Unicode object.

`bytes`, `bytearray` and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be `NULL` to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a `TypeError` to be set.

The API returns `NULL` if there was an error. The caller is responsible for decref'ing the returned objects.

void **PyUnicode_Append**(*PyObject* **p_left, *PyObject* *right)

Bir parçası Kararlı ABI. Append the string *right* to the end of *p_left*. *p_left* must point to a *strong reference* to a Unicode object; `PyUnicode_Append()` releases ("steals") this reference.

On error, set **p_left* to `NULL` and set an exception.

On success, set **p_left* to a new strong reference to the result.

void **PyUnicode_AppendAndDel**(*PyObject* **p_left, *PyObject* *right)

Bir parçası Kararlı ABI. The function is similar to *`PyUnicode_Append()`*, with the only difference being that it decrements the reference count of *right* by one.

PyObject ***PyUnicode_BuildEncodingMap**(*PyObject* *string)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a mapping suitable for decoding a custom single-byte encoding. Given a Unicode string *string* of up to 256 characters representing an encoding table, returns either a compact internal mapping object or a dictionary mapping character ordinals to byte values. Raises a `TypeError` and return `NULL` on invalid input.

Added in version 3.2.

const char ***PyUnicode_GetDefaultEncoding**(void)

Bir parçası Kararlı ABI. Return the name of the default string encoding, `"utf-8"`. See `sys.getdefaultencoding()`.

The returned string does not need to be freed, and is valid until interpreter shutdown.

Py_ssize_t **PyUnicode_GetLength**(*PyObject* *unicode)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return the length of the Unicode object, in code points.

On error, set an exception and return `-1`.

Added in version 3.3.

Py_ssize_t **PyUnicode_CopyCharacters**(*PyObject* *to, *Py_ssize_t* to_start, *PyObject* *from, *Py_ssize_t* from_start, *Py_ssize_t* how_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to `memcpy()` if possible. Returns `-1` and sets an exception on error, otherwise returns the number of copied characters.

The string must not have been "used" yet. See *PyUnicode_New()* for details.

Added in version 3.3.

int **PyUnicode_Resize**(*PyObject* **unicode, *Py_ssize_t* length);

Bir parçası Kararlı ABI. Resize a Unicode object **unicode* to the new *length* in code points.

Try to resize the string in place (which is usually faster than allocating a new string and copying characters), or create a new string.

**unicode* is modified to point to the new (resized) object and `0` is returned on success. Otherwise, `-1` is returned and an exception is set, and **unicode* is left untouched.

The function doesn't check string content, the result may not be a string in canonical representation.

Py_ssize_t **PyUnicode_Fill**(*PyObject* *unicode, *Py_ssize_t* start, *Py_ssize_t* length, *Py_UCS4* fill_char)

Fill a string with a character: write *fill_char* into `unicode[start:start+length]`.

Fail if *fill_char* is bigger than the string maximum character, or if the string has more than 1 reference.

The string must not have been "used" yet. See *PyUnicode_New()* for details.

Return the number of written character, or return `-1` and raise an exception on error.

Added in version 3.3.

int **PyUnicode_WriteChar**(*PyObject* *unicode, *Py_ssize_t* index, *Py_UCS4* character)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Write a *character* to the string *unicode* at the zero-based *index*. Return `0` on success, `-1` on error with an exception set.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object's reference count is one). See *PyUnicode_WRITE()* for a version that skips these checks, making them your responsibility.

The string must not have been "used" yet. See *PyUnicode_New()* for details.

Added in version 3.3.

Py_UCS4 **PyUnicode_ReadChar**(*PyObject* *unicode, *Py_ssize_t* index)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Read a character from a string. This function checks that *unicode* is a Unicode object and the index is not out of bounds, in contrast to *PyUnicode_READ_CHAR()*, which performs no error checking.

Return character on success, `-1` on error with an exception set.

Added in version 3.3.

PyObject ***PyUnicode_Substring**(*PyObject* *unicode, *Py_ssize_t* start, *Py_ssize_t* end)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a substring of *unicode*, from character index *start* (included) to character index *end* (excluded). Negative indices are not supported. On error, set an exception and return `NULL`.

Added in version 3.3.

Py_UCS4 ***PyUnicode_AsUCS4**(*PyObject* *unicode, *Py_UCS4* *buffer, *Py_ssize_t* buflen, int copy_null)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Copy the string *unicode* into a UCS4 buffer, including a null character, if *copy_null* is set. Returns `NULL` and sets an exception on error (in particular, a `SystemError` if *buflen* is smaller than the length of *unicode*). *buffer* is returned on success.

Added in version 3.3.

Py_UCS4 ***PyUnicode_AsUCS4Copy**(*PyObject* *unicode)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Copy the string *unicode* into a new UCS4 buffer that is allocated using *PyMem_Malloc()*. If this fails, `NULL` is returned with a `MemoryError` set. The returned buffer always has an extra null code point appended.

Added in version 3.3.

Locale Encoding

The current locale encoding can be used to decode text from the operating system.

PyObject ***PyUnicode_DecodeLocaleAndSize**(const char *str, *Py_ssize_t* length, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are `"strict"` and `"surrogateescape"` (**PEP 383**). The decoder uses `"strict"` error handler if *errors* is `NULL`. *str* must end with a null character but cannot contain embedded null characters.

Use *PyUnicode_DecodeFSDefaultAndSize()* to decode a string from the *filesystem encoding and error handler*.

This function ignores the Python UTF-8 Mode.

Ayrıca bakınız

The *Py_DecodeLocale()* function.

Added in version 3.3.

3.7 sürümünde değişti: The function now also uses the current locale encoding for the `surrogateescape` error handler, except on Android. Previously, *Py_DecodeLocale()* was used for the `surrogateescape`, and the current locale encoding was used for `strict`.

PyObject ***PyUnicode_DecodeLocale**(const char *str, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Similar to *PyUnicode_DecodeLocaleAndSize()*, but compute the string length using `strlen()`.

Added in version 3.3.

PyObject ***PyUnicode_EncodeLocale**(*PyObject* *unicode, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are `"strict"` and `"surrogateescape"` (**PEP 383**). The encoder uses `"strict"` error handler if *errors* is `NULL`. Return a `bytes` object. *unicode* cannot contain embedded null characters.

Use *PyUnicode_EncodeFSDefault()* to encode a string to the *filesystem encoding and error handler*.

This function ignores the Python UTF-8 Mode.

Ayrıca bakınız

The *Py_EncodeLocale()* function.

Added in version 3.3.

3.7 sürümünde değişti: The function now also uses the current locale encoding for the `surrogateescape` error handler, except on Android. Previously, *Py_EncodeLocale()* was used for the `surrogateescape`, and the current locale encoding was used for `strict`.

File System Encoding

Functions encoding to and decoding from the *filesystem encoding and error handler* (**PEP 383** and **PEP 529**).

To encode file names to `bytes` during argument parsing, the `"O&"` converter should be used, passing `PyUnicode_FSConverter()` as the conversion function:

int **PyUnicode_FSConverter**(*PyObject* *obj, void *result)

Bir parçası Kararlı ABI. *PyArg_Parse* converter*: encode `str` objects – obtained directly or through the `os.PathLike` interface – to `bytes` using *PyUnicode_EncodeFSDefault()*; `bytes` objects are output as-is. *result* must be an address of a C variable of type *PyObject** (or *PyBytesObject**). On success, set the variable to a new *strong reference* to a *bytes object* which must be released when it is no longer used and return a non-zero value (*Py_CLEANUP_SUPPORTED*). Embedded null bytes are not allowed in the result. On failure, return `0` with an exception set.

If *obj* is `NULL`, the function releases a strong reference stored in the variable referred by *result* and returns `1`.

Added in version 3.1.

3.6 sürümünde değişti: Accepts a *path-like object*.

To decode file names to `str` during argument parsing, the `"O&"` converter should be used, passing `PyUnicode_FSDecoder()` as the conversion function:

int **PyUnicode_FSDecoder**(*PyObject* *obj, void *result)

Bir parçası Kararlı ABI. *PyArg_Parse* converter*: decode `bytes` objects – obtained either directly or indirectly through the `os.PathLike` interface – to `str` using *PyUnicode_DecodeFSDefaultAndSize()*; `str` objects are output as-is. *result* must be an address of a C variable of type *PyObject** (or *PyUnicodeObject**). On success, set the variable to a new *strong reference* to a *Unicode object* which must be released when it is no longer used and return a non-zero value (*Py_CLEANUP_SUPPORTED*). Embedded null characters are not allowed in the result. On failure, return `0` with an exception set.

If *obj* is `NULL`, release the strong reference to the object referred to by *result* and return `1`.

Added in version 3.2.

3.6 sürümünde değişti: Accepts a *path-like object*.

PyObject ***PyUnicode_DecodeFSDefaultAndSize**(const char *str, *Py_ssize_t* size)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Decode a string from the *filesystem encoding and error handler*.

If you need to decode a string from the current locale encoding, use *PyUnicode_DecodeLocaleAndSize()*.

Ayrıca bakınız

The *Py_DecodeLocale()* function.

3.6 sürümünde değişti: The *filesystem error handler* is now used.

PyObject ***PyUnicode_DecodeFSDefault**(const char *str)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Decode a null-terminated string from the *filesystem encoding and error handler*.

If the string length is known, use *PyUnicode_DecodeFSDefaultAndSize()*.

3.6 sürümünde değişti: The *filesystem error handler* is now used.

PyObject ***PyUnicode_EncodeFSDefault**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object to the *filesystem encoding and error handler*, and return `bytes`. Note that the resulting `bytes` object can contain null bytes.

If you need to encode a string to the current locale encoding, use `PyUnicode_EncodeLocale()`.

Ayrıca bakınız

The `Py_EncodeLocale()` function.

Added in version 3.2.

3.6 sürümünde değişti: The *filesystem error handler* is now used.

wchar_t Support

`wchar_t` support for platforms which support it:

PyObject ***PyUnicode_FromWideChar**(const wchar_t *wstr, *Py_ssize_t* size)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object from the `wchar_t` buffer *wstr* of the given *size*. Passing `-1` as the *size* indicates that the function must itself compute the length, using `wcslen()`. Return `NULL` on failure.

Py_ssize_t ***PyUnicode_AsWideChar**(*PyObject* *unicode, wchar_t *wstr, *Py_ssize_t* size)

Bir parçası Kararlı ABI. Copy the Unicode object contents into the `wchar_t` buffer *wstr*. At most *size* `wchar_t` characters are copied (excluding a possibly trailing null termination character). Return the number of `wchar_t` characters copied or `-1` in case of an error.

When *wstr* is `NULL`, instead return the *size* that would be required to store all of *unicode* including a terminating null.

Note that the resulting `wchar_t*` string may or may not be null-terminated. It is the responsibility of the caller to make sure that the `wchar_t*` string is null-terminated in case this is required by the application. Also, note that the `wchar_t*` string might contain null characters, which would cause the string to be truncated when used with most C functions.

wchar_t ***PyUnicode_AsWideCharString**(*PyObject* *unicode, *Py_ssize_t* *size)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Convert the Unicode object to a wide character string. The output string always ends with a null character. If *size* is not `NULL`, write the number of wide characters (excluding the trailing null termination character) into **size*. Note that the resulting `wchar_t` string might contain null characters, which would cause the string to be truncated when used with most C functions. If *size* is `NULL` and the `wchar_t*` string contains null characters a `ValueError` is raised.

Returns a buffer allocated by `PyMem_New` (use `PyMem_Free()` to free it) on success. On error, returns `NULL` and **size* is undefined. Raises a `MemoryError` if memory allocation is failed.

Added in version 3.2.

3.7 sürümünde değişti: Raises a `ValueError` if *size* is `NULL` and the `wchar_t*` string contains null characters.

Built-in Codecs

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in `str()` string object constructor.

Setting encoding to `NULL` causes the default encoding to be used which is UTF-8. The file system calls should use `PyUnicode_FSConverter()` for encoding file names. This uses the *filesystem encoding and error handler* internally.

Error handling is set by errors which may also be set to NULL meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is "strict" (ValueError is raised).

The codecs all use a similar interface. Only deviations from the following generic ones are documented for simplicity.

Generic Codecs

The following macro is provided:

Py_UNICODE_REPLACEMENT_CHARACTER

The Unicode code point U+FFFD (replacement character).

This Unicode character is used as the replacement character during decoding if the *errors* argument is set to "replace".

These are the generic codec APIs:

PyObject ***PyUnicode_Decode**(const char *str, *Py_ssize_t* size, const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the encoded string *str*. *encoding* and *errors* have the same meaning as the parameters of the same name in the str() built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

PyObject ***PyUnicode_AsEncodedString**(*PyObject* *unicode, const char *encoding, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object and return the result as Python bytes object. *encoding* and *errors* have the same meaning as the parameters of the same name in the Unicode encode() method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

UTF-8 Codecs

These are the UTF-8 codec APIs:

PyObject ***PyUnicode_DecodeUTF8**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *str*. Return NULL if an exception was raised by the codec.

PyObject ***PyUnicode_DecodeUTF8Stateful**(const char *str, *Py_ssize_t* size, const char *errors, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. If *consumed* is NULL, behave like *PyUnicode_DecodeUTF8()*. If *consumed* is not NULL, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

PyObject ***PyUnicode_AsUTF8String**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

The function fails if the string contains surrogate code points (U+D800 - U+DFFF).

const char ***PyUnicode_AsUTF8AndSize**(*PyObject* *unicode, *Py_ssize_t* *size)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in *size*. The *size* argument can be NULL; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in *size*), regardless of whether there are any other null code points.

On error, set an exception, set *size* to -1 (if it's not NULL) and return NULL.

The function fails if the string contains surrogate code points (U+D800 - U+DFFF).

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer. The buffer is deallocated and pointers to it become invalid when the Unicode object is garbage collected.

Added in version 3.3.

3.7 sürümünde değişti: The return type is now `const char *` rather of `char *`.

3.10 sürümünde değişti: This function is a part of the *limited API*.

const char ***PyUnicode_AsUTF8**(*PyObject* *unicode)

As `PyUnicode_AsUTF8AndSize()`, but does not store the size.

> **Uyarı**
>
> This function does not have any special behavior for null characters embedded within *unicode*. As a result, strings containing null characters will remain in the returned string, which some C functions might interpret as the end of the string, leading to truncation. If truncation is an issue, it is recommended to use `PyUnicode_AsUTF8AndSize()` instead.

Added in version 3.3.

3.7 sürümünde değişti: The return type is now `const char *` rather of `char *`.

UTF-32 Codecs

These are the UTF-32 codec APIs:

PyObject ***PyUnicode_DecodeUTF32**(const char *str, *Py_ssize_t* size, const char *errors, int *byteorder)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-`NULL`) defines the error handling. It defaults to "strict".

If *byteorder* is non-`NULL`, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0:  native order
*byteorder == 1:  big endian
```

If `*byteorder` is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If `*byteorder` is `-1` or `1`, any byte order mark is copied to the output.

After completion, **byteorder* is set to the current byte order at the end of input data.

If *byteorder* is `NULL`, the codec starts in native order mode.

Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_DecodeUTF32Stateful**(const char *str, *Py_ssize_t* size, const char *errors, int *byteorder, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. If *consumed* is `NULL`, behave like `PyUnicode_DecodeUTF32()`. If *consumed* is not `NULL`, `PyUnicode_DecodeUTF32Stateful()` will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

PyObject ***PyUnicode_AsUTF32String**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

UTF-16 Codecs

These are the UTF-16 codec APIs:

PyObject ***PyUnicode_DecodeUTF16**(const char *str, *Py_ssize_t* size, const char *errors, int *byteorder)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Decode *size* bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. *errors* (if non-`NULL`) defines the error handling. It defaults to "strict".

If *byteorder* is non-`NULL`, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian
*byteorder == 0:  native order
*byteorder == 1:  big endian
```

If `*byteorder` is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If `*byteorder` is `-1` or `1`, any byte order mark is copied to the output (where it will result in either a `\ufeff` or a `\ufffe` character).

After completion, `*byteorder` is set to the current byte order at the end of input data.

If *byteorder* is `NULL`, the codec starts in native order mode.

Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_DecodeUTF16Stateful**(const char *str, *Py_ssize_t* size, const char *errors, int *byteorder, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. If *consumed* is `NULL`, behave like *PyUnicode_DecodeUTF16()*. If *consumed* is not `NULL`, *PyUnicode_DecodeUTF16Stateful()* will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

PyObject ***PyUnicode_AsUTF16String**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

UTF-7 Codecs

These are the UTF-7 codec APIs:

PyObject ***PyUnicode_DecodeUTF7**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_DecodeUTF7Stateful**(const char *str, *Py_ssize_t* size, const char *errors, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. If *consumed* is `NULL`, behave like *PyUnicode_DecodeUTF7()*. If *consumed* is not `NULL`, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

Unicode-Escape Codecs

These are the "Unicode Escape" codec APIs:

PyObject ***PyUnicode_DecodeUnicodeEscape**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_AsUnicodeEscapeString**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

Raw-Unicode-Escape Codecs

These are the "Raw Unicode Escape" codec APIs:

PyObject ***PyUnicode_DecodeRawUnicodeEscape**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_AsRawUnicodeEscapeString**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

Latin-1 Codecs

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

PyObject ***PyUnicode_DecodeLatin1**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_AsLatin1String**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

ASCII Codecs

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

PyObject ***PyUnicode_DecodeASCII**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the ASCII encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_AsASCIIString**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

Character Map Codecs

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the `encodings` package). The codec uses mappings to encode and decode characters. The mapping objects provided must support the `__getitem__()` mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

PyObject ***PyUnicode_DecodeCharmap**(const char *str, *Py_ssize_t* length, *PyObject* *mapping, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Unicode object by decoding *size* bytes of the encoded string *str* using the given *mapping* object. Return `NULL` if an exception was raised by the codec.

If *mapping* is `NULL`, Latin-1 decoding will be applied. Else *mapping* must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or `None`.

Unmapped data bytes – ones which cause a `LookupError`, as well as ones which get mapped to `None`, `0xFFFE` or `'\ufffe'`, are treated as undefined mappings and cause an error.

PyObject ***PyUnicode_AsCharmapString**(*PyObject* *unicode, *PyObject* *mapping)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Encode a Unicode object using the given *mapping* object and return the result as a bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or `None`. Unmapped character ordinals (ones which cause a `LookupError`) as well as mapped to `None` are treated as "undefined mapping" and cause an error.

The following codec API is special in that maps Unicode to Unicode.

PyObject ***PyUnicode_Translate**(*PyObject* *unicode, *PyObject* *table, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Translate a string by applying a character mapping table to it and return the resulting Unicode object. Return `NULL` if an exception was raised by the codec.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or `None` (causing deletion of the character).

Mapping tables need only provide the `__getitem__()` interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a `LookupError`) are left untouched and are copied as-is.

errors has the usual meaning for codecs. It may be `NULL` which indicates to use the default error handling.

MBCS codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

PyObject ***PyUnicode_DecodeMBCS**(const char *str, *Py_ssize_t* size, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Create a Unicode object by decoding *size* bytes of the MBCS encoded string *str*. Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_DecodeMBCSStateful**(const char *str, *Py_ssize_t* size, const char *errors, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* If *consumed* is `NULL`, behave like *`PyUnicode_DecodeMBCS()`*. If *consumed* is not `NULL`, *`PyUnicode_DecodeMBCSStateful()`* will not decode trailing lead byte and the number of bytes that have been decoded will be stored in *consumed*.

PyObject ***PyUnicode_DecodeCodePageStateful**(int code_page, const char *str, *Py_ssize_t* size, const char *errors, *Py_ssize_t* *consumed)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Similar to *`PyUnicode_DecodeMBCSStateful()`*, except uses the code page specified by *code_page*.

PyObject ***PyUnicode_AsMBCSString**(*PyObject* *unicode)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is "strict". Return `NULL` if an exception was raised by the codec.

PyObject ***PyUnicode_EncodeCodePage**(int code_page, *PyObject* *unicode, const char *errors)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *on Windows 3.7 sürümünden beri.* Encode the Unicode object using the specified code page and return a Python bytes object. Return `NULL` if an exception was raised by the codec. Use `CP_ACP` code page to get the MBCS encoder.

Added in version 3.3.

Methods and Slot Functions

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return `NULL` or `-1` if an exception occurs.

PyObject ***PyUnicode_Concat**(*PyObject* *left, *PyObject* *right)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Concat two strings giving a new Unicode string.

PyObject ***PyUnicode_Split**(*PyObject* *unicode, *PyObject* *sep, *Py_ssize_t* maxsplit)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Split a string giving a list of Unicode strings. If *sep* is `NULL`, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most *maxsplit* splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

On error, return `NULL` with an exception set.

Equivalent to `str.split()`.

PyObject ***PyUnicode_RSplit**(*PyObject* *unicode, *PyObject* *sep, *Py_ssize_t* maxsplit)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Similar to *PyUnicode_Split()*, but splitting will be done beginning at the end of the string.

On error, return `NULL` with an exception set.

Equivalent to `str.rsplit()`.

PyObject ***PyUnicode_Splitlines**(*PyObject* *unicode, int keepends)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If *keepends* is `0`, the Line break characters are not included in the resulting strings.

PyObject ***PyUnicode_Partition**(*PyObject* *unicode, *PyObject* *sep)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Split a Unicode string at the first occurrence of *sep*, and return a 3-tuple containing the part before the separator, the separator itself, and the part after the separator. If the separator is not found, return a 3-tuple containing the string itself, followed by two empty strings.

sep must not be empty.

On error, return `NULL` with an exception set.

Equivalent to `str.partition()`.

PyObject ***PyUnicode_RPartition**(*PyObject* *unicode, *PyObject* *sep)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Similar to *PyUnicode_Partition()*, but split a Unicode string at the last occurrence of *sep*. If the separator is not found, return a 3-tuple containing two empty strings, followed by the string itself.

sep must not be empty.

On error, return `NULL` with an exception set.

Equivalent to `str.rpartition()`.

PyObject ***PyUnicode_Join**(*PyObject* *separator, *PyObject* *seq)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Join a sequence of strings using the given *separator* and return the resulting Unicode string.

Py_ssize_t **PyUnicode_Tailmatch**(*PyObject* *unicode, *PyObject* *substr, *Py_ssize_t* start, *Py_ssize_t* end, int direction)

Bir parçası Kararlı ABI. Return `1` if *substr* matches `unicode[start:end]` at the given tail end (*direction* == `-1` means to do a prefix match, *direction* == `1` a suffix match), `0` otherwise. Return `-1` if an error occurred.

Py_ssize_t **PyUnicode_Find**(*PyObject* *unicode, *PyObject* *substr, *Py_ssize_t* start, *Py_ssize_t* end, int direction)

Bir parçası Kararlı ABI. Return the first position of *substr* in `unicode[start:end]` using the given *direction* (*direction* == `1` means to do a forward search, *direction* == `-1` a backward search). The return value is the index of the first match; a value of `-1` indicates that no match was found, and `-2` indicates that an error occurred and an exception has been set.

Py_ssize_t **PyUnicode_FindChar**(*PyObject* *unicode, *Py_UCS4* ch, *Py_ssize_t* start, *Py_ssize_t* end, int direction)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return the first position of the character *ch* in `unicode[start:end]` using the given *direction* (*direction* == `1` means to do a forward search, *direction* == `-1` a backward search). The return value is the index of the first match; a value of `-1` indicates that no match was found, and `-2` indicates that an error occurred and an exception has been set.

Added in version 3.3.

3.7 sürümünde değişti: *start* and *end* are now adjusted to behave like `unicode[start:end]`.

Py_ssize_t **PyUnicode_Count**(*PyObject* *unicode, *PyObject* *substr, *Py_ssize_t* start, *Py_ssize_t* end)

Bir parçası Kararlı ABI. Return the number of non-overlapping occurrences of *substr* in `unicode[start:end]`. Return `-1` if an error occurred.

PyObject ***PyUnicode_Replace**(*PyObject* *unicode, *PyObject* *substr, *PyObject* *replstr, *Py_ssize_t* maxcount)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Replace at most *maxcount* occurrences of *substr* in *unicode* with *replstr* and return the resulting Unicode object. *maxcount* == `-1` means replace all occurrences.

int **PyUnicode_Compare**(*PyObject* *left, *PyObject* *right)

Bir parçası Kararlı ABI. Compare two strings and return `-1`, `0`, `1` for less than, equal, and greater than, respectively.

This function returns `-1` upon failure, so one should call *PyErr_Occurred()* to check for errors.

Ayrıca bakınız

The *PyUnicode_Equal()* function.

int **PyUnicode_Equal**(*PyObject* *a, *PyObject* *b)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Test if two strings are equal:

- Return `1` if *a* is equal to *b*.
- Return `0` if *a* is not equal to *b*.
- Set a `TypeError` exception and return `-1` if *a* or *b* is not a `str` object.

The function always succeeds if *a* and *b* are `str` objects.

The function works for `str` subclasses, but does not honor custom `__eq__()` method.

Ayrıca bakınız

The *PyUnicode_Compare()* function.

Added in version 3.14.

int **PyUnicode_EqualToUTF8AndSize**(*PyObject* *unicode, const char *string, *Py_ssize_t* size)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Compare a Unicode object with a char buffer which is interpreted as being UTF-8 or ASCII encoded and return true (`1`) if they are equal, or false (`0`) otherwise. If the Unicode object contains surrogate code points (`U+D800` - `U+DFFF`) or the C string is not valid UTF-8, false (`0`) is returned.

This function does not raise exceptions.

Added in version 3.13.

int **PyUnicode_EqualToUTF8**(*PyObject* *unicode, const char *string)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to `PyUnicode_EqualToUTF8AndSize()`, but compute *string* length using `strlen()`. If the Unicode object contains null characters, false (`0`) is returned.

Added in version 3.13.

int **PyUnicode_CompareWithASCIIString**(*PyObject* *unicode, const char *string)

Bir parçası Kararlı ABI. Compare a Unicode object, *unicode*, with *string* and return `-1`, `0`, `1` for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

PyObject ***PyUnicode_RichCompare**(*PyObject* *left, *PyObject* *right, int op)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Rich compare two Unicode strings and return one of the following:

- `NULL` in case an exception was raised
- `Py_True` or `Py_False` for successful comparisons
- `Py_NotImplemented` in case the type combination is unknown

Possible values for *op* are `Py_GT`, `Py_GE`, `Py_EQ`, `Py_NE`, `Py_LT`, and `Py_LE`.

PyObject ***PyUnicode_Format**(*PyObject* *format, *PyObject* *args)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new string object from *format* and *args*; this is analogous to `format % args`.

int **PyUnicode_Contains**(*PyObject* *unicode, *PyObject* *substr)

Bir parçası Kararlı ABI. Check whether *substr* is contained in *unicode* and return true or false accordingly.

substr has to coerce to a one element Unicode string. `-1` is returned if there was an error.

void **PyUnicode_InternInPlace**(*PyObject* **p_unicode)

Bir parçası Kararlı ABI. Intern the argument `*p_unicode` in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as `*p_unicode`, it sets `*p_unicode` to it (releasing the reference to the old string object and creating a new *strong reference* to the interned string object), otherwise it leaves `*p_unicode` alone and interns it.

(Clarification: even though there is a lot of talk about references, think of this function as reference-neutral. You must own the object you pass in; after the call you no longer own the passed-in reference, but you newly own the result.)

This function never raises an exception. On error, it leaves its argument unchanged without interning it.

Instances of subclasses of `str` may not be interned, that is, `PyUnicode_CheckExact(*p_unicode)` must be true. If it is not, then – as with any other error – the argument is left unchanged.

Note that interned strings are not "immortal". You must keep a reference to the result to benefit from interning.

PyObject ***PyUnicode_InternFromString**(const char *str)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. A combination of `PyUnicode_FromString()` and `PyUnicode_InternInPlace()`, meant for statically allocated strings.

Return a new ("owned") reference to either a new Unicode string object that has been interned, or an earlier interned string object with the same value.

Python may keep a reference to the result, or make it *immortal*, preventing it from being garbage-collected promptly. For interning an unbounded number of different strings, such as ones coming from user input, prefer calling `PyUnicode_FromString()` and `PyUnicode_InternInPlace()` directly.

unsigned int **PyUnicode_CHECK_INTERNED**(*PyObject* *str)

Return a non-zero value if *str* is interned, zero if not. The *str* argument must be a string; this is not checked. This function always succeeds.

CPython uygulama ayrıntısı: A non-zero return value may carry additional information about *how* the string is interned. The meaning of such non-zero values, as well as each specific string's intern-related details, may change between CPython versions.

PyUnicodeWriter

The *PyUnicodeWriter* API can be used to create a Python `str` object.

Added in version 3.14.

type **PyUnicodeWriter**

A Unicode writer instance.

The instance must be destroyed by *PyUnicodeWriter_Finish()* on success, or *PyUnicodeWriter_Discard()* on error.

PyUnicodeWriter ***PyUnicodeWriter_Create**(*Py_ssize_t* length)

Create a Unicode writer instance.

length must be greater than or equal to `0`.

If *length* is greater than `0`, preallocate an internal buffer of *length* characters.

Set an exception and return `NULL` on error.

PyObject ***PyUnicodeWriter_Finish**(*PyUnicodeWriter* *writer)

Return the final Python `str` object and destroy the writer instance.

Set an exception and return `NULL` on error.

The writer instance is invalid after this call.

void **PyUnicodeWriter_Discard**(*PyUnicodeWriter* *writer)

Discard the internal Unicode buffer and destroy the writer instance.

If *writer* is `NULL`, no operation is performed.

The writer instance is invalid after this call.

int **PyUnicodeWriter_WriteChar**(*PyUnicodeWriter* *writer, *Py_UCS4* ch)

Write the single Unicode character *ch* into *writer*.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_WriteUTF8**(*PyUnicodeWriter* *writer, const char *str, *Py_ssize_t* size)

Decode the string *str* from UTF-8 in strict mode and write the output into *writer*.

size is the string length in bytes. If *size* is equal to `-1`, call `strlen(str)` to get the string length.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

See also *PyUnicodeWriter_DecodeUTF8Stateful()*.

int **PyUnicodeWriter_WriteASCII**(*PyUnicodeWriter* *writer, const char *str, *Py_ssize_t* size)

Write the ASCII string *str* into *writer*.

size is the string length in bytes. If *size* is equal to `-1`, call `strlen(str)` to get the string length.

str must only contain ASCII characters. The behavior is undefined if *str* contains non-ASCII characters.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

Added in version 3.14.

int **PyUnicodeWriter_WriteWideChar**(*PyUnicodeWriter* *writer, const wchar_t *str, *Py_ssize_t* size)

Write the wide string *str* into *writer*.

size is a number of wide characters. If *size* is equal to `-1`, call `wcslen(str)` to get the string length.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_WriteUCS4**(*PyUnicodeWriter* *writer, *Py_UCS4* *str, *Py_ssize_t* size)

Writer the UCS4 string *str* into *writer*.

size is a number of UCS4 characters.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_WriteStr**(*PyUnicodeWriter* *writer, *PyObject* *obj)

Call *PyObject_Str()* on *obj* and write the output into *writer*.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_WriteRepr**(*PyUnicodeWriter* *writer, *PyObject* *obj)

Call *PyObject_Repr()* on *obj* and write the output into *writer*.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_WriteSubstring**(*PyUnicodeWriter* *writer, *PyObject* *str, *Py_ssize_t* start, *Py_ssize_t* end)

Write the substring `str[start:end]` into *writer*.

str must be Python `str` object. *start* must be greater than or equal to 0, and less than or equal to *end*. *end* must be less than or equal to *str* length.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_Format**(*PyUnicodeWriter* *writer, const char *format, ...)

Similar to *PyUnicode_FromFormat()*, but write the output directly into *writer*.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

int **PyUnicodeWriter_DecodeUTF8Stateful**(*PyUnicodeWriter* *writer, const char *string, *Py_ssize_t* length, const char *errors, *Py_ssize_t* *consumed)

Decode the string *str* from UTF-8 with *errors* error handler and write the output into *writer*.

size is the string length in bytes. If *size* is equal to `-1`, call `strlen(str)` to get the string length.

errors is an error handler name, such as `"replace"`. If *errors* is `NULL`, use the strict error handler.

If *consumed* is not `NULL`, set **consumed* to the number of decoded bytes on success. If *consumed* is `NULL`, treat trailing incomplete UTF-8 byte sequences as an error.

On success, return `0`. On error, set an exception, leave the writer unchanged, and return `-1`.

See also *PyUnicodeWriter_WriteUTF8()*.

Deprecated API

The following API is deprecated.

type **Py_UNICODE**

This is a typedef of `wchar_t`, which is a 16-bit type or 32-bit type depending on the platform. Please use `wchar_t` directly instead.

3.3 sürümünde değişti: In previous versions, this was a 16-bit type or a 32-bit type depending on whether you selected a “narrow” or “wide” Unicode version of Python at build time.

Deprecated since version 3.13, will be removed in version 3.15.

int **PyUnicode_READY**(*PyObject* *unicode)

Do nothing and return `0`. This API is kept only for backward compatibility, but there are no plans to remove it.

Added in version 3.3.

3.10 sürümünden beri kullanım dışı: This API does nothing since Python 3.12. Previously, this needed to be called for each string created using the old API (`PyUnicode_FromUnicode()` or similar).

unsigned int **PyUnicode_IS_READY**(*PyObject* *unicode)

Do nothing and return `1`. This API is kept only for backward compatibility, but there are no plans to remove it.

Added in version 3.3.

3.14 sürümünden beri kullanım dışı: This API does nothing since Python 3.12. Previously, this could be called to check if *PyUnicode_READY()* is necessary.

9.3.4 Tuple Objects

type **PyTupleObject**

This subtype of *PyObject* represents a Python tuple object.

PyTypeObject **PyTuple_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python tuple type; it is the same object as `tuple` in the Python layer.

int **PyTuple_Check**(*PyObject* *p)

Return true if *p* is a tuple object or an instance of a subtype of the tuple type. This function always succeeds.

int **PyTuple_CheckExact**(*PyObject* *p)

Return true if *p* is a tuple object, but not an instance of a subtype of the tuple type. This function always succeeds.

PyObject ***PyTuple_New**(*Py_ssize_t* len)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new tuple object of size *len*, or `NULL` with an exception set on failure.

PyObject ***PyTuple_Pack**(*Py_ssize_t* n, ...)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new tuple object of size *n*, or `NULL` with an exception set on failure. The tuple values are initialized to the subsequent *n* C arguments pointing to Python objects. `PyTuple_Pack(2, a, b)` is equivalent to `Py_BuildValue("(OO)", a, b)`.

Py_ssize_t **PyTuple_Size**(*PyObject* *p)

Bir parçası Kararlı ABI. Take a pointer to a tuple object, and return the size of that tuple. On error, return `-1` and with an exception set.

Py_ssize_t **PyTuple_GET_SIZE**(*PyObject* *p)

Like *PyTuple_Size()*, but without error checking.

PyObject ***PyTuple_GetItem**(*PyObject* *p, *Py_ssize_t* pos)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the object at position *pos* in the tuple pointed to by *p*. If *pos* is negative or out of bounds, return `NULL` and set an `IndexError` exception.

The returned reference is borrowed from the tuple *p* (that is: it is only valid as long as you hold a reference to *p*). To get a *strong reference*, use *Py_NewRef(PyTuple_GetItem(...))* or *PySequence_GetItem()*.

PyObject ***PyTuple_GET_ITEM**(*PyObject* *p, *Py_ssize_t* pos)

Döndürdüğü değer: Ödünç alınmış referans. Like *PyTuple_GetItem()*, but does no checking of its arguments.

PyObject ***PyTuple_GetSlice**(*PyObject* *p, *Py_ssize_t* low, *Py_ssize_t* high)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the slice of the tuple pointed to by *p* between *low* and *high*, or `NULL` with an exception set on failure.

This is the equivalent of the Python expression `p[low:high]`. Indexing from the end of the tuple is not supported.

int **PyTuple_SetItem**(*PyObject* *p, *Py_ssize_t* pos, *PyObject* *o)

Bir parçası Kararlı ABI. Insert a reference to object *o* at position *pos* of the tuple pointed to by *p*. Return `0` on success. If *pos* is out of bounds, return `-1` and set an `IndexError` exception.

Not

This function "steals" a reference to *o* and discards a reference to an item already in the tuple at the affected position.

void **PyTuple_SET_ITEM**(*PyObject* *p, *Py_ssize_t* pos, *PyObject* *o)

Like *PyTuple_SetItem()*, but does no error checking, and should *only* be used to fill in brand new tuples.

Bounds checking is performed as an assertion if Python is built in debug mode or `with assertions`.

Not

This function "steals" a reference to *o*, and, unlike *PyTuple_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in the tuple at position *pos* will be leaked.

Uyarı

This macro should *only* be used on tuples that are newly created. Using this macro on a tuple that is already in use (or in other words, has a refcount > 1) could lead to undefined behavior.

int **_PyTuple_Resize**(*PyObject* **p, *Py_ssize_t* newsize)

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns `0` on success. Client code should never assume that the resulting value of `*p` will be the same as before calling this function. If the object referenced by `*p` is replaced, the original `*p` is destroyed. On failure, returns `-1` and sets `*p` to `NULL`, and raises `MemoryError` or `SystemError`.

9.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of `namedtuple()` objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

PyTypeObject ***PyStructSequence_NewType**(*PyStructSequence_Desc* *desc)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a new struct sequence type from the data in *desc*, described below. Instances of the resulting type can be created with *PyStructSequence_New()*.

Return `NULL` with an exception set on failure.

void **PyStructSequence_InitType**(*PyTypeObject* *type, *PyStructSequence_Desc* *desc)

Initializes a struct sequence type *type* from *desc* in place.

int **PyStructSequence_InitType2**(*PyTypeObject* *type, *PyStructSequence_Desc* *desc)

Like `PyStructSequence_InitType()`, but returns `0` on success and `-1` with an exception set on failure.

Added in version 3.4.

type **PyStructSequence_Desc**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Contains the meta information of a struct sequence type to create.

const char ***name**

Fully qualified name of the type; null-terminated UTF-8 encoded. The name must contain the module name.

const char ***doc**

Pointer to docstring for the type or `NULL` to omit.

PyStructSequence_Field ***fields**

Pointer to `NULL`-terminated array with field names of the new type.

int **n_in_sequence**

Number of fields visible to the Python side (if used as tuple).

type **PyStructSequence_Field**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as `PyObject*`. The index in the `fields` array of the `PyStructSequence_Desc` determines which field of the struct sequence is described.

const char ***name**

Name for the field or `NULL` to end the list of named fields, set to `PyStructSequence_UnnamedField` to leave unnamed.

const char ***doc**

Field docstring or `NULL` to omit.

const char *const **PyStructSequence_UnnamedField**

Bir parçası Kararlı ABI *3.11 sürümünden beri.* Special value for a field name to leave it unnamed.

3.9 sürümünde değişti: The type was changed from `char *`.

PyObject ***PyStructSequence_New**(*PyTypeObject* *type)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Creates an instance of *type*, which must have been created with `PyStructSequence_NewType()`.

Return `NULL` with an exception set on failure.

PyObject ***PyStructSequence_GetItem**(*PyObject* *p, *Py_ssize_t* pos)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the object at position *pos* in the struct sequence pointed to by *p*.

Bounds checking is performed as an assertion if Python is built in debug mode or `with assertions`.

PyObject ***PyStructSequence_GET_ITEM**(*PyObject* *p, *Py_ssize_t* pos)

Döndürdüğü değer: Ödünç alınmış referans. Alias to `PyStructSequence_GetItem()`.

3.13 sürümünde değişti: Now implemented as an alias to `PyStructSequence_GetItem()`.

void **PyStructSequence_SetItem**(*PyObject* *p, *Py_ssize_t* pos, *PyObject* *o)

Bir parçası Kararlı ABI. Sets the field at index *pos* of the struct sequence *p* to value *o*. Like `PyTuple_SET_ITEM()`, this should only be used to fill in brand new instances.

Bounds checking is performed as an assertion if Python is built in debug mode or `with assertions`.

> **Not**
>
> This function "steals" a reference to *o*.

void **PyStructSequence_SET_ITEM**(*PyObject* *p, *Py_ssize_t* *pos, *PyObject* *o)

Alias to `PyStructSequence_SetItem()`.

3.13 sürümünde değişti: Now implemented as an alias to `PyStructSequence_SetItem()`.

9.3.6 List Objects

type **PyListObject**

This subtype of `PyObject` represents a Python list object.

PyTypeObject **PyList_Type**

Bir parçası Kararlı ABI. This instance of `PyTypeObject` represents the Python list type. This is the same object as `list` in the Python layer.

int **PyList_Check**(*PyObject* *p)

Return true if *p* is a list object or an instance of a subtype of the list type. This function always succeeds.

int **PyList_CheckExact**(*PyObject* *p)

Return true if *p* is a list object, but not an instance of a subtype of the list type. This function always succeeds.

PyObject ***PyList_New**(*Py_ssize_t* len)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new list of length *len* on success, or `NULL` on failure.

> **Not**
>
> If *len* is greater than zero, the returned list object's items are set to `NULL`. Thus you cannot use abstract API functions such as `PySequence_SetItem()` or expose the object to Python code before setting all items to a real object with `PyList_SetItem()` or `PyList_SET_ITEM()`. The following APIs are safe APIs before the list is fully initialized: `PyList_SetItem()` and `PyList_SET_ITEM()`.

Py_ssize_t **PyList_Size**(*PyObject* *list)

Bir parçası Kararlı ABI. Return the length of the list object in *list*; this is equivalent to `len(list)` on a list object.

Py_ssize_t **PyList_GET_SIZE**(*PyObject* *list)

Similar to `PyList_Size()`, but without error checking.

PyObject ***PyList_GetItemRef**(*PyObject* *list, *Py_ssize_t* index)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return the object at position *index* in the list pointed to by *list*. The position must be non-negative; indexing from the end of the list is not supported. If *index* is out of bounds (`<0 or > =len(list)`), return `NULL` and set an `IndexError` exception.

Added in version 3.13.

PyObject ***PyList_GetItem**(*PyObject* *list, *Py_ssize_t* index)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Like `PyList_GetItemRef()`, but returns a *borrowed reference* instead of a *strong reference*.

PyObject ***PyList_GET_ITEM**(*PyObject* *list, *Py_ssize_t* i)

Döndürdüğü değer: Ödünç alınmış referans. Similar to `PyList_GetItem()`, but without error checking.

int **PyList_SetItem**(*PyObject* *list, *Py_ssize_t* index, *PyObject* *item)

Bir parçası Kararlı ABI. Set the item at index *index* in list to *item*. Return `0` on success. If *index* is out of bounds, return `-1` and set an `IndexError` exception.

> **Not**
>
> This function "steals" a reference to *item* and discards a reference to an item already in the list at the affected position.

void **PyList_SET_ITEM**(*PyObject* *list, *Py_ssize_t* i, *PyObject* *o)

Macro form of `PyList_SetItem()` without error checking. This is normally only used to fill in new lists where there is no previous content.

Bounds checking is performed as an assertion if Python is built in debug mode or `with assertions`.

> **Not**
>
> This macro "steals" a reference to *item*, and, unlike `PyList_SetItem()`, does *not* discard a reference to any item that is being replaced; any reference in *list* at position *i* will be leaked.

int **PyList_Insert**(*PyObject* *list, *Py_ssize_t* index, *PyObject* *item)

Bir parçası Kararlı ABI. Insert the item *item* into list *list* in front of index *index*. Return `0` if successful; return `-1` and set an exception if unsuccessful. Analogous to `list.insert(index, item)`.

int **PyList_Append**(*PyObject* *list, *PyObject* *item)

Bir parçası Kararlı ABI. Append the object *item* at the end of list *list*. Return `0` if successful; return `-1` and set an exception if unsuccessful. Analogous to `list.append(item)`.

PyObject ***PyList_GetSlice**(*PyObject* *list, *Py_ssize_t* low, *Py_ssize_t* high)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a list of the objects in *list* containing the objects *between low* and *high*. Return `NULL` and set an exception if unsuccessful. Analogous to `list[low:high]`. Indexing from the end of the list is not supported.

int **PyList_SetSlice**(*PyObject* *list, *Py_ssize_t* low, *Py_ssize_t* high, *PyObject* *itemlist)

Bir parçası Kararlı ABI. Set the slice of *list* between *low* and *high* to the contents of *itemlist*. Analogous to `list[low:high] = itemlist`. The *itemlist* may be `NULL`, indicating the assignment of an empty list (slice deletion). Return `0` on success, `-1` on failure. Indexing from the end of the list is not supported.

int **PyList_Extend**(*PyObject* *list, *PyObject* *iterable)

Extend *list* with the contents of *iterable*. This is the same as `PyList_SetSlice(list, PY_SSIZE_T_MAX, PY_SSIZE_T_MAX, iterable)` and analogous to `list.extend(iterable)` or `list += iterable`.

Raise an exception and return `-1` if *list* is not a `list` object. Return 0 on success.

Added in version 3.13.

int **PyList_Clear**(*PyObject* *list)

Remove all items from *list*. This is the same as `PyList_SetSlice(list, 0, PY_SSIZE_T_MAX, NULL)` and analogous to `list.clear()` or `del list[:]`.

Raise an exception and return `-1` if *list* is not a `list` object. Return 0 on success.

Added in version 3.13.

int **PyList_Sort**(*PyObject* *list)

Bir parçası Kararlı ABI. Sort the items of *list* in place. Return `0` on success, `-1` on failure. This is equivalent to `list.sort()`.

int **PyList_Reverse**(*PyObject* *list)

Bir parçası Kararlı ABI. Reverse the items of *list* in place. Return `0` on success, `-1` on failure. This is the equivalent of `list.reverse()`.

PyObject ***PyList_AsTuple**(*PyObject* *list)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new tuple object containing the contents of *list*; equivalent to `tuple(list)`.

9.4 Container Objects

9.4.1 Dictionary Objects

type **PyDictObject**

This subtype of *PyObject* represents a Python dictionary object.

PyTypeObject **PyDict_Type**

Bir parçası Kararlı ABI. This instance of *PyTypeObject* represents the Python dictionary type. This is the same object as `dict` in the Python layer.

int **PyDict_Check**(*PyObject* *p)

Return true if *p* is a dict object or an instance of a subtype of the dict type. This function always succeeds.

int **PyDict_CheckExact**(*PyObject* *p)

Return true if *p* is a dict object, but not an instance of a subtype of the dict type. This function always succeeds.

PyObject ***PyDict_New**()

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new empty dictionary, or `NULL` on failure.

PyObject ***PyDictProxy_New**(*PyObject* *mapping)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a `types.MappingProxyType` object for a mapping which enforces read-only behavior. This is normally used to create a view to prevent modification of the dictionary for non-dynamic class types.

void **PyDict_Clear**(*PyObject* *p)

Bir parçası Kararlı ABI. Empty an existing dictionary of all key-value pairs.

int **PyDict_Contains**(*PyObject* *p, *PyObject* *key)

Bir parçası Kararlı ABI. Determine if dictionary *p* contains *key*. If an item in *p* is matches *key*, return `1`, otherwise return `0`. On error, return `-1`. This is equivalent to the Python expression `key in p`.

int **PyDict_ContainsString**(*PyObject* *p, const char *key)

This is the same as *PyDict_Contains()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

Added in version 3.13.

PyObject ***PyDict_Copy**(*PyObject* *p)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new dictionary that contains the same key-value pairs as *p*.

int **PyDict_SetItem**(*PyObject* *p, *PyObject* *key, *PyObject* *val)

Bir parçası Kararlı ABI. Insert *val* into the dictionary *p* with a key of *key*. *key* must be *hashable*; if it isn't, `TypeError` will be raised. Return `0` on success or `-1` on failure. This function *does not* steal a reference to *val*.

int **PyDict_SetItemString**(*PyObject* *p, const char *key, *PyObject* *val)

Bir parçası Kararlı ABI. This is the same as *PyDict_SetItem()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

int **PyDict_DelItem**(*PyObject* *p, *PyObject* *key)

Bir parçası Kararlı ABI. Remove the entry in dictionary *p* with key *key*. *key* must be *hashable*; if it isn't, `TypeError` is raised. If *key* is not in the dictionary, `KeyError` is raised. Return `0` on success or `-1` on failure.

int **PyDict_DelItemString**(*PyObject* *p, const char *key)

Bir parçası Kararlı ABI. This is the same as `PyDict_DelItem()`, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

int **PyDict_GetItemRef**(*PyObject* *p, *PyObject* *key, *PyObject* **result)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return a new *strong reference* to the object from dictionary *p* which has a key *key*:

- If the key is present, set **result* to a new *strong reference* to the value and return `1`.
- If the key is missing, set **result* to `NULL` and return `0`.
- On error, raise an exception and return `-1`.

Added in version 3.13.

See also the `PyObject_GetItem()` function.

PyObject ***PyDict_GetItem**(*PyObject* *p, *PyObject* *key)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return a *borrowed reference* to the object from dictionary *p* which has a key *key*. Return `NULL` if the key *key* is missing *without* setting an exception.

> **Not**
>
> Exceptions that occur while this calls `__hash__()` and `__eq__()` methods are silently ignored. Prefer the `PyDict_GetItemWithError()` function instead.

3.10 sürümünde değişti: Calling this API without an *attached thread state* had been allowed for historical reason. It is no longer allowed.

PyObject ***PyDict_GetItemWithError**(*PyObject* *p, *PyObject* *key)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Variant of `PyDict_GetItem()` that does not suppress exceptions. Return `NULL` **with** an exception set if an exception occurred. Return `NULL` **without** an exception set if the key wasn't present.

PyObject ***PyDict_GetItemString**(*PyObject* *p, const char *key)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. This is the same as `PyDict_GetItem()`, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

> **Not**
>
> Exceptions that occur while this calls `__hash__()` and `__eq__()` methods or while creating the temporary `str` object are silently ignored. Prefer using the `PyDict_GetItemWithError()` function with your own `PyUnicode_FromString()` *key* instead.

int **PyDict_GetItemStringRef**(*PyObject* *p, const char *key, *PyObject* **result)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to `PyDict_GetItemRef()`, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a `PyObject*`.

Added in version 3.13.

PyObject ***PyDict_SetDefault**(*PyObject* *p, *PyObject* *key, *PyObject* *defaultobj)

Döndürdüğü değer: Ödünç alınmış referans. This is the same as the Python-level `dict.setdefault()`. If present, it returns the value corresponding to *key* from the dictionary *p*. If the key is not in the dict, it is inserted with value *defaultobj* and *defaultobj* is returned. This function evaluates the hash function of *key* only once, instead of evaluating it independently for the lookup and the insertion.

Added in version 3.4.

int **PyDict_SetDefaultRef**(*PyObject* *p, *PyObject* *key, *PyObject* *default_value, *PyObject* **result)

Inserts *default_value* into the dictionary *p* with a key of *key* if the key is not already present in the dictionary. If *result* is not `NULL`, then **result* is set to a *strong reference* to either *default_value*, if the key was not present, or the existing value, if *key* was already present in the dictionary. Returns `1` if the key was present and *default_value* was not inserted, or `0` if the key was not present and *default_value* was inserted. On failure, returns `-1`, sets an exception, and sets `*result` to `NULL`.

For clarity: if you have a strong reference to *default_value* before calling this function, then after it returns, you hold a strong reference to both *default_value* and **result* (if it's not `NULL`). These may refer to the same object: in that case you hold two separate references to it.

Added in version 3.13.

int **PyDict_Pop**(*PyObject* *p, *PyObject* *key, *PyObject* **result)

Remove *key* from dictionary *p* and optionally return the removed value. Do not raise `KeyError` if the key missing.

- If the key is present, set **result* to a new reference to the removed value if *result* is not `NULL`, and return `1`.
- If the key is missing, set **result* to `NULL` if *result* is not `NULL`, and return `0`.
- On error, raise an exception and return `-1`.

Similar to `dict.pop()`, but without the default value and not raising `KeyError` if the key missing.

Added in version 3.13.

int **PyDict_PopString**(*PyObject* *p, const char *key, *PyObject* **result)

Similar to *PyDict_Pop()*, but *key* is specified as a `const char*` UTF-8 encoded bytes string, rather than a *PyObject**.

Added in version 3.13.

PyObject ***PyDict_Items**(*PyObject* *p)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a *PyListObject* containing all the items from the dictionary.

PyObject ***PyDict_Keys**(*PyObject* *p)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a *PyListObject* containing all the keys from the dictionary.

PyObject ***PyDict_Values**(*PyObject* *p)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a *PyListObject* containing all the values from the dictionary *p*.

Py_ssize_t **PyDict_Size**(*PyObject* *p)

Bir parçası Kararlı ABI. Return the number of items in the dictionary. This is equivalent to `len(p)` on a dictionary.

int **PyDict_Next**(*PyObject* *p, *Py_ssize_t* *ppos, *PyObject* **pkey, *PyObject* **pvalue)

Bir parçası Kararlı ABI. Iterate over all key-value pairs in the dictionary *p*. The *Py_ssize_t* referred to by *ppos* must be initialized to `0` prior to the first call to this function to start the iteration; the function returns true for each pair in the dictionary, and false once all pairs have been reported. The parameters *pkey* and *pvalue* should either point to *PyObject** variables that will be filled in with each key and value, respectively, or may be `NULL`. Any references returned through them are borrowed. *ppos* should not be altered during iteration. Its value represents offsets within the internal dictionary structure, and since the structure is sparse, the offsets are not consecutive.

For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

The dictionary *p* should not be mutated during iteration. It is safe to modify the values of the keys as you iterate over the dictionary, but only so long as the set of keys does not change. For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}
```

The function is not thread-safe in the *free-threaded* build without external synchronization. You can use `Py_BEGIN_CRITICAL_SECTION` to lock the dictionary while iterating over it:

```
Py_BEGIN_CRITICAL_SECTION(self->dict);
while (PyDict_Next(self->dict, &pos, &key, &value)) {
    ...
}
Py_END_CRITICAL_SECTION();
```

Not

On the free-threaded build, this function can be used safely inside a critical section. However, the references returned for *pkey* and *pvalue* are *borrowed* and are only valid while the critical section is held. If you need to use these objects outside the critical section or when the critical section can be suspended, create a *strong reference* (for example, using `Py_NewRef()`).

int **PyDict_Merge**(*PyObject* *a, *PyObject* *b, int override)

Bir parçası Kararlı ABI. Iterate over mapping object *b* adding key-value pairs to dictionary *a*. *b* may be a dictionary, or any object supporting `PyMapping_Keys()` and `PyObject_GetItem()`. If *override* is true, existing pairs in *a* will be replaced if a matching key is found in *b*, otherwise pairs will only be added if there is not a matching key in *a*. Return `0` on success or `-1` if an exception was raised.

int **PyDict_Update**(*PyObject* *a, *PyObject* *b)

Bir parçası Kararlı ABI. This is the same as `PyDict_Merge(a, b, 1)` in C, and is similar to `a.update(b)` in Python except that `PyDict_Update()` doesn't fall back to the iterating over a sequence of key value pairs if the second argument has no "keys" attribute. Return `0` on success or `-1` if an exception was raised.

int **PyDict_MergeFromSeq2**(*PyObject* *a, *PyObject* *seq2, int override)

Bir parçası Kararlı ABI. Update or merge into dictionary *a*, from the key-value pairs in *seq2*. *seq2* must be an iterable object producing iterable objects of length 2, viewed as key-value pairs. In case of duplicate keys, the

last wins if *override* is true, else the first wins. Return `0` on success or `-1` if an exception was raised. Equivalent Python (except for the return value):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
            a[key] = value
```

int **PyDict_AddWatcher**(*PyDict_WatchCallback* callback)

Register *callback* as a dictionary watcher. Return a non-negative integer id which must be passed to future calls to `PyDict_Watch()`. In case of error (e.g. no more watcher IDs available), return `-1` and set an exception.

Added in version 3.12.

int **PyDict_ClearWatcher**(int watcher_id)

Clear watcher identified by *watcher_id* previously returned from `PyDict_AddWatcher()`. Return `0` on success, `-1` on error (e.g. if the given *watcher_id* was never registered.)

Added in version 3.12.

int **PyDict_Watch**(int watcher_id, *PyObject* *dict)

Mark dictionary *dict* as watched. The callback granted *watcher_id* by `PyDict_AddWatcher()` will be called when *dict* is modified or deallocated. Return `0` on success or `-1` on error.

Added in version 3.12.

int **PyDict_Unwatch**(int watcher_id, *PyObject* *dict)

Mark dictionary *dict* as no longer watched. The callback granted *watcher_id* by `PyDict_AddWatcher()` will no longer be called when *dict* is modified or deallocated. The dict must previously have been watched by this watcher. Return `0` on success or `-1` on error.

Added in version 3.12.

type **PyDict_WatchEvent**

Enumeration of possible dictionary watcher events: `PyDict_EVENT_ADDED`, `PyDict_EVENT_MODIFIED`, `PyDict_EVENT_DELETED`, `PyDict_EVENT_CLONED`, `PyDict_EVENT_CLEARED`, or `PyDict_EVENT_DEALLOCATED`.

Added in version 3.12.

typedef int (***PyDict_WatchCallback**)(*PyDict_WatchEvent* event, *PyObject* *dict, *PyObject* *key, *PyObject* *new_value)

Type of a dict watcher callback function.

If *event* is `PyDict_EVENT_CLEARED` or `PyDict_EVENT_DEALLOCATED`, both *key* and *new_value* will be `NULL`. If *event* is `PyDict_EVENT_ADDED` or `PyDict_EVENT_MODIFIED`, *new_value* will be the new value for *key*. If *event* is `PyDict_EVENT_DELETED`, *key* is being deleted from the dictionary and *new_value* will be `NULL`.

`PyDict_EVENT_CLONED` occurs when *dict* was previously empty and another dict is merged into it. To maintain efficiency of this operation, per-key `PyDict_EVENT_ADDED` events are not issued in this case; instead a single `PyDict_EVENT_CLONED` is issued, and *key* will be the source dictionary.

The callback may inspect but must not modify *dict*; doing so could have unpredictable effects, including infinite recursion. Do not trigger Python code execution in the callback, as it could modify the dict as a side effect.

If *event* is `PyDict_EVENT_DEALLOCATED`, taking a new reference in the callback to the about-to-be-destroyed dictionary will resurrect it and prevent it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

Callbacks occur before the notified modification to *dict* takes place, so the prior state of *dict* can be inspected.

If the callback sets an exception, it must return `-1`; this exception will be printed as an unraisable exception using `PyErr_WriteUnraisable()`. Otherwise it should return `0`.

There may already be a pending exception set on entry to the callback. In this case, the callback should return `0` with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Added in version 3.12.

9.4.2 Set Objects

This section details the public API for `set` and `frozenset` objects. Any functionality not listed below is best accessed using either the abstract object protocol (including *PyObject_CallMethod()*, *PyObject_RichCompareBool()*, *PyObject_Hash()*, *PyObject_Repr()*, *PyObject_IsTrue()*, *PyObject_Print()*, and *PyObject_GetIter()*) or the abstract number protocol (including *PyNumber_And()*, *PyNumber_Subtract()*, *PyNumber_Or()*, *PyNumber_Xor()*, *PyNumber_InPlaceAnd()*, *PyNumber_InPlaceSubtract()*, *PyNumber_InPlaceOr()*, and *PyNumber_InPlaceXor()*).

type **PySetObject**

This subtype of *PyObject* is used to hold the internal data for both `set` and `frozenset` objects. It is like a *PyDictObject* in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and all are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

PyTypeObject **PySet_Type**

Bir parçası Kararlı ABI. This is an instance of *PyTypeObject* representing the Python `set` type.

PyTypeObject **PyFrozenSet_Type**

Bir parçası Kararlı ABI. This is an instance of *PyTypeObject* representing the Python `frozenset` type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

int **PySet_Check**(*PyObject* *p)

Return true if *p* is a `set` object or an instance of a subtype. This function always succeeds.

int **PyFrozenSet_Check**(*PyObject* *p)

Return true if *p* is a `frozenset` object or an instance of a subtype. This function always succeeds.

int **PyAnySet_Check**(*PyObject* *p)

Return true if *p* is a `set` object, a `frozenset` object, or an instance of a subtype. This function always succeeds.

int **PySet_CheckExact**(*PyObject* *p)

Return true if *p* is a `set` object but not an instance of a subtype. This function always succeeds.

Added in version 3.10.

int **PyAnySet_CheckExact**(*PyObject* *p)

Return true if *p* is a `set` object or a `frozenset` object but not an instance of a subtype. This function always succeeds.

int **PyFrozenSet_CheckExact**(*PyObject* *p)

Return true if *p* is a `frozenset` object but not an instance of a subtype. This function always succeeds.

PyObject ***PySet_New**(*PyObject* *iterable)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `set` containing objects returned by the *iterable*. The *iterable* may be `NULL` to create a new empty set. Return the new set on success or `NULL` on failure. Raise `TypeError` if *iterable* is not actually iterable. The constructor is also useful for copying a set (`c =set(s)`).

PyObject ***PyFrozenSet_New**(*PyObject* *iterable)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new `frozenset` containing objects returned by the *iterable*. The *iterable* may be `NULL` to create a new empty frozenset. Return the new set on success or `NULL` on failure. Raise `TypeError` if *iterable* is not actually iterable.

The following functions and macros are available for instances of `set` or `frozenset` or instances of their subtypes.

Py_ssize_t **PySet_Size**(*PyObject* *anyset)

Bir parçası Kararlı ABI. Return the length of a `set` or `frozenset` object. Equivalent to `len(anyset)`. Raises a `SystemError` if *anyset* is not a `set`, `frozenset`, or an instance of a subtype.

Py_ssize_t **PySet_GET_SIZE**(*PyObject* *anyset)

Macro form of *`PySet_Size()`* without error checking.

int **PySet_Contains**(*PyObject* *anyset, *PyObject* *key)

Bir parçası Kararlı ABI. Return `1` if found, `0` if not found, and `-1` if an error is encountered. Unlike the Python `__contains__()` method, this function does not automatically convert unhashable sets into temporary frozensets. Raise a `TypeError` if the *key* is unhashable. Raise `SystemError` if *anyset* is not a `set`, `frozenset`, or an instance of a subtype.

int **PySet_Add**(*PyObject* *set, *PyObject* *key)

Bir parçası Kararlı ABI. Add *key* to a `set` instance. Also works with `frozenset` instances (like *`PyTuple_SetItem()`* it can be used to fill in the values of brand new frozensets before they are exposed to other code). Return `0` on success or `-1` on failure. Raise a `TypeError` if the *key* is unhashable. Raise a `MemoryError` if there is no room to grow. Raise a `SystemError` if *set* is not an instance of `set` or its subtype.

The following functions are available for instances of `set` or its subtypes but not for instances of `frozenset` or its subtypes.

int **PySet_Discard**(*PyObject* *set, *PyObject* *key)

Bir parçası Kararlı ABI. Return `1` if found and removed, `0` if not found (no action taken), and `-1` if an error is encountered. Does not raise `KeyError` for missing keys. Raise a `TypeError` if the *key* is unhashable. Unlike the Python `discard()` method, this function does not automatically convert unhashable sets into temporary frozensets. Raise `SystemError` if *set* is not an instance of `set` or its subtype.

PyObject ***PySet_Pop**(*PyObject* *set)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new reference to an arbitrary object in the *set*, and removes the object from the *set*. Return `NULL` on failure. Raise `KeyError` if the set is empty. Raise a `SystemError` if *set* is not an instance of `set` or its subtype.

int **PySet_Clear**(*PyObject* *set)

Bir parçası Kararlı ABI. Empty an existing set of all elements. Return `0` on success. Return `-1` and raise `SystemError` if *set* is not an instance of `set` or its subtype.

9.5 Function Objects

9.5.1 Function Objects

There are a few functions specific to Python functions.

type **PyFunctionObject**

The C structure used for functions.

PyTypeObject **PyFunction_Type**

This is an instance of *`PyTypeObject`* and represents the Python function type. It is exposed to Python programmers as `types.FunctionType`.

int **PyFunction_Check**(*PyObject* *o)

Return true if *o* is a function object (has type *`PyFunction_Type`*). The parameter must not be `NULL`. This function always succeeds.

PyObject ***PyFunction_New**(*PyObject* *code, *PyObject* *globals)

Döndürdüğü değer: Yeni referans. Return a new function object associated with the code object *code*. *globals* must be a dictionary with the global variables accessible to the function.

The function's docstring and name are retrieved from the code object. `__module__` is retrieved from *globals*. The argument defaults, annotations and closure are set to `NULL`. `__qualname__` is set to the same value as the code object's `co_qualname` field.

PyObject ***PyFunction_NewWithQualName**(*PyObject* *code, *PyObject* *globals, *PyObject* *qualname)

Döndürdüğü değer: Yeni referans. As `PyFunction_New()`, but also allows setting the function object's `__qualname__` attribute. *qualname* should be a unicode object or `NULL`; if `NULL`, the `__qualname__` attribute is set to the same value as the code object's `co_qualname` field.

Added in version 3.3.

PyObject ***PyFunction_GetCode**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the code object associated with the function object *op*.

PyObject ***PyFunction_GetGlobals**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the globals dictionary associated with the function object *op*.

PyObject ***PyFunction_GetModule**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return a *borrowed reference* to the `__module__` attribute of the function object *op*. It can be *NULL*.

This is normally a `string` containing the module name, but can be set to any other object by Python code.

PyObject ***PyFunction_GetDefaults**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the argument default values of the function object *op*. This can be a tuple of arguments or `NULL`.

int **PyFunction_SetDefaults**(*PyObject* *op, *PyObject* *defaults)

Set the argument default values for the function object *op*. *defaults* must be `Py_None` or a tuple.

Raises `SystemError` and returns `-1` on failure.

void **PyFunction_SetVectorcall**(*PyFunctionObject* *func, *vectorcallfunc* vectorcall)

Set the vectorcall field of a given function object *func*.

Warning: extensions using this API must preserve the behavior of the unaltered (default) vectorcall function!

Added in version 3.12.

PyObject ***PyFunction_GetKwDefaults**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the keyword-only argument default values of the function object *op*. This can be a dictionary of arguments or `NULL`.

PyObject ***PyFunction_GetClosure**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the closure associated with the function object *op*. This can be `NULL` or a tuple of cell objects.

int **PyFunction_SetClosure**(*PyObject* *op, *PyObject* *closure)

Set the closure associated with the function object *op*. *closure* must be `Py_None` or a tuple of cell objects.

Raises `SystemError` and returns `-1` on failure.

PyObject ***PyFunction_GetAnnotations**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. Return the annotations of the function object *op*. This can be a mutable dictionary or `NULL`.

int **PyFunction_SetAnnotations**(*PyObject* *op, *PyObject* *annotations)

Set the annotations for the function object *op*. *annotations* must be a dictionary or `Py_None`.

Raises `SystemError` and returns `-1` on failure.

PyObject ***PyFunction_GET_CODE**(*PyObject* *op)

PyObject ***PyFunction_GET_GLOBALS**(*PyObject* *op)

PyObject ***PyFunction_GET_MODULE**(*PyObject* *op)

PyObject ***PyFunction_GET_DEFAULTS**(*PyObject* *op)

PyObject ***PyFunction_GET_KW_DEFAULTS**(*PyObject* *op)

PyObject ***PyFunction_GET_CLOSURE**(*PyObject* *op)

PyObject ***PyFunction_GET_ANNOTATIONS**(*PyObject* *op)

Döndürdüğü değer: Ödünç alınmış referans. These functions are similar to their `PyFunction_Get*` counterparts, but do not do type checking. Passing anything other than an instance of *`PyFunction_Type`* is undefined behavior.

int **PyFunction_AddWatcher**(*PyFunction_WatchCallback* callback)

Register *callback* as a function watcher for the current interpreter. Return an ID which may be passed to *`PyFunction_ClearWatcher()`*. In case of error (e.g. no more watcher IDs available), return `-1` and set an exception.

Added in version 3.12.

int **PyFunction_ClearWatcher**(int watcher_id)

Clear watcher identified by *watcher_id* previously returned from *`PyFunction_AddWatcher()`* for the current interpreter. Return `0` on success, or `-1` and set an exception on error (e.g. if the given *watcher_id* was never registered.)

Added in version 3.12.

type **PyFunction_WatchEvent**

Enumeration of possible function watcher events:

- `PyFunction_EVENT_CREATE`
- `PyFunction_EVENT_DESTROY`
- `PyFunction_EVENT_MODIFY_CODE`
- `PyFunction_EVENT_MODIFY_DEFAULTS`
- `PyFunction_EVENT_MODIFY_KWDEFAULTS`

Added in version 3.12.

typedef int (***PyFunction_WatchCallback**)(*PyFunction_WatchEvent* event, *PyFunctionObject* *func, *PyObject* *new_value)

Type of a function watcher callback function.

If *event* is `PyFunction_EVENT_CREATE` or `PyFunction_EVENT_DESTROY` then *new_value* will be `NULL`. Otherwise, *new_value* will hold a *borrowed reference* to the new value that is about to be stored in *func* for the attribute that is being modified.

The callback may inspect but must not modify *func*; doing so could have unpredictable effects, including infinite recursion.

If *event* is `PyFunction_EVENT_CREATE`, then the callback is invoked after *func* has been fully initialized. Otherwise, the callback is invoked before the modification to *func* takes place, so the prior state of *func* can be inspected. The runtime is permitted to optimize away the creation of function objects when possible. In such cases no event will be emitted. Although this creates the possibility of an observable difference of runtime behavior depending on optimization decisions, it does not change the semantics of the Python code being executed.

If *event* is `PyFunction_EVENT_DESTROY`, Taking a reference in the callback to the about-to-be-destroyed function will resurrect it, preventing it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

If the callback sets an exception, it must return `-1`; this exception will be printed as an unraisable exception using *`PyErr_WriteUnraisable()`*. Otherwise it should return `0`.

There may already be a pending exception set on entry to the callback. In this case, the callback should return `0` with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Added in version 3.12.

9.5.2 Instance Method Objects

An instance method is a wrapper for a *PyCFunction* and the new way to bind a *PyCFunction* to a class object. It replaces the former call `PyMethod_New(func, NULL, class)`.

PyTypeObject **PyInstanceMethod_Type**

This instance of *PyTypeObject* represents the Python instance method type. It is not exposed to Python programs.

int **PyInstanceMethod_Check**(*PyObject* *o)

Return true if *o* is an instance method object (has type *PyInstanceMethod_Type*). The parameter must not be `NULL`. This function always succeeds.

PyObject ***PyInstanceMethod_New**(*PyObject* *func)

Döndürdüğü değer: Yeni referans. Return a new instance method object, with *func* being any callable object. *func* is the function that will be called when the instance method is called.

PyObject ***PyInstanceMethod_Function**(*PyObject* *im)

Döndürdüğü değer: Ödünç alınmış referans. Return the function object associated with the instance method *im*.

PyObject ***PyInstanceMethod_GET_FUNCTION**(*PyObject* *im)

Döndürdüğü değer: Ödünç alınmış referans. Macro version of *PyInstanceMethod_Function()* which avoids error checking.

9.5.3 Method Objects

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

PyTypeObject **PyMethod_Type**

This instance of *PyTypeObject* represents the Python method type. This is exposed to Python programs as `types.MethodType`.

int **PyMethod_Check**(*PyObject* *o)

Return true if *o* is a method object (has type *PyMethod_Type*). The parameter must not be `NULL`. This function always succeeds.

PyObject ***PyMethod_New**(*PyObject* *func, *PyObject* *self)

Döndürdüğü değer: Yeni referans. Return a new method object, with *func* being any callable object and *self* the instance the method should be bound. *func* is the function that will be called when the method is called. *self* must not be `NULL`.

PyObject ***PyMethod_Function**(*PyObject* *meth)

Döndürdüğü değer: Ödünç alınmış referans. Return the function object associated with the method *meth*.

PyObject ***PyMethod_GET_FUNCTION**(*PyObject* *meth)

Döndürdüğü değer: Ödünç alınmış referans. Macro version of *PyMethod_Function()* which avoids error checking.

PyObject ***PyMethod_Self**(*PyObject* *meth)

Döndürdüğü değer: Ödünç alınmış referans. Return the instance associated with the method *meth*.

PyObject ***PyMethod_GET_SELF**(*PyObject* *meth)

Döndürdüğü değer: Ödünç alınmış referans. Macro version of *PyMethod_Self()* which avoids error checking.

9.5.4 Cell Objects

"Cell" objects are used to implement variables referenced by multiple scopes. For each such variable, a cell object is created to store the value; the local variables of each stack frame that references the value contains a reference to the cells from outer scopes which also use that variable. When the value is accessed, the value contained in the cell is used instead of the cell object itself. This de-referencing of the cell object requires support from the generated byte-code; these are not automatically de-referenced when accessed. Cell objects are not likely to be useful elsewhere.

type **PyCellObject**

The C structure used for cell objects.

PyTypeObject **PyCell_Type**

The type object corresponding to cell objects.

int **PyCell_Check**(*PyObject* *ob)

Return true if *ob* is a cell object; *ob* must not be `NULL`. This function always succeeds.

PyObject ***PyCell_New**(*PyObject* *ob)

Döndürdüğü değer: Yeni referans. Create and return a new cell object containing the value *ob*. The parameter may be `NULL`.

PyObject ***PyCell_Get**(*PyObject* *cell)

Döndürdüğü değer: Yeni referans. Return the contents of the cell *cell*, which can be `NULL`. If *cell* is not a cell object, returns `NULL` with an exception set.

PyObject ***PyCell_GET**(*PyObject* *cell)

Döndürdüğü değer: Ödünç alınmış referans. Return the contents of the cell *cell*, but without checking that *cell* is non-`NULL` and a cell object.

int **PyCell_Set**(*PyObject* *cell, *PyObject* *value)

Set the contents of the cell object *cell* to *value*. This releases the reference to any current content of the cell. *value* may be `NULL`. *cell* must be non-`NULL`.

On success, return `0`. If *cell* is not a cell object, set an exception and return `-1`.

void **PyCell_SET**(*PyObject* *cell, *PyObject* *value)

Sets the value of the cell object *cell* to *value*. No reference counts are adjusted, and no checks are made for safety; *cell* must be non-`NULL` and must be a cell object.

9.5.5 Code Objects

Code objects are a low-level detail of the CPython implementation. Each one represents a chunk of executable code that hasn't yet been bound into a function.

type **PyCodeObject**

The C structure of the objects used to describe code objects. The fields of this type are subject to change at any time.

PyTypeObject **PyCode_Type**

This is an instance of `PyTypeObject` representing the Python code object.

int **PyCode_Check**(*PyObject* *co)

Return true if *co* is a code object. This function always succeeds.

Py_ssize_t **PyCode_GetNumFree**(*PyCodeObject* *co)

Return the number of *free (closure) variables* in a code object.

int **PyUnstable_Code_GetFirstFree**(*PyCodeObject* *co)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return the position of the first *free (closure) variable* in a code object.

3.13 sürümünde değişti: Renamed from `PyCode_GetFirstFree` as part of *Unstable C API*. The old name is deprecated, but will remain available until the signature changes again.

PyCodeObject ***PyUnstable_Code_New**(int argcount, int kwonlyargcount, int nlocals, int stacksize, int flags, *PyObject* *code, *PyObject* *consts, *PyObject* *names, *PyObject* *varnames, *PyObject* *freevars, *PyObject* *cellvars, *PyObject* *filename, *PyObject* *name, *PyObject* *qualname, int firstlineno, *PyObject* *linetable, *PyObject* *exceptiontable)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return a new code object. If you need a dummy code object to create a frame, use *PyCode_NewEmpty()* instead.

Since the definition of the bytecode changes often, calling *PyUnstable_Code_New()* directly can bind you to a precise Python version.

The many arguments of this function are inter-dependent in complex ways, meaning that subtle changes to values are likely to result in incorrect execution or VM crashes. Use this function only with extreme care.

3.11 sürümünde değişti: Added `qualname` and `exceptiontable` parameters.

3.12 sürümünde değişti: Renamed from `PyCode_New` as part of *Unstable C API*. The old name is deprecated, but will remain available until the signature changes again.

PyCodeObject ***PyUnstable_Code_NewWithPosOnlyArgs**(int argcount, int posonlyargcount, int kwonlyargcount, int nlocals, int stacksize, int flags, *PyObject* *code, *PyObject* *consts, *PyObject* *names, *PyObject* *varnames, *PyObject* *freevars, *PyObject* *cellvars, *PyObject* *filename, *PyObject* *name, *PyObject* *qualname, int firstlineno, *PyObject* *linetable, *PyObject* *exceptiontable)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Similar to *PyUnstable_Code_New()*, but with an extra "posonlyargcount" for positional-only arguments. The same caveats that apply to `PyUnstable_Code_New` also apply to this function.

Added in version 3.8: as `PyCode_NewWithPosOnlyArgs`

3.11 sürümünde değişti: Added `qualname` and `exceptiontable` parameters.

3.12 sürümünde değişti: Renamed to `PyUnstable_Code_NewWithPosOnlyArgs`. The old name is deprecated, but will remain available until the signature changes again.

PyCodeObject ***PyCode_NewEmpty**(const char *filename, const char *funcname, int firstlineno)

Döndürdüğü değer: Yeni referans. Return a new empty code object with the specified filename, function name, and first line number. The resulting code object will raise an `Exception` if executed.

int **PyCode_Addr2Line**(*PyCodeObject* *co, int byte_offset)

Return the line number of the instruction that occurs on or before `byte_offset` and ends after it. If you just need the line number of a frame, use *PyFrame_GetLineNumber()* instead.

For efficiently iterating over the line numbers in a code object, use **the API described in PEP 626**.

int **PyCode_Addr2Location**(*PyObject* *co, int byte_offset, int *start_line, int *start_column, int *end_line, int *end_column)

Sets the passed `int` pointers to the source code line and column numbers for the instruction at `byte_offset`. Sets the value to `0` when information is not available for any particular element.

Returns `1` if the function succeeds and 0 otherwise.

Added in version 3.11.

PyObject ***PyCode_GetCode**(*PyCodeObject* *co)

Equivalent to the Python code `getattr(co, 'co_code')`. Returns a strong reference to a *PyBytesObject* representing the bytecode in a code object. On error, `NULL` is returned and an exception is raised.

This `PyBytesObject` may be created on-demand by the interpreter and does not necessarily represent the bytecode actually executed by CPython. The primary use case for this function is debuggers and profilers.

Added in version 3.11.

PyObject ***PyCode_GetVarnames**(*PyCodeObject* *co)

Equivalent to the Python code `getattr(co, 'co_varnames')`. Returns a new reference to a *PyTupleObject* containing the names of the local variables. On error, `NULL` is returned and an exception is raised.

Added in version 3.11.

PyObject ***PyCode_GetCellvars**(*PyCodeObject* *co)

Equivalent to the Python code `getattr(co, 'co_cellvars')`. Returns a new reference to a *PyTupleObject* containing the names of the local variables that are referenced by nested functions. On error, `NULL` is returned and an exception is raised.

Added in version 3.11.

PyObject ***PyCode_GetFreevars**(*PyCodeObject* *co)

Equivalent to the Python code `getattr(co, 'co_freevars')`. Returns a new reference to a *PyTupleObject* containing the names of the *free (closure) variables*. On error, `NULL` is returned and an exception is raised.

Added in version 3.11.

int **PyCode_AddWatcher**(*PyCode_WatchCallback* callback)

Register *callback* as a code object watcher for the current interpreter. Return an ID which may be passed to *PyCode_ClearWatcher()*. In case of error (e.g. no more watcher IDs available), return `-1` and set an exception.

Added in version 3.12.

int **PyCode_ClearWatcher**(int watcher_id)

Clear watcher identified by *watcher_id* previously returned from *PyCode_AddWatcher()* for the current interpreter. Return `0` on success, or `-1` and set an exception on error (e.g. if the given *watcher_id* was never registered.)

Added in version 3.12.

type **PyCodeEvent**

Enumeration of possible code object watcher events: - `PY_CODE_EVENT_CREATE` - `PY_CODE_EVENT_DESTROY`

Added in version 3.12.

typedef int (***PyCode_WatchCallback**)(*PyCodeEvent* event, *PyCodeObject* *co)

Type of a code object watcher callback function.

If *event* is `PY_CODE_EVENT_CREATE`, then the callback is invoked after *co* has been fully initialized. Otherwise, the callback is invoked before the destruction of *co* takes place, so the prior state of *co* can be inspected.

If *event* is PY_CODE_EVENT_DESTROY, taking a reference in the callback to the about-to-be-destroyed code object will resurrect it and prevent it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

Users of this API should not rely on internal runtime implementation details. Such details may include, but are not limited to, the exact order and timing of creation and destruction of code objects. While changes in these details may result in differences observable by watchers (including whether a callback is invoked or not), it does not change the semantics of the Python code being executed.

If the callback sets an exception, it must return -1; this exception will be printed as an unraisable exception using *PyErr_WriteUnraisable()*. Otherwise it should return 0.

There may already be a pending exception set on entry to the callback. In this case, the callback should return 0 with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Added in version 3.12.

9.5.6 Code Object Flags

Code objects contain a bit-field of flags, which can be retrieved as the co_flags Python attribute (for example using *PyObject_GetAttrString()*), and set using a *flags* argument to *PyUnstable_Code_New()* and similar functions.

Flags whose names start with CO_FUTURE_ correspond to features normally selectable by future statements. These flags can be used in *PyCompilerFlags.cf_flags*. Note that many CO_FUTURE_ flags are mandatory in current versions of Python, and setting them has no effect.

The following flags are available. For their meaning, see the linked documentation of their Python equivalents.

Flag	Meaning
CO_OPTIMIZED	`inspect.CO_OPTIMIZED`
CO_NEWLOCALS	`inspect.CO_NEWLOCALS`
CO_VARARGS	`inspect.CO_VARARGS`
CO_VARKEYWORDS	`inspect.CO_VARKEYWORDS`
CO_NESTED	`inspect.CO_NESTED`
CO_GENERATOR	`inspect.CO_GENERATOR`
CO_COROUTINE	`inspect.CO_COROUTINE`
CO_ITERABLE_COROUTINE	`inspect.CO_ITERABLE_COROUTINE`
CO_ASYNC_GENERATOR	`inspect.CO_ASYNC_GENERATOR`
CO_HAS_DOCSTRING	`inspect.CO_HAS_DOCSTRING`
CO_METHOD	`inspect.CO_METHOD`
CO_FUTURE_DIVISION	no effect (`__future__.division`)
CO_FUTURE_ABSOLUTE_IMPORT	no effect (`__future__.absolute_import`)
CO_FUTURE_WITH_STATEMENT	no effect (`__future__.with_statement`)
CO_FUTURE_PRINT_FUNCTION	no effect (`__future__.print_function`)
CO_FUTURE_UNICODE_LITERALS	no effect (`__future__.unicode_literals`)
CO_FUTURE_GENERATOR_STOP	no effect (`__future__.generator_stop`)
CO_FUTURE_ANNOTATIONS	`__future__.annotations`

9.5.7 Extra information

To support low-level extensions to frame evaluation, such as external just-in-time compilers, it is possible to attach arbitrary extra data to code objects.

These functions are part of the unstable C API tier: this functionality is a CPython implementation detail, and the API may change without deprecation warnings.

Py_ssize_t **PyUnstable_Eval_RequestCodeExtraIndex**(*freefunc* free)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return a new an opaque index value used to adding data to code objects.

You generally call this function once (per interpreter) and use the result with `PyCode_GetExtra` and `PyCode_SetExtra` to manipulate data on individual code objects.

If *free* is not `NULL`: when a code object is deallocated, *free* will be called on non-`NULL` data stored under the new index. Use *`Py_DecRef()`* when storing *`PyObject`*.

Added in version 3.6: as `_PyEval_RequestCodeExtraIndex`

3.12 sürümünde değişti: Renamed to `PyUnstable_Eval_RequestCodeExtraIndex`. The old private name is deprecated, but will be available until the API changes.

int **PyUnstable_Code_GetExtra**(*PyObject* *code, *Py_ssize_t* index, void **extra)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Set *extra* to the extra data stored under the given index. Return 0 on success. Set an exception and return -1 on failure.

If no data was set under the index, set *extra* to `NULL` and return 0 without setting an exception.

Added in version 3.6: as `_PyCode_GetExtra`

3.12 sürümünde değişti: Renamed to `PyUnstable_Code_GetExtra`. The old private name is deprecated, but will be available until the API changes.

int **PyUnstable_Code_SetExtra**(*PyObject* *code, *Py_ssize_t* index, void *extra)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Set the extra data stored under the given index to *extra*. Return 0 on success. Set an exception and return -1 on failure.

Added in version 3.6: as `_PyCode_SetExtra`

3.12 sürümünde değişti: Renamed to `PyUnstable_Code_SetExtra`. The old private name is deprecated, but will be available until the API changes.

9.6 Other Objects

9.6.1 File Objects

These APIs are a minimal emulation of the Python 2 C API for built-in file objects, which used to rely on the buffered I/O (`FILE*`) support from the C standard library. In Python 3, files and streams use the new `io` module, which defines several layers over the low-level unbuffered I/O of the operating system. The functions described below are convenience C wrappers over these new APIs, and meant mostly for internal error reporting in the interpreter; third-party code is advised to access the `io` APIs instead.

PyObject ***PyFile_FromFd**(int fd, const char *name, const char *mode, int buffering, const char *encoding, const char *errors, const char *newline, int closefd)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a Python file object from the file descriptor of an already opened file *fd*. The arguments *name*, *encoding*, *errors* and *newline* can be `NULL` to use the defaults; *buffering* can be *-1* to use the default. *name* is ignored and kept for backward compatibility. Return `NULL` on failure. For a more comprehensive description of the arguments, please refer to the `io.open()` function documentation.

> **Uyarı**
>
> Since Python streams have their own buffering layer, mixing them with OS-level file descriptors can produce various issues (such as unexpected ordering of data).

3.2 sürümünde değişti: Ignore *name* attribute.

int **PyObject_AsFileDescriptor**(*PyObject* *p)

Bir parçası Kararlı ABI. Return the file descriptor associated with *p* as an `int`. If the object is an integer, its value is returned. If not, the object's `fileno()` method is called if it exists; the method must return an integer, which is returned as the file descriptor value. Sets an exception and returns `-1` on failure.

PyObject ***PyFile_GetLine**(*PyObject* *p, int n)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Equivalent to `p.readline([n])`, this function reads one line from the object *p*. *p* may be a file object or any object with a `readline()` method. If *n* is `0`, exactly one line is read, regardless of the length of the line. If *n* is greater than `0`, no more than *n* bytes will be read from the file; a partial line can be returned. In both cases, an empty string is returned if the end of the file is reached immediately. If *n* is less than `0`, however, one line is read regardless of length, but `EOFError` is raised if the end of the file is reached immediately.

int **PyFile_SetOpenCodeHook**(*Py_OpenCodeHookFunction* handler)

Overrides the normal behavior of `io.open_code()` to pass its parameter through the provided handler.

The *handler* is a function of type:

typedef *PyObject* *(***Py_OpenCodeHookFunction**)(*PyObject**, void*)

Equivalent of `PyObject *(*)(PyObject *path, void *userData)`, where *path* is guaranteed to be `PyUnicodeObject`.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

As this hook is intentionally used during import, avoid importing new modules during its execution unless they are known to be frozen or available in `sys.modules`.

Once a hook has been set, it cannot be removed or replaced, and later calls to `PyFile_SetOpenCodeHook()` will fail. On failure, the function returns -1 and sets an exception if the interpreter has been initialized.

This function is safe to call before `Py_Initialize()`.

Raises an auditing event `setopencodehook` with no arguments.

Added in version 3.8.

int **PyFile_WriteObject**(*PyObject* *obj, *PyObject* *p, int flags)

Bir parçası Kararlı ABI. Write object *obj* to file object *p*. The only supported flag for *flags* is `Py_PRINT_RAW`; if given, the `str()` of the object is written instead of the `repr()`. Return `0` on success or `-1` on failure; the appropriate exception will be set.

int **PyFile_WriteString**(const char *s, *PyObject* *p)

Bir parçası Kararlı ABI. Write string *s* to file object *p*. Return `0` on success or `-1` on failure; the appropriate exception will be set.

9.6.2 Module Objects

PyTypeObject **PyModule_Type**

Bir parçası Kararlı ABI. This instance of `PyTypeObject` represents the Python module type. This is exposed to Python programs as `types.ModuleType`.

int **PyModule_Check**(*PyObject* *p)

Return true if *p* is a module object, or a subtype of a module object. This function always succeeds.

int **PyModule_CheckExact**(*PyObject* *p)

Return true if *p* is a module object, but not a subtype of `PyModule_Type`. This function always succeeds.

PyObject ***PyModule_NewObject**(*PyObject* *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a new module object with `module.__name__` set to *name*. The module's `__name__`, `__doc__`, `__package__` and `__loader__` attributes are filled in (all but `__name__` are set to `None`). The caller is responsible for setting a `__file__` attribute.

Return `NULL` with an exception set on error.

Added in version 3.3.

3.4 sürümünde değişti: `__package__` and `__loader__` are now set to `None`.

PyObject ***PyModule_New**(const char *name)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Similar to `PyModule_NewObject()`, but the name is a UTF-8 encoded string instead of a Unicode object.

PyObject ***PyModule_GetDict**(*PyObject* *module)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return the dictionary object that implements *module*'s namespace; this object is the same as the `__dict__` attribute of the module object. If *module* is not a module object (or a subtype of a module object), `SystemError` is raised and `NULL` is returned.

It is recommended extensions use other `PyModule_*` and `PyObject_*` functions rather than directly manipulate a module's `__dict__`.

PyObject ***PyModule_GetNameObject**(*PyObject* *module)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return *module*'s `__name__` value. If the module does not provide one, or if it is not a string, `SystemError` is raised and `NULL` is returned.

Added in version 3.3.

const char ***PyModule_GetName**(*PyObject* *module)

Bir parçası Kararlı ABI. Similar to `PyModule_GetNameObject()` but return the name encoded to `'utf-8'`.

void ***PyModule_GetState**(*PyObject* *module)

Bir parçası Kararlı ABI. Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or `NULL`. See `PyModuleDef.m_size`.

PyModuleDef ***PyModule_GetDef**(*PyObject* *module)

Bir parçası Kararlı ABI. Return a pointer to the `PyModuleDef` struct from which the module was created, or `NULL` if the module wasn't created from a definition.

PyObject ***PyModule_GetFilenameObject**(*PyObject* *module)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return the name of the file from which *module* was loaded using *module*'s `__file__` attribute. If this is not defined, or if it is not a string, raise `SystemError` and return `NULL`; otherwise return a reference to a Unicode object.

Added in version 3.2.

const char ***PyModule_GetFilename**(*PyObject* *module)

Bir parçası Kararlı ABI. Similar to *`PyModule_GetFilenameObject()`* but return the filename encoded to 'utf-8'.

3.2 sürümünden beri kullanım dışı: *`PyModule_GetFilename()`* raises `UnicodeEncodeError` on unencodable filenames, use *`PyModule_GetFilenameObject()`* instead.

9.6.3 Module definitions

The functions in the previous section work on any module object, including modules imported from Python code.

Modules defined using the C API typically use a *module definition*, *`PyModuleDef`* – a statically allocated, constant "description" of how a module should be created.

The definition is usually used to define an extension's "main" module object (see *Defining extension modules* for details). It is also used to *create extension modules dynamically*.

Unlike *`PyModule_New()`*, the definition allows management of *module state* – a piece of memory that is allocated and cleared together with the module object. Unlike the module's Python attributes, Python code cannot replace or delete data stored in module state.

type **PyModuleDef**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* The module definition struct, which holds all information needed to create a module object. This structure must be statically allocated (or be otherwise guaranteed to be valid while any modules created from it exist). Usually, there is only one variable of this type for each extension module.

PyModuleDef_Base **m_base**

Always initialize this member to `PyModuleDef_HEAD_INIT`.

const char ***m_name**

Name for the new module.

const char ***m_doc**

Docstring for the module; usually a docstring variable created with *`PyDoc_STRVAR`* is used.

Py_ssize_t **m_size**

Module state may be kept in a per-module memory area that can be retrieved with *`PyModule_GetState()`*, rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on *m_size* on module creation, and freed when the module object is deallocated, after the *`m_free`* function has been called, if present.

Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state.

Setting `m_size` to `-1` means that the module does not support sub-interpreters, because it has global state. Negative `m_size` is only allowed when using *legacy single-phase initialization* or when *creating modules dynamically*.

See **PEP 3121** for more details.

PyMethodDef ***m_methods**

A pointer to a table of module-level functions, described by *`PyMethodDef`* values. Can be `NULL` if no functions are present.

PyModuleDef_Slot ***m_slots***

An array of slot definitions for multi-phase initialization, terminated by a `{0, NULL}` entry. When using legacy single-phase initialization, *m_slots* must be `NULL`.

3.5 sürümünde değişti: Prior to version 3.5, this member was always set to `NULL`, and was defined as:

inquiry **m_reload**

traverseproc **m_traverse**

A traversal function to call during GC traversal of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py_mod_exec* function). More precisely, this function is not called if *m_size* is greater than 0 and the module state (as returned by *PyModule_GetState()*) is `NULL`.

3.9 sürümünde değişti: No longer called before the module state is allocated.

inquiry **m_clear**

A clear function to call during GC clearing of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py_mod_exec* function). More precisely, this function is not called if *m_size* is greater than 0 and the module state (as returned by *PyModule_GetState()*) is `NULL`.

Like *PyTypeObject.tp_clear*, this function is not *always* called before a module is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and *m_free* is called directly.

3.9 sürümünde değişti: No longer called before the module state is allocated.

freefunc **m_free**

A function to call during deallocation of the module object, or `NULL` if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (*Py_mod_exec* function). More precisely, this function is not called if *m_size* is greater than 0 and the module state (as returned by *PyModule_GetState()*) is `NULL`.

3.9 sürümünde değişti: No longer called before the module state is allocated.

Module slots

type **PyModuleDef_Slot**

int **slot**

A slot ID, chosen from the available values explained below.

void ***value**

Value of the slot, whose meaning depends on the slot ID.

Added in version 3.5.

The available slot types are:

Py_mod_create

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature:

PyObject ***create_module**(*PyObject* *spec, *PyModuleDef* *def)

The function receives a `ModuleSpec` instance, as defined in **PEP 451**, and the module definition. It should return a new module object, or set an error and return `NULL`.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple `Py_mod_create` slots may not be specified in one module definition.

If `Py_mod_create` is not specified, the import machinery will create a normal module object using *PyModule_New()*. The name is taken from *spec*, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of *PyModule_Type*. Any type can be used, as long as it supports setting and getting import-related attributes. However, only `PyModule_Type` instances may be returned if the `PyModuleDef` has non-`NULL` `m_traverse`, `m_clear`, `m_free`; non-zero `m_size`; or slots other than `Py_mod_create`.

Py_mod_exec

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

int **exec_module**(*PyObject* *module)

If multiple `Py_mod_exec` slots are specified, they are processed in the order they appear in the *m_slots* array.

Py_mod_multiple_interpreters

Specifies one of the following values:

Py_MOD_MULTIPLE_INTERPRETERS_NOT_SUPPORTED

The module does not support being imported in subinterpreters.

Py_MOD_MULTIPLE_INTERPRETERS_SUPPORTED

The module supports being imported in subinterpreters, but only when they share the main interpreter's GIL. (See isolating-extensions-howto.)

Py_MOD_PER_INTERPRETER_GIL_SUPPORTED

The module supports being imported in subinterpreters, even when they have their own GIL. (See isolating-extensions-howto.)

This slot determines whether or not importing this module in a subinterpreter will fail.

Multiple `Py_mod_multiple_interpreters` slots may not be specified in one module definition.

If `Py_mod_multiple_interpreters` is not specified, the import machinery defaults to `Py_MOD_MULTIPLE_INTERPRETERS_SUPPORTED`.

Added in version 3.12.

Py_mod_gil

Specifies one of the following values:

Py_MOD_GIL_USED

The module depends on the presence of the global interpreter lock (GIL), and may access global state without synchronization.

Py_MOD_GIL_NOT_USED

The module is safe to run without an active GIL.

This slot is ignored by Python builds not configured with `--disable-gil`. Otherwise, it determines whether or not importing this module will cause the GIL to be automatically enabled. See whatsnew313-free-threaded-cpython for more detail.

Multiple `Py_mod_gil` slots may not be specified in one module definition.

If `Py_mod_gil` is not specified, the import machinery defaults to `Py_MOD_GIL_USED`.

Added in version 3.13.

9.6.4 Creating extension modules dynamically

The following functions may be used to create a module outside of an extension's *initialization function*. They are also used in *single-phase initialization*.

PyObject ***PyModule_Create**(*PyModuleDef* *def)

Döndürdüğü değer: Yeni referans. Create a new module object, given the definition in *def*. This is a macro that calls `PyModule_Create2()` with *module_api_version* set to `PYTHON_API_VERSION`, or to `PYTHON_ABI_VERSION` if using the *limited API*.

PyObject ***PyModule_Create2**(*PyModuleDef* *def, int module_api_version)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a new module object, given the definition in *def*, assuming the API version *module_api_version*. If that version does not match the version of the running interpreter, a `RuntimeWarning` is emitted.

Return `NULL` with an exception set on error.

This function does not support slots. The `m_slots` member of *def* must be `NULL`.

> **Not**
>
> Most uses of this function should be using `PyModule_Create()` instead; only use this if you are sure you need it.

PyObject ***PyModule_FromDefAndSpec**(*PyModuleDef* *def, *PyObject* *spec)

Döndürdüğü değer: Yeni referans. This macro calls `PyModule_FromDefAndSpec2()` with *module_api_version* set to `PYTHON_API_VERSION`, or to `PYTHON_ABI_VERSION` if using the *limited API*.

Added in version 3.5.

PyObject ***PyModule_FromDefAndSpec2**(*PyModuleDef* *def, *PyObject* *spec, int module_api_version)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Create a new module object, given the definition in *def* and the ModuleSpec *spec*, assuming the API version *module_api_version*. If that version does not match the version of the running interpreter, a `RuntimeWarning` is emitted.

Return `NULL` with an exception set on error.

Note that this does not process execution slots (`Py_mod_exec`). Both `PyModule_FromDefAndSpec` and `PyModule_ExecDef` must be called to fully initialize a module.

> **Not**
>
> Most uses of this function should be using `PyModule_FromDefAndSpec()` instead; only use this if you are sure you need it.

Added in version 3.5.

int **PyModule_ExecDef**(*PyObject* *module, *PyModuleDef* *def)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Process any execution slots (`Py_mod_exec`) given in *def*.

Added in version 3.5.

PYTHON_API_VERSION

The C API version. Defined for backwards compatibility.

Currently, this constant is not updated in new Python versions, and is not useful for versioning. This may change in the future.

PYTHON_ABI_VERSION

Defined as `3` for backwards compatibility.

Currently, this constant is not updated in new Python versions, and is not useful for versioning. This may change in the future.

9.6.5 Support functions

The following functions are provided to help initialize a module state. They are intended for a module's execution slots (*Py_mod_exec*), the initialization function for legacy *single-phase initialization*, or code that creates modules dynamically.

int **PyModule_AddObjectRef**(*PyObject* *module, const char *name, *PyObject* *value)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Add an object to *module* as *name*. This is a convenience function which can be used from the module's initialization function.

On success, return `0`. On error, raise an exception and return `-1`.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_DECREF(obj);
    return res;
}
```

To be convenient, the function accepts `NULL` *value* with an exception set. In this case, return `-1` and just leave the raised exception unchanged.

The example can also be written without checking explicitly if *obj* is `NULL`:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_XDECREF(obj);
    return res;
}
```

Note that `Py_XDECREF()` should be used instead of `Py_DECREF()` in this case, since *obj* can be `NULL`.

The number of different *name* strings passed to this function should be kept small, usually by only using statically allocated strings as *name*. For names that aren't known at compile time, prefer calling *PyUnicode_FromString()* and *PyObject_SetAttr()* directly. For more details, see *PyUnicode_InternFromString()*, which may be used internally to create a key object.

Added in version 3.10.

int **PyModule_Add**(*PyObject* *module, const char *name, *PyObject* *value)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Similar to *PyModule_AddObjectRef()*, but "steals" a reference to *value*. It can be called with a result of function that returns a new reference without bothering to check its result or even saving it to a variable.

Example usage:

```
if (PyModule_Add(module, "spam", PyBytes_FromString(value)) < 0) {
    goto error;
}
```

Added in version 3.13.

int **PyModule_AddObject**(*PyObject* *module, const char *name, *PyObject* *value)

Bir parçası Kararlı ABI. Similar to `PyModule_AddObjectRef()`, but steals a reference to *value* on success (if it returns `0`).

The new `PyModule_Add()` or `PyModule_AddObjectRef()` functions are recommended, since it is easy to introduce reference leaks by misusing the `PyModule_AddObject()` function.

Not

Unlike other functions that steal references, `PyModule_AddObject()` only releases the reference to *value* **on success**.

This means that its return value must be checked, and calling code must `Py_XDECREF()` *value* manually on error.

Example usage:

```
PyObject *obj = PyBytes_FromString(value);
if (PyModule_AddObject(module, "spam", obj) < 0) {
    // If 'obj' is not NULL and PyModule_AddObject() failed,
    // 'obj' strong reference must be deleted with Py_XDECREF().
    // If 'obj' is NULL, Py_XDECREF() does nothing.
    Py_XDECREF(obj);
    goto error;
}
// PyModule_AddObject() stole a reference to obj:
// Py_XDECREF(obj) is not needed here.
```

3.13 sürümünden beri kullanım dışı: `PyModule_AddObject()` is *soft deprecated*.

int **PyModule_AddIntConstant**(*PyObject* *module, const char *name, long value)

Bir parçası Kararlı ABI. Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return `-1` with an exception set on error, `0` on success.

This is a convenience function that calls `PyLong_FromLong()` and `PyModule_AddObjectRef()`; see their documentation for details.

int **PyModule_AddStringConstant**(*PyObject* *module, const char *name, const char *value)

Bir parçası Kararlı ABI. Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be `NULL`-terminated. Return `-1` with an exception set on error, `0` on success.

This is a convenience function that calls `PyUnicode_InternFromString()` and `PyModule_AddObjectRef()`; see their documentation for details.

PyModule_AddIntMacro(module, macro)

Add an int constant to *module*. The name and the value are taken from *macro*. For example `PyModule_AddIntMacro(module, AF_INET)` adds the int constant *AF_INET* with the value of *AF_INET* to *module*. Return `-1` with an exception set on error, `0` on success.

PyModule_AddStringMacro(module, macro)

Add a string constant to *module*.

int **PyModule_AddType**(*PyObject* *module, *PyTypeObject* *type)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Add a type object to *module*. The type object is finalized by calling internally `PyType_Ready()`. The name of the type object is taken from the last component of `tp_name` after dot. Return `-1` with an exception set on error, `0` on success.

Added in version 3.9.

int **PyModule_AddFunctions**(*PyObject* *module, *PyMethodDef* *functions)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Add the functions from the `NULL` terminated *functions* array to *module*. Refer to the `PyMethodDef` documentation for details on individual entries (due to the lack of a shared module namespace, module level "functions" implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes).

This function is called automatically when creating a module from `PyModuleDef` (such as when using *Multi-phase initialization*, `PyModule_Create`, or `PyModule_FromDefAndSpec`). Some module authors may prefer defining functions in multiple `PyMethodDef` arrays; in that case they should call this function directly.

Added in version 3.5.

int **PyModule_SetDocString**(*PyObject* *module, const char *docstring)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Set the docstring for *module* to *docstring*. This function is called automatically when creating a module from `PyModuleDef` (such as when using *Multi-phase initialization*, `PyModule_Create`, or `PyModule_FromDefAndSpec`).

Added in version 3.5.

int **PyUnstable_Module_SetGIL**(*PyObject* *module, void *gil)



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Indicate that *module* does or does not support running without the global interpreter lock (GIL), using one of the values from `Py_mod_gil`. It must be called during *module*'s initialization function when using *Legacy single-phase initialization*. If this function is not called during module initialization, the import machinery assumes the module does not support running without the GIL. This function is only available in Python builds configured with `--disable-gil`. Return `-1` with an exception set on error, `0` on success.

Added in version 3.13.

Module lookup (single-phase initialization)

The legacy *single-phase initialization* initialization scheme creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

PyObject ***PyState_FindModule**(*PyModuleDef* *def)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Returns the module object that was created from *def* for the current interpreter. This method requires that the module object has been attached to the interpreter state with `PyState_AddModule()` beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns `NULL`.

int **PyState_AddModule**(*PyObject* *module, *PyModuleDef* *def)

Bir parçası Kararlı ABI *3.3 sürümünden beri.* Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via `PyState_FindModule()`.

Only effective on modules created using single-phase initialization.

Python calls `PyState_AddModule` automatically after importing a module that uses *single-phase initialization*, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls `PyState_FindModule`. The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

If a module was attached previously using the same *def*, it is replaced by the new *module*.

The caller must have an *attached thread state*.

Return `-1` with an exception set on error, `0` on success.

Added in version 3.3.

int **PyState_RemoveModule**(*PyModuleDef* *def)

Bir parçası Kararlı ABI *3.3 sürümünden beri.* Removes the module object created from *def* from the interpreter state. Return `-1` with an exception set on error, `0` on success.

The caller must have an *attached thread state*.

Added in version 3.3.

9.6.6 Iterator Objects

Python provides two general-purpose iterator objects. The first, a sequence iterator, works with an arbitrary sequence supporting the `__getitem__()` method. The second works with a callable object and a sentinel value, calling the callable for each item in the sequence, and ending the iteration when the sentinel value is returned.

PyTypeObject **PySeqIter_Type**

Bir parçası Kararlı ABI. Type object for iterator objects returned by `PySeqIter_New()` and the one-argument form of the `iter()` built-in function for built-in sequence types.

int **PySeqIter_Check**(*PyObject* *op)

Return true if the type of *op* is `PySeqIter_Type`. This function always succeeds.

PyObject ***PySeqIter_New**(*PyObject* *seq)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return an iterator that works with a general sequence object, *seq*. The iteration ends when the sequence raises `IndexError` for the subscripting operation.

PyTypeObject **PyCallIter_Type**

Bir parçası Kararlı ABI. Type object for iterator objects returned by `PyCallIter_New()` and the two-argument form of the `iter()` built-in function.

int **PyCallIter_Check**(*PyObject* *op)

Return true if the type of *op* is `PyCallIter_Type`. This function always succeeds.

PyObject ***PyCallIter_New**(*PyObject* *callable, *PyObject* *sentinel)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new iterator. The first parameter, *callable*, can be any Python callable object that can be called with no parameters; each call to it should return the next item in the iteration. When *callable* returns a value equal to *sentinel*, the iteration will be terminated.

9.6.7 Descriptor Objects

"Descriptors" are objects that describe some attribute of an object. They are found in the dictionary of type objects.

PyTypeObject **PyProperty_Type**

Bir parçası Kararlı ABI. The type object for the built-in descriptor types.

PyObject ***PyDescr_NewGetSet**(*PyTypeObject* *type, struct *PyGetSetDef* *getset)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI.

PyObject ***PyDescr_NewMember**(*PyTypeObject* *type, struct *PyMemberDef* *meth)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI.

PyObject ***PyDescr_NewMethod**(*PyTypeObject* *type, struct *PyMethodDef* *meth)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI.

PyObject ***PyDescr_NewWrapper**(*PyTypeObject* *type, struct wrapperbase *wrapper, void *wrapped)

Döndürdüğü değer: Yeni referans.

PyObject ***PyDescr_NewClassMethod**(*PyTypeObject* *type, *PyMethodDef* *method)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI.

int **PyDescr_IsData**(*PyObject* *descr)

Return non-zero if the descriptor objects *descr* describes a data attribute, or `0` if it describes a method. *descr* must be a descriptor object; there is no error checking.

PyObject ***PyWrapper_New**(*PyObject**, *PyObject**)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI.

9.6.8 Slice Objects

PyTypeObject **PySlice_Type**

Bir parçası Kararlı ABI. The type object for slice objects. This is the same as `slice` in the Python layer.

int **PySlice_Check**(*PyObject* *ob)

Return true if *ob* is a slice object; *ob* must not be `NULL`. This function always succeeds.

PyObject ***PySlice_New**(*PyObject* *start, *PyObject* *stop, *PyObject* *step)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a new slice object with the given values. The *start*, *stop*, and *step* parameters are used as the values of the slice object attributes of the same names. Any of the values may be `NULL`, in which case the `None` will be used for the corresponding attribute.

Return `NULL` with an exception set if the new object could not be allocated.

int **PySlice_GetIndices**(*PyObject* *slice, *Py_ssize_t* length, *Py_ssize_t* *start, *Py_ssize_t* *stop, *Py_ssize_t* *step)

Bir parçası Kararlı ABI. Retrieve the start, stop and step indices from the slice object *slice*, assuming a sequence of length *length*. Treats indices greater than *length* as errors.

Returns `0` on success and `-1` on error with no exception set (unless one of the indices was not `None` and failed to be converted to an integer, in which case `-1` is returned with an exception set).

You probably do not want to use this function.

3.2 sürümünde değişti: The parameter type for the *slice* parameter was `PySliceObject*` before.

int **PySlice_GetIndicesEx**(*PyObject* *slice, *Py_ssize_t* length, *Py_ssize_t* *start, *Py_ssize_t* *stop, *Py_ssize_t* *step, *Py_ssize_t* *slicelength)

Bir parçası Kararlı ABI. Usable replacement for *`PySlice_GetIndices()`*. Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return `0` on success and `-1` on error with an exception set.

Not

This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of *`PySlice_Unpack()`* and *`PySlice_AdjustIndices()`* where

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength)
↪< 0) {
    // return error
}
```

is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);
```

3.2 sürümünde değişti: The parameter type for the *slice* parameter was `PySliceObject*` before.

3.6.1 sürümünde değişti: If `Py_LIMITED_API` is not set or set to the value between `0x03050400` and `0x03060000` (not including) or `0x03060100` or higher `PySlice_GetIndicesEx()` is implemented as a macro using `PySlice_Unpack()` and `PySlice_AdjustIndices()`. Arguments *start*, *stop* and *step* are evaluated more than once.

3.6.1 sürümünden beri kullanım dışı: If `Py_LIMITED_API` is set to the value less than `0x03050400` or between `0x03060000` and `0x03060100` (not including) `PySlice_GetIndicesEx()` is a deprecated function.

int **PySlice_Unpack**(*PyObject* *slice, *Py_ssize_t* *start, *Py_ssize_t* *stop, *Py_ssize_t* *step)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than `PY_SSIZE_T_MAX` to `PY_SSIZE_T_MAX`, silently boost the start and stop values less than `PY_SSIZE_T_MIN` to `PY_SSIZE_T_MIN`, and silently boost the step values less than `-PY_SSIZE_T_MAX` to `-PY_SSIZE_T_MAX`.

Return `-1` with an exception set on error, `0` on success.

Added in version 3.6.1.

Py_ssize_t **PySlice_AdjustIndices**(*Py_ssize_t* length, *Py_ssize_t* *start, *Py_ssize_t* *stop, *Py_ssize_t* step)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

Added in version 3.6.1.

Ellipsis Object

PyTypeObject **PyEllipsis_Type**

Bir parçası Kararlı ABI. The type of Python `Ellipsis` object. Same as `types.EllipsisType` in the Python layer.

PyObject ***Py_Ellipsis**

The Python `Ellipsis` object. This object has no methods. Like *Py_None*, it is an *immortal* singleton object.

3.12 sürümünde değişti: *Py_Ellipsis* is immortal.

9.6.9 MemoryView objects

A `memoryview` object exposes the C level *buffer interface* as a Python object which can then be passed around like any other object.

PyObject ***PyMemoryView_FromObject**(*PyObject* *obj)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a memoryview object from an object that provides the buffer interface. If *obj* supports writable buffer exports, the memoryview object will be read/write, otherwise it may be either read-only or read/write at the discretion of the exporter.

PyBUF_READ

Flag to request a readonly buffer.

PyBUF_WRITE

Flag to request a writable buffer.

PyObject ***PyMemoryView_FromMemory**(char *mem, *Py_ssize_t* size, int flags)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.7 sürümünden beri.* Create a memoryview object using *mem* as the underlying buffer. *flags* can be one of *PyBUF_READ* or *PyBUF_WRITE*.

Added in version 3.3.

PyObject ***PyMemoryView_FromBuffer**(const *Py_buffer* *view)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.11 sürümünden beri.* Create a memoryview object wrapping the given buffer structure *view*. For simple byte buffers, *PyMemoryView_FromMemory()* is the preferred function.

PyObject ***PyMemoryView_GetContiguous**(*PyObject* *obj, int buffertype, char order)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a memoryview object to a *contiguous* chunk of memory (in either 'C' or 'F'ortran *order*) from an object that defines the buffer interface. If memory is contiguous, the memoryview object points to the original memory. Otherwise, a copy is made and the memoryview points to a new bytes object.

buffertype can be one of `PyBUF_READ` or `PyBUF_WRITE`.

int **PyMemoryView_Check**(*PyObject* *obj)

Return true if the object *obj* is a memoryview object. It is not currently allowed to create subclasses of `memoryview`. This function always succeeds.

Py_buffer ***PyMemoryView_GET_BUFFER**(*PyObject* *mview)

Return a pointer to the memoryview's private copy of the exporter's buffer. *mview* **must** be a memoryview instance; this macro doesn't check its type, you must do it yourself or you will risk crashes.

PyObject ***PyMemoryView_GET_BASE**(*PyObject* *mview)

Return either a pointer to the exporting object that the memoryview is based on or `NULL` if the memoryview has been created by one of the functions `PyMemoryView_FromMemory()` or `PyMemoryView_FromBuffer()`. *mview* **must** be a memoryview instance.

9.6.10 Weak Reference Objects

Python supports *weak references* as first-class objects. There are two specific object types which directly implement weak references. The first is a simple reference object, and the second acts as a proxy for the original object as much as it can.

int **PyWeakref_Check**(*PyObject* *ob)

Return non-zero if *ob* is either a reference or proxy object. This function always succeeds.

int **PyWeakref_CheckRef**(*PyObject* *ob)

Return non-zero if *ob* is a reference object. This function always succeeds.

int **PyWeakref_CheckProxy**(*PyObject* *ob)

Return non-zero if *ob* is a proxy object. This function always succeeds.

PyObject ***PyWeakref_NewRef**(*PyObject* *ob, *PyObject* *callback)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a weak reference object for the object *ob*. This will always return a new reference, but is not guaranteed to create a new object; an existing reference object may be returned. The second parameter, *callback*, can be a callable object that receives notification when *ob* is garbage collected; it should accept a single parameter, which will be the weak reference object itself. *callback* may also be `None` or `NULL`. If *ob* is not a weakly referenceable object, or if *callback* is not callable, `None`, or `NULL`, this will return `NULL` and raise `TypeError`.

PyObject ***PyWeakref_NewProxy**(*PyObject* *ob, *PyObject* *callback)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Return a weak reference proxy object for the object *ob*. This will always return a new reference, but is not guaranteed to create a new object; an existing proxy object may be returned. The second parameter, *callback*, can be a callable object that receives notification when *ob* is garbage collected; it should accept a single parameter, which will be the weak reference object itself. *callback* may also be `None` or `NULL`. If *ob* is not a weakly referenceable object, or if *callback* is not callable, `None`, or `NULL`, this will return `NULL` and raise `TypeError`.

int **PyWeakref_GetRef**(*PyObject* *ref, *PyObject* **pobj)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Get a *strong reference* to the referenced object from a weak reference, *ref*, into **pobj*.

- On success, set **pobj* to a new *strong reference* to the referenced object and return 1.
- If the reference is dead, set **pobj* to `NULL` and return 0.
- On error, raise an exception and return -1.

Added in version 3.13.

PyObject ***PyWeakref_GetObject**(*PyObject* *ref)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return a *borrowed reference* to the referenced object from a weak reference, *ref*. If the referent is no longer live, returns `Py_None`.

> **Not**
>
> This function returns a *borrowed reference* to the referenced object. This means that you should always call `Py_INCREF()` on the object except when it cannot be destroyed before the last usage of the borrowed reference.

Deprecated since version 3.13, will be removed in version 3.15: Use `PyWeakref_GetRef()` instead.

PyObject ***PyWeakref_GET_OBJECT**(*PyObject* *ref)

Döndürdüğü değer: Ödünç alınmış referans. Similar to `PyWeakref_GetObject()`, but does no error checking.

Deprecated since version 3.13, will be removed in version 3.15: Use `PyWeakref_GetRef()` instead.

int **PyWeakref_IsDead**(*PyObject* *ref)

Test if the weak reference *ref* is dead. Returns 1 if the reference is dead, 0 if it is alive, and -1 with an error set if *ref* is not a weak reference object.

Added in version 3.14.

void **PyObject_ClearWeakRefs**(*PyObject* *object)

Bir parçası Kararlı ABI. This function is called by the `tp_dealloc` handler to clear weak references.

This iterates through the weak references for *object* and calls callbacks for those references which have one. It returns when all callbacks have been attempted.

void **PyUnstable_Object_ClearWeakRefsNoCallbacks**(*PyObject* *object)

> Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Clears the weakrefs for *object* without calling the callbacks.

This function is called by the `tp_dealloc` handler for types with finalizers (i.e., `__del__()`). The handler for those objects first calls `PyObject_ClearWeakRefs()` to clear weakrefs and call their callbacks, then the finalizer, and finally this function to clear any weakrefs that may have been created by the finalizer.

In most circumstances, it's more appropriate to use `PyObject_ClearWeakRefs()` to clear weakrefs instead of this function.

Added in version 3.13.

9.6.11 Capsules

Refer to using-capsules for more information on using these objects.

Added in version 3.1.

type **PyCapsule**

This subtype of `PyObject` represents an opaque value, useful for C extension modules who need to pass an opaque value (as a `void*` pointer) through Python code to other C code. It is often used to make a C function pointer defined in one module available to other modules, so the regular import mechanism can be used to access C APIs defined in dynamically loaded modules.

type **PyCapsule_Destructor**

Bir parçası Kararlı ABI. The type of a destructor callback for a capsule. Defined as:

```
typedef void (*PyCapsule_Destructor)(PyObject *);
```

See *PyCapsule_New()* for the semantics of PyCapsule_Destructor callbacks.

int **PyCapsule_CheckExact**(*PyObject* *p)

Return true if its argument is a *PyCapsule*. This function always succeeds.

PyObject ***PyCapsule_New**(void *pointer, const char *name, *PyCapsule_Destructor* destructor)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Create a *PyCapsule* encapsulating the *pointer*. The *pointer* argument may not be `NULL`.

On failure, set an exception and return `NULL`.

The *name* string may either be `NULL` or a pointer to a valid C string. If non-`NULL`, this string must outlive the capsule. (Though it is permitted to free it inside the *destructor*.)

If the *destructor* argument is not `NULL`, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the *name* should be specified as `modulename.attributename`. This will enable other modules to import the capsule using *PyCapsule_Import()*.

void ***PyCapsule_GetPointer**(*PyObject* *capsule, const char *name)

Bir parçası Kararlı ABI. Retrieve the *pointer* stored in the capsule. On failure, set an exception and return `NULL`.

The *name* parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is `NULL`, the *name* passed in must also be `NULL`. Python uses the C function `strcmp()` to compare capsule names.

PyCapsule_Destructor **PyCapsule_GetDestructor**(*PyObject* *capsule)

Bir parçası Kararlı ABI. Return the current destructor stored in the capsule. On failure, set an exception and return `NULL`.

It is legal for a capsule to have a `NULL` destructor. This makes a `NULL` return code somewhat ambiguous; use *PyCapsule_IsValid()* or *PyErr_Occurred()* to disambiguate.

void ***PyCapsule_GetContext**(*PyObject* *capsule)

Bir parçası Kararlı ABI. Return the current context stored in the capsule. On failure, set an exception and return `NULL`.

It is legal for a capsule to have a `NULL` context. This makes a `NULL` return code somewhat ambiguous; use *PyCapsule_IsValid()* or *PyErr_Occurred()* to disambiguate.

const char ***PyCapsule_GetName**(*PyObject* *capsule)

Bir parçası Kararlı ABI. Return the current name stored in the capsule. On failure, set an exception and return `NULL`.

It is legal for a capsule to have a `NULL` name. This makes a `NULL` return code somewhat ambiguous; use *PyCapsule_IsValid()* or *PyErr_Occurred()* to disambiguate.

void ***PyCapsule_Import**(const char *name, int no_block)

Bir parçası Kararlı ABI. Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in `module.attribute`. The *name* stored in the capsule must match this string exactly.

This function splits *name* on the `.` character, and imports the first element. It then processes further elements using attribute lookups.

Return the capsule's internal *pointer* on success. On failure, set an exception and return `NULL`.

> **Not**
>
> If *name* points to an attribute of some submodule or subpackage, this submodule or subpackage must be previously imported using other means (for example, by using `PyImport_ImportModule()`) for the attribute lookups to succeed.

3.3 sürümünde değişti: *no_block* has no effect anymore.

int **PyCapsule_IsValid**(*PyObject* *capsule, const char *name)

Bir parçası Kararlı ABI. Determines whether or not *capsule* is a valid capsule. A valid capsule is non-`NULL`, passes `PyCapsule_CheckExact()`, has a non-`NULL` pointer stored in it, and its internal name matches the *name* parameter. (See `PyCapsule_GetPointer()` for information on how capsule names are compared.)

In other words, if `PyCapsule_IsValid()` returns a true value, calls to any of the accessors (any function starting with `PyCapsule_Get`) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return `0` otherwise. This function will not fail.

int **PyCapsule_SetContext**(*PyObject* *capsule, void *context)

Bir parçası Kararlı ABI. Set the context pointer inside *capsule* to *context*.

Return `0` on success. Return nonzero and set an exception on failure.

int **PyCapsule_SetDestructor**(*PyObject* *capsule, *PyCapsule_Destructor* destructor)

Bir parçası Kararlı ABI. Set the destructor inside *capsule* to *destructor*.

Return `0` on success. Return nonzero and set an exception on failure.

int **PyCapsule_SetName**(*PyObject* *capsule, const char *name)

Bir parçası Kararlı ABI. Set the name inside *capsule* to *name*. If non-`NULL`, the name must outlive the capsule. If the previous *name* stored in the capsule was not `NULL`, no attempt is made to free it.

Return `0` on success. Return nonzero and set an exception on failure.

int **PyCapsule_SetPointer**(*PyObject* *capsule, void *pointer)

Bir parçası Kararlı ABI. Set the void pointer inside *capsule* to *pointer*. The pointer may not be `NULL`.

Return `0` on success. Return nonzero and set an exception on failure.

9.6.12 Frame Objects

type **PyFrameObject**

Bir parçası Sınırlı API *(bir opak yapı olarak).* The C structure of the objects used to describe frame objects.

There are no public members in this structure.

3.11 sürümünde değişti: The members of this structure were removed from the public C API. Refer to the What's New entry for details.

The `PyEval_GetFrame()` and `PyThreadState_GetFrame()` functions can be used to get a frame object.

See also *Reflection*.

PyTypeObject **PyFrame_Type**

The type of frame objects. It is the same object as `types.FrameType` in the Python layer.

3.11 sürümünde değişti: Previously, this type was only available after including `<frameobject.h>`.

int **PyFrame_Check**(*PyObject* *obj)

Return non-zero if *obj* is a frame object.

3.11 sürümünde değişti: Previously, this function was only available after including `<frameobject.h>`.

PyFrameObject ***PyFrame_GetBack**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Get the *frame* next outer frame.

Return a *strong reference*, or `NULL` if *frame* has no outer frame.

Added in version 3.9.

PyObject ***PyFrame_GetBuiltins**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Get the *frame*'s `f_builtins` attribute.

Return a *strong reference*. The result cannot be `NULL`.

Added in version 3.11.

PyCodeObject ***PyFrame_GetCode**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.10 sürümünden beri.* Get the *frame* code.

Return a *strong reference*.

The result (frame code) cannot be `NULL`.

Added in version 3.9.

PyObject ***PyFrame_GetGenerator**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Get the generator, coroutine, or async generator that owns this frame, or `NULL` if this frame is not owned by a generator. Does not raise an exception, even if the return value is `NULL`.

Return a *strong reference*, or `NULL`.

Added in version 3.11.

PyObject ***PyFrame_GetGlobals**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Get the *frame*'s `f_globals` attribute.

Return a *strong reference*. The result cannot be `NULL`.

Added in version 3.11.

int **PyFrame_GetLasti**(*PyFrameObject* *frame)

Get the *frame*'s `f_lasti` attribute.

Returns -1 if `frame.f_lasti` is `None`.

Added in version 3.11.

PyObject ***PyFrame_GetVar**(*PyFrameObject* *frame, *PyObject* *name)

Döndürdüğü değer: Yeni referans. Get the variable *name* of *frame*.

- Return a *strong reference* to the variable value on success.
- Raise `NameError` and return `NULL` if the variable does not exist.
- Raise an exception and return `NULL` on error.

name type must be a `str`.

Added in version 3.12.

PyObject ***PyFrame_GetVarString**(*PyFrameObject* *frame, const char *name)

Döndürdüğü değer: Yeni referans. Similar to *`PyFrame_GetVar()`*, but the variable name is a C string encoded in UTF-8.

Added in version 3.12.

PyObject ***PyFrame_GetLocals**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Get the *frame*'s `f_locals` attribute. If the frame refers to an *optimized scope*, this returns a write-through proxy object that allows modifying the locals. In all other cases (classes, modules, `exec()`, `eval()`) it returns the mapping representing the frame locals directly (as described for `locals()`).

Return a *strong reference*.

Added in version 3.11.

3.13 sürümünde değişti: As part of **PEP 667**, return an instance of `PyFrameLocalsProxy_Type`.

int **PyFrame_GetLineNumber**(*PyFrameObject* *frame)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Return the line number that *frame* is currently executing.

Frame Locals Proxies

Added in version 3.13.

The `f_locals` attribute on a frame object is an instance of a "frame-locals proxy". The proxy object exposes a write-through view of the underlying locals dictionary for the frame. This ensures that the variables exposed by `f_locals` are always up to date with the live local variables in the frame itself.

See **PEP 667** for more information.

PyTypeObject **PyFrameLocalsProxy_Type**

The type of frame `locals()` proxy objects.

int **PyFrameLocalsProxy_Check**(*PyObject* *obj)

Return non-zero if *obj* is a frame `locals()` proxy.

Internal Frames

Unless using **PEP 523**, you will not need this.

struct **_PyInterpreterFrame**

The interpreter's internal frame representation.

Added in version 3.11.

PyObject ***PyUnstable_InterpreterFrame_GetCode**(struct *_PyInterpreterFrame* *frame);



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return a *strong reference* to the code object for the frame.

Added in version 3.12.

int **PyUnstable_InterpreterFrame_GetLasti**(struct *_PyInterpreterFrame* *frame);



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return the byte offset into the last executed instruction.

Added in version 3.12.

int **PyUnstable_InterpreterFrame_GetLine**(struct *_PyInterpreterFrame* *frame);



Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Return the currently executing line number, or -1 if there is no line number.

Added in version 3.12.

9.6.13 Generator Objects

Generator objects are what Python uses to implement generator iterators. They are normally created by iterating over a function that yields values, rather than explicitly calling *PyGen_New()* or *PyGen_NewWithQualName()*.

type **PyGenObject**

The C structure used for generator objects.

PyTypeObject **PyGen_Type**

The type object corresponding to generator objects.

int **PyGen_Check**(*PyObject* *ob)

Return true if *ob* is a generator object; *ob* must not be `NULL`. This function always succeeds.

int **PyGen_CheckExact**(*PyObject* *ob)

Return true if *ob*'s type is *PyGen_Type*; *ob* must not be `NULL`. This function always succeeds.

PyObject ***PyGen_New**(*PyFrameObject* *frame)

Döndürdüğü değer: Yeni referans. Create and return a new generator object based on the *frame* object. A reference to *frame* is stolen by this function. The argument must not be `NULL`.

PyObject ***PyGen_NewWithQualName**(*PyFrameObject* *frame, *PyObject* *name, *PyObject* *qualname)

Döndürdüğü değer: Yeni referans. Create and return a new generator object based on the *frame* object, with `__name__` and `__qualname__` set to *name* and *qualname*. A reference to *frame* is stolen by this function. The *frame* argument must not be `NULL`.

9.6.14 Coroutine Objects

Added in version 3.5.

Coroutine objects are what functions declared with an `async` keyword return.

type **PyCoroObject**

The C structure used for coroutine objects.

PyTypeObject **PyCoro_Type**

The type object corresponding to coroutine objects.

int **PyCoro_CheckExact**(*PyObject* *ob)

Return true if *ob*'s type is *PyCoro_Type*; *ob* must not be `NULL`. This function always succeeds.

PyObject ***PyCoro_New**(*PyFrameObject* *frame, *PyObject* *name, *PyObject* *qualname)

Döndürdüğü değer: Yeni referans. Create and return a new coroutine object based on the *frame* object, with `__name__` and `__qualname__` set to *name* and *qualname*. A reference to *frame* is stolen by this function. The *frame* argument must not be `NULL`.

9.6.15 Context Variables Objects

Added in version 3.7.

3.7.1 sürümünde değişti:

Not

In Python 3.7.1 the signatures of all context variables C APIs were **changed** to use *PyObject* pointers instead of *PyContext*, *PyContextVar*, and *PyContextToken*, e.g.:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

See bpo-34762 for more details.

This section details the public C API for the `contextvars` module.

type **PyContext**

The C structure used to represent a `contextvars.Context` object.

type **PyContextVar**

The C structure used to represent a `contextvars.ContextVar` object.

type **PyContextToken**

The C structure used to represent a `contextvars.Token` object.

PyTypeObject **PyContext_Type**

The type object representing the *context* type.

PyTypeObject **PyContextVar_Type**

The type object representing the *context variable* type.

PyTypeObject **PyContextToken_Type**

The type object representing the *context variable token* type.

Type-check macros:

int **PyContext_CheckExact**(*PyObject* *o)

Return true if *o* is of type *PyContext_Type*. *o* must not be `NULL`. This function always succeeds.

int **PyContextVar_CheckExact**(*PyObject* *o)

Return true if *o* is of type *PyContextVar_Type*. *o* must not be `NULL`. This function always succeeds.

int **PyContextToken_CheckExact**(*PyObject* *o)

Return true if *o* is of type *PyContextToken_Type*. *o* must not be `NULL`. This function always succeeds.

Context object management functions:

PyObject ***PyContext_New**(void)

Döndürdüğü değer: Yeni referans. Create a new empty context object. Returns `NULL` if an error has occurred.

PyObject ***PyContext_Copy**(*PyObject* *ctx)

Döndürdüğü değer: Yeni referans. Create a shallow copy of the passed *ctx* context object. Returns `NULL` if an error has occurred.

PyObject ***PyContext_CopyCurrent**(void)

Döndürdüğü değer: Yeni referans. Create a shallow copy of the current thread context. Returns `NULL` if an error has occurred.

int **PyContext_Enter**(*PyObject* *ctx)

Set *ctx* as the current context for the current thread. Returns `0` on success, and `-1` on error.

int **PyContext_Exit**(*PyObject* *ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns `0` on success, and `-1` on error.

int **PyContext_AddWatcher**(*PyContext_WatchCallback* callback)

Register *callback* as a context object watcher for the current interpreter. Return an ID which may be passed to *PyContext_ClearWatcher()*. In case of error (e.g. no more watcher IDs available), return `-1` and set an exception.

Added in version 3.14.

int **PyContext_ClearWatcher**(int watcher_id)

Clear watcher identified by *watcher_id* previously returned from `PyContext_AddWatcher()` for the current interpreter. Return `0` on success, or `-1` and set an exception on error (e.g. if the given *watcher_id* was never registered.)

Added in version 3.14.

type **PyContextEvent**

Enumeration of possible context object watcher events:

- `Py_CONTEXT_SWITCHED`: The *current context* has switched to a different context. The object passed to the watch callback is the now-current `contextvars.Context` object, or None if no context is current.

Added in version 3.14.

typedef int (***PyContext_WatchCallback**)(*PyContextEvent* event, *PyObject* *obj)

Context object watcher callback function. The object passed to the callback is event-specific; see `PyContextEvent` for details.

If the callback returns with an exception set, it must return `-1`; this exception will be printed as an unraisable exception using `PyErr_FormatUnraisable()`. Otherwise it should return `0`.

There may already be a pending exception set on entry to the callback. In this case, the callback should return `0` with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Added in version 3.14.

Context variable functions:

PyObject ***PyContextVar_New**(const char *name, *PyObject* *def)

Döndürdüğü değer: Yeni referans. Create a new `ContextVar` object. The *name* parameter is used for introspection and debug purposes. The *def* parameter specifies a default value for the context variable, or `NULL` for no default. If an error has occurred, this function returns `NULL`.

int **PyContextVar_Get**(*PyObject* *var, *PyObject* *default_value, *PyObject* **value)

Get the value of a context variable. Returns `-1` if an error has occurred during lookup, and `0` if no error occurred, whether or not a value was found.

If the context variable was found, *value* will be a pointer to it. If the context variable was *not* found, *value* will point to:

- *default_value*, if not `NULL`;
- the default value of *var*, if not `NULL`;
- `NULL`

Except for `NULL`, the function returns a new reference.

PyObject ***PyContextVar_Set**(*PyObject* *var, *PyObject* *value)

Döndürdüğü değer: Yeni referans. Set the value of *var* to *value* in the current context. Returns a new token object for this change, or `NULL` if an error has occurred.

int **PyContextVar_Reset**(*PyObject* *var, *PyObject* *token)

Reset the state of the *var* context variable to that it was in before `PyContextVar_Set()` that returned the *token* was called. This function returns `0` on success and `-1` on error.

9.6.16 DateTime Objects

Various date and time objects are supplied by the `datetime` module. Before using any of these functions, the header file `datetime.h` must be included in your source (note that this is not included by `Python.h`), and the macro `PyDateTime_IMPORT` must be invoked, usually as part of the module initialisation function. The macro puts a pointer to a C structure into a static variable, `PyDateTimeAPI`, that is used by the following macros.

type **PyDateTime_Date**

This subtype of *PyObject* represents a Python date object.

type **PyDateTime_DateTime**

This subtype of *PyObject* represents a Python datetime object.

type **PyDateTime_Time**

This subtype of *PyObject* represents a Python time object.

type **PyDateTime_Delta**

This subtype of *PyObject* represents the difference between two datetime values.

PyTypeObject **PyDateTime_DateType**

This instance of *PyTypeObject* represents the Python date type; it is the same object as `datetime.date` in the Python layer.

PyTypeObject **PyDateTime_DateTimeType**

This instance of *PyTypeObject* represents the Python datetime type; it is the same object as `datetime.datetime` in the Python layer.

PyTypeObject **PyDateTime_TimeType**

This instance of *PyTypeObject* represents the Python time type; it is the same object as `datetime.time` in the Python layer.

PyTypeObject **PyDateTime_DeltaType**

This instance of *PyTypeObject* represents Python type for the difference between two datetime values; it is the same object as `datetime.timedelta` in the Python layer.

PyTypeObject **PyDateTime_TZInfoType**

This instance of *PyTypeObject* represents the Python time zone info type; it is the same object as `datetime.tzinfo` in the Python layer.

Macro for access to the UTC singleton:

PyObject ***PyDateTime_TimeZone_UTC**

Returns the time zone singleton representing UTC, the same object as `datetime.timezone.utc`.

Added in version 3.7.

Type-check macros:

int **PyDate_Check**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DateType* or a subtype of `PyDateTime_DateType`. *ob* must not be `NULL`. This function always succeeds.

int **PyDate_CheckExact**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DateType*. *ob* must not be `NULL`. This function always succeeds.

int **PyDateTime_Check**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DateTimeType* or a subtype of `PyDateTime_DateTimeType`. *ob* must not be `NULL`. This function always succeeds.

int **PyDateTime_CheckExact**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DateTimeType*. *ob* must not be `NULL`. This function always succeeds.

int **PyTime_Check**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_TimeType* or a subtype of `PyDateTime_TimeType`. *ob* must not be `NULL`. This function always succeeds.

int **PyTime_CheckExact**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_TimeType*. *ob* must not be `NULL`. This function always succeeds.

int **PyDelta_Check**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DeltaType* or a subtype of `PyDateTime_DeltaType`. *ob* must not be `NULL`. This function always succeeds.

int **PyDelta_CheckExact**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_DeltaType*. *ob* must not be `NULL`. This function always succeeds.

int **PyTZInfo_Check**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_TZInfoType* or a subtype of `PyDateTime_TZInfoType`. *ob* must not be `NULL`. This function always succeeds.

int **PyTZInfo_CheckExact**(*PyObject* *ob)

Return true if *ob* is of type *PyDateTime_TZInfoType*. *ob* must not be `NULL`. This function always succeeds.

Macros to create objects:

PyObject ***PyDate_FromDate**(int year, int month, int day)

Döndürdüğü değer: Yeni referans. Return a `datetime.date` object with the specified year, month and day.

PyObject ***PyDateTime_FromDateAndTime**(int year, int month, int day, int hour, int minute, int second, int usecond)

Döndürdüğü değer: Yeni referans. Return a `datetime.datetime` object with the specified year, month, day, hour, minute, second and microsecond.

PyObject ***PyDateTime_FromDateAndTimeAndFold**(int year, int month, int day, int hour, int minute, int second, int usecond, int fold)

Döndürdüğü değer: Yeni referans. Return a `datetime.datetime` object with the specified year, month, day, hour, minute, second, microsecond and fold.

Added in version 3.6.

PyObject ***PyTime_FromTime**(int hour, int minute, int second, int usecond)

Döndürdüğü değer: Yeni referans. Return a `datetime.time` object with the specified hour, minute, second and microsecond.

PyObject ***PyTime_FromTimeAndFold**(int hour, int minute, int second, int usecond, int fold)

Döndürdüğü değer: Yeni referans. Return a `datetime.time` object with the specified hour, minute, second, microsecond and fold.

Added in version 3.6.

PyObject ***PyDelta_FromDSU**(int days, int seconds, int useconds)

Döndürdüğü değer: Yeni referans. Return a `datetime.timedelta` object representing the given number of days, seconds and microseconds. Normalization is performed so that the resulting number of microseconds and seconds lie in the ranges documented for `datetime.timedelta` objects.

PyObject ***PyTimeZone_FromOffset**(*PyObject* *offset)

Döndürdüğü değer: Yeni referans. Return a `datetime.timezone` object with an unnamed fixed offset represented by the *offset* argument.

Added in version 3.7.

PyObject ***PyTimeZone_FromOffsetAndName**(*PyObject* *offset, *PyObject* *name)

Döndürdüğü değer: Yeni referans. Return a `datetime.timezone` object with a fixed offset represented by the *offset* argument and with tzname *name*.

Added in version 3.7.

Macros to extract fields from date objects. The argument must be an instance of *PyDateTime_Date*, including subclasses (such as *PyDateTime_DateTime*). The argument must not be `NULL`, and the type is not checked:

int **PyDateTime_GET_YEAR**(*PyDateTime_Date* *o)

Return the year, as a positive int.

int **PyDateTime_GET_MONTH**(*PyDateTime_Date* *o)

Return the month, as an int from 1 through 12.

int **PyDateTime_GET_DAY**(*PyDateTime_Date* *o)

Return the day, as an int from 1 through 31.

Macros to extract fields from datetime objects. The argument must be an instance of *PyDateTime_DateTime*, including subclasses. The argument must not be `NULL`, and the type is not checked:

int **PyDateTime_DATE_GET_HOUR**(*PyDateTime_DateTime* *o)

Return the hour, as an int from 0 through 23.

int **PyDateTime_DATE_GET_MINUTE**(*PyDateTime_DateTime* *o)

Return the minute, as an int from 0 through 59.

int **PyDateTime_DATE_GET_SECOND**(*PyDateTime_DateTime* *o)

Return the second, as an int from 0 through 59.

int **PyDateTime_DATE_GET_MICROSECOND**(*PyDateTime_DateTime* *o)

Return the microsecond, as an int from 0 through 999999.

int **PyDateTime_DATE_GET_FOLD**(*PyDateTime_DateTime* *o)

Return the fold, as an int from 0 through 1.

Added in version 3.6.

PyObject ***PyDateTime_DATE_GET_TZINFO**(*PyDateTime_DateTime* *o)

Return the tzinfo (which may be `None`).

Added in version 3.10.

Macros to extract fields from time objects. The argument must be an instance of *PyDateTime_Time*, including subclasses. The argument must not be `NULL`, and the type is not checked:

int **PyDateTime_TIME_GET_HOUR**(*PyDateTime_Time* *o)

Return the hour, as an int from 0 through 23.

int **PyDateTime_TIME_GET_MINUTE**(*PyDateTime_Time* *o)

Return the minute, as an int from 0 through 59.

int **PyDateTime_TIME_GET_SECOND**(*PyDateTime_Time* *o)

Return the second, as an int from 0 through 59.

int **PyDateTime_TIME_GET_MICROSECOND**(*PyDateTime_Time* *o)

Return the microsecond, as an int from 0 through 999999.

int **PyDateTime_TIME_GET_FOLD**(*PyDateTime_Time* *o)

Return the fold, as an int from 0 through 1.

Added in version 3.6.

PyObject ***PyDateTime_TIME_GET_TZINFO**(*PyDateTime_Time* *o)

Return the tzinfo (which may be `None`).

Added in version 3.10.

Macros to extract fields from time delta objects. The argument must be an instance of *PyDateTime_Delta*, including subclasses. The argument must not be `NULL`, and the type is not checked:

int **PyDateTime_DELTA_GET_DAYS**(*PyDateTime_Delta* *o)

Return the number of days, as an int from -999999999 to 999999999.

Added in version 3.3.

int **PyDateTime_DELTA_GET_SECONDS**(*PyDateTime_Delta* *o)

Return the number of seconds, as an int from 0 through 86399.

Added in version 3.3.

int **PyDateTime_DELTA_GET_MICROSECONDS**(*PyDateTime_Delta* *o)

Return the number of microseconds, as an int from 0 through 999999.

Added in version 3.3.

Macros for the convenience of modules implementing the DB API:

PyObject ***PyDateTime_FromTimestamp**(*PyObject* *args)

Döndürdüğü değer: Yeni referans. Create and return a new `datetime.datetime` object given an argument tuple suitable for passing to `datetime.datetime.fromtimestamp()`.

PyObject ***PyDate_FromTimestamp**(*PyObject* *args)

Döndürdüğü değer: Yeni referans. Create and return a new `datetime.date` object given an argument tuple suitable for passing to `datetime.date.fromtimestamp()`.

9.6.17 Objects for Type Hinting

Various built-in types for type hinting are provided. Currently, two types exist – GenericAlias and Union. Only `GenericAlias` is exposed to C.

PyObject ***Py_GenericAlias**(*PyObject* *origin, *PyObject* *args)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Create a GenericAlias object. Equivalent to calling the Python class `types.GenericAlias`. The *origin* and *args* arguments set the `GenericAlias`'s `__origin__` and `__args__` attributes respectively. *origin* should be a *PyTypeObject**, and *args* can be a *PyTupleObject** or any `PyObject*`. If *args* passed is not a tuple, a 1-tuple is automatically constructed and `__args__` is set to `(args,)`. Minimal checking is done for the arguments, so the function will succeed even if *origin* is not a type. The `GenericAlias`'s `__parameters__` attribute is constructed lazily from `__args__`. On failure, an exception is raised and `NULL` is returned.

Here's an example of how to make an extension type generic:

```
...
static PyMethodDef my_obj_methods[] = {
    // Other methods.
    ...
    {"__class_getitem__", Py_GenericAlias, METH_O|METH_CLASS, "See PEP 585"}
    ...
}
```

Ayrıca bakınız

The data model method `__class_getitem__()`.

Added in version 3.9.

PyTypeObject **Py_GenericAliasType**

Bir parçası Kararlı ABI *3.9 sürümünden beri.* The C type of the object returned by *Py_GenericAlias()*. Equivalent to `types.GenericAlias` in Python.

Added in version 3.9.

BÖLÜM 10

Initialization, Finalization, and Threads

See *Python Initialization Configuration* for details on how to configure the interpreter prior to initialization.

10.1 Before Python Initialization

In an application embedding Python, the `Py_Initialize()` function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

The following functions can be safely called before Python is initialized:

- Functions that initialize the interpreter:
  - `Py_Initialize()`
  - `Py_InitializeEx()`
  - `Py_InitializeFromConfig()`
  - `Py_BytesMain()`
  - `Py_Main()`
  - the runtime pre-initialization functions covered in *Python Initialization Configuration*
- Configuration functions:
  - `PyImport_AppendInittab()`
  - `PyImport_ExtendInittab()`
  - `PyInitFrozenExtensions()`
  - `PyMem_SetAllocator()`
  - `PyMem_SetupDebugHooks()`
  - `PyObject_SetArenaAllocator()`
  - `Py_SetProgramName()`
  - `Py_SetPythonHome()`
  - `PySys_ResetWarnOptions()`
  - the configuration functions covered in *Python Initialization Configuration*
- Informative functions:

  - *Py_IsInitialized()*
  - *PyMem_GetAllocator()*
  - *PyObject_GetArenaAllocator()*
  - *Py_GetBuildInfo()*
  - *Py_GetCompiler()*
  - *Py_GetCopyright()*
  - *Py_GetPlatform()*
  - *Py_GetVersion()*
  - *Py_IsInitialized()*
- Utilities:
  - *Py_DecodeLocale()*
  - the status reporting and utility functions covered in *Python Initialization Configuration*
- Memory allocators:
  - *PyMem_RawMalloc()*
  - *PyMem_RawRealloc()*
  - *PyMem_RawCalloc()*
  - *PyMem_RawFree()*
- Synchronization:
  - *PyMutex_Lock()*
  - *PyMutex_Unlock()*

Not

Despite their apparent similarity to some of the functions listed above, the following functions **should not be called** before the interpreter has been initialized: *Py_EncodeLocale()*, *Py_GetPath()*, *Py_GetPrefix()*, *Py_GetExecPrefix()*, *Py_GetProgramFullPath()*, *Py_GetPythonHome()*, *Py_GetProgramName()*, *PyEval_InitThreads()*, and *Py_RunMain()*.

10.2 Global configuration variables

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example, `-b` sets *Py_BytesWarningFlag* to 1 and `-bb` sets *Py_BytesWarningFlag* to 2.

int **Py_BytesWarningFlag**

This API is kept for backward compatibility: setting *PyConfig.bytes_warning* should be used instead, see *Python Initialization Configuration*.

Issue a warning when comparing `bytes` or `bytearray` with `str` or `bytes` with `int`. Issue an error if greater or equal to `2`.

Set by the `-b` option.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_DebugFlag**

This API is kept for backward compatibility: setting *PyConfig.parser_debug* should be used instead, see *Python Initialization Configuration*.

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the `-d` option and the `PYTHONDEBUG` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_DontWriteBytecodeFlag**

This API is kept for backward compatibility: setting *PyConfig.write_bytecode* should be used instead, see *Python Initialization Configuration*.

If set to non-zero, Python won't try to write `.pyc` files on the import of source modules.

Set by the `-B` option and the `PYTHONDONTWRITEBYTECODE` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_FrozenFlag**

This API is kept for backward compatibility: setting *PyConfig.pathconfig_warnings* should be used instead, see *Python Initialization Configuration*.

Suppress error messages when calculating the module search path in *Py_GetPath()*.

Private flag used by `_freeze_module` and `frozenmain` programs.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_HashRandomizationFlag**

This API is kept for backward compatibility: setting *PyConfig.hash_seed* and *PyConfig.use_hash_seed* should be used instead, see *Python Initialization Configuration*.

Set to `1` if the `PYTHONHASHSEED` environment variable is set to a non-empty string.

If the flag is non-zero, read the `PYTHONHASHSEED` environment variable to initialize the secret hash seed.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_IgnoreEnvironmentFlag**

This API is kept for backward compatibility: setting *PyConfig.use_environment* should be used instead, see *Python Initialization Configuration*.

Ignore all `PYTHON*` environment variables, e.g. `PYTHONPATH` and `PYTHONHOME`, that might be set.

Set by the `-E` and `-I` options.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_InspectFlag**

This API is kept for backward compatibility: setting *PyConfig.inspect* should be used instead, see *Python Initialization Configuration*.

When a script is passed as first argument or the `-c` option is used, enter interactive mode after executing the script or the command, even when `sys.stdin` does not appear to be a terminal.

Set by the `-i` option and the `PYTHONINSPECT` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_InteractiveFlag**

This API is kept for backward compatibility: setting *PyConfig.interactive* should be used instead, see *Python Initialization Configuration*.

Set by the `-i` option.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_IsolatedFlag**

This API is kept for backward compatibility: setting *PyConfig.isolated* should be used instead, see *Python Initialization Configuration*.

Run Python in isolated mode. In isolated mode `sys.path` contains neither the script's directory nor the user's site-packages directory.

Set by the `-I` option.

Added in version 3.4.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_LegacyWindowsFSEncodingFlag**

This API is kept for backward compatibility: setting *PyPreConfig.legacy_windows_fs_encoding* should be used instead, see *Python Initialization Configuration*.

If the flag is non-zero, use the `mbcs` encoding with `replace` error handler, instead of the UTF-8 encoding with `surrogatepass` error handler, for the *filesystem encoding and error handler*.

Set to `1` if the `PYTHONLEGACYWINDOWSFSENCODING` environment variable is set to a non-empty string.

See **PEP 529** for more details.

Availability: Windows.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_LegacyWindowsStdioFlag**

This API is kept for backward compatibility: setting *PyConfig.legacy_windows_stdio* should be used instead, see *Python Initialization Configuration*.

If the flag is non-zero, use `io.FileIO` instead of `io._WindowsConsoleIO` for `sys` standard streams.

Set to `1` if the `PYTHONLEGACYWINDOWSSTDIO` environment variable is set to a non-empty string.

See **PEP 528** for more details.

Availability: Windows.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_NoSiteFlag**

This API is kept for backward compatibility: setting *PyConfig.site_import* should be used instead, see *Python Initialization Configuration*.

Disable the import of the module `site` and the site-dependent manipulations of `sys.path` that it entails. Also disable these manipulations if `site` is explicitly imported later (call `site.main()` if you want them to be triggered).

Set by the `-S` option.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_NoUserSiteDirectory**

This API is kept for backward compatibility: setting *PyConfig.user_site_directory* should be used instead, see *Python Initialization Configuration*.

Don't add the `user site-packages directory` to `sys.path`.

Set by the `-s` and `-I` options, and the `PYTHONNOUSERSITE` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_OptimizeFlag**

This API is kept for backward compatibility: setting *PyConfig.optimization_level* should be used instead, see *Python Initialization Configuration*.

Set by the `-O` option and the `PYTHONOPTIMIZE` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_QuietFlag**

This API is kept for backward compatibility: setting `PyConfig.quiet` should be used instead, see *Python Initialization Configuration*.

Don't display the copyright and version messages even in interactive mode.

Set by the `-q` option.

Added in version 3.2.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_UnbufferedStdioFlag**

This API is kept for backward compatibility: setting `PyConfig.buffered_stdio` should be used instead, see *Python Initialization Configuration*.

Force the stdout and stderr streams to be unbuffered.

Set by the `-u` option and the `PYTHONUNBUFFERED` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

int **Py_VerboseFlag**

This API is kept for backward compatibility: setting `PyConfig.verbose` should be used instead, see *Python Initialization Configuration*.

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to `2`, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the `-v` option and the `PYTHONVERBOSE` environment variable.

Deprecated since version 3.12, will be removed in version 3.15.

10.3 Initializing and finalizing the interpreter

void **Py_Initialize**()

Bir parçası Kararlı ABI. Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (`sys.modules`), and creates the fundamental modules `builtins`, `__main__` and `sys`. It also initializes the module search path (`sys.path`). It does not set `sys.argv`; use the *Python Initialization Configuration* API for that. This is a no-op when called for a second time (without calling `Py_FinalizeEx()` first). There is no return value; it is a fatal error if the initialization fails.

Use `Py_InitializeFromConfig()` to customize the *Python Initialization Configuration*.

Not

On Windows, changes the console mode from `O_TEXT` to `O_BINARY`, which will also affect non-Python uses of the console using the C Runtime.

void **Py_InitializeEx**(int initsigs)

Bir parçası Kararlı ABI. This function works like `Py_Initialize()` if *initsigs* is `1`. If *initsigs* is `0`, it skips initialization registration of signal handlers, which may be useful when CPython is embedded as part of a larger application.

Use `Py_InitializeFromConfig()` to customize the *Python Initialization Configuration*.

PyStatus **Py_InitializeFromConfig**(const *PyConfig* *config)

Initialize Python from *config* configuration, as described in *Initialization with PyConfig*.

See the *Python Initialization Configuration* section for details on pre-initializing the interpreter, populating the runtime configuration structure, and querying the returned status structure.

int **Py_IsInitialized**()

Bir parçası Kararlı ABI. Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After `Py_FinalizeEx()` is called, this returns false until `Py_Initialize()` is called again.

int **Py_IsFinalizing**()

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Return true (non-zero) if the main Python interpreter is *shutting down*. Return false (zero) otherwise.

Added in version 3.13.

int **Py_FinalizeEx**()

Bir parçası Kararlı ABI *3.6 sürümünden beri.* Undo all initializations made by `Py_Initialize()` and subsequent use of Python/C API functions, and destroy all sub-interpreters (see `Py_NewInterpreter()` below) that were created and not yet destroyed since the last call to `Py_Initialize()`. This is a no-op when called for a second time (without calling `Py_Initialize()` again first).

Since this is the reverse of `Py_Initialize()`, it should be called in the same thread with the same interpreter active. That means the main thread and the main interpreter. This should never be called while `Py_RunMain()` is running.

Normally the return value is `0`. If there were errors during finalization (flushing buffered data), `-1` is returned.

Note that Python will do a best effort at freeing all memory allocated by the Python interpreter. Therefore, any C-Extension should make sure to correctly clean up all of the preveiously allocated PyObjects before using them in subsequent calls to `Py_Initialize()`. Otherwise it could introduce vulnerabilities and incorrect behavior.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

Bugs and caveats: The destruction of modules and objects in modules is done in random order; this may cause destructors (`__del__()` methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Interned strings will all be deallocated regardless of their reference count. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls `Py_Initialize()` and `Py_FinalizeEx()` more than once. `Py_FinalizeEx()` must not be called recursively from within itself. Therefore, it must not be called by any code that may be run as part of the interpreter shutdown process, such as `atexit` handlers, object finalizers, or any code that may be run while flushing the stdout and stderr files.

Raises an auditing event `cpython._PySys_ClearAuditHooks` with no arguments.

Added in version 3.6.

void **Py_Finalize**()

Bir parçası Kararlı ABI. This is a backwards-compatible version of `Py_FinalizeEx()` that disregards the return value.

int **Py_BytesMain**(int argc, char **argv)

Bir parçası Kararlı ABI *3.8 sürümünden beri.* Similar to `Py_Main()` but *argv* is an array of bytes strings, allowing the calling application to delegate the text decoding step to the CPython runtime.

Added in version 3.8.

int **Py_Main**(int argc, wchar_t **argv)

Bir parçası Kararlı ABI. The main program for the standard interpreter, encapsulating a full initialization/finalization cycle, as well as additional behaviour to implement reading configurations settings from the environment and command line, and then executing `__main__` in accordance with using-on-cmdline.

This is made available for programs which wish to support the full CPython command line interface, rather than just embedding a Python runtime in a larger application.

The *argc* and *argv* parameters are similar to those which are passed to a C program's `main()` function, except that the *argv* entries are first converted to `wchar_t` using *Py_DecodeLocale()*. It is also important to note that the argument list entries may be modified to point to strings other than those passed in (however, the contents of the strings pointed to by the argument list are not modified).

The return value is `2` if the argument list does not represent a valid Python command line, and otherwise the same as *Py_RunMain()*.

In terms of the CPython runtime configuration APIs documented in the *runtime configuration* section (and without accounting for error handling), `Py_Main` is approximately equivalent to:

```
PyConfig config;
PyConfig_InitPythonConfig(&config);
PyConfig_SetArgv(&config, argc, argv);
Py_InitializeFromConfig(&config);
PyConfig_Clear(&config);

Py_RunMain();
```

In normal usage, an embedding application will call this function *instead* of calling *Py_Initialize()*, *Py_InitializeEx()* or *Py_InitializeFromConfig()* directly, and all settings will be applied as described elsewhere in this documentation. If this function is instead called *after* a preceding runtime initialization API call, then exactly which environmental and command line configuration settings will be updated is version dependent (as it depends on which settings correctly support being modified after they have already been set once when the runtime was first initialized).

int **Py_RunMain**(void)

Executes the main module in a fully configured CPython runtime.

Executes the command (*PyConfig.run_command*), the script (*PyConfig.run_filename*) or the module (*PyConfig.run_module*) specified on the command line or in the configuration. If none of these values are set, runs the interactive Python prompt (REPL) using the `__main__` module's global namespace.

If *PyConfig.inspect* is not set (the default), the return value will be `0` if the interpreter exits normally (that is, without raising an exception), the exit status of an unhandled `SystemExit`, or `1` for any other unhandled exception.

If *PyConfig.inspect* is set (such as when the `-i` option is used), rather than returning when the interpreter exits, execution will instead resume in an interactive Python prompt (REPL) using the `__main__` module's global namespace. If the interpreter exited with an exception, it is immediately raised in the REPL session. The function return value is then determined by the way the *REPL session* terminates: `0`, `1`, or the status of a `SystemExit`, as specified above.

This function always finalizes the Python interpreter before it returns.

See *Python Configuration* for an example of a customized Python that always runs in isolated mode using *Py_RunMain()*.

int **PyUnstable_AtExit**(*PyInterpreterState* *interp, void (*func)(void*), void *data)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Register an `atexit` callback for the target interpreter *interp*. This is similar to *Py_AtExit()*, but takes an explicit interpreter and data pointer for the callback.

There must be an *attached thread state* for *interp*.

Added in version 3.13.

10.4 Process-wide parameters

void **Py_SetProgramName**(const wchar_t *name)

Bir parçası Kararlı ABI. This API is kept for backward compatibility: setting *PyConfig.program_name* should be used instead, see *Python Initialization Configuration*.

This function should be called before *Py_Initialize()* is called for the first time, if it is called at all. It tells the interpreter the value of the `argv[0]` argument to the `main()` function of the program (converted to wide characters). This is used by *Py_GetPath()* and some other functions below to find the Python run-time libraries relative to the interpreter executable. The default value is `'python'`. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use *Py_DecodeLocale()* to decode a bytes string to get a `wchar_t*` string.

Deprecated since version 3.11, will be removed in version 3.15.

wchar_t ***Py_GetProgramName**()

Bir parçası Kararlı ABI. Return the program name set with *PyConfig.program_name*, or the default. The returned string points into static storage; the caller should not modify its value.

This function should not be called before *Py_Initialize()*, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before *Py_Initialize()*.

Deprecated since version 3.13, will be removed in version 3.15: Use *PyConfig_Get("executable")* (`sys.executable`) instead.

wchar_t ***Py_GetPrefix**()

Bir parçası Kararlı ABI. Return the *prefix* for installed platform-independent files. This is derived through a number of complicated rules from the program name set with *PyConfig.program_name* and some environment variables; for example, if the program name is `'/usr/local/bin/python'`, the prefix is `'/usr/local'`. The returned string points into static storage; the caller should not modify its value. This corresponds to the **prefix** variable in the top-level `Makefile` and the `--prefix` argument to the **configure** script at build time. The value is available to Python code as `sys.base_prefix`. It is only useful on Unix. See also the next function.

This function should not be called before *Py_Initialize()*, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before *Py_Initialize()*.

Deprecated since version 3.13, will be removed in version 3.15: Use *PyConfig_Get("base_prefix")* (`sys.base_prefix`) instead. Use *PyConfig_Get("prefix")* (`sys.prefix`) if virtual environments need to be handled.

wchar_t ***Py_GetExecPrefix**()

Bir parçası Kararlı ABI. Return the *exec-prefix* for installed platform-*dependent* files. This is derived through a number of complicated rules from the program name set with *PyConfig.program_name* and some environment variables; for example, if the program name is `'/usr/local/bin/python'`, the exec-prefix is `'/usr/local'`. The returned string points into static storage; the caller should not modify its value. This corresponds to the **exec_prefix** variable in the top-level `Makefile` and the `--exec-prefix` argument to the **configure** script at build time. The value is available to Python code as `sys.base_exec_prefix`. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the `/usr/local/plat` subtree while platform independent may be installed in `/usr/local`.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share `/usr/local` between platforms while having `/usr/local/plat` be a different filesystem for each platform.

This function should not be called before *`Py_Initialize()`*, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before *`Py_Initialize()`*.

Deprecated since version 3.13, will be removed in version 3.15: Use *`PyConfig_Get("base_exec_prefix")`* (`sys.base_exec_prefix`) instead. Use *`PyConfig_Get("exec_prefix")`* (`sys.exec_prefix`) if virtual environments need to be handled.

wchar_t ***Py_GetProgramFullPath**()*

Bir parçası Kararlı ABI. Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by *`PyConfig.program_name`*). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.executable`.

This function should not be called before *`Py_Initialize()`*, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before *`Py_Initialize()`*.

Deprecated since version 3.13, will be removed in version 3.15: Use *`PyConfig_Get("executable")`* (`sys.executable`) instead.

wchar_t ***Py_GetPath**()*

Bir parçası Kararlı ABI. Return the default module search path; this is computed from the program name (set by *`PyConfig.program_name`*) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is `':'` on Unix and macOS, `';'` on Windows. The returned string points into static storage; the caller should not modify its value. The list `sys.path` is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

This function should not be called before *`Py_Initialize()`*, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before *`Py_Initialize()`*.

Deprecated since version 3.13, will be removed in version 3.15: Use *`PyConfig_Get("module_search_paths")`* (`sys.path`) instead.

const char ***Py_GetVersion**()*

Bir parçası Kararlı ABI. Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.version`.

See also the *`Py_Version`* constant.

const char ***Py_GetPlatform**()*

Bir parçası Kararlı ABI. Return the platform identifier for the current platform. On Unix, this is formed from the "official" name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is `'sunos5'`. On macOS, it is `'darwin'`. On Windows, it is `'win'`. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.platform`.

const char *Py_GetCopyright()

Bir parçası Kararlı ABI. Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as `sys.copyright`.

const char *Py_GetCompiler()

Bir parçası Kararlı ABI. Return an indication of the compiler used to build the current Python version, in square brackets, for example:

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

const char *Py_GetBuildInfo()

Bir parçası Kararlı ABI. Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug  1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable `sys.version`.

void PySys_SetArgvEx(int argc, wchar_t **argv, int updatepath)

Bir parçası Kararlı ABI. This API is kept for backward compatibility: setting *PyConfig.argv*, *PyConfig.parse_argv* and *PyConfig.safe_path* should be used instead, see *Python Initialization Configuration*.

Set `sys.argv` based on *argc* and *argv*. These parameters are similar to those passed to the program's `main()` function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in *argv* can be an empty string. If this function fails to initialize `sys.argv`, a fatal condition is signalled using *Py_FatalError()*.

If *updatepath* is zero, this is all the function does. If *updatepath* is non-zero, the function also modifies `sys.path` according to the following algorithm:

- If the name of an existing script is passed in `argv[0]`, the absolute path of the directory where the script is located is prepended to `sys.path`.
- Otherwise (that is, if *argc* is `0` or `argv[0]` doesn't point to an existing file name), an empty string is prepended to `sys.path`, which is the same as prepending the current working directory (`"."`).

Use *Py_DecodeLocale()* to decode a bytes string to get a `wchar_t*` string.

See also *PyConfig.orig_argv* and *PyConfig.argv* members of the *Python Initialization Configuration*.

Not

It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass `0` as *updatepath*, and update `sys.path` themselves if desired. See **CVE 2008-5983**.

On versions before 3.1.3, you can achieve the same effect by manually popping the first `sys.path` element after having called *PySys_SetArgv()*, for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

Added in version 3.1.3.

Deprecated since version 3.11, will be removed in version 3.15.

void **PySys_SetArgv**(int argc, wchar_t **argv)

Bir parçası Kararlı ABI. This API is kept for backward compatibility: setting `PyConfig.argv` and `PyConfig.parse_argv` should be used instead, see *Python Initialization Configuration*.

This function works like `PySys_SetArgvEx()` with *updatepath* set to `1` unless the **python** interpreter was started with the `-I`.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

See also `PyConfig.orig_argv` and `PyConfig.argv` members of the *Python Initialization Configuration*.

3.4 sürümünde değişti: The *updatepath* value depends on `-I`.

Deprecated since version 3.11, will be removed in version 3.15.

void **Py_SetPythonHome**(const wchar_t *home)

Bir parçası Kararlı ABI. This API is kept for backward compatibility: setting `PyConfig.home` should be used instead, see *Python Initialization Configuration*.

Set the default "home" directory, that is, the location of the standard Python libraries. See `PYTHONHOME` for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use `Py_DecodeLocale()` to decode a bytes string to get a `wchar_t*` string.

Deprecated since version 3.11, will be removed in version 3.15.

wchar_t ***Py_GetPythonHome**()

Bir parçası Kararlı ABI. Return the default "home", that is, the value set by `PyConfig.home`, or the value of the `PYTHONHOME` environment variable if it is set.

This function should not be called before `Py_Initialize()`, otherwise it returns `NULL`.

3.10 sürümünde değişti: It now returns `NULL` if called before `Py_Initialize()`.

Deprecated since version 3.13, will be removed in version 3.15: Use `PyConfig_Get("home")` or the `PYTHONHOME` environment variable instead.

10.5 Thread State and the Global Interpreter Lock

Unless on a *free-threaded* build of *CPython*, the Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see `sys.setswitchinterval()`). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called `PyThreadState`, known as a *thread state*. Each OS thread has a thread-local pointer to a `PyThreadState`; a thread state referenced by this pointer is considered to be *attached*.

A thread can only have one *attached thread state* at a time. An attached thread state is typically analogous with holding the *GIL*, except on *free-threaded* builds. On builds with the *GIL* enabled, *attaching* a thread state will block until the *GIL* can be acquired. However, even on builds with the *GIL* disabled, it is still required to have an attached thread state to call most of the C API.

In general, there will always be an *attached thread state* when using Python's C API. Only in some specific cases (such as in a `Py_BEGIN_ALLOW_THREADS` block) will the thread not have an attached thread state. If uncertain, check if `PyThreadState_GetUnchecked()` returns `NULL`.

10.5.1 Detaching the thread state from extension code

Most extension code manipulating the *thread state* has the following simple structure:

```
Save the thread state in a local variable.
... Do some blocking I/O operation ...
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The *Py_BEGIN_ALLOW_THREADS* macro opens a new block and declares a hidden local variable; the *Py_END_ALLOW_THREADS* macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work:

The *attached thread state* holds the *GIL* for the entire interpreter. When detaching the *attached thread state*, the *GIL* is released, allowing other threads to attach a thread state to their own thread, thus getting the *GIL* and can start executing. The pointer to the prior *attached thread state* is stored as a local variable. Upon reaching *Py_END_ALLOW_THREADS*, the thread state that was previously *attached* is passed to *PyEval_RestoreThread()*. This function will block until another releases its *thread state*, thus allowing the old *thread state* to get re-attached and the C API can be called again.

For *free-threaded* builds, the *GIL* is normally out of the question, but detaching the *thread state* is still required for blocking I/O and long operations. The difference is that threads don't have to wait for the *GIL* to be released to attach their thread state, allowing true multi-core parallelism.

Not

Calling system I/O functions is the most common use case for detaching the *thread state*, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard `zlib` and `hashlib` modules detach the *thread state* when compressing or hashing data.

10.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the `threading` module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the *GIL*, because they don't have an *attached thread state*.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating an *attached thread state* before you can start using the Python/C API. When you are done, you should detach the *thread state*, and finally free it.

The *PyGILState_Ensure()* and *PyGILState_Release()* functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the `PyGILState_*` functions assume there is only one global interpreter (created automatically by *`Py_Initialize()`*). Python supports the creation of additional interpreters (using *`Py_NewInterpreter()`*), but mixing multiple interpreters and the `PyGILState_*` API is unsupported. This is because *`PyGILState_Ensure()`* and similar functions default to *attaching* a *thread state* for the main interpreter, meaning that the thread can't safely interact with the calling subinterpreter.

10.5.3 Supporting subinterpreters in non-Python threads

If you would like to support subinterpreters with non-Python created threads, you must use the `PyThreadState_*` API instead of the traditional `PyGILState_*` API.

In particular, you must store the interpreter state from the calling function and pass it to *`PyThreadState_New()`*, which will ensure that the *thread state* is targeting the correct interpreter:

```
/* The return value of PyInterpreterState_Get() from the
   function that created this thread. */
PyInterpreterState *interp = ThreadData->interp;
PyThreadState *tstate = PyThreadState_New(interp);
PyThreadState_Swap(tstate);

/* GIL of the subinterpreter is now held.
   Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Destroy the thread state. No Python API allowed beyond this point. */
PyThreadState_Clear(tstate);
PyThreadState_DeleteCurrent();
```

10.5.4 Cautions about fork()

Another important thing to note about threads is their behaviour in the face of the C `fork()` call. On most systems with `fork()`, after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the "current" thread remains means any locks held by other threads will never be released. Python solves this for `os.fork()` by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as `pthread_atfork()` would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling `fork()` directly rather than through `os.fork()` (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork. *`PyOS_AfterFork_Child()`* tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which `os.fork()` does. This means finalizing all other *`PyThreadState`* objects belonging to the current interpreter and all other *`PyInterpreterState`* objects. Due to this and the special nature of the *"main" interpreter*, `fork()` should only be called in that interpreter's "main" thread, where the CPython global runtime was originally initialized. The only exception is if `exec()` will be called immediately after.

10.5.5 Cautions regarding runtime finalization

In the late stage of *interpreter shutdown*, after attempting to wait for non-daemon threads to exit (though this can be interrupted by `KeyboardInterrupt`) and running the `atexit` functions, the runtime is marked as *finalizing*: `Py_IsFinalizing()` and `sys.is_finalizing()` return true. At this point, only the *finalization thread* that initiated finalization (typically the main thread) is allowed to acquire the *GIL*.

If any thread, other than the finalization thread, attempts to attach a *thread state* during finalization, either explicitly or implicitly, the thread enters **a permanently blocked state** where it remains until the program exits. In most cases this is harmless, but this can result in deadlock if a later stage of finalization attempts to acquire a lock owned by the blocked thread, or otherwise waits on the blocked thread.

Gross? Yes. This prevents random crashes and/or unexpectedly skipped C++ finalizations further up the call stack when such threads were forcibly exited here in CPython 3.13 and earlier. The CPython runtime *thread state* C APIs have never had any error reporting or handling expectations at *thread state* attachment time that would've allowed for graceful exit from this situation. Changing that would require new stable C APIs and rewriting the majority of C code in the CPython ecosystem to use those with error handling.

10.5.6 High-level API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

type **PyInterpreterState**

Bir parçası Sınırlı API *(bir opak yapı olarak).* This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

3.12 sürümünde değişti: **PEP 684** introduced the possibility of a *per-interpreter GIL*. See `Py_NewInterpreterFromConfig()`.

type **PyThreadState**

Bir parçası Sınırlı API *(bir opak yapı olarak).* This data structure represents the state of a single thread. The only public data member is:

PyInterpreterState ***interp**

This thread's interpreter state.

void **PyEval_InitThreads**()

Bir parçası Kararlı ABI. Deprecated function which does nothing.

In Python 3.6 and older, this function created the GIL if it didn't exist.

3.9 sürümünde değişti: The function now does nothing.

3.7 sürümünde değişti: This function is now called by `Py_Initialize()`, so you don't have to call it yourself anymore.

3.2 sürümünde değişti: This function cannot be called before `Py_Initialize()` anymore.

3.9 sürümünden beri kullanım dışı.

PyThreadState ***PyEval_SaveThread**()

Bir parçası Kararlı ABI. Detach the *attached thread state* and return it. The thread will have no *thread state* upon returning.

void **PyEval_RestoreThread**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Set the *attached thread state* to *tstate*. The passed *thread state* **should not** be *attached*, otherwise deadlock ensues. *tstate* will be attached upon returning.

> **Not**
>
> Calling this function from a thread when the runtime is finalizing will hang the thread until the program exits, even if the thread was not created by Python. Refer to *Cautions regarding runtime finalization* for more details.

3.14 sürümünde değişti: Hangs the current thread, rather than terminating it, if called while the interpreter is finalizing.

PyThreadState ***PyThreadState_Get**()

Bir parçası Kararlı ABI. Return the *attached thread state*. If the thread has no attached thread state, (such as when inside of `Py_BEGIN_ALLOW_THREADS` block), then this issues a fatal error (so that the caller needn't check for `NULL`).

See also `PyThreadState_GetUnchecked()`.

PyThreadState ***PyThreadState_GetUnchecked**()

Similar to `PyThreadState_Get()`, but don't kill the process with a fatal error if it is NULL. The caller is responsible to check if the result is NULL.

Added in version 3.13: In Python 3.5 to 3.12, the function was private and known as `_PyThreadState_UncheckedGet()`.

PyThreadState ***PyThreadState_Swap**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Set the *attached thread state* to *tstate*, and return the *thread state* that was attached prior to calling.

This function is safe to call without an *attached thread state*; it will simply return `NULL` indicating that there was no prior thread state.

> **Not**
>
> Similar to `PyGILState_Ensure()`, this function will hang the thread if the runtime is finalizing.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

PyGILState_STATE **PyGILState_Ensure**()

Bir parçası Kararlı ABI. Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the *attached thread state*. This may be called as many times as desired by a thread as long as each call is matched with a call to `PyGILState_Release()`. In general, other thread-related APIs may be used between `PyGILState_Ensure()` and `PyGILState_Release()` calls as long as the thread state is restored to its previous state before the Release(). For example, normal usage of the `Py_BEGIN_ALLOW_THREADS` and `Py_END_ALLOW_THREADS` macros is acceptable.

The return value is an opaque "handle" to the *attached thread state* when `PyGILState_Ensure()` was called, and must be passed to `PyGILState_Release()` to ensure Python is left in the same state. Even though recursive calls are allowed, these handles *cannot* be shared - each unique call to `PyGILState_Ensure()` must save the handle for its call to `PyGILState_Release()`.

When the function returns, there will be an *attached thread state* and the thread will be able to call arbitrary Python code. Failure is a fatal error.

> **Uyarı**
>
> Calling this function when the runtime is finalizing is unsafe. Doing so will either hang the thread until the program ends, or fully crash the interpreter in rare cases. Refer to *Cautions regarding runtime finalization* for more details.

3.14 sürümünde değişti: Hangs the current thread, rather than terminating it, if called while the interpreter is finalizing.

void **PyGILState_Release**(PyGILState_STATE)

Bir parçası Kararlı ABI. Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding *PyGILState_Ensure()* call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to *PyGILState_Ensure()* must be matched by a call to *PyGILState_Release()* on the same thread.

PyThreadState ***PyGILState_GetThisThreadState**()

Bir parçası Kararlı ABI. Get the *attached thread state* for this thread. May return `NULL` if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

Not

This function does not account for *thread states* created by something other than *PyGILState_Ensure()* (such as *PyThreadState_New()*). Prefer *PyThreadState_Get()* or *PyThreadState_GetUnchecked()* for most cases.

int **PyGILState_Check**()

Return `1` if the current thread is holding the *GIL* and `0` otherwise. This function can be called from any thread at any time. Only if it has had its *thread state* initialized via *PyGILState_Ensure()* will it return `1`. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the *GIL* is locked can allow the caller to perform sensitive actions or otherwise behave differently.

Not

If the current Python process has ever created a subinterpreter, this function will *always* return `1`. Prefer *PyThreadState_GetUnchecked()* for most cases.

Added in version 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

Py_BEGIN_ALLOW_THREADS

Bir parçası Kararlı ABI. This macro expands to `{ PyThreadState *_save; _save = PyEval_SaveThread();`. Note that it contains an opening brace; it must be matched with a following *Py_END_ALLOW_THREADS* macro. See above for further discussion of this macro.

Py_END_ALLOW_THREADS

Bir parçası Kararlı ABI. This macro expands to `PyEval_RestoreThread(_save); }`. Note that it contains a closing brace; it must be matched with an earlier *Py_BEGIN_ALLOW_THREADS* macro. See above for further discussion of this macro.

Py_BLOCK_THREADS

Bir parçası Kararlı ABI. This macro expands to `PyEval_RestoreThread(_save);`: it is equivalent to *Py_END_ALLOW_THREADS* without the closing brace.

Py_UNBLOCK_THREADS

Bir parçası Kararlı ABI. This macro expands to `_save = PyEval_SaveThread();`: it is equivalent to *Py_BEGIN_ALLOW_THREADS* without the opening brace and variable declaration.

10.5.7 Low-level API

All of the following functions must be called after *Py_Initialize()*.

3.7 sürümünde değişti: *Py_Initialize()* now initializes the *GIL* and sets an *attached thread state*.

PyInterpreterState ***PyInterpreterState_New**()

Bir parçası Kararlı ABI. Create a new interpreter state object. An *attached thread state* is not needed, but may optionally exist if it is necessary to serialize calls to this function.

Raises an auditing event `cpython.PyInterpreterState_New` with no arguments.

void **PyInterpreterState_Clear**(*PyInterpreterState* *interp)

Bir parçası Kararlı ABI. Reset all information in an interpreter state object. There must be an *attached thread state* for the interpreter.

Raises an auditing event `cpython.PyInterpreterState_Clear` with no arguments.

void **PyInterpreterState_Delete**(*PyInterpreterState* *interp)

Bir parçası Kararlı ABI. Destroy an interpreter state object. There **should not** be an *attached thread state* for the target interpreter. The interpreter state must have been reset with a previous call to *PyInterpreterState_Clear()*.

PyThreadState ***PyThreadState_New**(*PyInterpreterState* *interp)

Bir parçası Kararlı ABI. Create a new thread state object belonging to the given interpreter object. An *attached thread state* is not needed.

void **PyThreadState_Clear**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Reset all information in a *thread state* object. *tstate* must be *attached*

3.9 sürümünde değişti: This function now calls the `PyThreadState.on_delete` callback. Previously, that happened in *PyThreadState_Delete()*.

3.13 sürümünde değişti: The `PyThreadState.on_delete` callback was removed.

void **PyThreadState_Delete**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Destroy a *thread state* object. *tstate* should not be *attached* to any thread. *tstate* must have been reset with a previous call to *PyThreadState_Clear()*.

void **PyThreadState_DeleteCurrent**(void)

Detach the *attached thread state* (which must have been reset with a previous call to *PyThreadState_Clear()*) and then destroy it.

No *thread state* will be *attached* upon returning.

PyFrameObject ***PyThreadState_GetFrame**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Get the current frame of the Python thread state *tstate*.

Return a *strong reference*. Return `NULL` if no frame is currently executing.

See also *PyEval_GetFrame()*.

tstate must not be `NULL`, and must be *attached*.

Added in version 3.9.

uint64_t **PyThreadState_GetID**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Get the unique *thread state* identifier of the Python thread state *tstate*.

tstate must not be `NULL`, and must be *attached*.

Added in version 3.9.

PyInterpreterState ***PyThreadState_GetInterpreter**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Get the interpreter of the Python thread state *tstate*.

tstate must not be `NULL`, and must be *attached*.

Added in version 3.9.

void **PyThreadState_EnterTracing**(*PyThreadState* *tstate)

Suspend tracing and profiling in the Python thread state *tstate*.

Resume them using the `PyThreadState_LeaveTracing()` function.

Added in version 3.11.

void **PyThreadState_LeaveTracing**(*PyThreadState* *tstate)

Resume tracing and profiling in the Python thread state *tstate* suspended by the `PyThreadState_EnterTracing()` function.

See also `PyEval_SetTrace()` and `PyEval_SetProfile()` functions.

Added in version 3.11.

PyInterpreterState ***PyInterpreterState_Get**(void)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Get the current interpreter.

Issue a fatal error if there no *attached thread state*. It cannot return NULL.

Added in version 3.9.

int64_t **PyInterpreterState_GetID**(*PyInterpreterState* *interp)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return the interpreter's unique ID. If there was any error in doing so then `-1` is returned and an error is set.

The caller must have an *attached thread state*.

Added in version 3.7.

PyObject ***PyInterpreterState_GetDict**(*PyInterpreterState* *interp)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI *3.8 sürümünden beri.* Return a dictionary in which interpreter-specific data may be stored. If this function returns `NULL` then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for `PyModule_GetState()`, which extensions should use to store interpreter-specific state information.

The returned dictionary is borrowed from the interpreter and is valid until interpreter shutdown.

Added in version 3.8.

typedef *PyObject* *(***_PyFrameEvalFunction**)(*PyThreadState* *tstate, *_PyInterpreterFrame* *frame, int throwflag)

Type of a frame evaluation function.

The *throwflag* parameter is used by the `throw()` method of generators: if non-zero, handle the current exception.

3.9 sürümünde değişti: The function now takes a *tstate* parameter.

3.11 sürümünde değişti: The *frame* parameter changed from `PyFrameObject*` to `_PyInterpreterFrame*`.

_PyFrameEvalFunction ***_PyInterpreterState_GetEvalFrameFunc**(*PyInterpreterState* *interp)

Get the frame evaluation function.

See the **PEP 523** "Adding a frame evaluation API to CPython".

Added in version 3.9.

void **_PyInterpreterState_SetEvalFrameFunc**(*PyInterpreterState* *interp, *_PyFrameEvalFunction* eval_frame)

Set the frame evaluation function.

See the **PEP 523** "Adding a frame evaluation API to CPython".

Added in version 3.9.

PyObject ***PyThreadState_GetDict**()

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no *thread state* is *attached*. If this function returns `NULL`, no exception has been raised and the caller should assume no thread state is attached.

int **PyThreadState_SetAsyncExc**(unsigned long id, *PyObject* *exc)

Bir parçası Kararlı ABI. Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with an *attached thread state*. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is `NULL`, the pending exception (if any) for the thread is cleared. This raises no exceptions.

3.7 sürümünde değişti: The type of the *id* parameter changed from `long` to `unsigned long`.

void **PyEval_AcquireThread**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. *Attach tstate* to the current thread, which must not be `NULL` or already *attached*.

The calling thread must not already have an *attached thread state*.

> **Not**
>
> Calling this function from a thread when the runtime is finalizing will hang the thread until the program exits, even if the thread was not created by Python. Refer to *Cautions regarding runtime finalization* for more details.

3.8 sürümünde değişti: Updated to be consistent with *PyEval_RestoreThread()*, *Py_END_ALLOW_THREADS()*, and *PyGILState_Ensure()*, and terminate the current thread if called while the interpreter is finalizing.

3.14 sürümünde değişti: Hangs the current thread, rather than terminating it, if called while the interpreter is finalizing.

PyEval_RestoreThread() is a higher-level function which is always available (even when threads have not been initialized).

void **PyEval_ReleaseThread**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Detach the *attached thread state*. The *tstate* argument, which must not be `NULL`, is only used to check that it represents the *attached thread state* — if it isn't, a fatal error is reported.

PyEval_SaveThread() is a higher-level function which is always available (even when threads have not been initialized).

10.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The "main" interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The *PyInterpreterState_Main()* function returns a pointer to its state.

You can switch between sub-interpreters using the *PyThreadState_Swap()* function. You can create and destroy them using the following functions:

type **PyInterpreterConfig**

Structure containing most parameters to configure a sub-interpreter. Its values are used only in *Py_NewInterpreterFromConfig()* and never modified by the runtime.

Added in version 3.12.

Structure fields:

int **use_main_obmalloc**

If this is `0` then the sub-interpreter will use its own "object" allocator state. Otherwise it will use (share) the main interpreter's.

If this is `0` then *check_multi_interp_extensions* must be `1` (non-zero). If this is `1` then *gil* must not be *PyInterpreterConfig_OWN_GIL*.

int **allow_fork**

If this is `0` then the runtime will not support forking the process in any thread where the sub-interpreter is currently active. Otherwise fork is unrestricted.

Note that the `subprocess` module still works when fork is disallowed.

int **allow_exec**

If this is `0` then the runtime will not support replacing the current process via exec (e.g. `os.execv()`) in any thread where the sub-interpreter is currently active. Otherwise exec is unrestricted.

Note that the `subprocess` module still works when exec is disallowed.

int **allow_threads**

If this is `0` then the sub-interpreter's `threading` module won't create threads. Otherwise threads are allowed.

int **allow_daemon_threads**

If this is `0` then the sub-interpreter's `threading` module won't create daemon threads. Otherwise daemon threads are allowed (as long as *allow_threads* is non-zero).

int **check_multi_interp_extensions**

If this is `0` then all extension modules may be imported, including legacy (single-phase init) modules, in any thread where the sub-interpreter is currently active. Otherwise only multi-phase init extension modules (see **PEP 489**) may be imported. (Also see *Py_mod_multiple_interpreters*.)

This must be `1` (non-zero) if *use_main_obmalloc* is `0`.

int **gil**

This determines the operation of the GIL for the sub-interpreter. It may be one of the following:

PyInterpreterConfig_DEFAULT_GIL

Use the default selection (*PyInterpreterConfig_SHARED_GIL*).

PyInterpreterConfig_SHARED_GIL

Use (share) the main interpreter's GIL.

PyInterpreterConfig_OWN_GIL

Use the sub-interpreter's own GIL.

If this is *PyInterpreterConfig_OWN_GIL* then *PyInterpreterConfig.use_main_obmalloc* must be `0`.

PyStatus **Py_NewInterpreterFromConfig**(*PyThreadState* **tstate_p, const *PyInterpreterConfig* *config)

Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules `builtins`, `__main__` and `sys`. The table of loaded modules (`sys.modules`) and the module search path (`sys.path`) are also separate. The new environment has no `sys.argv` variable. It

has new standard I/O stream file objects `sys.stdin`, `sys.stdout` and `sys.stderr` (however these refer to the same underlying file descriptors).

The given *config* controls the options with which the interpreter is initialized.

Upon success, *tstate_p* will be set to the first *thread state* created in the new sub-interpreter. This thread state is *attached*. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, *tstate_p* is set to `NULL`; no exception is set since the exception state is stored in the *attached thread state*, which might not exist.

Like all other Python/C API functions, an *attached thread state* must be present before calling this function, but it might be detached upon returning. On success, the returned thread state will be *attached*. If the sub-interpreter is created with its own *GIL* then the *attached thread state* of the calling interpreter will be detached. When the function returns, the new interpreter's *thread state* will be *attached* to the current thread and the previous interpreter's *attached thread state* will remain detached.

Added in version 3.12.

Sub-interpreters are most effective when isolated from each other, with certain functionality restricted:

```
PyInterpreterConfig config = {
    .use_main_obmalloc = 0,
    .allow_fork = 0,
    .allow_exec = 0,
    .allow_threads = 1,
    .allow_daemon_threads = 0,
    .check_multi_interp_extensions = 1,
    .gil = PyInterpreterConfig_OWN_GIL,
};
PyThreadState *tstate = NULL;
PyStatus status = Py_NewInterpreterFromConfig(&tstate, &config);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}
```

Note that the config is used only briefly and does not get modified. During initialization the config's values are converted into various `PyInterpreterState` values. A read-only copy of the config may be stored internally on the `PyInterpreterState`.

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. `PyModule_FromDefAndSpec()`, a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g. `PyModule_Create()`, the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's `init` function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see *Bugs and caveats* below).

  Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling `Py_FinalizeEx()` and `Py_Initialize()`; in that case, the extension's `initmodule` function *is* called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

PyThreadState ***Py_NewInterpreter**(void)

Bir parçası Kararlı ABI. Create a new sub-interpreter. This is essentially just a wrapper around `Py_NewInterpreterFromConfig()` with a config that preserves the existing behavior. The result is an unisolated sub-interpreter that shares the main interpreter's GIL, allows fork/exec, allows daemon threads, and allows single-phase init modules.

void **Py_EndInterpreter**(*PyThreadState* *tstate)

Bir parçası Kararlı ABI. Destroy the (sub-)interpreter represented by the given *thread state*. The given thread state must be *attached*. When the call returns, there will be no *attached thread state*. All thread states associated with this interpreter are destroyed.

`Py_FinalizeEx()` will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

10.6.1 A Per-Interpreter GIL

Using `Py_NewInterpreterFromConfig()` you can create a sub-interpreter that is completely isolated from other interpreters, including having its own GIL. The most important benefit of this isolation is that such an interpreter can execute Python code without being blocked by other interpreters or blocking any others. Thus a single Python process can truly take advantage of multiple CPU cores when running Python code. The isolation also encourages a different approach to concurrency than that of just using threads. (See **PEP 554** and **PEP 684**.)

Using an isolated interpreter requires vigilance in preserving that isolation. That especially means not sharing any objects or mutable state without guarantees about thread-safety. Even objects that are otherwise immutable (e.g. `None`, `(1, 5)`) can't normally be shared because of the refcount. One simple but less-efficient approach around this is to use a global lock around all use of some state (or object). Alternately, effectively immutable objects (like integers or strings) can be made safe in spite of their refcounts by making them *immortal*. In fact, this has been done for the builtin singletons, small integers, and a number of other builtin objects.

If you preserve isolation then you will have access to proper multi-core computing without the complications that come with free-threading. Failure to preserve isolation will expose you to the full consequences of free-threading, including races and hard-to-debug crashes.

Aside from that, one of the main challenges of using multiple isolated interpreters is how to communicate between them safely (not break isolation) and efficiently. The runtime and stdlib do not provide any standard approach to this yet. A future stdlib module would help mitigate the effort of preserving isolation and expose effective tools for communicating (and sharing) data between interpreters.

Added in version 3.12.

10.6.2 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect — for example, using low-level file operations like `os.close()` they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with `PyGILState_*` APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching `PyGILState_Ensure()` and `PyGILState_Release()` calls. Furthermore, extensions (such as `ctypes`) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

10.7 Asynchronous Notifications

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int **Py_AddPendingCall**(int (*func)(void*), void *arg)

Bir parçası Kararlı ABI. Schedule a function to be called from the main interpreter thread. On success, `0` is returned and *func* is queued for being called in the main thread. On failure, `-1` is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

- on a *bytecode* boundary;
- with the main thread holding an *attached thread state* (*func* can therefore use the full C API).

func must return `0` on success, or `-1` on failure with an exception set. *func* won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the *thread state* is detached.

This function doesn't need an *attached thread state*. However, to call this function in a subinterpreter, the caller must have an *attached thread state*. Otherwise, the function *func* can be scheduled to be called from the wrong interpreter.

Uyarı

This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the *PyGILState API*.

Added in version 3.1.

3.9 sürümünde değişti: If this function is called in a subinterpreter, the function *func* is now scheduled to be called from the subinterpreter, rather than being called from the main interpreter. Each subinterpreter now has its own list of scheduled calls.

10.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

typedef int (***Py_tracefunc**)(*PyObject* *obj, *PyFrameObject* *frame, int what, *PyObject* *arg)

The type of the trace function registered using `PyEval_SetProfile()` and `PyEval_SetTrace()`. The first parameter is the object passed to the registration function as *obj*, *frame* is the frame object to which the event pertains, *what* is one of the constants `PyTrace_CALL`, `PyTrace_EXCEPTION`, `PyTrace_LINE`, `PyTrace_RETURN`, `PyTrace_C_CALL`, `PyTrace_C_EXCEPTION`, `PyTrace_C_RETURN`, or `PyTrace_OPCODE`, and *arg* depends on the value of *what*:

Value of *what*	Meaning of *arg*
`PyTrace_CALL`	Always `Py_None`.
`PyTrace_EXCEPTION`	Exception information as returned by `sys.exc_info()`.
`PyTrace_LINE`	Always `Py_None`.
`PyTrace_RETURN`	Value being returned to the caller, or `NULL` if caused by an exception.
`PyTrace_C_CALL`	Function object being called.
`PyTrace_C_EXCEPTION`	Function object being called.
`PyTrace_C_RETURN`	Function object being called.
`PyTrace_OPCODE`	Always `Py_None`.

int **PyTrace_CALL**

The value of the *what* parameter to a *Py_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

int **PyTrace_EXCEPTION**

The value of the *what* parameter to a *Py_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

int **PyTrace_LINE**

The value passed as the *what* parameter to a *Py_tracefunc* function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting `f_trace_lines` to *0* on that frame.

int **PyTrace_RETURN**

The value for the *what* parameter to *Py_tracefunc* functions when a call is about to return.

int **PyTrace_C_CALL**

The value for the *what* parameter to *Py_tracefunc* functions when a C function is about to be called.

int **PyTrace_C_EXCEPTION**

The value for the *what* parameter to *Py_tracefunc* functions when a C function has raised an exception.

int **PyTrace_C_RETURN**

The value for the *what* parameter to *Py_tracefunc* functions when a C function has returned.

int **PyTrace_OPCODE**

The value for the *what* parameter to *Py_tracefunc* functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting `f_trace_opcodes` to *1* on the frame.

void **PyEval_SetProfile**(*Py_tracefunc* func, *PyObject* *obj)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or `NULL`. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except *PyTrace_LINE* *PyTrace_OPCODE* and *PyTrace_EXCEPTION*.

See also the `sys.setprofile()` function.

The caller must have an *attached thread state*.

void **PyEval_SetProfileAllThreads**(*Py_tracefunc* func, *PyObject* *obj)

Like *PyEval_SetProfile()* but sets the profile function in all running threads belonging to the current interpreter instead of the setting it only on the current thread.

The caller must have an *attached thread state*.

As *PyEval_SetProfile()*, this function ignores any exceptions raised while setting the profile functions in all threads.

Added in version 3.12.

void **PyEval_SetTrace**(*Py_tracefunc* func, *PyObject* *obj)

Set the tracing function to *func*. This is similar to *PyEval_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval_SetTrace()* will not receive *PyTrace_C_CALL*, *PyTrace_C_EXCEPTION* or *PyTrace_C_RETURN* as a value for the *what* parameter.

See also the `sys.settrace()` function.

The caller must have an *attached thread state*.

void **PyEval_SetTraceAllThreads**(*Py_tracefunc* func, *PyObject* *obj)

Like `PyEval_SetTrace()` but sets the tracing function in all running threads belonging to the current interpreter instead of the setting it only on the current thread.

The caller must have an *attached thread state*.

As `PyEval_SetTrace()`, this function ignores any exceptions raised while setting the trace functions in all threads.

Added in version 3.12.

10.9 Reference tracing

Added in version 3.13.

typedef int (***PyRefTracer**)(*PyObject**, int event, void *data)

The type of the trace function registered using `PyRefTracer_SetTracer()`. The first parameter is a Python object that has been just created (when **event** is set to `PyRefTracer_CREATE`) or about to be destroyed (when **event** is set to `PyRefTracer_DESTROY`). The **data** argument is the opaque pointer that was provided when `PyRefTracer_SetTracer()` was called.

Added in version 3.13.

int **PyRefTracer_CREATE**

The value for the *event* parameter to `PyRefTracer` functions when a Python object has been created.

int **PyRefTracer_DESTROY**

The value for the *event* parameter to `PyRefTracer` functions when a Python object has been destroyed.

int **PyRefTracer_SetTracer**(*PyRefTracer* tracer, void *data)

Register a reference tracer function. The function will be called when a new Python has been created or when an object is going to be destroyed. If **data** is provided it must be an opaque pointer that will be provided when the tracer function is called. Return `0` on success. Set an exception and return `-1` on error.

Not that tracer functions **must not** create Python objects inside or otherwise the call will be re-entrant. The tracer also **must not** clear any existing exception or set an exception. A *thread state* will be active every time the tracer function is called.

There must be an *attached thread state* when calling this function.

Added in version 3.13.

PyRefTracer **PyRefTracer_GetTracer**(void **data)

Get the registered reference tracer function and the value of the opaque data pointer that was registered when `PyRefTracer_SetTracer()` was called. If no tracer was registered this function will return NULL and will set the **data** pointer to NULL.

There must be an *attached thread state* when calling this function.

Added in version 3.13.

10.10 Advanced Debugger Support

These functions are only intended to be used by advanced debugging tools.

PyInterpreterState ***PyInterpreterState_Head**()

Return the interpreter state object at the head of the list of all such objects.

PyInterpreterState ***PyInterpreterState_Main**()

Return the main interpreter state object.

PyInterpreterState ***PyInterpreterState_Next**(*PyInterpreterState* *interp)

Return the next interpreter state object after *interp* from the list of all such objects.

PyThreadState ***PyInterpreterState_ThreadHead**(*PyInterpreterState* *interp)

Return the pointer to the first `PyThreadState` object in the list of threads associated with the interpreter *interp*.

PyThreadState ***PyThreadState_Next**(*PyThreadState* *tstate)

Return the next thread state object after *tstate* from the list of all such objects belonging to the same `PyInterpreterState` object.

10.11 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (`threading.local`). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a `void*` value per thread.

A *thread state* does *not* need to be *attached* when calling these functions; they suppl their own locking.

Note that `Python.h` does not include the declaration of the TLS APIs, you need to include `pythread.h` to use thread-local storage.

Not

None of these API functions handle memory management on behalf of the `void*` values. You need to allocate and deallocate them yourself. If the `void*` values happen to be `PyObject*`, these functions don't do refcount operations on them either.

10.11.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type `Py_tss_t` instead of `int` to represent thread keys.

Added in version 3.7.

Ayrıca bakınız

"A New C-API for Thread-Local Storage in CPython" (**PEP 539**)

type **Py_tss_t**

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure.

When *Py_LIMITED_API* is not defined, static allocation of this type by `Py_tss_NEEDS_INIT` is allowed.

Py_tss_NEEDS_INIT

This macro expands to the initializer for `Py_tss_t` variables. Note that this macro won't be defined with *Py_LIMITED_API*.

Dynamic Allocation

Dynamic allocation of the `Py_tss_t`, required in extension modules built with *Py_LIMITED_API*, where static allocation of this type is not possible due to its implementation being opaque at build time.

Py_tss_t ***PyThread_tss_alloc**()

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a value which is the same state as a value initialized with `Py_tss_NEEDS_INIT`, or `NULL` in the case of dynamic allocation failure.

void **PyThread_tss_free**(*Py_tss_t* *key)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Free the given *key* allocated by `PyThread_tss_alloc()`, after first calling `PyThread_tss_delete()` to ensure any associated thread locals have been unassigned. This is a no-op if the *key* argument is `NULL`.

> **Not**
>
> A freed key becomes a dangling pointer. You should reset the key to `NULL`.

Methods

The parameter *key* of these functions must not be `NULL`. Moreover, the behaviors of `PyThread_tss_set()` and `PyThread_tss_get()` are undefined if the given `Py_tss_t` has not been initialized by `PyThread_tss_create()`.

int **PyThread_tss_is_created**(*Py_tss_t* *key)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a non-zero value if the given `Py_tss_t` has been initialized by `PyThread_tss_create()`.

int **PyThread_tss_create**(*Py_tss_t* *key)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the *key* argument is not initialized by `Py_tss_NEEDS_INIT`. This function can be called repeatedly on the same key – calling it on an already initialized key is a no-op and immediately returns success.

void **PyThread_tss_delete**(*Py_tss_t* *key)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by `PyThread_tss_create()`. This function can be called repeatedly on the same key – calling it on an already destroyed key is a no-op.

int **PyThread_tss_set**(*Py_tss_t* *key, void *value)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return a zero value to indicate successfully associating a `void*` value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a `void*` value.

void ***PyThread_tss_get**(*Py_tss_t* *key)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Return the `void*` value associated with a TSS key in the current thread. This returns `NULL` if no value is associated with the key in the current thread.

10.11.2 Thread Local Storage (TLS) API

3.7 sürümünden beri kullanım dışı: This API is superseded by *Thread Specific Storage (TSS) API*.

> **Not**
>
> This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to `int`. On such platforms, `PyThread_create_key()` will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

Due to the compatibility problem noted above, this version of the API should not be used in new code.

int **PyThread_create_key**()

Bir parçası Kararlı ABI.

void **PyThread_delete_key**(int key)

Bir parçası Kararlı ABI.

int **PyThread_set_key_value**(int key, void *value)

Bir parçası Kararlı ABI.

void ***PyThread_get_key_value**(int key)

Bir parçası Kararlı ABI.

void **PyThread_delete_key_value**(int key)

Bir parçası Kararlı ABI.

void **PyThread_ReInitTLS**()

Bir parçası Kararlı ABI.

10.12 Synchronization Primitives

The C-API provides a basic mutual exclusion lock.

type **PyMutex**

A mutual exclusion lock. The `PyMutex` should be initialized to zero to represent the unlocked state. For example:

```
PyMutex mutex = {0};
```

Instances of `PyMutex` should not be copied or moved. Both the contents and address of a `PyMutex` are meaningful, and it must remain at a fixed, writable location in memory.

Not

A `PyMutex` currently occupies one byte, but the size should be considered unstable. The size may change in future Python releases without a deprecation period.

Added in version 3.13.

void **PyMutex_Lock**(*PyMutex* *m)

Lock mutex *m*. If another thread has already locked it, the calling thread will block until the mutex is unlocked. While blocked, the thread will temporarily detach the *thread state* if one exists.

Added in version 3.13.

void **PyMutex_Unlock**(*PyMutex* *m)

Unlock mutex *m*. The mutex must be locked — otherwise, the function will issue a fatal error.

Added in version 3.13.

int **PyMutex_IsLocked**(*PyMutex* *m)

Returns non-zero if the mutex *m* is currently locked, zero otherwise.

Not

This function is intended for use in assertions and debugging only and should not be used to make concurrency control decisions, as the lock state may change immediately after the check.

Added in version 3.14.

10.12.1 Python Critical Section API

The critical section API provides a deadlock avoidance layer on top of per-object locks for *free-threaded* CPython. They are intended to replace reliance on the *global interpreter lock*, and are no-ops in versions of Python with the global interpreter lock.

Critical sections are intended to be used for custom types implemented in C-API extensions. They should generally not be used with built-in types like `list` and `dict` because their public C-APIs already use critical sections internally, with the notable exception of *PyDict_Next()*, which requires critical section to be acquired externally.

Critical sections avoid deadlocks by implicitly suspending active critical sections, hence, they do not provide exclusive access such as provided by traditional locks like *PyMutex*. When a critical section is started, the per-object lock for the object is acquired. If the code executed inside the critical section calls C-API functions then it can suspend the critical section thereby releasing the per-object lock, so other threads can acquire the per-object lock for the same object.

Variants that accept *PyMutex* pointers rather than Python objects are also available. Use these variants to start a critical section in a situation where there is no *PyObject* – for example, when working with a C type that does not extend or wrap *PyObject* but still needs to call into the C API in a manner that might lead to deadlocks.

The functions and structs used by the macros are exposed for cases where C macros are not available. They should only be used as in the given macro expansions. Note that the sizes and contents of the structures may change in future Python versions.

Not

Operations that need to lock two objects at once must use *Py_BEGIN_CRITICAL_SECTION2*. You *cannot* use nested critical sections to lock more than one object at once, because the inner critical section may suspend the outer critical sections. This API does not provide a way to lock more than two objects at once.

Example usage:

```
static PyObject *
set_field(MyObject *self, PyObject *value)
{
   Py_BEGIN_CRITICAL_SECTION(self);
   Py_SETREF(self->field, Py_XNewRef(value));
   Py_END_CRITICAL_SECTION();
   Py_RETURN_NONE;
}
```

In the above example, *Py_SETREF* calls *Py_DECREF*, which can call arbitrary code through an object's deallocation function. The critical section API avoids potential deadlocks due to reentrancy and lock ordering by allowing the runtime to temporarily suspend the critical section if the code triggered by the finalizer blocks and calls *PyEval_SaveThread()*.

Py_BEGIN_CRITICAL_SECTION(op)

Acquires the per-object lock for the object *op* and begins a critical section.

In the free-threaded build, this macro expands to:

```
{
    PyCriticalSection _py_cs;
    PyCriticalSection_Begin(&_py_cs, (PyObject*)(op))
```

In the default build, this macro expands to `{`.

Added in version 3.13.

Py_BEGIN_CRITICAL_SECTION_MUTEX(m)

Locks the mutex *m* and begins a critical section.

In the free-threaded build, this macro expands to:

```
{
     PyCriticalSection _py_cs;
     PyCriticalSection_BeginMutex(&_py_cs, m)
```

Note that unlike *Py_BEGIN_CRITICAL_SECTION*, there is no cast for the argument of the macro - it must be a *PyMutex* pointer.

On the default build, this macro expands to `{`.

Added in version 3.14.

Py_END_CRITICAL_SECTION()

Ends the critical section and releases the per-object lock.

In the free-threaded build, this macro expands to:

```
    PyCriticalSection_End(&_py_cs);
}
```

In the default build, this macro expands to `}`.

Added in version 3.13.

Py_BEGIN_CRITICAL_SECTION2(a, b)

Acquires the per-objects locks for the objects *a* and *b* and begins a critical section. The locks are acquired in a consistent order (lowest address first) to avoid lock ordering deadlocks.

In the free-threaded build, this macro expands to:

```
{
    PyCriticalSection2 _py_cs2;
    PyCriticalSection2_Begin(&_py_cs2, (PyObject*)(a), (PyObject*)(b))
```

In the default build, this macro expands to `{`.

Added in version 3.13.

Py_BEGIN_CRITICAL_SECTION2_MUTEX(m1, m2)

Locks the mutexes *m1* and *m2* and begins a critical section.

In the free-threaded build, this macro expands to:

```
{
     PyCriticalSection2 _py_cs2;
     PyCriticalSection2_BeginMutex(&_py_cs2, m1, m2)
```

Note that unlike *Py_BEGIN_CRITICAL_SECTION2*, there is no cast for the arguments of the macro - they must be *PyMutex* pointers.

On the default build, this macro expands to `{`.

Added in version 3.14.

Py_END_CRITICAL_SECTION2()

Ends the critical section and releases the per-object locks.

In the free-threaded build, this macro expands to:

```
    PyCriticalSection2_End(&_py_cs2);
}
```

In the default build, this macro expands to `}`.

Added in version 3.13.

BÖLÜM 11

Python Initialization Configuration

11.1 PyInitConfig C API

Added in version 3.14.

Python can be initialized with *Py_InitializeFromInitConfig()*.

The *Py_RunMain()* function can be used to write a customized Python program.

See also *Initialization, Finalization, and Threads*.

Ayrıca bakınız

PEP 741 "Python Configuration C API".

11.1.1 Example

Example of customized Python always running with the Python Development Mode enabled; return `-1` on error:

```
int init_python(void)
{
    PyInitConfig *config = PyInitConfig_Create();
    if (config == NULL) {
        printf("PYTHON INIT ERROR: memory allocation failed\n");
        return -1;
    }

    // Enable the Python Development Mode
    if (PyInitConfig_SetInt(config, "dev_mode", 1) < 0) {
        goto error;
    }

    // Initialize Python with the configuration
    if (Py_InitializeFromInitConfig(config) < 0) {
        goto error;
    }
    PyInitConfig_Free(config);
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    return 0;

error:
    {
        // Display the error message.
        //
        // This uncommon braces style is used, because you cannot make
        // goto targets point to variable declarations.
        const char *err_msg;
        (void)PyInitConfig_GetError(config, &err_msg);
        printf("PYTHON INIT ERROR: %s\n", err_msg);
        PyInitConfig_Free(config);
        return -1;
    }
}
```

11.1.2 Create Config

struct **PyInitConfig**

Opaque structure to configure the Python initialization.

PyInitConfig ***PyInitConfig_Create**(void)

Create a new initialization configuration using *Isolated Configuration* default values.

It must be freed by `PyInitConfig_Free()`.

Return `NULL` on memory allocation failure.

void **PyInitConfig_Free**(*PyInitConfig* *config)

Free memory of the initialization configuration *config*.

If *config* is `NULL`, no operation is performed.

11.1.3 Error Handling

int **PyInitConfig_GetError**(*PyInitConfig* *config, const char **err_msg)

Get the *config* error message.

- Set **err_msg* and return `1` if an error is set.
- Set **err_msg* to `NULL` and return `0` otherwise.

An error message is an UTF-8 encoded string.

If *config* has an exit code, format the exit code as an error message.

The error message remains valid until another `PyInitConfig` function is called with *config*. The caller doesn't have to free the error message.

int **PyInitConfig_GetExitCode**(*PyInitConfig* *config, int *exitcode)

Get the *config* exit code.

- Set **exitcode* and return `1` if *config* has an exit code set.
- Return `0` if *config* has no exit code set.

Only the `Py_InitializeFromInitConfig()` function can set an exit code if the `parse_argv` option is non-zero.

An exit code can be set when parsing the command line failed (exit code `2`) or when a command line option asks to display the command line help (exit code `0`).

11.1.4 Get Options

The configuration option *name* parameter must be a non-NULL null-terminated UTF-8 encoded string. See *Configuration Options*.

int **PyInitConfig_HasOption**(*PyInitConfig* *config, const char *name)

Test if the configuration has an option called *name*.

Return `1` if the option exists, or return `0` otherwise.

int **PyInitConfig_GetInt**(*PyInitConfig* *config, const char *name, int64_t *value)

Get an integer configuration option.

- Set **value*, and return `0` on success.
- Set an error in *config* and return `-1` on error.

int **PyInitConfig_GetStr**(*PyInitConfig* *config, const char *name, char **value)

Get a string configuration option as a null-terminated UTF-8 encoded string.

- Set **value*, and return `0` on success.
- Set an error in *config* and return `-1` on error.

**value* can be set to `NULL` if the option is an optional string and the option is unset.

On success, the string must be released with `free(value)` if it's not `NULL`.

int **PyInitConfig_GetStrList**(*PyInitConfig* *config, const char *name, size_t *length, char ***items)

Get a string list configuration option as an array of null-terminated UTF-8 encoded strings.

- Set **length* and **value*, and return `0` on success.
- Set an error in *config* and return `-1` on error.

On success, the string list must be released with `PyInitConfig_FreeStrList(length, items)`.

void **PyInitConfig_FreeStrList**(size_t length, char **items)

Free memory of a string list created by `PyInitConfig_GetStrList()`.

11.1.5 Set Options

The configuration option *name* parameter must be a non-NULL null-terminated UTF-8 encoded string. See *Configuration Options*.

Some configuration options have side effects on other options. This logic is only implemented when `Py_InitializeFromInitConfig()` is called, not by the "Set" functions below. For example, setting `dev_mode` to `1` does not set `faulthandler` to `1`.

int **PyInitConfig_SetInt**(*PyInitConfig* *config, const char *name, int64_t value)

Set an integer configuration option.

- Return `0` on success.
- Set an error in *config* and return `-1` on error.

int **PyInitConfig_SetStr**(*PyInitConfig* *config, const char *name, const char *value)

Set a string configuration option from a null-terminated UTF-8 encoded string. The string is copied.

- Return `0` on success.
- Set an error in *config* and return `-1` on error.

int **PyInitConfig_SetStrList**(*PyInitConfig* *config, const char *name, size_t length, char *const *items)

Set a string list configuration option from an array of null-terminated UTF-8 encoded strings. The string list is copied.

- Return `0` on success.
- Set an error in *config* and return `-1` on error.

11.1.6 Module

int **PyInitConfig_AddModule**(*PyInitConfig* *config, const char *name, *PyObject* *(*initfunc)(void))

Add a built-in extension module to the table of built-in modules.

The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import.

- Return `0` on success.
- Set an error in *config* and return `-1` on error.

If Python is initialized multiple times, `PyInitConfig_AddModule()` must be called at each Python initialization.

Similar to the *PyImport_AppendInittab()* function.

11.1.7 Initialize Python

int **Py_InitializeFromInitConfig**(*PyInitConfig* *config)

Initialize Python from the initialization configuration.

- Return `0` on success.
- Set an error in *config* and return `-1` on error.
- Set an exit code in *config* and return `-1` if Python wants to exit.

See `PyInitConfig_GetExitcode()` for the exit code case.

11.2 Configuration Options

Option	PyConfig/PyPreConfig member	Type	Visibility
"allocator"	*allocator*	int	Read-only
"argv"	*argv*	list[str]	Public
"base_exec_prefix"	*base_exec_prefix*	str	Public
"base_executable"	*base_executable*	str	Public
"base_prefix"	*base_prefix*	str	Public
"buffered_stdio"	*buffered_stdio*	bool	Read-only
"bytes_warning"	*bytes_warning*	int	Public
"check_hash_pycs_mode"	*check_hash_pycs_mode*	str	Read-only
"code_debug_ranges"	*code_debug_ranges*	bool	Read-only
"coerce_c_locale"	*coerce_c_locale*	bool	Read-only
"coerce_c_locale_warn"	*coerce_c_locale_warn*	bool	Read-only
"configure_c_stdio"	*configure_c_stdio*	bool	Read-only
"configure_locale"	*configure_locale*	bool	Read-only
"cpu_count"	*cpu_count*	int	Public
"dev_mode"	*dev_mode*	bool	Read-only
"dump_refs"	*dump_refs*	bool	Read-only
"dump_refs_file"	*dump_refs_file*	str	Read-only
"exec_prefix"	*exec_prefix*	str	Public
"executable"	*executable*	str	Public
"faulthandler"	*faulthandler*	bool	Read-only
"filesystem_encoding"	*filesystem_encoding*	str	Read-only
"filesystem_errors"	*filesystem_errors*	str	Read-only
"hash_seed"	*hash_seed*	int	Read-only
"home"	*home*	str	Read-only
"import_time"	*import_time*	int	Read-only
"inspect"	*inspect*	bool	Public

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

Option	PyConfig/PyPreConfig member	Type	Visibility
"install_signal_handlers"	*install_signal_handlers*	bool	Read-only
"int_max_str_digits"	*int_max_str_digits*	int	Public
"interactive"	*interactive*	bool	Public
"isolated"	*isolated*	bool	Read-only
"legacy_windows_fs_encoding"	*legacy_windows_fs_encoding*	bool	Read-only
"legacy_windows_stdio"	*legacy_windows_stdio*	bool	Read-only
"malloc_stats"	*malloc_stats*	bool	Read-only
"module_search_paths"	*module_search_paths*	list[str]	Public
"optimization_level"	*optimization_level*	int	Public
"orig_argv"	*orig_argv*	list[str]	Read-only
"parse_argv"	*parse_argv*	bool	Read-only
"parser_debug"	*parser_debug*	bool	Public
"pathconfig_warnings"	*pathconfig_warnings*	bool	Read-only
"perf_profiling"	*perf_profiling*	bool	Read-only
"platlibdir"	*platlibdir*	str	Public
"prefix"	*prefix*	str	Public
"program_name"	*program_name*	str	Read-only
"pycache_prefix"	*pycache_prefix*	str	Public
"quiet"	*quiet*	bool	Public
"run_command"	*run_command*	str	Read-only
"run_filename"	*run_filename*	str	Read-only
"run_module"	*run_module*	str	Read-only
"run_presite"	*run_presite*	str	Read-only
"safe_path"	*safe_path*	bool	Read-only
"show_ref_count"	*show_ref_count*	bool	Read-only
"site_import"	*site_import*	bool	Read-only
"skip_source_first_line"	*skip_source_first_line*	bool	Read-only
"stdio_encoding"	*stdio_encoding*	str	Read-only
"stdio_errors"	*stdio_errors*	str	Read-only
"stdlib_dir"	*stdlib_dir*	str	Public
"tracemalloc"	*tracemalloc*	int	Read-only
"use_environment"	*use_environment*	bool	Public
"use_frozen_modules"	*use_frozen_modules*	bool	Read-only
"use_hash_seed"	*use_hash_seed*	bool	Read-only
"use_system_logger"	*use_system_logger*	bool	Read-only
"user_site_directory"	*user_site_directory*	bool	Read-only
"utf8_mode"	*utf8_mode*	bool	Read-only
"verbose"	*verbose*	int	Public
"warn_default_encoding"	*warn_default_encoding*	bool	Read-only
"warnoptions"	*warnoptions*	list[str]	Public
"write_bytecode"	*write_bytecode*	bool	Public
"xoptions"	*xoptions*	dict[str, str]	Public
"_pystats"	*_pystats*	bool	Read-only

Visibility:

- Public: Can by get by *PyConfig_Get()* and set by *PyConfig_Set()*.
- Read-only: Can by get by *PyConfig_Get()*, but cannot be set by *PyConfig_Set()*.

11.3 Runtime Python configuration API

At runtime, it's possible to get and set configuration options using *PyConfig_Get()* and *PyConfig_Set()* functions.

The configuration option *name* parameter must be a non-NULL null-terminated UTF-8 encoded string. See *Configuration Options*.

Some options are read from the `sys` attributes. For example, the option `"argv"` is read from `sys.argv`.

PyObject ***PyConfig_Get**(const char *name)

Get the current runtime value of a configuration option as a Python object.

- Return a new reference on success.
- Set an exception and return `NULL` on error.

The object type depends on the configuration option. It can be:

- `bool`
- `int`
- `str`
- `list[str]`
- `dict[str, str]`

The caller must have an *attached thread state*. The function cannot be called before Python initialization nor after Python finalization.

Added in version 3.14.

int **PyConfig_GetInt**(const char *name, int *value)

Similar to *PyConfig_Get()*, but get the value as a C int.

- Return `0` on success.
- Set an exception and return `-1` on error.

Added in version 3.14.

PyObject ***PyConfig_Names**(void)

Get all configuration option names as a `frozenset`.

- Return a new reference on success.
- Set an exception and return `NULL` on error.

The caller must have an *attached thread state*. The function cannot be called before Python initialization nor after Python finalization.

Added in version 3.14.

int **PyConfig_Set**(const char *name, *PyObject* *value)

Set the current runtime value of a configuration option.

- Raise a `ValueError` if there is no option *name*.
- Raise a `ValueError` if *value* is an invalid value.
- Raise a `ValueError` if the option is read-only (cannot be set).
- Raise a `TypeError` if *value* has not the proper type.

The caller must have an *attached thread state*. The function cannot be called before Python initialization nor after Python finalization.

Raises an auditing event `cpython.PyConfig_Set` with arguments `name`, `value`.

Added in version 3.14.

11.4 PyConfig C API

Added in version 3.8.

Python can be initialized with `Py_InitializeFromConfig()` and the `PyConfig` structure. It can be preinitialized with `Py_PreInitialize()` and the `PyPreConfig` structure.

There are two kinds of configuration:

- The *Python Configuration* can be used to build a customized Python which behaves as the regular Python. For example, environment variables and command line arguments are used to configure Python.
- The *Isolated Configuration* can be used to embed Python into an application. It isolates Python from the system. For example, environment variables are ignored, the LC_CTYPE locale is left unchanged and no signal handler is registered.

The `Py_RunMain()` function can be used to write a customized Python program.

See also *Initialization, Finalization, and Threads*.

Ayrıca bakınız

PEP 587 "Python Initialization Configuration".

11.4.1 Example

Example of customized Python always running in isolated mode:

```
int main(int argc, char **argv)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config.isolated = 1;

    /* Decode command line arguments.
       Implicitly preinitialize Python (in isolated mode). */
    status = PyConfig_SetBytesArgv(&config, argc, argv);
    if (PyStatus_Exception(status)) {
        goto exception;
    }

    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto exception;
    }
    PyConfig_Clear(&config);

    return Py_RunMain();

exception:
    PyConfig_Clear(&config);
    if (PyStatus_IsExit(status)) {
        return status.exitcode;
    }
    /* Display the error message and exit the process with
       non-zero exit code */
    Py_ExitStatusException(status);
}
```

11.4.2 PyWideStringList

type **PyWideStringList**

List of `wchar_t*` strings.

If *length* is non-zero, *items* must be non-`NULL` and all strings must be non-`NULL`.

Methods:

PyStatus **PyWideStringList_Append**(*PyWideStringList* *list, const wchar_t *item)

Append *item* to *list*.

Python must be preinitialized to call this function.

PyStatus **PyWideStringList_Insert**(*PyWideStringList* *list, *Py_ssize_t* index, const wchar_t *item)

Insert *item* into *list* at *index*.

If *index* is greater than or equal to *list* length, append *item* to *list*.

index must be greater than or equal to `0`.

Python must be preinitialized to call this function.

Structure fields:

Py_ssize_t **length**

List length.

wchar_t ****items**

List items.

11.4.3 PyStatus

type **PyStatus**

Structure to store an initialization function status: success, error or exit.

For an error, it can store the C function name which created the error.

Structure fields:

int **exitcode**

Exit code. Argument passed to `exit()`.

const char ***err_msg**

Error message.

const char ***func**

Name of the function which created an error, can be `NULL`.

Functions to create a status:

PyStatus **PyStatus_Ok**(void)

Success.

PyStatus **PyStatus_Error**(const char *err_msg)

Initialization error with a message.

err_msg must not be `NULL`.

PyStatus **PyStatus_NoMemory**(void)

Memory allocation failure (out of memory).

PyStatus **PyStatus_Exit**(int exitcode)

Exit Python with the specified exit code.

Functions to handle a status:

int **PyStatus_Exception**(*PyStatus* status)

Is the status an error or an exit? If true, the exception must be handled; by calling *Py_ExitStatusException()* for example.

int **PyStatus_IsError**(*PyStatus* status)

Is the result an error?

int **PyStatus_IsExit**(*PyStatus* status)

Is the result an exit?

void **Py_ExitStatusException**(*PyStatus* status)

Call `exit(exitcode)` if *status* is an exit. Print the error message and exit with a non-zero exit code if *status* is an error. Must only be called if `PyStatus_Exception(status)` is non-zero.

Not

Internally, Python uses macros which set `PyStatus.func`, whereas functions to create a status set `func` to `NULL`.

Example:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}

int main(int argc, char **argv)
{
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
    PyMem_Free(ptr);
    return 0;
}
```

11.4.4 PyPreConfig

type **PyPreConfig**

Structure used to preinitialize Python.

Function to initialize a preconfiguration:

void **PyPreConfig_InitPythonConfig**(*PyPreConfig* *preconfig)

Initialize the preconfiguration with *Python Configuration*.

void **PyPreConfig_InitIsolatedConfig**(*PyPreConfig* *preconfig)

Initialize the preconfiguration with *Isolated Configuration*.

Structure fields:

int **allocator**

Name of the Python memory allocators:

- `PYMEM_ALLOCATOR_NOT_SET` (`0`): don't change memory allocators (use defaults).

- `PYMEM_ALLOCATOR_DEFAULT` (`1`): *default memory allocators*.
- `PYMEM_ALLOCATOR_DEBUG` (`2`): *default memory allocators* with *debug hooks*.
- `PYMEM_ALLOCATOR_MALLOC` (`3`): use `malloc()` of the C library.
- `PYMEM_ALLOCATOR_MALLOC_DEBUG` (`4`): force usage of `malloc()` with *debug hooks*.
- `PYMEM_ALLOCATOR_PYMALLOC` (`5`): *Python pymalloc memory allocator*.
- `PYMEM_ALLOCATOR_PYMALLOC_DEBUG` (`6`): *Python pymalloc memory allocator* with *debug hooks*.
- `PYMEM_ALLOCATOR_MIMALLOC` (`6`): use `mimalloc`, a fast malloc replacement.
- `PYMEM_ALLOCATOR_MIMALLOC_DEBUG` (`7`): use `mimalloc`, a fast malloc replacement with *debug hooks*.

`PYMEM_ALLOCATOR_PYMALLOC` and `PYMEM_ALLOCATOR_PYMALLOC_DEBUG` are not supported if Python is `configured using --without-pymalloc`.

`PYMEM_ALLOCATOR_MIMALLOC` and `PYMEM_ALLOCATOR_MIMALLOC_DEBUG` are not supported if Python is `configured using --without-mimalloc` or if the underlying atomic support isn't available.

See *Memory Management*.

Default: `PYMEM_ALLOCATOR_NOT_SET`.

int **configure_locale**

Set the LC_CTYPE locale to the user preferred locale.

If equals to `0`, set *coerce_c_locale* and *coerce_c_locale_warn* members to `0`.

See the *locale encoding*.

Default: `1` in Python config, `0` in isolated config.

int **coerce_c_locale**

If equals to `2`, coerce the C locale.

If equals to `1`, read the LC_CTYPE locale to decide if it should be coerced.

See the *locale encoding*.

Default: `-1` in Python config, `0` in isolated config.

int **coerce_c_locale_warn**

If non-zero, emit a warning if the C locale is coerced.

Default: `-1` in Python config, `0` in isolated config.

int **dev_mode**

Python Development Mode: see *PyConfig.dev_mode*.

Default: `-1` in Python mode, `0` in isolated mode.

int **isolated**

Isolated mode: see *PyConfig.isolated*.

Default: `0` in Python mode, `1` in isolated mode.

int **legacy_windows_fs_encoding**

If non-zero:

- Set *PyPreConfig.utf8_mode* to `0`,
- Set *PyConfig.filesystem_encoding* to `"mbcs"`,
- Set *PyConfig.filesystem_errors* to `"replace"`.

Initialized from the `PYTHONLEGACYWINDOWSFSENCODING` environment variable value.

Only available on Windows. `#ifdef MS_WINDOWS` macro can be used for Windows specific code.

Default: `0`.

int **parse_argv**

If non-zero, *Py_PreInitializeFromArgs()* and *Py_PreInitializeFromBytesArgs()* parse their `argv` argument the same way the regular Python parses command line arguments: see Command Line Arguments.

Default: `1` in Python config, `0` in isolated config.

int **use_environment**

Use environment variables? See *PyConfig.use_environment*.

Default: `1` in Python config and `0` in isolated config.

int **utf8_mode**

If non-zero, enable the Python UTF-8 Mode.

Set to `0` or `1` by the `-X utf8` command line option and the `PYTHONUTF8` environment variable.

Also set to `1` if the `LC_CTYPE` locale is `C` or `POSIX`.

Default: `-1` in Python config and `0` in isolated config.

11.4.5 Preinitialize Python with PyPreConfig

The preinitialization of Python:

- Set the Python memory allocators (*PyPreConfig.allocator*)
- Configure the LC_CTYPE locale (*locale encoding*)
- Set the Python UTF-8 Mode (*PyPreConfig.utf8_mode*)

The current preconfiguration (`PyPreConfig` type) is stored in `_PyRuntime.preconfig`.

Functions to preinitialize Python:

PyStatus **Py_PreInitialize**(const *PyPreConfig* *preconfig)

Preinitialize Python from *preconfig* preconfiguration.

preconfig must not be `NULL`.

PyStatus **Py_PreInitializeFromBytesArgs**(const *PyPreConfig* *preconfig, int argc, char *const *argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (bytes strings) if *parse_argv* of *preconfig* is non-zero.

preconfig must not be `NULL`.

PyStatus **Py_PreInitializeFromArgs**(const *PyPreConfig* *preconfig, int argc, wchar_t *const *argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (wide strings) if *parse_argv* of *preconfig* is non-zero.

preconfig must not be `NULL`.

The caller is responsible to handle exceptions (error or exit) using *PyStatus_Exception()* and *Py_ExitStatusException()*.

For *Python Configuration* (*PyPreConfig_InitPythonConfig()*), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the `-X utf8` command line option enables the Python UTF-8 Mode.

`PyMem_SetAllocator()` can be called after *Py_PreInitialize()* and before *Py_InitializeFromConfig()* to install a custom memory allocator. It can be called before *Py_PreInitialize()* if *PyPreConfig.allocator* is set to `PYMEM_ALLOCATOR_NOT_SET`.

Python memory allocation functions like *PyMem_RawMalloc()* must not be used before the Python preinitialization, whereas calling directly `malloc()` and `free()` is always safe. *Py_DecodeLocale()* must not be called before the Python preinitialization.

Example using the preinitialization to enable the Python UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}

/* at this point, Python speaks UTF-8 */

Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

11.4.6 PyConfig

type **PyConfig**

Structure containing most parameters to configure Python.

When done, the *PyConfig_Clear()* function must be used to release the configuration memory.

Structure methods:

void **PyConfig_InitPythonConfig**(*PyConfig* *config)

Initialize configuration with the *Python Configuration*.

void **PyConfig_InitIsolatedConfig**(*PyConfig* *config)

Initialize configuration with the *Isolated Configuration*.

PyStatus **PyConfig_SetString**(*PyConfig* *config, wchar_t *const *config_str, const wchar_t *str)

Copy the wide character string *str* into `*config_str`.

Preinitialize Python if needed.

PyStatus **PyConfig_SetBytesString**(*PyConfig* *config, wchar_t *const *config_str, const char *str)

Decode *str* using *Py_DecodeLocale()* and set the result into `*config_str`.

Preinitialize Python if needed.

PyStatus **PyConfig_SetArgv**(*PyConfig* *config, int argc, wchar_t *const *argv)

Set command line arguments (*argv* member of *config*) from the *argv* list of wide character strings.

Preinitialize Python if needed.

PyStatus **PyConfig_SetBytesArgv**(*PyConfig* *config, int argc, char *const *argv)

Set command line arguments (*argv* member of *config*) from the *argv* list of bytes strings. Decode bytes using *Py_DecodeLocale()*.

Preinitialize Python if needed.

PyStatus **PyConfig_SetWideStringList**(*PyConfig* *config, *PyWideStringList* *list, *Py_ssize_t* length, wchar_t **items)

Set the list of wide strings *list* to *length* and *items*.

Preinitialize Python if needed.

PyStatus **PyConfig_Read**(*PyConfig* *config)

Read all Python configuration.

Fields which are already initialized are left unchanged.

Fields for *path configuration* are no longer calculated or modified when calling this function, as of Python 3.11.

The *PyConfig_Read()* function only parses *PyConfig.argv* arguments once: *PyConfig.parse_argv* is set to `2` after arguments are parsed. Since Python arguments are stripped from *PyConfig.argv*, parsing arguments twice would parse the application options as Python options.

Preinitialize Python if needed.

3.10 sürümünde değişti: The *PyConfig.argv* arguments are now only parsed once, *PyConfig.parse_argv* is set to `2` after arguments are parsed, and arguments are only parsed if *PyConfig.parse_argv* equals `1`.

3.11 sürümünde değişti: *PyConfig_Read()* no longer calculates all paths, and so fields listed under *Python Path Configuration* may no longer be updated until *Py_InitializeFromConfig()* is called.

void **PyConfig_Clear**(*PyConfig* *config)

Release configuration memory.

Most `PyConfig` methods *preinitialize Python* if needed. In that case, the Python preinitialization configuration (*PyPreConfig*) in based on the *PyConfig*. If configuration fields which are in common with *PyPreConfig* are tuned, they must be set before calling a *PyConfig* method:

- *PyConfig.dev_mode*
- *PyConfig.isolated*
- *PyConfig.parse_argv*
- *PyConfig.use_environment*

Moreover, if *PyConfig_SetArgv()* or *PyConfig_SetBytesArgv()* is used, this method must be called before other methods, since the preinitialization configuration depends on command line arguments (if *parse_argv* is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using `PyStatus_Exception()` and `Py_ExitStatusException()`.

Structure fields:

PyWideStringList **argv**

Set `sys.argv` command line arguments based on *argv*. These parameters are similar to those passed to the program's `main()` function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in *argv* can be an empty string.

Set *parse_argv* to `1` to parse *argv* the same way the regular Python parses Python command line arguments and then to strip Python arguments from *argv*.

If *argv* is empty, an empty string is added to ensure that `sys.argv` always exists and is never empty.

Default: `NULL`.

See also the *orig_argv* member.

int **safe_path**

If equals to zero, `Py_RunMain()` prepends a potentially unsafe path to `sys.path` at startup:

- If *argv[0]* is equal to `L"-m"` (`python -m module`), prepend the current working directory.
- If running a script (`python script.py`), prepend the script's directory. If it's a symbolic link, resolve symbolic links.

- Otherwise (`python -c code` and `python`), prepend an empty string, which means the current working directory.

Set to `1` by the `-P` command line option and the `PYTHONSAFEPATH` environment variable.

Default: `0` in Python config, `1` in isolated config.

Added in version 3.11.

wchar_t ***base_exec_prefix**

`sys.base_exec_prefix`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.exec_prefix`*.

wchar_t ***base_executable**

Python base executable: `sys._base_executable`.

Set by the `__PYVENV_LAUNCHER__` environment variable.

Set from *`PyConfig.executable`* if `NULL`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.executable`*.

wchar_t ***base_prefix**

`sys.base_prefix`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.prefix`*.

int **buffered_stdio**

If equals to `0` and *`configure_c_stdio`* is non-zero, disable buffering on the C streams stdout and stderr.

Set to `0` by the `-u` command line option and the `PYTHONUNBUFFERED` environment variable.

stdin is always opened in buffered mode.

Default: `1`.

int **bytes_warning**

If equals to `1`, issue a warning when comparing `bytes` or `bytearray` with `str`, or comparing `bytes` with `int`.

If equal or greater to `2`, raise a `BytesWarning` exception in these cases.

Incremented by the `-b` command line option.

Default: `0`.

int **warn_default_encoding**

If non-zero, emit a `EncodingWarning` warning when `io.TextIOWrapper` uses its default encoding. See io-encoding-warning for details.

Default: `0`.

Added in version 3.10.

int **code_debug_ranges**

If equals to `0`, disables the inclusion of the end line and column mappings in code objects. Also disables traceback printing carets to specific error locations.

Set to `0` by the `PYTHONNODEBUGRANGES` environment variable and by the `-X no_debug_ranges` command line option.

Default: `1`.

Added in version 3.11.

wchar_t ***check_hash_pycs_mode**

Control the validation behavior of hash-based `.pyc` files: value of the `--check-hash-based-pycs` command line option.

Valid values:

- `L"always"`: Hash the source file for invalidation regardless of value of the 'check_source' flag.
- `L"never"`: Assume that hash-based pycs always are valid.
- `L"default"`: The 'check_source' flag in hash-based pycs determines invalidation.

Default: `L"default"`.

See also **PEP 552** "Deterministic pycs".

int **configure_c_stdio**

If non-zero, configure C standard streams:

- On Windows, set the binary mode (`O_BINARY`) on stdin, stdout and stderr.
- If *buffered_stdio* equals zero, disable buffering of stdin, stdout and stderr streams.
- If *interactive* is non-zero, enable stream buffering on stdin and stdout (only stdout on Windows).

Default: `1` in Python config, `0` in isolated config.

int **dev_mode**

If non-zero, enable the Python Development Mode.

Set to `1` by the `-X dev` option and the `PYTHONDEVMODE` environment variable.

Default: `-1` in Python mode, `0` in isolated mode.

int **dump_refs**

Dump Python references?

If non-zero, dump all objects which are still alive at exit.

Set to `1` by the `PYTHONDUMPREFS` environment variable.

Needs a special build of Python with the `Py_TRACE_REFS` macro defined: see the `configure --with-trace-refs option`.

Default: `0`.

wchar_t ***dump_refs_file**

Filename where to dump Python references.

Set by the `PYTHONDUMPREFSFILE` environment variable.

Default: `NULL`.

Added in version 3.11.

wchar_t ***exec_prefix**

The site-specific directory prefix where the platform-dependent Python files are installed: `sys.exec_prefix`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.base_exec_prefix`*.

wchar_t ***executable**

The absolute path of the executable binary for the Python interpreter: `sys.executable`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.base_executable`*.

int **faulthandler**

Enable faulthandler?

If non-zero, call `faulthandler.enable()` at startup.

Set to `1` by `-X faulthandler` and the `PYTHONFAULTHANDLER` environment variable.

Default: `-1` in Python mode, `0` in isolated mode.

wchar_t ***filesystem_encoding**

Filesystem encoding: `sys.getfilesystemencoding()`.

On macOS, Android and VxWorks: use `"utf-8"` by default.

On Windows: use `"utf-8"` by default, or `"mbcs"` if *`legacy_windows_fs_encoding`* of *`PyPreConfig`* is non-zero.

Default encoding on other platforms:

- `"utf-8"` if *`PyPreConfig.utf8_mode`* is non-zero.
- `"ascii"` if Python detects that `nl_langinfo(CODESET)` announces the ASCII encoding, whereas the `mbstowcs()` function decodes from a different encoding (usually Latin1).
- `"utf-8"` if `nl_langinfo(CODESET)` returns an empty string.
- Otherwise, use the *locale encoding*: `nl_langinfo(CODESET)` result.

At Python startup, the encoding name is normalized to the Python codec name. For example, `"ANSI_X3.4-1968"` is replaced with `"ascii"`.

See also the *`filesystem_errors`* member.

wchar_t ***filesystem_errors**

Filesystem error handler: `sys.getfilesystemencodeerrors()`.

On Windows: use `"surrogatepass"` by default, or `"replace"` if *`legacy_windows_fs_encoding`* of *`PyPreConfig`* is non-zero.

On other platforms: use `"surrogateescape"` by default.

Supported error handlers:

- `"strict"`
- `"surrogateescape"`
- `"surrogatepass"` (only supported with the UTF-8 encoding)

See also the *`filesystem_encoding`* member.

int **use_frozen_modules**

If non-zero, use frozen modules.

Set by the `PYTHON_FROZEN_MODULES` environment variable.

Default: `1` in a release build, or `0` in a debug build.

unsigned long **hash_seed**

int **use_hash_seed**

Randomized hash function seed.

If *use_hash_seed* is zero, a seed is chosen randomly at Python startup, and *hash_seed* is ignored.

Set by the `PYTHONHASHSEED` environment variable.

Default *use_hash_seed* value: `-1` in Python mode, `0` in isolated mode.

wchar_t ***home**

Set the default Python "home" directory, that is, the location of the standard Python libraries (see `PYTHONHOME`).

Set by the `PYTHONHOME` environment variable.

Default: `NULL`.

Part of the *Python Path Configuration* input.

int **import_time**

If `1`, profile import time. If `2`, include additional output that indicates when an imported module has already been loaded.

Set by the `-X importtime` option and the `PYTHONPROFILEIMPORTTIME` environment variable.

Default: `0`.

3.14 sürümünde değişti: Added support for `import_time = 2`

int **inspect**

Enter interactive mode after executing a script or a command.

If greater than `0`, enable inspect: when a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when `sys.stdin` does not appear to be a terminal.

Incremented by the `-i` command line option. Set to `1` if the `PYTHONINSPECT` environment variable is non-empty.

Default: `0`.

int **install_signal_handlers**

Install Python signal handlers?

Default: `1` in Python mode, `0` in isolated mode.

int **interactive**

If greater than `0`, enable the interactive mode (REPL).

Incremented by the `-i` command line option.

Default: `0`.

int **int_max_str_digits**

Configures the integer string conversion length limitation. An initial value of `-1` means the value will be taken from the command line or environment or otherwise default to 4300 (`sys.int_info.default_max_str_digits`). A value of `0` disables the limitation. Values greater than zero but less

than 640 (`sys.int_info.str_digits_check_threshold`) are unsupported and will produce an error.

Configured by the `-X int_max_str_digits` command line flag or the `PYTHONINTMAXSTRDIGITS` environment variable.

Default: `-1` in Python mode. 4300 (`sys.int_info.default_max_str_digits`) in isolated mode.

Added in version 3.12.

int **cpu_count**

If the value of *cpu_count* is not `-1` then it will override the return values of `os.cpu_count()`, `os.process_cpu_count()`, and `multiprocessing.cpu_count()`.

Configured by the `-X cpu_count =n|default` command line flag or the `PYTHON_CPU_COUNT` environment variable.

Default: `-1`.

Added in version 3.13.

int **isolated**

If greater than `0`, enable isolated mode:

- Set *safe_path* to `1`: don't prepend a potentially unsafe path to `sys.path` at Python startup, such as the current directory, the script's directory or an empty string.
- Set *use_environment* to `0`: ignore `PYTHON` environment variables.
- Set *user_site_directory* to `0`: don't add the user site directory to `sys.path`.
- Python REPL doesn't import `readline` nor enable default readline configuration on interactive prompts.

Set to `1` by the `-I` command line option.

Default: `0` in Python mode, `1` in isolated mode.

See also the *Isolated Configuration* and *PyPreConfig.isolated*.

int **legacy_windows_stdio**

If non-zero, use `io.FileIO` instead of `io._WindowsConsoleIO` for `sys.stdin`, `sys.stdout` and `sys.stderr`.

Set to `1` if the `PYTHONLEGACYWINDOWSSTDIO` environment variable is set to a non-empty string.

Only available on Windows. `#ifdef MS_WINDOWS` macro can be used for Windows specific code.

Default: `0`.

See also the **PEP 528** (Change Windows console encoding to UTF-8).

int **malloc_stats**

If non-zero, dump statistics on *Python pymalloc memory allocator* at exit.

Set to `1` by the `PYTHONMALLOCSTATS` environment variable.

The option is ignored if Python is `configured using the --without-pymalloc option`.

Default: `0`.

wchar_t ***platlibdir**

Platform library directory name: `sys.platlibdir`.

Set by the `PYTHONPLATLIBDIR` environment variable.

Default: value of the `PLATLIBDIR` macro which is set by the `configure --with-platlibdir option` (default: `"lib"`, or `"DLLs"` on Windows).

Part of the *Python Path Configuration* input.

Added in version 3.9.

3.11 sürümünde değişti: This macro is now used on Windows to locate the standard library extension modules, typically under `DLLs`. However, for compatibility, note that this value is ignored for any non-standard layouts, including in-tree builds and virtual environments.

wchar_t ***pythonpath_env**

Module search paths (`sys.path`) as a string separated by `DELIM` (`os.pathsep`).

Set by the `PYTHONPATH` environment variable.

Default: `NULL`.

Part of the *Python Path Configuration* input.

PyWideStringList **module_search_paths**

int **module_search_paths_set**

Module search paths: `sys.path`.

If *module_search_paths_set* is equal to `0`, *Py_InitializeFromConfig()* will replace *module_search_paths* and sets *module_search_paths_set* to `1`.

Default: empty list (`module_search_paths`) and `0` (`module_search_paths_set`).

Part of the *Python Path Configuration* output.

int **optimization_level**

Compilation optimization level:

- `0`: Peephole optimizer, set `__debug__` to `True`.
- `1`: Level 0, remove assertions, set `__debug__` to `False`.
- `2`: Level 1, strip docstrings.

Incremented by the `-O` command line option. Set to the `PYTHONOPTIMIZE` environment variable value.

Default: `0`.

PyWideStringList **orig_argv**

The list of the original command line arguments passed to the Python executable: `sys.orig_argv`.

If *orig_argv* list is empty and *argv* is not a list only containing an empty string, *PyConfig_Read()* copies *argv* into *orig_argv* before modifying *argv* (if *parse_argv* is non-zero).

See also the *argv* member and the *Py_GetArgcArgv()* function.

Default: empty list.

Added in version 3.10.

int **parse_argv**

Parse command line arguments?

If equals to `1`, parse *argv* the same way the regular Python parses command line arguments, and strip Python arguments from *argv*.

The *PyConfig_Read()* function only parses *PyConfig.argv* arguments once: *PyConfig.parse_argv* is set to `2` after arguments are parsed. Since Python arguments are stripped from *PyConfig.argv*, parsing arguments twice would parse the application options as Python options.

Default: `1` in Python mode, `0` in isolated mode.

3.10 sürümünde değişti: The *PyConfig.argv* arguments are now only parsed if *PyConfig.parse_argv* equals to `1`.

int **parser_debug**

Parser debug mode. If greater than `0`, turn on parser debugging output (for expert only, depending on compilation options).

Incremented by the `-d` command line option. Set to the `PYTHONDEBUG` environment variable value.

Needs a debug build of Python (the `Py_DEBUG` macro must be defined).

Default: `0`.

int **pathconfig_warnings**

If non-zero, calculation of path configuration is allowed to log warnings into `stderr`. If equals to `0`, suppress these warnings.

Default: `1` in Python mode, `0` in isolated mode.

Part of the *Python Path Configuration* input.

3.11 sürümünde değişti: Now also applies on Windows.

wchar_t ***prefix**

The site-specific directory prefix where the platform independent Python files are installed: `sys.prefix`.

Default: `NULL`.

Part of the *Python Path Configuration* output.

See also *`PyConfig.base_prefix`*.

wchar_t ***program_name**

Program name used to initialize *`executable`* and in early error messages during Python initialization.

- On macOS, use `PYTHONEXECUTABLE` environment variable if set.
- If the `WITH_NEXT_FRAMEWORK` macro is defined, use `__PYVENV_LAUNCHER__` environment variable if set.
- Use `argv[0]` of *`argv`* if available and non-empty.
- Otherwise, use `L"python"` on Windows, or `L"python3"` on other platforms.

Default: `NULL`.

Part of the *Python Path Configuration* input.

wchar_t ***pycache_prefix**

Directory where cached `.pyc` files are written: `sys.pycache_prefix`.

Set by the `-X pycache_prefix =PATH` command line option and the `PYTHONPYCACHEPREFIX` environment variable. The command-line option takes precedence.

If `NULL`, `sys.pycache_prefix` is set to `None`.

Default: `NULL`.

int **quiet**

Quiet mode. If greater than `0`, don't display the copyright and version at Python startup in interactive mode.

Incremented by the `-q` command line option.

Default: `0`.

wchar_t ***run_command**

Value of the `-c` command line option.

Used by *`Py_RunMain()`*.

Default: `NULL`.

wchar_t ***run_filename**

Filename passed on the command line: trailing command line argument without `-c` or `-m`. It is used by the *Py_RunMain()* function.

For example, it is set to `script.py` by the `python3 script.py arg` command line.

See also the *PyConfig.skip_source_first_line* option.

Default: `NULL`.

wchar_t ***run_module**

Value of the `-m` command line option.

Used by *Py_RunMain()*.

Default: `NULL`.

wchar_t ***run_presite**

`package.module` path to module that should be imported before `site.py` is run.

Set by the `-X presite =package.module` command-line option and the `PYTHON_PRESITE` environment variable. The command-line option takes precedence.

Needs a debug build of Python (the `Py_DEBUG` macro must be defined).

Default: `NULL`.

int **show_ref_count**

Show total reference count at exit (excluding *immortal* objects)?

Set to `1` by `-X showrefcount` command line option.

Needs a debug build of Python (the `Py_REF_DEBUG` macro must be defined).

Default: `0`.

int **site_import**

Import the `site` module at startup?

If equal to zero, disable the import of the module site and the site-dependent manipulations of `sys.path` that it entails.

Also disable these manipulations if the `site` module is explicitly imported later (call `site.main()` if you want them to be triggered).

Set to `0` by the `-S` command line option.

`sys.flags.no_site` is set to the inverted value of *site_import*.

Default: `1`.

int **skip_source_first_line**

If non-zero, skip the first line of the *PyConfig.run_filename* source.

It allows the usage of non-Unix forms of `#!cmd`. This is intended for a DOS specific hack only.

Set to `1` by the `-x` command line option.

Default: `0`.

wchar_t ***stdio_encoding**

wchar_t ***stdio_errors**

Encoding and encoding errors of `sys.stdin`, `sys.stdout` and `sys.stderr` (but `sys.stderr` always uses `"backslashreplace"` error handler).

Use the `PYTHONIOENCODING` environment variable if it is non-empty.

Default encoding:

- `"UTF-8"` if *PyPreConfig.utf8_mode* is non-zero.

- Otherwise, use the *locale encoding*.

Default error handler:

- On Windows: use `"surrogateescape"`.
- `"surrogateescape"` if *PyPreConfig.utf8_mode* is non-zero, or if the LC_CTYPE locale is "C" or "POSIX".
- `"strict"` otherwise.

See also *PyConfig.legacy_windows_stdio*.

int **tracemalloc**

Enable tracemalloc?

If non-zero, call `tracemalloc.start()` at startup.

Set by `-X tracemalloc =N` command line option and by the `PYTHONTRACEMALLOC` environment variable.

Default: `-1` in Python mode, `0` in isolated mode.

int **perf_profiling**

Enable the Linux `perf` profiler support?

If equals to `1`, enable support for the Linux `perf` profiler.

If equals to `2`, enable support for the Linux `perf` profiler with DWARF JIT support.

Set to `1` by `-X perf` command-line option and the `PYTHONPERFSUPPORT` environment variable.

Set to `2` by the `-X perf_jit` command-line option and the `PYTHON_PERF_JIT_SUPPORT` environment variable.

Default: `-1`.

Ayrıca bakınız

See perf_profiling for more information.

Added in version 3.12.

wchar_t ***stdlib_dir**

Directory of the Python standard library.

Default: `NULL`.

Added in version 3.11.

int **use_environment**

Use environment variables?

If equals to zero, ignore the environment variables.

Set to `0` by the `-E` environment variable.

Default: `1` in Python config and `0` in isolated config.

int **use_system_logger**

If non-zero, `stdout` and `stderr` will be redirected to the system log.

Only available on macOS 10.12 and later, and on iOS.

Default: `0` (don't use the system log) on macOS; `1` on iOS (use the system log).

Added in version 3.14.

int **user_site_directory**

If non-zero, add the user site directory to `sys.path`.

Set to `0` by the `-s` and `-I` command line options.

Set to `0` by the `PYTHONNOUSERSITE` environment variable.

Default: `1` in Python mode, `0` in isolated mode.

int **verbose**

Verbose mode. If greater than `0`, print a message each time a module is imported, showing the place (filename or built-in module) from which it is loaded.

If greater than or equal to `2`, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Incremented by the `-v` command line option.

Set by the `PYTHONVERBOSE` environment variable value.

Default: `0`.

PyWideStringList **warnoptions**

Options of the `warnings` module to build warnings filters, lowest to highest priority: `sys.warnoptions`.

The `warnings` module adds `sys.warnoptions` in the reverse order: the last *PyConfig.warnoptions* item becomes the first item of `warnings.filters` which is checked first (highest priority).

The `-W` command line options adds its value to *warnoptions*, it can be used multiple times.

The `PYTHONWARNINGS` environment variable can also be used to add warning options. Multiple options can be specified, separated by commas (`,`).

Default: empty list.

int **write_bytecode**

If equal to `0`, Python won't try to write `.pyc` files on the import of source modules.

Set to `0` by the `-B` command line option and the `PYTHONDONTWRITEBYTECODE` environment variable.

`sys.dont_write_bytecode` is initialized to the inverted value of *write_bytecode*.

Default: `1`.

PyWideStringList **xoptions**

Values of the `-X` command line options: `sys._xoptions`.

Default: empty list.

int **_pystats**

If non-zero, write performance statistics at Python exit.

Need a special build with the `Py_STATS` macro: see `--enable-pystats`.

Default: `0`.

If *parse_argv* is non-zero, *argv* arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from *argv*.

The *xoptions* options are parsed to set other options: see the `-X` command line option.

3.9 sürümünde değişti: The `show_alloc_count` field has been removed.

11.4.7 Initialization with PyConfig

Initializing the interpreter from a populated configuration struct is handled by calling *Py_InitializeFromConfig()*.

The caller is responsible to handle exceptions (error or exit) using *PyStatus_Exception()* and *Py_ExitStatusException()*.

If *PyImport_FrozenModules()*, *PyImport_AppendInittab()* or *PyImport_ExtendInittab()* are used, they must be set or called after Python preinitialization and before the Python initialization. If Python is initialized multiple times, *PyImport_AppendInittab()* or *PyImport_ExtendInittab()* must be called before each Python initialization.

The current configuration (`PyConfig` type) is stored in `PyInterpreterState.config`.

Example setting the program name:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name. Implicitly preinitialize Python. */
    status = PyConfig_SetString(&config, &config.program_name,
                                L"/path/to/my_program");
    if (PyStatus_Exception(status)) {
        goto exception;
    }

    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto exception;
    }
    PyConfig_Clear(&config);
    return;

exception:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
}
```

More complete example modifying the default configuration, read the configuration, and then override some parameters. Note that since 3.11, many parameters are not calculated until initialization, and so values cannot be read from the configuration structure. Any values set before initialize is called will be left unchanged by initialization:

```
PyStatus init_python(const char *program_name)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).

       Implicitly preinitialize Python. */
    status = PyConfig_SetBytesString(&config, &config.program_name,
                                     program_name);
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    if (PyStatus_Exception(status)) {
        goto done;
    }

    /* Read all configuration at once */
    status = PyConfig_Read(&config);
    if (PyStatus_Exception(status)) {
        goto done;
    }

    /* Specify sys.path explicitly */
    /* If you want to modify the default set of paths, finish
       initialization first and then use PySys_GetObject("path") */
    config.module_search_paths_set = 1;
    status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/stdlib");
    if (PyStatus_Exception(status)) {
        goto done;
    }
    status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
    if (PyStatus_Exception(status)) {
        goto done;
    }

    /* Override executable computed by PyConfig_Read() */
    status = PyConfig_SetString(&config, &config.executable,
                                L"/path/to/my_executable");
    if (PyStatus_Exception(status)) {
        goto done;
    }

    status = Py_InitializeFromConfig(&config);

done:
    PyConfig_Clear(&config);
    return status;
}
```

11.4.8 Isolated Configuration

PyPreConfig_InitIsolatedConfig() and *PyConfig_InitIsolatedConfig()* functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environment variables, command line arguments (*PyConfig.argv* is not parsed) and user site directory. The C standard streams (ex: `stdout`) and the LC_CTYPE locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration to determine paths that are unspecified. Ensure *PyConfig.home* is specified to avoid computing the default path configuration.

11.4.9 Python Configuration

PyPreConfig_InitPythonConfig() and *PyConfig_InitPythonConfig()* functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (**PEP 538**) and Python UTF-8 Mode (**PEP 540**) depending on the LC_CTYPE locale, `PYTHONUTF8` and `PYTHONCOERCECLOCALE` environment variables.

11.4.10 Python Path Configuration

PyConfig contains multiple fields for the path configuration:

- Path configuration inputs:
  - *PyConfig.home*
  - *PyConfig.platlibdir*
  - *PyConfig.pathconfig_warnings*
  - *PyConfig.program_name*
  - *PyConfig.pythonpath_env*
  - current working directory: to get absolute paths
  - `PATH` environment variable to get the program full path (from *PyConfig.program_name*)
  - `__PYVENV_LAUNCHER__` environment variable
  - (Windows only) Application paths in the registry under "SoftwarePythonPythonCoreX.YPythonPath" of HKEY_CURRENT_USER and HKEY_LOCAL_MACHINE (where X.Y is the Python version).
- Path configuration output fields:
  - *PyConfig.base_exec_prefix*
  - *PyConfig.base_executable*
  - *PyConfig.base_prefix*
  - *PyConfig.exec_prefix*
  - *PyConfig.executable*
  - *PyConfig.module_search_paths_set*, *PyConfig.module_search_paths*
  - *PyConfig.prefix*

If at least one "output field" is not set, Python calculates the path configuration to fill unset fields. If *module_search_paths_set* is equal to `0`, *module_search_paths* is overridden and *module_search_paths_set* is set to `1`.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. `module_search_paths` is considered as set if `module_search_paths_set` is set to `1`. In this case, `module_search_paths` will be used without modification.

Set *pathconfig_warnings* to `0` to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If *base_prefix* or *base_exec_prefix* fields are not set, they inherit their value from *prefix* and *exec_prefix* respectively.

Py_RunMain() and *Py_Main()* modify `sys.path`:

- If *run_filename* is set and is a directory which contains a `__main__.py` script, prepend *run_filename* to `sys.path`.
- If *isolated* is zero:
  - If *run_module* is set, prepend the current directory to `sys.path`. Do nothing if the current directory cannot be read.
  - If *run_filename* is set, prepend the directory of the filename to `sys.path`.
  - Otherwise, prepend an empty string to `sys.path`.

If *site_import* is non-zero, `sys.path` can be modified by the `site` module. If *user_site_directory* is non-zero and the user's site-package directory exists, the `site` module appends the user's site-package directory to `sys.path`.

The following configuration files are used by the path configuration:

- `pyvenv.cfg`
- `._pth` file (ex: `python._pth`)
- `pybuilddir.txt` (Unix only)

If a `._pth` file is present:

- Set *isolated* to `1`.
- Set *use_environment* to `0`.
- Set *site_import* to `0`.
- Set *safe_path* to `1`.

If *home* is not set and a `pyvenv.cfg` file is present in the same directory as *executable*, or its parent, *prefix* and *exec_prefix* are set that location. When this happens, *base_prefix* and *base_exec_prefix* still keep their value, pointing to the base installation. See sys-path-init-virtual-environments for more information.

The `__PYVENV_LAUNCHER__` environment variable is used to set *PyConfig.base_executable*.

3.14 sürümünde değişti: *prefix*, and *exec_prefix*, are now set to the `pyvenv.cfg` directory. This was previously done by `site`, therefore affected by `-S`.

11.5 Py_GetArgcArgv()

void **Py_GetArgcArgv**(int *argc, wchar_t ***argv)

Get the original command line arguments, before Python modified them.

See also *PyConfig.orig_argv* member.

11.6 Delaying main module execution

In some embedding use cases, it may be desirable to separate interpreter initialization from the execution of the main module.

This separation can be achieved by setting `PyConfig.run_command` to the empty string during initialization (to prevent the interpreter from dropping into the interactive prompt), and then subsequently executing the desired main module code using `__main__.__dict__` as the global namespace.

BÖLÜM 12

Memory Management

12.1 Overview

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: `malloc()`, `calloc()`, `realloc()` and `free()`. This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

Ayrıca bakınız

The `PYTHONMALLOC` environment variable can be used to configure the memory allocators used by Python.

The `PYTHONMALLOCSTATS` environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

12.2 Allocator Domains

All allocating functions belong to one of three different "domains" (see also `PyMemAllocatorDomain`). These domains represent different allocation strategies and are optimized for different purposes. The specific details on how every domain allocates memory or what internal functions each domain calls is considered an implementation detail, but for debugging purposes a simplified table can be found at *here*. The APIs used to allocate and free a block of memory must be from the same domain. For example, `PyMem_Free()` must be used to free memory allocated using `PyMem_Malloc()`.

The three allocation domains are:

- Raw domain: intended for allocating memory for general-purpose memory buffers where the allocation *must* go to the system allocator or where the allocator can operate without an *attached thread state*. The memory is requested directly from the system. See *Raw Memory Interface*.
- "Mem" domain: intended for allocating memory for Python buffers and general-purpose memory buffers where the allocation must be performed with an *attached thread state*. The memory is taken from the Python private heap. See *Memory Interface*.
- Object domain: intended for allocating memory for Python objects. The memory is taken from the Python private heap. See *Object allocators*.

Not

The *free-threaded* build requires that only Python objects are allocated using the "object" domain and that all Python objects are allocated using that domain. This differs from the prior Python versions, where this was only a best practice and not a hard requirement.

For example, buffers (non-Python objects) should be allocated using `PyMem_Malloc()`, `PyMem_RawMalloc()`, or `malloc()`, but not `PyObject_Malloc()`.

See Memory Allocation APIs.

12.3 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, so a *thread state* does not need to be *attached*.

The *default raw memory allocator* uses the following functions: `malloc()`, `calloc()`, `realloc()` and `free()`; call `malloc(1)` (or `calloc(1, 1)`) when requesting zero bytes.

Added in version 3.4.

void *`PyMem_RawMalloc`(size_t n)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawMalloc(1)` had been called instead. The memory will not have been initialized in any way.

void *`PyMem_RawCalloc`(size_t nelem, size_t elsize)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_RawCalloc(1, 1)` had been called instead.

Added in version 3.5.

void *`PyMem_RawRealloc`(void *p, size_t n)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyMem_RawMalloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to *`PyMem_RawMalloc()`*, *`PyMem_RawRealloc()`* or *`PyMem_RawCalloc()`*.

If the request fails, *`PyMem_RawRealloc()`* returns `NULL` and *p* remains a valid pointer to the previous memory area.

void `PyMem_RawFree`(void *p)

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Frees the memory block pointed to by *p*, which must have been returned by a previous call to *`PyMem_RawMalloc()`*, *`PyMem_RawRealloc()`* or *`PyMem_RawCalloc()`*. Otherwise, or if `PyMem_RawFree(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

12.4 Memory Interface

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The *default memory allocator* uses the *pymalloc memory allocator*.

Uyarı

There must be an *attached thread state* when using these functions.

3.6 sürümünde değişti: The default allocator is now pymalloc instead of system `malloc()`.

void *`PyMem_Malloc`(size_t n)

Bir parçası Kararlı ABI. Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void *`PyMem_Calloc`(size_t nelem, size_t elsize)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyMem_Calloc(1, 1)` had been called instead.

Added in version 3.5.

void ***PyMem_Realloc**(void *p, size_t n)

Bir parçası Kararlı ABI. Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyMem_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to *PyMem_Malloc()*, *PyMem_Realloc()* or *PyMem_Calloc()*.

If the request fails, *PyMem_Realloc()* returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyMem_Free**(void *p)

Bir parçası Kararlı ABI. Frees the memory block pointed to by *p*, which must have been returned by a previous call to *PyMem_Malloc()*, *PyMem_Realloc()* or *PyMem_Calloc()*. Otherwise, or if `PyMem_Free(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

The following type-oriented macros are provided for convenience. Note that *TYPE* refers to any C type.

PyMem_New(TYPE, n)

Same as *PyMem_Malloc()*, but allocates `(n * sizeof(TYPE))` bytes of memory. Returns a pointer cast to `TYPE*`. The memory will not have been initialized in any way.

PyMem_Resize(p, TYPE, n)

Same as *PyMem_Realloc()*, but the memory block is resized to `(n * sizeof(TYPE))` bytes. Returns a pointer cast to `TYPE*`. On return, *p* will be a pointer to the new memory area, or `NULL` in the event of failure.

This is a C preprocessor macro; *p* is always reassigned. Save the original value of *p* to avoid losing memory when handling errors.

void **PyMem_Del**(void *p)

Same as *PyMem_Free()*.

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- `PyMem_MALLOC(size)`
- `PyMem_NEW(type, size)`
- `PyMem_REALLOC(ptr, size)`
- `PyMem_RESIZE(ptr, type, size)`
- `PyMem_FREE(ptr)`
- `PyMem_DEL(ptr)`

12.5 Object allocators

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

Not

There is no guarantee that the memory returned by these allocators can be successfully cast to a Python object when intercepting the allocating functions in this domain by the methods described in the *Customize Memory Allocators* section.

The *default object allocator* uses the *pymalloc memory allocator*.

Uyarı

There must be an *attached thread state* when using these functions.

void ***PyObject_Malloc**(size_t n)

Bir parçası Kararlı ABI. Allocates *n* bytes and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails.

Requesting zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Malloc(1)` had been called instead. The memory will not have been initialized in any way.

void ***PyObject_Calloc**(size_t nelem, size_t elsize)

Bir parçası Kararlı ABI *3.7 sürümünden beri.* Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type `void*` to the allocated memory, or `NULL` if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-`NULL` pointer if possible, as if `PyObject_Calloc(1, 1)` had been called instead.

Added in version 3.5.

void ***PyObject_Realloc**(void *p, size_t n)

Bir parçası Kararlı ABI. Resizes the memory block pointed to by *p* to *n* bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If *p* is `NULL`, the call is equivalent to `PyObject_Malloc(n)`; else if *n* is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-`NULL`.

Unless *p* is `NULL`, it must have been returned by a previous call to *`PyObject_Malloc()`*, *`PyObject_Realloc()`* or *`PyObject_Calloc()`*.

If the request fails, *`PyObject_Realloc()`* returns `NULL` and *p* remains a valid pointer to the previous memory area.

void **PyObject_Free**(void *p)

Bir parçası Kararlı ABI. Frees the memory block pointed to by *p*, which must have been returned by a previous call to *`PyObject_Malloc()`*, *`PyObject_Realloc()`* or *`PyObject_Calloc()`*. Otherwise, or if `PyObject_Free(p)` has been called before, undefined behavior occurs.

If *p* is `NULL`, no operation is performed.

Do not call this directly to free an object's memory; call the type's *`tp_free`* slot instead.

Do not use this for memory allocated by *`PyObject_GC_New`* or *`PyObject_GC_NewVar`*; use *`PyObject_GC_Del()`* instead.

Ayrıca bakınız

- *`PyObject_GC_Del()`* is the equivalent of this function for memory allocated by types that support garbage collection.
- *`PyObject_Malloc()`*

- *PyObject_Realloc()*
- *PyObject_Calloc()*
- *PyObject_New*
- *PyObject_NewVar*
- *PyType_GenericAlloc()*
- *tp_free*

12.6 Default Memory Allocators

Default memory allocators:

Configuration	Name	PyMem_RawMalloc	PyMem_Malloc	PyObject_Malloc
Release build	`"pymalloc"`	`malloc`	`pymalloc`	`pymalloc`
Debug build	`"pymalloc_debug`	`malloc` + debug	`pymalloc` + debug	`pymalloc` + debug
Release build, without pymalloc	`"malloc"`	`malloc`	`malloc`	`malloc`
Debug build, without pymalloc	`"malloc_debug"`	`malloc` + debug	`malloc` + debug	`malloc` + debug

Legend:

- Name: value for `PYTHONMALLOC` environment variable.
- `malloc`: system allocators from the standard C library, C functions: `malloc()`, `calloc()`, `realloc()` and `free()`.
- `pymalloc`: *pymalloc memory allocator*.
- `mimalloc`: *mimalloc memory allocator*. The pymalloc allocator will be used if mimalloc support isn't available.
- "+ debug": with *debug hooks on the Python memory allocators*.
- "Debug build": Python build in debug mode.

12.7 Customize Memory Allocators

Added in version 3.4.

type **PyMemAllocatorEx**

Structure used to describe a memory block allocator. The structure has the following fields:

Field	Meaning
`void *ctx`	user context passed as first argument
`void* malloc(void *ctx, size_t size)`	allocate a memory block
`void* calloc(void *ctx, size_t nelem, size_t elsize)`	allocate a memory block initialized with zeros
`void* realloc(void *ctx, void *ptr, size_t new_size)`	allocate or resize a memory block
`void free(void *ctx, void *ptr)`	free a memory block

3.5 sürümünde değişti: The `PyMemAllocator` structure was renamed to *PyMemAllocatorEx* and a new `calloc` field was added.

type **PyMemAllocatorDomain**

Enum used to identify an allocator domain. Domains:

PYMEM_DOMAIN_RAW

Functions:

- *PyMem_RawMalloc()*
- *PyMem_RawRealloc()*
- *PyMem_RawCalloc()*
- *PyMem_RawFree()*

PYMEM_DOMAIN_MEM

Functions:

- *PyMem_Malloc()*,
- *PyMem_Realloc()*
- *PyMem_Calloc()*
- *PyMem_Free()*

PYMEM_DOMAIN_OBJ

Functions:

- *PyObject_Malloc()*
- *PyObject_Realloc()*
- *PyObject_Calloc()*
- *PyObject_Free()*

void **PyMem_GetAllocator**(*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* *allocator)

Get the memory block allocator of the specified domain.

void **PyMem_SetAllocator**(*PyMemAllocatorDomain* domain, *PyMemAllocatorEx* *allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-`NULL` pointer when requesting zero bytes.

For the *PYMEM_DOMAIN_RAW* domain, the allocator must be thread-safe: a *thread state* is not *attached* when the allocator is called.

For the remaining domains, the allocator must also be thread-safe: the allocator may be called in different interpreters that do not share a *GIL*.

If the new allocator is not a hook (does not call the previous allocator), the *PyMem_SetupDebugHooks()* function must be called to reinstall the debug hooks on top on the new allocator.

See also *PyPreConfig.allocator* and *Preinitialize Python with PyPreConfig*.

Uyarı

PyMem_SetAllocator() does have the following contract:

- It can be called after *Py_PreInitialize()* and before *Py_InitializeFromConfig()* to install a custom memory allocator. There are no restrictions over the installed allocator other than the ones imposed by the domain (for instance, the Raw Domain allows the allocator to be called without an *attached thread state*). See *the section on allocator domains* for more information.
- If called after Python has finish initializing (after *Py_InitializeFromConfig()* has been called) the allocator **must** wrap the existing allocator. Substituting the current allocator for some other arbitrary one is **not supported**.

3.12 sürümünde değişti: All allocators must be thread-safe.

void **PyMem_SetupDebugHooks**(void)

Setup *debug hooks in the Python memory allocators* to detect memory errors.

12.8 Debug hooks on the Python memory allocators

When Python is built in debug mode, the *PyMem_SetupDebugHooks()* function is called at the *Python preinitialization* to setup debug hooks on Python memory allocators to detect memory errors.

The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode (ex: PYTHONMALLOC =debug).

The *PyMem_SetupDebugHooks()* function can be used to set debug hooks after calling *PyMem_SetAllocator()*.

These debug hooks fill dynamically allocated memory blocks with special, recognizable bit patterns. Newly allocated memory is filled with the byte 0xCD (PYMEM_CLEANBYTE), freed memory is filled with the byte 0xDD (PYMEM_DEADBYTE). Memory blocks are surrounded by "forbidden bytes" filled with the byte 0xFD (PYMEM_FORBIDDENBYTE). Strings of these bytes are unlikely to be valid addresses, floats, or ASCII strings.

Runtime checks:

- Detect API violations. For example, detect if *PyObject_Free()* is called on a memory block allocated by *PyMem_Malloc()*.
- Detect write before the start of the buffer (buffer underflow).
- Detect write after the end of the buffer (buffer overflow).
- Check that there is an *attached thread state* when allocator functions of *PYMEM_DOMAIN_OBJ* (ex: *PyObject_Malloc()*) and *PYMEM_DOMAIN_MEM* (ex: *PyMem_Malloc()*) domains are called.

On error, the debug hooks use the tracemalloc module to get the traceback where a memory block was allocated. The traceback is only displayed if tracemalloc is tracing Python memory allocations and the memory block was traced.

Let *S* = sizeof(size_t).2*S bytes are added at each end of each block of *N* bytes requested. The memory layout is like so, where p represents the address returned by a malloc-like or realloc-like function (p[i:j] means the slice of bytes from *(p+i) inclusive up to *(p+j) exclusive; note that the treatment of negative indices differs from a Python slice):

p[-2*S:-S]
Number of bytes originally asked for. This is a size_t, big-endian (easier to read in a memory dump).

p[-S]
API identifier (ASCII character):

- 'r' for *PYMEM_DOMAIN_RAW*.
- 'm' for *PYMEM_DOMAIN_MEM*.
- 'o' for *PYMEM_DOMAIN_OBJ*.

p[-S+1:0]
Copies of PYMEM_FORBIDDENBYTE. Used to catch under- writes and reads.

p[0:N]
The requested memory, filled with copies of PYMEM_CLEANBYTE, used to catch reference to uninitialized memory. When a realloc-like function is called requesting a larger memory block, the new excess bytes are also filled with PYMEM_CLEANBYTE. When a free-like function is called, these are overwritten with PYMEM_DEADBYTE, to catch reference to freed memory. When a realloc- like function is called requesting a smaller memory block, the excess old bytes are also filled with PYMEM_DEADBYTE.

p[N:N+S]
Copies of PYMEM_FORBIDDENBYTE. Used to catch over- writes and reads.

p[N+S:N+2*S]

Only used if the PYMEM_DEBUG_SERIALNO macro is defined (not defined by default).

A serial number, incremented by 1 on each call to a malloc-like or realloc-like function. Big-endian size_t. If "bad memory" is detected later, the serial number gives an excellent way to set a breakpoint on the next run, to capture the instant at which this block was passed out. The static function bumpserialno() in obmalloc.c is the only place the serial number is incremented, and exists so you can set such a breakpoint easily.

A realloc-like or free-like function first checks that the PYMEM_FORBIDDENBYTE bytes at each end are intact. If they've been altered, diagnostic output is written to stderr, and the program is aborted via Py_FatalError(). The other main failure mode is provoking a memory error when a program reads up one of the special bit patterns and tries to use it as an address. If you get in a debugger then and look at the object, you're likely to see that it's entirely filled with PYMEM_DEADBYTE (meaning freed memory is getting used) or PYMEM_CLEANBYTE (meaning uninitialized memory is getting used).

3.6 sürümünde değişti: The *PyMem_SetupDebugHooks()* function now also works on Python compiled in release mode. On error, the debug hooks now use tracemalloc to get the traceback where a memory block was allocated. The debug hooks now also check if there is an *attached thread state* when functions of *PYMEM_DOMAIN_OBJ* and *PYMEM_DOMAIN_MEM* domains are called.

3.8 sürümünde değişti: Byte patterns 0xCB (PYMEM_CLEANBYTE), 0xDB (PYMEM_DEADBYTE) and 0xFB (PYMEM_FORBIDDENBYTE) have been replaced with 0xCD, 0xDD and 0xFD to use the same values than Windows CRT debug malloc() and free().

12.9 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called "arenas" with a fixed size of either 256 KiB on 32-bit platforms or 1 MiB on 64-bit platforms. It falls back to *PyMem_RawMalloc()* and *PyMem_RawRealloc()* for allocations larger than 512 bytes.

pymalloc is the *default allocator* of the *PYMEM_DOMAIN_MEM* (ex: *PyMem_Malloc()*) and *PYMEM_DOMAIN_OBJ* (ex: *PyObject_Malloc()*) domains.

The arena allocator uses the following functions:

- VirtualAlloc() and VirtualFree() on Windows,
- mmap() and munmap() if available,
- malloc() and free() otherwise.

This allocator is disabled if Python is configured with the --without-pymalloc option. It can also be disabled at runtime using the PYTHONMALLOC environment variable (ex: PYTHONMALLOC =malloc).

Typically, it makes sense to disable the pymalloc allocator when building Python with AddressSanitizer (--with-address-sanitizer) which helps uncover low level bugs within the C code.

12.9.1 Customize pymalloc Arena Allocator

Added in version 3.4.

type **PyObjectArenaAllocator**

Structure used to describe an arena allocator. The structure has three fields:

Field	Meaning
void *ctx	user context passed as first argument
void* alloc(void *ctx, size_t size)	allocate an arena of size bytes
void free(void *ctx, void *ptr, size_t size)	free an arena

void **PyObject_GetArenaAllocator**(*PyObjectArenaAllocator* *allocator)

Get the arena allocator.

void **PyObject_SetArenaAllocator**(*PyObjectArenaAllocator* *allocator)

Set the arena allocator.

12.10 The mimalloc allocator

Added in version 3.13.

Python supports the mimalloc allocator when the underlying platform support is available. mimalloc "is a general purpose allocator with excellent performance characteristics. Initially developed by Daan Leijen for the runtime systems of the Koka and Lean languages."

12.11 tracemalloc C API

Added in version 3.7.

int **PyTraceMalloc_Track**(unsigned int domain, uintptr_t ptr, size_t size)

Track an allocated memory block in the `tracemalloc` module.

Return `0` on success, return `-1` on error (failed to allocate memory to store the trace). Return `-2` if tracemalloc is disabled.

If memory block is already tracked, update the existing trace.

int **PyTraceMalloc_Untrack**(unsigned int domain, uintptr_t ptr)

Untrack an allocated memory block in the `tracemalloc` module. Do nothing if the block was not tracked.

Return `-2` if tracemalloc is disabled, otherwise return `0`.

12.12 Examples

Here is the example from section *Overview*, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3);  /* Wrong -- should be PyMem_Free() */
free(buf2);       /* Right -- allocated via malloc() */
free(buf1);       /* Fatal -- should be PyMem_Free()  */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with *PyObject_New*, *PyObject_NewVar* and *PyObject_Free()*.

These will be explained in the next chapter on defining and implementing new object types in C.

BÖLÜM 13

Object Implementation Support

This chapter describes the functions, types, and macros used when defining new object types.

13.1 Allocating Objects on the Heap

PyObject ***_PyObject_New**(*PyTypeObject* *type)

Döndürdüğü değer: Yeni referans.

PyVarObject ***_PyObject_NewVar**(*PyTypeObject* *type, *Py_ssize_t* size)

Döndürdüğü değer: Yeni referans.

PyObject ***PyObject_Init**(*PyObject* *op, *PyTypeObject* *type)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. Initialize a newly allocated object *op* with its type and initial reference. Returns the initialized object. Other fields of the object are not initialized. Despite its name, this function is unrelated to the object's `__init__()` method (`tp_init` slot). Specifically, this function does **not** call the object's `__init__()` method.

In general, consider this function to be a low-level routine. Use `tp_alloc` where possible. For implementing `tp_alloc` for your type, prefer `PyType_GenericAlloc()` or `PyObject_New()`.

> **Not**
>
> This function only initializes the object's memory corresponding to the initial `PyObject` structure. It does not zero the rest.

PyVarObject ***PyObject_InitVar**(*PyVarObject* *op, *PyTypeObject* *type, *Py_ssize_t* size)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI. This does everything `PyObject_Init()` does, and also initializes the length information for a variable-size object.

> **Not**
>
> This function only initializes some of the object's memory. It does not zero the rest.

PyObject_New(TYPE, typeobj)

Allocates a new Python object using the C structure type *TYPE* and the Python type object *typeobj* (`PyTypeObject*`) by calling *PyObject_Malloc()* to allocate memory and initializing it like *PyObject_Init()*. The caller will own the only reference to the object (i.e. its reference count will be one).

Avoid calling this directly to allocate memory for an object; call the type's *tp_alloc* slot instead.

When populating a type's *tp_alloc* slot, *PyType_GenericAlloc()* is preferred over a custom function that simply calls this macro.

This macro does not call *tp_alloc*, *tp_new* (`__new__()`), or *tp_init* (`__init__()`).

This cannot be used for objects with *Py_TPFLAGS_HAVE_GC* set in *tp_flags*; use *PyObject_GC_New* instead.

Memory allocated by this macro must be freed with *PyObject_Free()* (usually called via the object's *tp_free* slot).

Not

The returned memory is not guaranteed to have been completely zeroed before it was initialized.

Not

This macro does not construct a fully initialized object of the given type; it merely allocates memory and prepares it for further initialization by *tp_init*. To construct a fully initialized object, call *typeobj* instead. For example:

```
PyObject *foo = PyObject_CallNoArgs((PyObject *)&PyFoo_Type);
```

Ayrıca bakınız

- *PyObject_Free()*
- *PyObject_GC_New*
- *PyType_GenericAlloc()*
- *tp_alloc*

PyObject_NewVar(TYPE, typeobj, size)

Like *PyObject_New* except:

- It allocates enough memory for the *TYPE* structure plus *size* (`Py_ssize_t`) fields of the size given by the *tp_itemsize* field of *typeobj*.
- The memory is initialized like *PyObject_InitVar()*.

This is useful for implementing objects like tuples, which are able to determine their size at construction time. Embedding the array of fields into the same allocation decreases the number of allocations, improving the memory management efficiency.

Avoid calling this directly to allocate memory for an object; call the type's *tp_alloc* slot instead.

When populating a type's *tp_alloc* slot, *PyType_GenericAlloc()* is preferred over a custom function that simply calls this macro.

This cannot be used for objects with *Py_TPFLAGS_HAVE_GC* set in *tp_flags*; use *PyObject_GC_NewVar* instead.

Memory allocated by this function must be freed with *PyObject_Free()* (usually called via the object's *tp_free* slot).

Not

The returned memory is not guaranteed to have been completely zeroed before it was initialized.

Not

This macro does not construct a fully initialized object of the given type; it merely allocates memory and prepares it for further initialization by *tp_init*. To construct a fully initialized object, call *typeobj* instead. For example:

```
PyObject *list_instance = PyObject_CallNoArgs((PyObject *)&PyList_Type);
```

Ayrıca bakınız

- *PyObject_Free()*
- *PyObject_GC_NewVar*
- *PyType_GenericAlloc()*
- *tp_alloc*

void **PyObject_Del**(void *op)

Same as *PyObject_Free()*.

PyObject **_Py_NoneStruct**

Object which is visible in Python as `None`. This should only be accessed using the *Py_None* macro, which evaluates to a pointer to this object.

Ayrıca bakınız

Module Objects
To allocate and create extension modules.

13.2 Object Life Cycle

This section explains how a type's slots relate to each other throughout the life of an object. It is not intended to be a complete canonical reference for the slots; instead, refer to the slot-specific documentation in *Type Object Structures* for details about a particular slot.

13.2.1 Life Events

The figure below illustrates the order of events that can occur throughout an object's life. An arrow from *A* to *B* indicates that event *B* can occur after event *A* has occurred, with the arrow's label indicating the condition that must be true for *B* to occur after *A*.


type call
tp_new
direct call
tp_alloc
tp_init
reachable
not in a cyclic isolate
periodic cyclic isolate detection
tp_traverse
no refs
resurrected (maybe remove finalized mark)
cyclic isolate
marked as finalized?
no (mark as finalized)
cyclic isolate (no GC support)
tp_finalize
yes
no refs
no refs or cyclic isolate
tp_clear
recommended call (see explanation)
no refs
cyclic isolate
uncollectable (leaked)
no refs
tp_dealloc
direct call
tp_free

Explanation:

- When a new object is constructed by calling its type:
  1. *tp_new* is called to create a new object.
  2. *tp_alloc* is directly called by *tp_new* to allocate the memory for the new object.
  3. *tp_init* initializes the newly created object. `tp_init` can be called again to re-initialize an object, if desired. The `tp_init` call can also be skipped entirely, for example by Python code calling `__new__()`.
- After `tp_init` completes, the object is ready to use.
- Some time after the last reference to an object is removed:
  1. If an object is not marked as *finalized*, it might be finalized by marking it as *finalized* and calling its *tp_finalize* function. Python does *not* finalize an object when the last reference to it is deleted; use *PyObject_CallFinalizerFromDealloc()* to ensure that *tp_finalize* is always called.
  2. If the object is marked as finalized, *tp_clear* might be called by the garbage collector to clear references held by the object. It is *not* called when the object's reference count reaches zero.
  3. *tp_dealloc* is called to destroy the object. To avoid code duplication, *tp_dealloc* typically calls into *tp_clear* to free up the object's references.
  4. When *tp_dealloc* finishes object destruction, it directly calls *tp_free* (usually set to *PyObject_Free()* or *PyObject_GC_Del()* automatically as appropriate for the type) to deallocate the memory.
- The *tp_finalize* function is permitted to add a reference to the object if desired. If it does, the object is *resurrected*, preventing its pending destruction. (Only `tp_finalize` is allowed to resurrect an object; *tp_clear* and *tp_dealloc* cannot without calling into `tp_finalize`.) Resurrecting an object may or may not cause the object's *finalized* mark to be removed. Currently, Python does not remove the *finalized* mark from a resurrected object if it supports garbage collection (i.e., the *Py_TPFLAGS_HAVE_GC* flag is set) but does remove the mark if the object does not support garbage collection; either or both of these behaviors may change in the future.
- *tp_dealloc* can optionally call *tp_finalize* via *PyObject_CallFinalizerFromDealloc()* if it wishes to reuse that code to help with object destruction. This is recommended because it guarantees that `tp_finalize` is always called before destruction. See the *tp_dealloc* documentation for example code.
- If the object is a member of a *cyclic isolate* and either *tp_clear* fails to break the reference cycle or the cyclic isolate is not detected (perhaps `gc.disable()` was called, or the *Py_TPFLAGS_HAVE_GC* flag was erroneously omitted in one of the involved types), the objects remain indefinitely uncollectable (they "leak"). See `gc.garbage`.

If the object is marked as supporting garbage collection (the *Py_TPFLAGS_HAVE_GC* flag is set in *tp_flags*), the following events are also possible:

- The garbage collector occasionally calls *tp_traverse* to identify *cyclic isolates*.
- When the garbage collector discovers a *cyclic isolate*, it finalizes one of the objects in the group by marking it as *finalized* and calling its *tp_finalize* function, if it has one. This repeats until the cyclic isolate doesn't exist or all of the objects have been finalized.
- *tp_finalize* is permitted to resurrect the object by adding a reference from outside the *cyclic isolate*. The new reference causes the group of objects to no longer form a cyclic isolate (the reference cycle may still exist, but if it does the objects are no longer isolated).
- When the garbage collector discovers a *cyclic isolate* and all of the objects in the group have already been marked as *finalized*, the garbage collector clears one or more of the uncleared objects in the group (possibly concurrently) by calling each's *tp_clear* function. This repeats as long as the cyclic isolate still exists and not all of the objects have been cleared.

13.2.2 Cyclic Isolate Destruction

Listed below are the stages of life of a hypothetical *cyclic isolate* that continues to exist after each member object is finalized or cleared. It is a memory leak if a cyclic isolate progresses through all of these stages; it should vanish once all objects are cleared, if not sooner. A cyclic isolate can vanish either because the reference cycle is broken or because the objects are no longer isolated due to finalizer resurrection (see `tp_finalize`).

0. **Reachable** (not yet a cyclic isolate): All objects are in their normal, reachable state. A reference cycle could exist, but an external reference means the objects are not yet isolated.
1. **Unreachable but consistent:** The final reference from outside the cyclic group of objects has been removed, causing the objects to become isolated (thus a cyclic isolate is born). None of the group's objects have been finalized or cleared yet. The cyclic isolate remains at this stage until some future run of the garbage collector (not necessarily the next run because the next run might not scan every object).
2. **Mix of finalized and not finalized:** Objects in a cyclic isolate are finalized one at a time, which means that there is a period of time when the cyclic isolate is composed of a mix of finalized and non-finalized objects. Finalization order is unspecified, so it can appear random. A finalized object must behave in a sane manner when non-finalized objects interact with it, and a non-finalized object must be able to tolerate the finalization of an arbitrary subset of its referents.
3. **All finalized:** All objects in a cyclic isolate are finalized before any of them are cleared.
4. **Mix of finalized and cleared:** The objects can be cleared serially or concurrently (but with the *GIL* held); either way, some will finish before others. A finalized object must be able to tolerate the clearing of a subset of its referents. **PEP 442** calls this stage "cyclic trash".
5. **Leaked:** If a cyclic isolate still exists after all objects in the group have been finalized and cleared, then the objects remain indefinitely uncollectable (see `gc.garbage`). It is a bug if a cyclic isolate reaches this stage—it means the `tp_clear` methods of the participating objects have failed to break the reference cycle as required.

If `tp_clear` did not exist, then Python would have no way to safely break a reference cycle. Simply destroying an object in a cyclic isolate would result in a dangling pointer, triggering undefined behavior when an object referencing the destroyed object is itself destroyed. The clearing step makes object destruction a two-phase process: first `tp_clear` is called to partially destroy the objects enough to detangle them from each other, then `tp_dealloc` is called to complete the destruction.

Unlike clearing, finalization is not a phase of destruction. A finalized object must still behave properly by continuing to fulfill its design contracts. An object's finalizer is allowed to execute arbitrary Python code, and is even allowed to prevent the impending destruction by adding a reference. The finalizer is only related to destruction by call order—if it runs, it runs before destruction, which starts with `tp_clear` (if called) and concludes with `tp_dealloc`.

The finalization step is not necessary to safely reclaim the objects in a cyclic isolate, but its existence makes it easier to design types that behave in a sane manner when objects are cleared. Clearing an object might necessarily leave it in a broken, partially destroyed state—it might be unsafe to call any of the cleared object's methods or access any of its attributes. With finalization, only finalized objects can possibly interact with cleared objects; non-finalized objects are guaranteed to interact with only non-cleared (but potentially finalized) objects.

To summarize the possible interactions:

- A non-finalized object might have references to or from non-finalized and finalized objects, but not to or from cleared objects.
- A finalized object might have references to or from non-finalized, finalized, and cleared objects.
- A cleared object might have references to or from finalized and cleared objects, but not to or from non-finalized objects.

Without any reference cycles, an object can be simply destroyed once its last reference is deleted; the finalization and clearing steps are not necessary to safely reclaim unused objects. However, it can be useful to automatically call `tp_finalize` and `tp_clear` before destruction anyway because type design is simplified when all objects always experience the same series of events regardless of whether they participated in a cyclic isolate. Python currently only calls `tp_finalize` and `tp_clear` as needed to destroy a cyclic isolate; this may change in a future version.

13.2.3 Functions

To allocate and free memory, see *Allocating Objects on the Heap*.

void **PyObject_CallFinalizer**(*PyObject* *op)

Finalizes the object as described in `tp_finalize`. Call this function (or `PyObject_CallFinalizerFromDealloc()`) instead of calling `tp_finalize` directly because this function may deduplicate multiple calls to `tp_finalize`. Currently, calls are only deduplicated if the type supports garbage collection (i.e., the `Py_TPFLAGS_HAVE_GC` flag is set); this may change in the future.

int **PyObject_CallFinalizerFromDealloc**(*PyObject* *op)

Same as `PyObject_CallFinalizer()` but meant to be called at the beginning of the object's destructor (`tp_dealloc`). There must not be any references to the object. If the object's finalizer resurrects the object, this function returns -1; no further destruction should happen. Otherwise, this function returns 0 and destruction can continue normally.

Ayrıca bakınız

`tp_dealloc` for example code.

13.3 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

13.3.1 Base object types and macros

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the `PyObject` and `PyVarObject` types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects. Additional macros can be found under *reference counting*.

type **PyObject**

Bir parçası Sınırlı API. *(Sadece bazı üyeler kararlı ABI'ın bir parçasıdır.)* All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal "release" build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a `PyObject`, but every pointer to a Python object can be cast to a `PyObject*`.

The members must not be accessed directly; instead use macros such as `Py_REFCNT` and `Py_TYPE`.

Py_ssize_t **ob_refcnt**

Bir parçası Kararlı ABI. The object's reference count, as returned by `Py_REFCNT`. Do not use this field directly; instead use functions and macros such as `Py_REFCNT`, `Py_INCREF()` and `Py_DecRef()`.

The field type may be different from `Py_ssize_t`, depending on build configuration and platform.

PyTypeObject ***ob_type**

Bir parçası Kararlı ABI. The object's type. Do not use this field directly; use `Py_TYPE` and `Py_SET_TYPE()` instead.

type **PyVarObject**

Bir parçası Sınırlı API. *(Sadece bazı üyeler kararlı ABI'ın bir parçasıdır.)* An extension of `PyObject` that adds the `ob_size` field. This is intended for objects that have some notion of *length*.

As with `PyObject`, the members must not be accessed directly; instead use macros such as `Py_SIZE`, `Py_REFCNT` and `Py_TYPE`.

Py_ssize_t **ob_size**

Bir parçası Kararlı ABI. A size field, whose contents should be considered an object's internal implementation detail.

Do not use this field directly; use *Py_SIZE* instead.

Object creation functions such as *PyObject_NewVar()* will generally set this field to the requested size (number of items). After creation, arbitrary values can be stored in `ob_size` using *Py_SET_SIZE*.

To get an object's publicly exposed length, as returned by the Python function `len()`, use *PyObject_Length()* instead.

PyObject_HEAD

This is a macro used when declaring new types which represent objects without a varying length. The PyObject_HEAD macro expands to:

```
PyObject ob_base;
```

See documentation of *PyObject* above.

PyObject_VAR_HEAD

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The PyObject_VAR_HEAD macro expands to:

```
PyVarObject ob_base;
```

See documentation of *PyVarObject* above.

PyTypeObject **PyBaseObject_Type**

Bir parçası Kararlı ABI. The base class of all other objects, the same as `object` in Python.

int **Py_Is**(*PyObject* *x, *PyObject* *y)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Test if the *x* object is the *y* object, the same as `x is y` in Python.

Added in version 3.10.

int **Py_IsNone**(*PyObject* *x)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Test if an object is the `None` singleton, the same as `x is None` in Python.

Added in version 3.10.

int **Py_IsTrue**(*PyObject* *x)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Test if an object is the `True` singleton, the same as `x is True` in Python.

Added in version 3.10.

int **Py_IsFalse**(*PyObject* *x)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Test if an object is the `False` singleton, the same as `x is False` in Python.

Added in version 3.10.

PyTypeObject ***Py_TYPE**(*PyObject* *o)

Döndürdüğü değer: Ödünç alınmış referans. Bir parçası Kararlı ABI *3.14 sürümünden beri.* Get the type of the Python object *o*.

The returned reference is *borrowed* from *o*. Do not release it with *Py_DECREF()* or similar.

3.11 sürümünde değişti: *Py_TYPE()* is changed to an inline static function. The parameter type is no longer `const` *PyObject*`*`.

int **Py_IS_TYPE**(*PyObject* *o, *PyTypeObject* *type)

Return non-zero if the object *o* type is *type*. Return zero otherwise. Equivalent to: `Py_TYPE(o) == type`.

Added in version 3.9.

void **Py_SET_TYPE**(*PyObject* *o, *PyTypeObject* *type)

Set the type of object *o* to *type*, without any checking or reference counting.

This is a very low-level operation. Consider instead setting the Python attribute `__class__` using *PyObject_SetAttrString()* or similar.

Note that assigning an incompatible type can lead to undefined behavior.

If *type* is a *heap type*, the caller must create a new reference to it. Similarly, if the old type of *o* is a heap type, the caller must release a reference to that type.

Added in version 3.9.

Py_ssize_t **Py_SIZE**(*PyVarObject* *o)

Get the *ob_size* field of *o*.

3.11 sürümünde değişti: *Py_SIZE()* is changed to an inline static function. The parameter type is no longer `const PyVarObject*`.

void **Py_SET_SIZE**(*PyVarObject* *o, *Py_ssize_t* size)

Set the *ob_size* field of *o* to *size*.

Added in version 3.9.

PyObject_HEAD_INIT(type)

This is a macro which expands to initialization values for a new *PyObject* type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

PyVarObject_HEAD_INIT(type, size)

This is a macro which expands to initialization values for a new *PyVarObject* type, including the *ob_size* field. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type, size,
```

13.3.2 Implementing functions and methods

type **PyCFunction**

Bir parçası Kararlı ABI. Type of the functions used to implement most Python callables in C. Functions of this type take two *PyObject** parameters and return one such value. If the return value is `NULL`, an exception shall have been set. If not `NULL`, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

The function signature is:

```
PyObject *PyCFunction(PyObject *self,
                      PyObject *args);
```

type **PyCFunctionWithKeywords**

Bir parçası Kararlı ABI. Type of the functions used to implement Python callables in C with signature *METH_VARARGS | METH_KEYWORDS*. The function signature is:

```
PyObject *PyCFunctionWithKeywords(PyObject *self,
                                  PyObject *args,
                                  PyObject *kwargs);
```

type **PyCFunctionFast**

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Type of the functions used to implement Python callables in C with signature *METH_FASTCALL*. The function signature is:

```
PyObject *PyCFunctionFast(PyObject *self,
                          PyObject *const *args,
                          Py_ssize_t nargs);
```

type **PyCFunctionFastWithKeywords**

Bir parçası Kararlı ABI *3.13 sürümünden beri.* Type of the functions used to implement Python callables in C with signature *METH_FASTCALL | METH_KEYWORDS*. The function signature is:

```
PyObject *PyCFunctionFastWithKeywords(PyObject *self,
                                      PyObject *const *args,
                                      Py_ssize_t nargs,
                                      PyObject *kwnames);
```

type **PyCMethod**

Type of the functions used to implement Python callables in C with signature *METH_METHOD | METH_FASTCALL | METH_KEYWORDS*. The function signature is:

```
PyObject *PyCMethod(PyObject *self,
                    PyTypeObject *defining_class,
                    PyObject *const *args,
                    Py_ssize_t nargs,
                    PyObject *kwnames)
```

Added in version 3.9.

type **PyMethodDef**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Structure used to describe a method of an extension type. This structure has four fields:

const char ***ml_name**

Name of the method.

PyCFunction **ml_meth**

Pointer to the C implementation.

int **ml_flags**

Flags bits indicating how the call should be constructed.

const char ***ml_doc**

Points to the contents of the docstring.

The *ml_meth* is a C function pointer. The functions may be of different types, but they always return *PyObject**. If the function is not of the *PyCFunction*, the compiler will require a cast in the method table. Even though *PyCFunction* defines the first parameter as *PyObject**, it is common that the method implementation uses the specific C type of the *self* object.

The *ml_flags* field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are these calling conventions:

METH_VARARGS

This is the typical calling convention, where the methods have the type *PyCFunction*. The function expects two *PyObject** values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using *PyArg_ParseTuple()* or *PyArg_UnpackTuple()*.

METH_KEYWORDS

Can only be used in certain combinations with other flags: *METH_VARARGS | METH_KEYWORDS*, *METH_FASTCALL | METH_KEYWORDS* and *METH_METHOD | METH_FASTCALL | METH_KEYWORDS*.

METH_VARARGS* | *METH_KEYWORDS

Methods with these flags must be of type *PyCFunctionWithKeywords*. The function expects three parameters: *self*, *args*, *kwargs* where *kwargs* is a dictionary of all the keyword arguments or possibly `NULL` if there are no keyword arguments. The parameters are typically processed using *PyArg_ParseTupleAndKeywords()*.

METH_FASTCALL

Fast calling convention supporting only positional arguments. The methods have the type *PyCFunctionFast*. The first parameter is *self*, the second parameter is a C array of *PyObject** values indicating the arguments and the third parameter is the number of arguments (the length of the array).

Added in version 3.7.

3.10 sürümünde değişti: `METH_FASTCALL` is now part of the *stable ABI*.

METH_FASTCALL* | *METH_KEYWORDS

Extension of *METH_FASTCALL* supporting also keyword arguments, with methods of type *PyCFunctionFastWithKeywords*. Keyword arguments are passed the same way as in the *vectorcall protocol*: there is an additional fourth *PyObject** parameter which is a tuple representing the names of the keyword arguments (which are guaranteed to be strings) or possibly `NULL` if there are no keywords. The values of the keyword arguments are stored in the *args* array, after the positional arguments.

Added in version 3.7.

METH_METHOD

Can only be used in the combination with other flags: *METH_METHOD | METH_FASTCALL | METH_KEYWORDS*.

METH_METHOD* | *METH_FASTCALL* | *METH_KEYWORDS

Extension of *METH_FASTCALL | METH_KEYWORDS* supporting the *defining class*, that is, the class that contains the method in question. The defining class might be a superclass of `Py_TYPE(self)`.

The method needs to be of type *PyCMethod*, the same as for `METH_FASTCALL | METH_KEYWORDS` with `defining_class` argument added after `self`.

Added in version 3.9.

METH_NOARGS

Methods without parameters don't need to check whether arguments are given if they are listed with the *METH_NOARGS* flag. They need to be of type *PyCFunction*. The first parameter is typically named *self* and will hold a reference to the module or object instance. In all cases the second parameter will be `NULL`.

The function must have 2 parameters. Since the second parameter is unused, *Py_UNUSED* can be used to prevent a compiler warning.

METH_O

Methods with a single object argument can be listed with the *METH_O* flag, instead of invoking *PyArg_ParseTuple()* with a `"O"` argument. They have the type *PyCFunction*, with the *self* parameter, and a *PyObject** parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

METH_CLASS

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the `classmethod()` built-in function.

METH_STATIC

The method will be passed `NULL` as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the `staticmethod()` built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

METH_COEXIST

The method will be loaded in place of existing definitions. Without *METH_COEXIST*, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq_contains* slot, for example, would generate a wrapped method named `__contains__()` and preclude the loading of a corresponding PyCFunction with the same name. With the flag defined, the PyCFunction will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to PyCFunctions are optimized more than wrapper object calls.

PyObject ***PyCMethod_New**(*PyMethodDef* *ml, *PyObject* *self, *PyObject* *module, *PyTypeObject* *cls)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.9 sürümünden beri.* Turn *ml* into a Python *callable* object. The caller must ensure that *ml* outlives the *callable*. Typically, *ml* is defined as a static variable.

The *self* parameter will be passed as the *self* argument to the C function in `ml->ml_meth` when invoked. *self* can be `NULL`.

The *callable* object's `__module__` attribute can be set from the given *module* argument. *module* should be a Python string, which will be used as name of the module the function is defined in. If unavailable, it can be set to `None` or `NULL`.

Ayrıca bakınız

`function.__module__`

The *cls* parameter will be passed as the *defining_class* argument to the C function. Must be set if *METH_METHOD* is set on `ml->ml_flags`.

Added in version 3.9.

PyObject ***PyCFunction_NewEx**(*PyMethodDef* *ml, *PyObject* *self, *PyObject* *module)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI. Equivalent to `PyCMethod_New(ml, self, module, NULL)`.

PyObject ***PyCFunction_New**(*PyMethodDef* *ml, *PyObject* *self)

Döndürdüğü değer: Yeni referans. Bir parçası Kararlı ABI *3.4 sürümünden beri.* Equivalent to `PyCMethod_New(ml, self, NULL, NULL)`.

13.3.3 Accessing attributes of extension types

type **PyMemberDef**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Structure which describes an attribute of a type which corresponds to a C struct member. When defining a class, put a NULL-terminated array of these structures in the *tp_members* slot.

Its fields are, in order:

const char ***name**

Name of the member. A NULL value marks the end of a `PyMemberDef[]` array.

The string should be static, no copy is made of it.

int **type**

The type of the member in the C struct. See *Member types* for the possible values.

Py_ssize_t **offset**

The offset in bytes that the member is located on the type's object struct.

int **flags**

Zero or more of the *Member flags*, combined using bitwise OR.

const char ***doc**

The docstring, or NULL. The string should be static, no copy is made of it. Typically, it is defined using *PyDoc_STR*.

By default (when *flags* is `0`), members allow both read and write access. Use the *Py_READONLY* flag for read-only access. Certain types, like *Py_T_STRING*, imply *Py_READONLY*. Only *Py_T_OBJECT_EX* (and legacy *T_OBJECT*) members can be deleted.

For heap-allocated types (created using *PyType_FromSpec()* or similar), `PyMemberDef` may contain a definition for the special member `"__vectorcalloffset__"`, corresponding to *tp_vectorcall_offset* in type objects. This member must be defined with `Py_T_PYSSIZET`, and either `Py_READONLY` or `Py_READONLY | Py_RELATIVE_OFFSET`. For example:

```
static PyMemberDef spam_type_members[] = {
    {"__vectorcalloffset__", Py_T_PYSSIZET,
     offsetof(Spam_object, vectorcall), Py_READONLY},
    {NULL}  /* Sentinel */
};
```

(You may need to `#include <stddef.h>` for `offsetof()`.)

The legacy offsets *tp_dictoffset* and *tp_weaklistoffset* can be defined similarly using `"__dictoffset__"` and `"__weaklistoffset__"` members, but extensions are strongly encouraged to use *Py_TPFLAGS_MANAGED_DICT* and *Py_TPFLAGS_MANAGED_WEAKREF* instead.

3.12 sürümünde değişti: `PyMemberDef` is always available. Previously, it required including `"structmember.h"`.

3.14 sürümünde değişti: *Py_RELATIVE_OFFSET* is now allowed for `"__vectorcalloffset__"`, `"__dictoffset__"` and `"__weaklistoffset__"`.

PyObject ***PyMember_GetOne**(const char *obj_addr, struct *PyMemberDef* *m)

Bir parçası Kararlı ABI. Get an attribute belonging to the object at address *obj_addr*. The attribute is described by `PyMemberDef` *m*. Returns `NULL` on error.

3.12 sürümünde değişti: `PyMember_GetOne` is always available. Previously, it required including `"structmember.h"`.

int **PyMember_SetOne**(char *obj_addr, struct *PyMemberDef* *m, *PyObject* *o)

Bir parçası Kararlı ABI. Set an attribute belonging to the object at address *obj_addr* to object *o*. The attribute to set is described by `PyMemberDef` *m*. Returns `0` if successful and a negative value on failure.

3.12 sürümünde değişti: `PyMember_SetOne` is always available. Previously, it required including `"structmember.h"`.

Member flags

The following flags can be used with *PyMemberDef.flags*:

Py_READONLY

Not writable.

Py_AUDIT_READ

Emit an `object.__getattr__` audit event before reading.

Py_RELATIVE_OFFSET

Indicates that the *offset* of this `PyMemberDef` entry indicates an offset from the subclass-specific data, rather than from `PyObject`.

Can only be used as part of *Py_tp_members slot* when creating a class using negative *basicsize*. It is mandatory in that case.

This flag is only used in *PyType_Slot*. When setting *tp_members* during class creation, Python clears it and sets *PyMemberDef.offset* to the offset from the `PyObject` struct.

3.10 sürümünde değişti: The `RESTRICTED`, `READ_RESTRICTED` and `WRITE_RESTRICTED` macros available with `#include "structmember.h"` are deprecated. `READ_RESTRICTED` and `RESTRICTED` are equivalent to *`Py_AUDIT_READ`*; `WRITE_RESTRICTED` does nothing.

3.12 sürümünde değişti: The `READONLY` macro was renamed to *`Py_READONLY`*. The `PY_AUDIT_READ` macro was renamed with the `Py_` prefix. The new names are now always available. Previously, these required `#include "structmember.h"`. The header is still available and it provides the old names.

Member types

`PyMemberDef.type` can be one of the following macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type. When it is set from Python, it will be converted back to the C type. If that is not possible, an exception such as `TypeError` or `ValueError` is raised.

Unless marked (D), attributes defined this way cannot be deleted using e.g. `del` or `delattr()`.

Macro name	C type	Python type
Py_T_BYTE	`char`	`int`
Py_T_SHORT	`short`	`int`
Py_T_INT	`int`	`int`
Py_T_LONG	`long`	`int`
Py_T_LONGLONG	`long long`	`int`
Py_T_UBYTE	`unsigned char`	`int`
Py_T_UINT	`unsigned int`	`int`
Py_T_USHORT	`unsigned short`	`int`
Py_T_ULONG	`unsigned long`	`int`
Py_T_ULONGLONG	`unsigned long long`	`int`
Py_T_PYSSIZET	*Py_ssize_t*	`int`
Py_T_FLOAT	`float`	`float`
Py_T_DOUBLE	`double`	`float`
Py_T_BOOL	`char` (written as 0 or 1)	`bool`
Py_T_STRING	`const char*` (*)	`str` (RO)
Py_T_STRING_INPLACE	`const char[]` (*)	`str` (RO)
Py_T_CHAR	`char` (0-127)	`str` (**)
Py_T_OBJECT_EX	*PyObject**	`object` (D)

(*): Zero-terminated, UTF8-encoded C string. With `Py_T_STRING` the C representation is a pointer; with `Py_T_STRING_INPLACE` the string is stored directly in the structure.

(**): String of length 1. Only ASCII is accepted.

(RO): Implies *Py_READONLY*.

(D): Can be deleted, in which case the pointer is set to NULL. Reading a NULL pointer raises AttributeError.

Added in version 3.12: In previous versions, the macros were only available with #include "structmember.h" and were named without the Py_ prefix (e.g. as T_INT). The header is still available and contains the old names, along with the following deprecated types:

T_OBJECT

Like Py_T_OBJECT_EX, but NULL is converted to None. This results in surprising behavior in Python: deleting the attribute effectively sets it to None.

T_NONE

Always None. Must be used with *Py_READONLY*.

Defining Getters and Setters

type **PyGetSetDef**

Bir parçası Kararlı ABI *(tüm üyeler dahil).* Structure to define property-like access for a type. See also description of the *PyTypeObject.tp_getset* slot.

const char ***name**

attribute name

getter **get**

C function to get the attribute.

setter **set**

Optional C function to set or delete the attribute. If NULL, the attribute is read-only.

const char ***doc**

optional docstring

void ***closure**

Optional user data pointer, providing additional data for getter and setter.

typedef *PyObject* *(***getter**)(*PyObject**, void*)

Bir parçası Kararlı ABI. The get function takes one *PyObject** parameter (the instance) and a user data pointer (the associated closure):

It should return a new reference on success or NULL with a set exception on failure.

typedef int (***setter**)(*PyObject**, *PyObject**, void*)

Bir parçası Kararlı ABI. set functions take two *PyObject** parameters (the instance and the value to be set) and a user data pointer (the associated closure):

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

13.4 Type Object Structures

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the *PyTypeObject* structure. Type objects can be handled using any of the PyObject_* or PyType_* functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the *Examples* section provides at-a-glance insight into the meaning and use of `PyTypeObject`.

13.4.1 Quick Reference

"tp slots"

PyTypeObject Slot[Sayfa 314, 1]	*Type*	special methods/attrs	Info[Sayfa 314, 2] C	T	D	I
<R> `tp_name`	const char *	__name__	X	X		
`tp_basicsize`	`Py_ssize_t`		X	X		X
`tp_itemsize`	`Py_ssize_t`			X		X
`tp_dealloc`	`destructor`		X	X		X
`tp_vectorcall_offset`	`Py_ssize_t`			X		X
(`tp_getattr`)	`getattrfunc`	__getattribute__, __getattr__				G
(`tp_setattr`)	`setattrfunc`	__setattr__, __delattr__				G
`tp_as_async`	`PyAsyncMethods` *	*sub-slots*				%
`tp_repr`	`reprfunc`	__repr__	X	X		X
`tp_as_number`	`PyNumberMethods` *	*sub-slots*				%
`tp_as_sequence`	`PySequenceMethods` *	*sub-slots*				%
`tp_as_mapping`	`PyMappingMethods` *	*sub-slots*				%
`tp_hash`	`hashfunc`	__hash__	X			G
`tp_call`	`ternaryfunc`	__call__		X		X
`tp_str`	`reprfunc`	__str__	X			X
`tp_getattro`	`getattrofunc`	__getattribute__, __getattr__	X	X		G
`tp_setattro`	`setattrofunc`	__setattr__, __delattr__	X	X		G
`tp_as_buffer`	`PyBufferProcs` *	*sub-slots*				%
`tp_flags`	unsigned long		X	X		?
`tp_doc`	const char *	__doc__	X	X		
`tp_traverse`	`traverseproc`			X		G
`tp_clear`	`inquiry`			X		G
`tp_richcompare`	`richcmpfunc`	__lt__, __le__, __eq__, __ne__, __gt__, __ge__	X			G
(`tp_weaklistoffset`)	`Py_ssize_t`			X		?
`tp_iter`	`getiterfunc`	__iter__				X
`tp_iternext`	`iternextfunc`	__next__				X
`tp_methods`	`PyMethodDef` []		X	X		
`tp_members`	`PyMemberDef` []			X		
`tp_getset`	`PyGetSetDef` []		X	X		
`tp_base`	`PyTypeObject` *	__base__			X	
`tp_dict`	`PyObject` *	__dict__			?	
`tp_descr_get`	`descrgetfunc`	__get__				X
`tp_descr_set`	`descrsetfunc`	__set__, __delete__				X
(`tp_dictoffset`)	`Py_ssize_t`			X		?
`tp_init`	`initproc`	__init__	X	X		X
`tp_alloc`	`allocfunc`		X		?	?
`tp_new`	`newfunc`	__new__	X	X	?	?
`tp_free`	`freefunc`		X	X	?	?
`tp_is_gc`	`inquiry`			X		X
<`tp_bases`>	`PyObject` *	__bases__			~	
<`tp_mro`>	`PyObject` *	__mro__			~	
[`tp_cache`]	`PyObject` *					
[`tp_subclasses`]	void *	__subclasses__				
[`tp_weaklist`]	`PyObject` *					
(`tp_del`)	`destructor`					

sonraki sayfaya devam

Tablo 1 – önceki sayfadan devam

PyTypeObject Slot[1]	*Type*	special methods/attrs	Info[2] C T D I
[*tp_version_tag*]	unsigned int		
tp_finalize	*destructor*	__del__	X
tp_vectorcall	*vectorcallfunc*		
[*tp_watched*]	unsigned char		

sub-slots

Slot	*Type*	special methods
am_await	*unaryfunc*	__await__
am_aiter	*unaryfunc*	__aiter__
am_anext	*unaryfunc*	__anext__
am_send	*sendfunc*	
nb_add	*binaryfunc*	__add__ __radd__
nb_inplace_add	*binaryfunc*	__iadd__
nb_subtract	*binaryfunc*	__sub__ __rsub__
nb_inplace_subtract	*binaryfunc*	__isub__
nb_multiply	*binaryfunc*	__mul__ __rmul__
nb_inplace_multiply	*binaryfunc*	__imul__
nb_remainder	*binaryfunc*	__mod__ __rmod__
nb_inplace_remainder	*binaryfunc*	__imod__
nb_divmod	*binaryfunc*	__divmod__ __rdivmod__
nb_power	*ternaryfunc*	__pow__ __rpow__
nb_inplace_power	*ternaryfunc*	__ipow__
nb_negative	*unaryfunc*	__neg__
nb_positive	*unaryfunc*	__pos__
nb_absolute	*unaryfunc*	__abs__
nb_bool	*inquiry*	__bool__
nb_invert	*unaryfunc*	__invert__
nb_lshift	*binaryfunc*	__lshift__ __rlshift__
nb_inplace_lshift	*binaryfunc*	__ilshift__

sonraki sayfaya devam

[1] (): A slot name in parentheses indicates it is (effectively) deprecated.
<>: Names in angle brackets should be initially set to `NULL` and treated as read-only.
[]: Names in square brackets are for internal use only.
<R> (as a prefix) means the field is required (must be non-`NULL`).
[2] Columns:
"O": set on *PyBaseObject_Type*
"T": set on *PyType_Type*
"D": default (if slot is set to `NULL`)

```
X - PyType_Ready sets this value if it is NULL
~ - PyType_Ready always sets this value (it should be NULL)
? - PyType_Ready may set this value depending on other slots

Also see the inheritance column ("I").
```

"I": inheritance

```
X - type slot is inherited via *PyType_Ready* if defined with a *NULL* value
% - the slots of the sub-struct are inherited individually
G - inherited, but only in combination with other slots; see the slot's description
? - it's complicated; see the slot's description
```

Note that some slots are effectively inherited through the normal attribute lookup chain.

Tablo 2 – önceki sayfadan devam

Slot	*Type*	special methods
nb_rshift	*binaryfunc*	__rshift__ __rrshift__
nb_inplace_rshift	*binaryfunc*	__irshift__
nb_and	*binaryfunc*	__and__ __rand__
nb_inplace_and	*binaryfunc*	__iand__
nb_xor	*binaryfunc*	__xor__ __rxor__
nb_inplace_xor	*binaryfunc*	__ixor__
nb_or	*binaryfunc*	__or__ __ror__
nb_inplace_or	*binaryfunc*	__ior__
nb_int	*unaryfunc*	__int__
nb_reserved	void *	
nb_float	*unaryfunc*	__float__
nb_floor_divide	*binaryfunc*	__floordiv__
nb_inplace_floor_divide	*binaryfunc*	__ifloordiv__
nb_true_divide	*binaryfunc*	__truediv__
nb_inplace_true_divide	*binaryfunc*	__itruediv__
nb_index	*unaryfunc*	__index__
nb_matrix_multiply	*binaryfunc*	__matmul__ __rmatmul__
nb_inplace_matrix_multiply	*binaryfunc*	__imatmul__
mp_length	*lenfunc*	__len__
mp_subscript	*binaryfunc*	__getitem__
mp_ass_subscript	*objobjargproc*	__setitem__, __delitem__
sq_length	*lenfunc*	__len__
sq_concat	*binaryfunc*	__add__
sq_repeat	*ssizeargfunc*	__mul__
sq_item	*ssizeargfunc*	__getitem__
sq_ass_item	*ssizeobjargproc*	__setitem__ __delitem__
sq_contains	*objobjproc*	__contains__
sq_inplace_concat	*binaryfunc*	__iadd__
sq_inplace_repeat	*ssizeargfunc*	__imul__
bf_getbuffer	*getbufferproc()*	__buffer__
bf_releasebuffer	*releasebufferproc()*	__release_buffer__

slot typedefs

typedef	Parameter Types	Return Type
allocfunc	*PyTypeObject* * *Py_ssize_t*	*PyObject* *
destructor	*PyObject* *	void
freefunc	void *	void
traverseproc	*PyObject* * *visitproc* void *	int
newfunc	*PyTypeObject* * *PyObject* * *PyObject* *	*PyObject* *
initproc	*PyObject* * *PyObject* * *PyObject* *	int
reprfunc	*PyObject* *	*PyObject* *
getattrfunc	*PyObject* * const char *	*PyObject* *
setattrfunc	*PyObject* * const char * *PyObject* *	int
getattrofunc	*PyObject* * *PyObject* *	*PyObject* *
setattrofunc	*PyObject* * *PyObject* * *PyObject* *	int
descrgetfunc	*PyObject* * *PyObject* * *PyObject* *	*PyObject* *
descrsetfunc	*PyObject* * *PyObject* * *PyObject* *	int
hashfunc	*PyObject* *	Py_hash_t
richcmpfunc		*PyObject* *

See *Slot Type typedefs* below for more detail.

13.4.2 PyTypeObject Definition

The structure definition for *PyTypeObject* can be found in `Include/cpython/object.h`. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
    PyObject_VAR_HEAD
    const char *tp_name; /* For printing, in format "<module>.<name>" */
    Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */

    /* Methods to implement standard operations */

    destructor tp_dealloc;
    Py_ssize_t tp_vectorcall_offset;
    getattrfunc tp_getattr;
    setattrfunc tp_setattr;
    PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                    or tp_reserved (Python 3) */
    reprfunc tp_repr;

    /* Method suites for standard classes */

    PyNumberMethods *tp_as_number;
    PySequenceMethods *tp_as_sequence;
    PyMappingMethods *tp_as_mapping;

    /* More standard operations (here for binary compatibility) */

    hashfunc tp_hash;
    ternaryfunc tp_call;
    reprfunc tp_str;
    getattrofunc tp_getattro;
    setattrofunc tp_setattro;

    /* Functions to access object as input/output buffer */
    PyBufferProcs *tp_as_buffer;

    /* Flags to define presence of optional/expanded features */
    unsigned long tp_flags;

    const char *tp_doc; /* Documentation string */

    /* Assigned meaning in release 2.0 */
    /* call function for all accessible objects */
    traverseproc tp_traverse;

    /* delete references to contained objects */
    inquiry tp_clear;

    /* Assigned meaning in release 2.1 */
    /* rich comparisons */
    richcmpfunc tp_richcompare;

    /* weak reference enabler */
    Py_ssize_t tp_weaklistoffset;
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    /* Iterators */
    getiterfunc tp_iter;
    iternextfunc tp_iternext;

    /* Attribute descriptor and subclassing stuff */
    PyMethodDef *tp_methods;
    PyMemberDef *tp_members;
    PyGetSetDef *tp_getset;
    // Strong reference on a heap type, borrowed reference on a static type
    PyTypeObject *tp_base;
    PyObject *tp_dict;
    descrgetfunc tp_descr_get;
    descrsetfunc tp_descr_set;
    Py_ssize_t tp_dictoffset;
    initproc tp_init;
    allocfunc tp_alloc;
    newfunc tp_new;
    freefunc tp_free; /* Low-level free-memory routine */
    inquiry tp_is_gc; /* For PyObject_IS_GC */
    PyObject *tp_bases;
    PyObject *tp_mro; /* method resolution order */
    PyObject *tp_cache; /* no longer used */
    void *tp_subclasses;  /* for static builtin types this is an index */
    PyObject *tp_weaklist; /* not used for static builtin types */
    destructor tp_del;

    /* Type attribute cache version tag. Added in version 2.6.
     * If zero, the cache is invalid and must be initialized.
     */
    unsigned int tp_version_tag;

    destructor tp_finalize;
    vectorcallfunc tp_vectorcall;

    /* bitset of which type-watchers care about this type */
    unsigned char tp_watched;

    /* Number of tp_version_tag values used.
     * Set to _Py_ATTR_CACHE_UNUSED if the attribute cache is
     * disabled for this type (e.g. due to custom MRO entries).
     * Otherwise, limited to MAX_VERSIONS_PER_CLASS (defined elsewhere).
     */
    uint16_t tp_versions_used;
} PyTypeObject;
```

13.4.3 PyObject Slots

The type object structure extends the *PyVarObject* structure. The *ob_size* field is used for dynamic types (created by `type_new()`, usually called from a class statement). Note that *PyType_Type* (the metatype) initializes *tp_itemsize*, which means that its instances (i.e. type objects) *must* have the *ob_size* field.

PyObject.ob_refcnt

The type object's reference count is initialized to `1` by the `PyObject_HEAD_INIT` macro. Note that for *statically allocated type objects*, the type's instances (objects whose *ob_type* points back to the type) do *not* count as references. But for *dynamically allocated type objects*, the instances *do* count as references.

Inheritance:

This field is not inherited by subtypes.

PyObject.ob_type

This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject_HEAD_INIT macro, and its value should normally be &PyType_Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass NULL to the PyObject_HEAD_INIT macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. *PyType_Ready()* checks if *ob_type* is NULL, and if so, initializes it to the *ob_type* field of the base class. *PyType_Ready()* will not change this field if it is non-zero.

Inheritance:

This field is inherited by subtypes.

13.4.4 PyVarObject Slots

PyVarObject.ob_size

For *statically allocated type objects*, this should be initialized to zero. For *dynamically allocated type objects*, this field has a special internal meaning.

This field should be accessed using the *Py_SIZE()* macro.

Inheritance:

This field is not inherited by subtypes.

13.4.5 PyTypeObject Slots

Each slot has a section describing inheritance. If *PyType_Ready()* may set a value when the field is set to NULL then there will also be a "Default" section. (Note that many fields set on *PyBaseObject_Type* and *PyType_Type* effectively act as defaults.)

const char **PyTypeObject*.**tp_name**

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the *tp_name* initializer "P.Q.M.T".

For *dynamically allocated type objects*, this should just be the type name, and the module name explicitly stored in the type dict as the value for key '__module__'.

For *statically allocated type objects*, the *tp_name* field should contain a dot. Everything before the last dot is made accessible as the __module__ attribute, and everything after the last dot is made accessible as the __name__ attribute.

If no dot is present, the entire *tp_name* field is made accessible as the __name__ attribute, and the __module__ attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc.

This field must not be NULL. It is the only required field in *PyTypeObject()* (other than potentially *tp_itemsize*).

Inheritance:

This field is not inherited by subtypes.

Py_ssize_t *PyTypeObject*.**tp_basicsize**

Py_ssize_t *PyTypeObject*.**tp_itemsize**

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero `tp_itemsize` field, types with variable-length instances have a non-zero `tp_itemsize` field. For a type with fixed-length instances, all instances have the same size, given in `tp_basicsize`. (Exceptions to this rule can be made using *PyUnstable_Object_GC_NewWithExtraData()*.)

For a type with variable-length instances, the instances must have an *ob_size* field, and the instance size is `tp_basicsize` plus N times `tp_itemsize`, where N is the "length" of the object.

Functions like *PyObject_NewVar()* will take the value of N as an argument, and store in the instance's *ob_size* field. Note that the *ob_size* field may later be used for other purposes. For example, `int` instances use the bits of *ob_size* in an implementation-defined way; the underlying storage and its size should be accessed using *PyLong_Export()*.

Not

The *ob_size* field should be accessed using the *Py_SIZE()* and *Py_SET_SIZE()* macros.

Also, the presence of an *ob_size* field in the instance layout doesn't mean that the instance structure is variable-length. For example, the `list` type has fixed-length instances, yet those instances have a *ob_size* field. (As with `int`, avoid reading lists' `ob_size` directly. Call *PyList_Size()* instead.)

The `tp_basicsize` includes size needed for data of the type's *tp_base*, plus any extra data needed by each instance.

The correct way to set `tp_basicsize` is to use the `sizeof` operator on the struct used to declare the instance layout. This struct must include the struct used to declare the base type. In other words, `tp_basicsize` must be greater than or equal to the base's `tp_basicsize`.

Since every type is a subtype of `object`, this struct must include *PyObject* or *PyVarObject* (depending on whether *ob_size* should be included). These are usually defined by the macro *PyObject_HEAD* or *PyObject_VAR_HEAD*, respectively.

The basic size does not include the GC header size, as that header is not part of *PyObject_HEAD*.

For cases where struct used to declare the base type is unknown, see *PyType_Spec.basicsize* and *PyType_FromMetaclass()*.

Notes about alignment:

- `tp_basicsize` must be a multiple of `_Alignof(PyObject)`. When using `sizeof` on a `struct` that includes *PyObject_HEAD*, as recommended, the compiler ensures this. When not using a C `struct`, or when using compiler extensions like `__attribute__((packed))`, it is up to you.
- If the variable items require a particular alignment, `tp_basicsize` and `tp_itemsize` must each be a multiple of that alignment. For example, if a type's variable part stores a `double`, it is your responsibility that both fields are a multiple of `_Alignof(double)`.

Inheritance:

These fields are inherited separately by subtypes. (That is, if the field is set to zero, *PyType_Ready()* will copy the value from the base type, indicating that the instances do not need additional storage.)

If the base type has a non-zero *tp_itemsize*, it is generally not safe to set *tp_itemsize* to a different non-zero value in a subtype (though this depends on the implementation of the base type).

destructor *PyTypeObject*.**tp_dealloc**

A pointer to the instance destructor function. The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function should remove all references which the instance owns (e.g., call *Py_CLEAR()*), free all memory buffers owned by the instance, and call the type's *tp_free* function to free the object itself.

If you may call functions that may set the error indicator, you must use *PyErr_GetRaisedException()* and *PyErr_SetRaisedException()* to ensure you don't clobber a preexisting error indicator (the deallocation could have occurred while processing a different error):

```
static void
foo_dealloc(foo_object *self)
{
    PyObject *et, *ev, *etb;
    PyObject *exc = PyErr_GetRaisedException();
    ...
    PyErr_SetRaisedException(exc);
}
```

The dealloc handler itself must not raise an exception; if it hits an error case it should call *PyErr_FormatUnraisable()* to log (and clear) an unraisable exception.

No guarantees are made about when an object is destroyed, except:

- Python will destroy an object immediately or some time after the final reference to the object is deleted, unless its finalizer (*tp_finalize*) subsequently resurrects the object.
- An object will not be destroyed while it is being automatically finalized (*tp_finalize*) or automatically cleared (*tp_clear*).

CPython currently destroys an object immediately from *Py_DECREF()* when the new reference count is zero, but this may change in a future version.

It is recommended to call *PyObject_CallFinalizerFromDealloc()* at the beginning of `tp_dealloc` to guarantee that the object is always finalized before destruction.

If the type supports garbage collection (the *Py_TPFLAGS_HAVE_GC* flag is set), the destructor should call *PyObject_GC_UnTrack()* before clearing any member fields.

It is permissible to call *tp_clear* from `tp_dealloc` to reduce code duplication and to guarantee that the object is always cleared before destruction. Beware that `tp_clear` might have already been called.

If the type is heap allocated (*Py_TPFLAGS_HEAPTYPE*), the deallocator should release the owned reference to its type object (via *Py_DECREF()*) after calling the type deallocator. See the example code below.:

```
static void
foo_dealloc(PyObject *op)
{
   foo_object *self = (foo_object *) op;
   PyObject_GC_UnTrack(self);
   Py_CLEAR(self->ref);
   Py_TYPE(self)->tp_free(self);
}
```

`tp_dealloc` must leave the exception status unchanged. If it needs to call something that might raise an exception, the exception state must be backed up first and restored later (after logging any exceptions with *PyErr_WriteUnraisable()*).

Example:

```
static void
foo_dealloc(PyObject *self)
{
    PyObject *exc = PyErr_GetRaisedException();

    if (PyObject_CallFinalizerFromDealloc(self) < 0) {
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
        // self was resurrected.
        goto done;
    }

    PyTypeObject *tp = Py_TYPE(self);

    if (tp->tp_flags & Py_TPFLAGS_HAVE_GC) {
        PyObject_GC_UnTrack(self);
    }

    // Optional, but convenient to avoid code duplication.
    if (tp->tp_clear && tp->tp_clear(self) < 0) {
        PyErr_WriteUnraisable(self);
    }

    // Any additional destruction goes here.

    tp->tp_free(self);
    self = NULL;  // In case PyErr_WriteUnraisable() is called below.

    if (tp->tp_flags & Py_TPFLAGS_HEAPTYPE) {
        Py_CLEAR(tp);
    }

done:
    // Optional, if something was called that might have raised an
    // exception.
    if (PyErr_Occurred()) {
        PyErr_WriteUnraisable(self);
    }
    PyErr_SetRaisedException(exc);
}
```

`tp_dealloc` may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which `tp_dealloc` is called with an *attached thread state*. However, if the object being destroyed in turn destroys objects from some other C library, care should be taken to ensure that destroying those objects on the thread which called `tp_dealloc` will not violate any assumptions of the library.

Inheritance:

This field is inherited by subtypes.

Ayrıca bakınız

Object Life Cycle for details about how this slot relates to other slots.

Py_ssize_t `PyTypeObject`**.tp_vectorcall_offset**

An optional offset to a per-instance function that implements calling the object using the *vectorcall protocol*, a more efficient alternative of the simpler `tp_call`.

This field is only used if the flag `Py_TPFLAGS_HAVE_VECTORCALL` is set. If so, this must be a positive integer containing the offset in the instance of a `vectorcallfunc` pointer.

The *vectorcallfunc* pointer may be `NULL`, in which case the instance behaves as if `Py_TPFLAGS_HAVE_VECTORCALL` was not set: calling the instance falls back to `tp_call`.

Any class that sets `Py_TPFLAGS_HAVE_VECTORCALL` must also set *tp_call* and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting *tp_call* to *PyVectorcall_Call()*.

3.8 sürümünde değişti: Before version 3.8, this slot was named `tp_print`. In Python 2.x, it was used for printing to a file. In Python 3.0 to 3.7, it was unused.

3.12 sürümünde değişti: Before version 3.12, it was not recommended for *mutable heap types* to implement the vectorcall protocol. When a user sets `__call__` in Python code, only *tp_call* is updated, likely making it inconsistent with the vectorcall function. Since 3.12, setting `__call__` will disable vectorcall optimization by clearing the *Py_TPFLAGS_HAVE_VECTORCALL* flag.

Inheritance:

This field is always inherited. However, the *Py_TPFLAGS_HAVE_VECTORCALL* flag is not always inherited. If it's not set, then the subclass won't use *vectorcall*, except when *PyVectorcall_Call()* is explicitly called.

getattrfunc *PyTypeObject*.**tp_getattr**

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the *tp_getattro* function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

Group: *tp_getattr*, *tp_getattro*

This field is inherited by subtypes together with *tp_getattro*: a subtype inherits both *tp_getattr* and *tp_getattro* from its base type when the subtype's *tp_getattr* and *tp_getattro* are both `NULL`.

setattrfunc *PyTypeObject*.**tp_setattr**

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the *tp_setattro* function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

Group: *tp_setattr*, *tp_setattro*

This field is inherited by subtypes together with *tp_setattro*: a subtype inherits both *tp_setattr* and *tp_setattro* from its base type when the subtype's *tp_setattr* and *tp_setattro* are both `NULL`.

PyAsyncMethods **PyTypeObject*.**tp_as_async**

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

Added in version 3.5: Formerly known as `tp_compare` and `tp_reserved`.

Inheritance:

The *tp_as_async* field is not inherited, but the contained fields are inherited individually.

reprfunc *PyTypeObject*.**tp_repr**

An optional pointer to a function that implements the built-in function `repr()`.

The signature is the same as for *PyObject_Repr()*:

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to `eval()`, given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with `'<'` and ending with `'>'` from which both the type and the value of the object can be deduced.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, a string of the form `<%s object at %p>` is returned, where `%s` is replaced by the type name, and `%p` by the object's memory address.

PyNumberMethods ***PyTypeObject*.tp_as_number**

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

Inheritance:

The *tp_as_number* field is not inherited, but the contained fields are inherited individually.

PySequenceMethods ***PyTypeObject*.tp_as_sequence**

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

Inheritance:

The *tp_as_sequence* field is not inherited, but the contained fields are inherited individually.

PyMappingMethods ***PyTypeObject*.tp_as_mapping**

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

Inheritance:

The *tp_as_mapping* field is not inherited, but the contained fields are inherited individually.

hashfunc *PyTypeObject*.tp_hash**

An optional pointer to a function that implements the built-in function `hash()`.

The signature is the same as for *PyObject_Hash()*:

```
Py_hash_t tp_hash(PyObject *);
```

The value `-1` should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return `-1`.

When this field is not set (*and* *tp_richcompare* is not set), an attempt to take the hash of the object raises `TypeError`. This is the same as setting it to *PyObject_HashNotImplemented()*.

This field can be set explicitly to *PyObject_HashNotImplemented()* to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of `__hash__ = None` at the Python level, causing `isinstance(o, collections.Hashable)` to correctly return `False`. Note that the converse is also true - setting `__hash__ = None` on a class at the Python level will result in the `tp_hash` slot being set to *PyObject_HashNotImplemented()*.

Inheritance:

Group: *tp_hash*, *tp_richcompare*

This field is inherited by subtypes together with *tp_richcompare*: a subtype inherits both of *tp_richcompare* and *tp_hash*, when the subtype's *tp_richcompare* and *tp_hash* are both `NULL`.

Default:

PyBaseObject_Type uses *PyObject_GenericHash()*.

ternaryfunc *PyTypeObject*.tp_call**

An optional pointer to a function that implements calling the object. This should be `NULL` if the object is not callable. The signature is the same as for *PyObject_Call()*:

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

Inheritance:

This field is inherited by subtypes.

reprfunc *PyTypeObject*.**tp_str**

An optional pointer to a function that implements the built-in operation `str()`. (Note that `str` is a type now, and `str()` calls the constructor for that type. This constructor calls *PyObject_Str()* to do the actual work, and *PyObject_Str()* will call this handler.)

The signature is the same as for *PyObject_Str()*:

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the `print()` function.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, *PyObject_Repr()* is called to return a string representation.

getattrofunc *PyTypeObject*.**tp_getattro**

An optional pointer to the get-attribute function.

The signature is the same as for *PyObject_GetAttr()*:

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to *PyObject_GenericGetAttr()*, which implements the normal way of looking for object attributes.

Inheritance:

Group: *tp_getattr*, *tp_getattro*

This field is inherited by subtypes together with *tp_getattr*: a subtype inherits both *tp_getattr* and *tp_getattro* from its base type when the subtype's *tp_getattr* and *tp_getattro* are both `NULL`.

Default:

PyBaseObject_Type uses *PyObject_GenericGetAttr()*.

setattrofunc *PyTypeObject*.**tp_setattro**

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for *PyObject_SetAttr()*:

```
int tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to `NULL` to delete an attribute must be supported. It is usually convenient to set this field to *PyObject_GenericSetAttr()*, which implements the normal way of setting object attributes.

Inheritance:

Group: *tp_setattr*, *tp_setattro*

This field is inherited by subtypes together with *tp_setattr*: a subtype inherits both *tp_setattr* and *tp_setattro* from its base type when the subtype's *tp_setattr* and *tp_setattro* are both `NULL`.

Default:

PyBaseObject_Type uses *PyObject_GenericSetAttr()*.

PyBufferProcs **PyTypeObject*.**tp_as_buffer**

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

Inheritance:

The *tp_as_buffer* field is not inherited, but the contained fields are inherited individually.

unsigned long *PyTypeObject*.**tp_flags**

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via *tp_as_number*, *tp_as_sequence*, *tp_as_mapping*, and *tp_as_buffer*) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or `NULL` value instead.

Inheritance:

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The *Py_TPFLAGS_HAVE_GC* flag bit is inherited together with the *tp_traverse* and *tp_clear* fields, i.e. if the *Py_TPFLAGS_HAVE_GC* flag bit is clear in the subtype and the *tp_traverse* and *tp_clear* fields in the subtype exist and have `NULL` values.

Default:

PyBaseObject_Type uses `Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE`.

Bit Masks:

The following bit masks are currently defined; these can be ORed together using the `|` operator to form the value of the *tp_flags* field. The macro *PyType_HasFeature()* takes a type and a flags value, *tp* and *f*, and checks whether `tp->tp_flags & f` is non-zero.

Py_TPFLAGS_HEAPTYPE

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using *PyType_FromSpec()*. In this case, the *ob_type* field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob_type gets INCREF'ed or DECREF'ed). Heap types should also *support garbage collection* as they can form a reference cycle with their own module object.

Inheritance:

???

Py_TPFLAGS_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

Inheritance:

???

Py_TPFLAGS_READY

This bit is set when the type object has been fully initialized by *PyType_Ready()*.

Inheritance:

???

Py_TPFLAGS_READYING

This bit is set while *PyType_Ready()* is in the process of initializing the type object.

Inheritance:

???

Py_TPFLAGS_HAVE_GC

This bit is set when the object supports garbage collection. If this bit is set, memory for new instances (see *tp_alloc*) must be allocated using *PyObject_GC_New* or *PyType_GenericAlloc()* and deallocated (see *tp_free*) using *PyObject_GC_Del()*. More information in section *Supporting Cyclic Garbage Collection*.

Inheritance:

Group: *Py_TPFLAGS_HAVE_GC*, *tp_traverse*, *tp_clear*

The *Py_TPFLAGS_HAVE_GC* flag bit is inherited together with the *tp_traverse* and *tp_clear* fields, i.e. if the *Py_TPFLAGS_HAVE_GC* flag bit is clear in the subtype and the *tp_traverse* and *tp_clear* fields in the subtype exist and have `NULL` values.

Py_TPFLAGS_DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: `Py_TPFLAGS_HAVE_STACKLESS_EXTENSION`.

Inheritance:

???

Py_TPFLAGS_METHOD_DESCRIPTOR

This bit indicates that objects behave like unbound methods.

If this flag is set for `type(meth)`, then:

- `meth.__get__(obj, cls)(*args, **kwds)` (with `obj` not None) must be equivalent to `meth(obj, *args, **kwds)`.
- `meth.__get__(None, cls)(*args, **kwds)` must be equivalent to `meth(*args, **kwds)`.

This flag enables an optimization for typical method calls like `obj.meth()`: it avoids creating a temporary "bound method" object for `obj.meth`.

Added in version 3.8.

Inheritance:

This flag is never inherited by types without the *Py_TPFLAGS_IMMUTABLETYPE* flag set. For extension types, it is inherited whenever *tp_descr_get* is inherited.

Py_TPFLAGS_MANAGED_DICT

This bit indicates that instances of the class have a `__dict__` attribute, and that the space for the dictionary is managed by the VM.

If this flag is set, *Py_TPFLAGS_HAVE_GC* should also be set.

The type traverse function must call *PyObject_VisitManagedDict()* and its clear function must call *PyObject_ClearManagedDict()*.

Added in version 3.12.

Inheritance:

This flag is inherited unless the *tp_dictoffset* field is set in a superclass.

Py_TPFLAGS_MANAGED_WEAKREF

This bit indicates that instances of the class should be weakly referenceable.

Added in version 3.12.

Inheritance:

This flag is inherited unless the *tp_weaklistoffset* field is set in a superclass.

Py_TPFLAGS_ITEMS_AT_END

Only usable with variable-size types, i.e. ones with non-zero *tp_itemsize*.

Indicates that the variable-sized portion of an instance of this type is at the end of the instance's memory area, at an offset of `Py_TYPE(obj)->tp_basicsize` (which may be different in each subclass).

When setting this flag, be sure that all superclasses either use this memory layout, or are not variable-sized. Python does not check this.

Added in version 3.12.

Inheritance:

This flag is inherited.

Py_TPFLAGS_LONG_SUBCLASS

Py_TPFLAGS_LIST_SUBCLASS

Py_TPFLAGS_TUPLE_SUBCLASS

Py_TPFLAGS_BYTES_SUBCLASS

Py_TPFLAGS_UNICODE_SUBCLASS

Py_TPFLAGS_DICT_SUBCLASS

Py_TPFLAGS_BASE_EXC_SUBCLASS

Py_TPFLAGS_TYPE_SUBCLASS

These flags are used by functions such as *PyLong_Check()* to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like *PyObject_IsInstance()*. Custom types that inherit from built-ins should have their *tp_flags* set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

Py_TPFLAGS_HAVE_FINALIZE

This bit is set when the *tp_finalize* slot is present in the type structure.

Added in version 3.4.

3.8 sürümünden beri kullanım dışı: This flag isn't necessary anymore, as the interpreter assumes the *tp_finalize* slot is always present in the type structure.

Py_TPFLAGS_HAVE_VECTORCALL

This bit is set when the class implements the *vectorcall protocol*. See *tp_vectorcall_offset* for details.

Inheritance:

This bit is inherited if *tp_call* is also inherited.

Added in version 3.9.

3.12 sürümünde değişti: This flag is now removed from a class when the class's `__call__()` method is reassigned.

This flag can now be inherited by mutable classes.

Py_TPFLAGS_IMMUTABLETYPE

This bit is set for type objects that are immutable: type attributes cannot be set nor deleted.

PyType_Ready() automatically applies this flag to *static types*.

Inheritance:

This flag is not inherited.

Added in version 3.10.

Py_TPFLAGS_DISALLOW_INSTANTIATION

Disallow creating instances of the type: set *tp_new* to NULL and don't create the `__new__` key in the type dictionary.

The flag must be set before creating the type, not after. For example, it must be set before *PyType_Ready()* is called on the type.

The flag is set automatically on *static types* if *tp_base* is NULL or `&PyBaseObject_Type` and *tp_new* is NULL.

Inheritance:

This flag is not inherited. However, subclasses will not be instantiable unless they provide a non-NULL *tp_new* (which is only possible via the C API).

Not

To disallow instantiating a class directly but allow instantiating its subclasses (e.g. for an *abstract base class*), do not use this flag. Instead, make *tp_new* only succeed for subclasses.

Added in version 3.10.

Py_TPFLAGS_MAPPING

This bit indicates that instances of the class may match mapping patterns when used as the subject of a `match` block. It is automatically set when registering or subclassing `collections.abc.Mapping`, and unset when registering `collections.abc.Sequence`.

Not

Py_TPFLAGS_MAPPING and *Py_TPFLAGS_SEQUENCE* are mutually exclusive; it is an error to enable both flags simultaneously.

Inheritance:

This flag is inherited by types that do not already set *Py_TPFLAGS_SEQUENCE*.

Ayrıca bakınız

PEP 634 – Structural Pattern Matching: Specification

Added in version 3.10.

Py_TPFLAGS_SEQUENCE

This bit indicates that instances of the class may match sequence patterns when used as the subject of a `match` block. It is automatically set when registering or subclassing `collections.abc.Sequence`, and unset when registering `collections.abc.Mapping`.

Not

Py_TPFLAGS_MAPPING and *Py_TPFLAGS_SEQUENCE* are mutually exclusive; it is an error to enable both flags simultaneously.

Inheritance:

This flag is inherited by types that do not already set *Py_TPFLAGS_MAPPING*.

Ayrıca bakınız

PEP 634 – Structural Pattern Matching: Specification

Added in version 3.10.

Py_TPFLAGS_VALID_VERSION_TAG

Internal. Do not set or unset this flag. To indicate that a class has changed call *PyType_Modified()*

> **Uyarı**
>
> This flag is present in header files, but is not be used. It will be removed in a future version of CPython

const char *_PyTypeObject_.**tp_doc**

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the `__doc__` attribute on the type and instances of the type.

Inheritance:

This field is *not* inherited by subtypes.

traverseproc _PyTypeObject_.**tp_traverse**

An optional pointer to a traversal function for the garbage collector. This is only used if the *Py_TPFLAGS_HAVE_GC* flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

The *tp_traverse* pointer is used by the garbage collector to detect reference cycles. A typical implementation of a *tp_traverse* function simply calls *Py_VISIT()* on each of the instance's members that are Python objects that the instance owns. For example, this is function `local_traverse()` from the `_thread` extension module:

```
static int
local_traverse(PyObject *op, visitproc visit, void *arg)
{
    localobject *self = (localobject *) op;
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that *Py_VISIT()* is called only on those members that can participate in reference cycles. Although there is also a `self->key` member, it can only be `NULL` or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the `gc` module's `get_referents()` function will include it.

Heap types (*Py_TPFLAGS_HEAPTYPE*) must visit their type with:

```
Py_VISIT(Py_TYPE(self));
```

It is only needed since Python 3.9. To support Python 3.8 and older, this line must be conditional:

```
#if PY_VERSION_HEX >= 0x03090000
    Py_VISIT(Py_TYPE(self));
#endif
```

If the *Py_TPFLAGS_MANAGED_DICT* bit is set in the *tp_flags* field, the traverse function must call *PyObject_VisitManagedDict()* like this:

```
PyObject_VisitManagedDict((PyObject*)self, visit, arg);
```

Uyarı

When implementing *tp_traverse*, only the members that the instance *owns* (by having *strong references* to them) must be visited. For instance, if an object supports weak references via the *tp_weaklist* slot, the pointer supporting the linked list (what *tp_weaklist* points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that *Py_VISIT()* requires the *visit* and *arg* parameters to `local_traverse()` to have these specific names; don't name them just anything.

Instances of *heap-allocated types* hold a reference to their type. Their traversal function must therefore either visit *Py_TYPE(self)*, or delegate this responsibility by calling `tp_traverse` of another heap-allocated type (such as a heap-allocated superclass). If they do not, the type object may not be garbage-collected.

Not

The *tp_traverse* function can be called from any thread.

3.9 sürümünde değişti: Heap-allocated types are expected to visit `Py_TYPE(self)` in `tp_traverse`. In earlier versions of Python, due to bug 40217, doing this may lead to crashes in subclasses.

Inheritance:

Group: *Py_TPFLAGS_HAVE_GC*, *tp_traverse*, *tp_clear*

This field is inherited by subtypes together with *tp_clear* and the *Py_TPFLAGS_HAVE_GC* flag bit: the flag bit, *tp_traverse*, and *tp_clear* are all inherited from the base type if they are all zero in the subtype.

inquiry *PyTypeObject*.**tp_clear**

An optional pointer to a clear function. The signature is:

```
int tp_clear(PyObject *);
```

The purpose of this function is to break reference cycles that are causing a *cyclic isolate* so that the objects can be safely destroyed. A cleared object is a partially destroyed object; the object is not obligated to satisfy design invariants held during normal use.

`tp_clear` does not need to delete references to objects that can't participate in reference cycles, such as Python strings or Python integers. However, it may be convenient to clear all references, and write the type's *tp_dealloc* function to invoke `tp_clear` to avoid code duplication. (Beware that `tp_clear` might have already been called. Prefer calling idempotent functions like *Py_CLEAR()*.)

Any non-trivial cleanup should be performed in *tp_finalize* instead of `tp_clear`.

Not

If `tp_clear` fails to break a reference cycle then the objects in the *cyclic isolate* may remain indefinitely uncollectable ("leak"). See `gc.garbage`.

Not

Referents (direct and indirect) might have already been cleared; they are not guaranteed to be in a consistent state.

Not

The *tp_clear* function can be called from any thread.

Not

An object is not guaranteed to be automatically cleared before its destructor (*tp_dealloc*) is called.

This function differs from the destructor (*tp_dealloc*) in the following ways:

- The purpose of clearing an object is to remove references to other objects that might participate in a reference cycle. The purpose of the destructor, on the other hand, is a superset: it must release *all* resources it owns, including references to objects that cannot participate in a reference cycle (e.g., integers) as well as the object's own memory (by calling *tp_free*).
- When `tp_clear` is called, other objects might still hold references to the object being cleared. Because of this, `tp_clear` must not deallocate the object's own memory (*tp_free*). The destructor, on the other hand, is only called when no (strong) references exist, and as such, must safely destroy the object itself by deallocating it.
- `tp_clear` might never be automatically called. An object's destructor, on the other hand, will be automatically called some time after the object becomes unreachable (i.e., either there are no references to the object or the object is a member of a *cyclic isolate*).

No guarantees are made about when, if, or how often Python automatically clears an object, except:

- Python will not automatically clear an object if it is reachable, i.e., there is a reference to it and it is not a member of a *cyclic isolate*.
- Python will not automatically clear an object if it has not been automatically finalized (see *tp_finalize*). (If the finalizer resurrected the object, the object may or may not be automatically finalized again before it is cleared.)
- If an object is a member of a *cyclic isolate*, Python will not automatically clear it if any member of the cyclic isolate has not yet been automatically finalized (*tp_finalize*).
- Python will not destroy an object until after any automatic calls to its `tp_clear` function have returned. This ensures that the act of breaking a reference cycle does not invalidate the `self` pointer while `tp_clear` is still executing.
- Python will not automatically call `tp_clear` multiple times concurrently.

CPython currently only automatically clears objects as needed to break reference cycles in a *cyclic isolate*, but future versions might clear objects regularly before their destruction.

Taken together, all *tp_clear* functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a *tp_clear* function. For example, the tuple type does not implement a *tp_clear* function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the *tp_clear* functions of other types are responsible for breaking any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing *tp_clear*.

Implementations of *tp_clear* should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to `NULL`, as in the following example:

```
static int
local_clear(PyObject *op)
{
    localobject *self = (localobject *) op;
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    Py_CLEAR(self->dict);
    return 0;
}
```

The *Py_CLEAR()* macro should be used, because clearing references is delicate: the reference to the contained object must not be released (via *Py_DECREF()*) until after the pointer to the contained object is set to `NULL`. This is because releasing the reference may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference *self* again, it's important that the pointer to the contained object be `NULL` at that time, so that *self* knows the contained object can no longer be used. The *Py_CLEAR()* macro performs the operations in a safe order.

If the *Py_TPFLAGS_MANAGED_DICT* bit is set in the *tp_flags* field, the traverse function must call *PyObject_ClearManagedDict()* like this:

```
PyObject_ClearManagedDict((PyObject*)self);
```

More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

Inheritance:

Group: *Py_TPFLAGS_HAVE_GC*, *tp_traverse*, *tp_clear*

This field is inherited by subtypes together with *tp_traverse* and the *Py_TPFLAGS_HAVE_GC* flag bit: the flag bit, *tp_traverse*, and *tp_clear* are all inherited from the base type if they are all zero in the subtype.

Ayrıca bakınız

Object Life Cycle for details about how this slot relates to other slots.

richcmpfunc *PyTypeObject*.**tp_richcompare**

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by *PyTypeObject*.

The function should return the result of the comparison (usually `Py_True` or `Py_False`). If the comparison is undefined, it must return `Py_NotImplemented`, if another error occurred it must return `NULL` and set an exception condition.

The following constants are defined to be used as the third argument for *tp_richcompare* and for *PyObject_RichCompare()*:

Constant	Comparison
Py_LT	<
Py_LE	< =
Py_EQ	==
Py_NE	!=
Py_GT	>
Py_GE	> =

The following macro is defined to ease writing rich comparison functions:

Py_RETURN_RICHCOMPARE(VAL_A, VAL_B, op)

Return `Py_True` or `Py_False` from the function, depending on the result of a comparison. VAL_A and VAL_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for *PyObject_RichCompare()*.

The returned value is a new *strong reference*.

On error, sets an exception and returns `NULL` from the function.

Added in version 3.7.

Inheritance:

Group: *tp_hash*, *tp_richcompare*

This field is inherited by subtypes together with *tp_hash*: a subtype inherits *tp_richcompare* and *tp_hash* when the subtype's *tp_richcompare* and *tp_hash* are both `NULL`.

Default:

PyBaseObject_Type provides a *tp_richcompare* implementation, which may be inherited. However, if only *tp_hash* is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

Py_ssize_t *PyTypeObject*.**tp_weaklistoffset**

While this field is still supported, *Py_TPFLAGS_MANAGED_WEAKREF* should be used instead, if at all possible.

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by *PyObject_ClearWeakRefs()* and the `PyWeakref_*` functions. The instance structure needs to include a field of type *PyObject*`*` which is initialized to `NULL`.

Do not confuse this field with *tp_weaklist*; that is the list head for weak references to the type object itself.

It is an error to set both the *Py_TPFLAGS_MANAGED_WEAKREF* bit and *tp_weaklistoffset*.

Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via *tp_weaklistoffset*, this should not be a problem.

Default:

If the *Py_TPFLAGS_MANAGED_WEAKREF* bit is set in the *tp_flags* field, then *tp_weaklistoffset* will be set to a negative value, to indicate that it is unsafe to use this field.

getiterfunc *PyTypeObject*.**tp_iter**

An optional pointer to a function that returns an *iterator* for the object. Its presence normally signals that the instances of this type are *iterable* (although sequences may be iterable without this function).

This function has the same signature as *PyObject_GetIter()*:

```
PyObject *tp_iter(PyObject *self);
```

Inheritance:

This field is inherited by subtypes.

iternextfunc *PyTypeObject*.**tp_iternext**

An optional pointer to a function that returns the next item in an *iterator*. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return `NULL`; a `StopIteration` exception may or may not be set. When another error occurs, it must return `NULL` too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the *tp_iter* function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as *PyIter_Next()*.

Inheritance:

This field is inherited by subtypes.

struct *PyMethodDef* **PyTypeObject*.**tp_methods**

An optional pointer to a static `NULL`-terminated array of *PyMethodDef* structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see *tp_dict* below) containing a method descriptor.

Inheritance:

This field is not inherited by subtypes (methods are inherited through a different mechanism).

struct *PyMemberDef* **PyTypeObject*.**tp_members**

An optional pointer to a static `NULL`-terminated array of *PyMemberDef* structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see *tp_dict* below) containing a member descriptor.

Inheritance:

This field is not inherited by subtypes (members are inherited through a different mechanism).

struct *PyGetSetDef* **PyTypeObject*.**tp_getset**

An optional pointer to a static `NULL`-terminated array of *PyGetSetDef* structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see *tp_dict* below) containing a getset descriptor.

Inheritance:

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

PyTypeObject **PyTypeObject.tp_base*

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

> **Not**
>
> Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be "address constants". Function designators like *PyType_GenericNew()*, with implicit conversion to a pointer, are valid C99 address constants.
>
> However, the unary '&' operator applied to a non-static variable like *PyBaseObject_Type* is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.
>
> Consequently, *tp_base* should be set in the extension module's init function.

Inheritance:

This field is not inherited by subtypes (obviously).

Default:

This field defaults to `&PyBaseObject_Type` (which to Python programmers is known as the type `object`).

PyObject **PyTypeObject.tp_dict*

The type's dictionary is stored here by *PyType_Ready()*.

This field should normally be initialized to `NULL` before PyType_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once *PyType_Ready()* has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like `__add__()`). Once initialization for the type has finished, this field should be treated as read-only.

Some types may not store their dictionary in this slot. Use *PyType_GetDict()* to retrieve the dictionary for an arbitrary type.

3.12 sürümünde değişti: Internals detail: For static builtin types, this is always `NULL`. Instead, the dict for such types is stored on `PyInterpreterState`. Use *PyType_GetDict()* to get the dict for an arbitrary type.

Inheritance:

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

Default:

If this field is `NULL`, *PyType_Ready()* will assign a new dictionary to it.

> **Uyarı**
>
> It is not safe to use *PyDict_SetItem()* on or otherwise modify *tp_dict* with the dictionary C-API.

descrgetfunc *PyTypeObject*.**tp_descr_get**

An optional pointer to a "descriptor get" function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

Inheritance:

This field is inherited by subtypes.

descrsetfunc *PyTypeObject*.**tp_descr_set**

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to `NULL` to delete the value.

Inheritance:

This field is inherited by subtypes.

Py_ssize_t *PyTypeObject*.**tp_dictoffset**

While this field is still supported, *Py_TPFLAGS_MANAGED_DICT* should be used instead, if at all possible.

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by *PyObject_GenericGetAttr()*.

Do not confuse this field with *tp_dict*; that is the dictionary for attributes of the type object itself.

The value specifies the offset of the dictionary from the start of the instance structure.

The *tp_dictoffset* should be regarded as write-only. To get the pointer to the dictionary call *PyObject_GenericGetDict()*. Calling *PyObject_GenericGetDict()* may need to allocate memory for the dictionary, so it is may be more efficient to call *PyObject_GetAttr()* when accessing an attribute on the object.

It is an error to set both the *Py_TPFLAGS_MANAGED_DICT* bit and *tp_dictoffset*.

Inheritance:

This field is inherited by subtypes. A subtype should not override this offset; doing so could be unsafe, if C code tries to access the dictionary at the previous offset. To properly support inheritance, use *Py_TPFLAGS_MANAGED_DICT*.

Default:

This slot has no default. For *static types*, if the field is `NULL` then no `__dict__` gets created for instances.

If the *Py_TPFLAGS_MANAGED_DICT* bit is set in the *tp_flags* field, then *tp_dictoffset* will be set to `-1`, to indicate that it is unsafe to use this field.

initproc *PyTypeObject*.**tp_init**

An optional pointer to an instance initialization function.

This function corresponds to the `__init__()` method of classes. Like `__init__()`, it is possible to create an instance without calling `__init__()`, and it is possible to reinitialize an instance by calling its `__init__()` method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to `__init__()`.

The *tp_init* function, if not `NULL`, is called when an instance is created normally by calling its type, after the type's *tp_new* function has returned an instance of the type. If the *tp_new* function returns an instance of some other type that is not a subtype of the original type, no *tp_init* function is called; if *tp_new* returns an instance of a subtype of the original type, the subtype's *tp_init* is called.

Returns `0` on success, `-1` and sets an exception on error.

Inheritance:

This field is inherited by subtypes.

Default:

For *static types* this field does not have a default.

allocfunc *PyTypeObject*.**tp_alloc**

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

Inheritance:

Static subtypes inherit this slot, which will be *PyType_GenericAlloc()* if inherited from `object`.

Heap subtypes do not inherit this slot.

Default:

For heap subtypes, this field is always set to *PyType_GenericAlloc()*.

For static subtypes, this slot is inherited (see above).

newfunc *PyTypeObject*.**tp_new**

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwds);
```

The *subtype* argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that *subtype* doesn't have to equal the type whose *tp_new* function is called; it may be a subtype of that type (but not an unrelated type).

The *tp_new* function should call `subtype->tp_alloc(subtype, nitems)` to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the *tp_init* handler. A good rule of thumb is that for immutable types, all initialization should take place in *tp_new*, while for mutable types, most initialization should be deferred to *tp_init*.

Set the *Py_TPFLAGS_DISALLOW_INSTANTIATION* flag to disallow creating instances of the type in Python.

Inheritance:

This field is inherited by subtypes, except it is not inherited by *static types* whose *tp_base* is `NULL` or `&PyBaseObject_Type`.

Default:

For *static types* this field has no default. This means if the slot is defined as `NULL`, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

freefunc *PyTypeObject*.**tp_free**

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

This function must free the memory allocated by *tp_alloc*.

Inheritance:

Static subtypes inherit this slot, which will be *PyObject_Free()* if inherited from `object`. Exception: If the type supports garbage collection (i.e., the *Py_TPFLAGS_HAVE_GC* flag is set in *tp_flags*) and it would inherit *PyObject_Free()*, then this slot is not inherited but instead defaults to *PyObject_GC_Del()*.

Heap subtypes do not inherit this slot.

Default:

For *heap subtypes*, this slot defaults to a deallocator suitable to match `PyType_GenericAlloc()` and the value of the `Py_TPFLAGS_HAVE_GC` flag.

For static subtypes, this slot is inherited (see above).

inquiry `PyTypeObject`**.tp_is_gc**

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's `tp_flags` field, and check the `Py_TPFLAGS_HAVE_GC` flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return `1` for a collectible instance, and `0` for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype, `PyType_Type`, defines this function to distinguish between statically and *dynamically allocated types*.)

Inheritance:

This field is inherited by subtypes.

Default:

This slot has no default. If this field is `NULL`, `Py_TPFLAGS_HAVE_GC` is used as the functional equivalent.

PyObject *`PyTypeObject`**.tp_bases**

Tuple of base types.

This field should be set to `NULL` and treated as read-only. Python will fill it in when the type is *initialized*.

For dynamically created classes, the `Py_tp_bases` *slot* can be used instead of the *bases* argument of `PyType_FromSpecWithBases()`. The argument form is preferred.

> **Uyarı**
>
> Multiple inheritance does not work well for statically defined types. If you set `tp_bases` to a tuple, Python will not raise an error, but some slots will only be inherited from the first base.

Inheritance:

This field is not inherited.

PyObject *`PyTypeObject`**.tp_mro**

Tuple containing the expanded set of base types, starting with the type itself and ending with `object`, in Method Resolution Order.

This field should be set to `NULL` and treated as read-only. Python will fill it in when the type is *initialized*.

Inheritance:

This field is not inherited; it is calculated fresh by `PyType_Ready()`.

PyObject *`PyTypeObject`**.tp_cache**

Unused. Internal use only.

Inheritance:

This field is not inherited.

void *`PyTypeObject`**.tp_subclasses**

A collection of subclasses. Internal use only. May be an invalid pointer.

To get a list of subclasses, call the Python method `__subclasses__()`.

3.12 sürümünde değişti: For some types, this field does not hold a valid *PyObject**. The type was changed to `void*` to indicate this.

Inheritance:

This field is not inherited.

PyObject ***PyTypeObject*.tp_weaklist**

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

3.12 sürümünde değişti: Internals detail: For the static builtin types this is always `NULL`, even if weakrefs are added. Instead, the weakrefs for each are stored on `PyInterpreterState`. Use the public C-API or the internal `_PyObject_GET_WEAKREFS_LISTPTR()` macro to avoid the distinction.

Inheritance:

This field is not inherited.

destructor *PyTypeObject*.tp_del**

This field is deprecated. Use *tp_finalize* instead.

unsigned int *PyTypeObject*.tp_version_tag**

Used to index into the method cache. Internal use only.

Inheritance:

This field is not inherited.

destructor *PyTypeObject*.tp_finalize**

An optional pointer to an instance finalization function. This is the C implementation of the `__del__()` special method. Its signature is:

```
void tp_finalize(PyObject *self);
```

The primary purpose of finalization is to perform any non-trivial cleanup that must be performed before the object is destroyed, while the object and any other objects it directly or indirectly references are still in a consistent state. The finalizer is allowed to execute arbitrary Python code.

Before Python automatically finalizes an object, some of the object's direct or indirect referents might have themselves been automatically finalized. However, none of the referents will have been automatically cleared (*tp_clear*) yet.

Other non-finalized objects might still be using a finalized object, so the finalizer must leave the object in a sane state (e.g., invariants are still met).

Not

After Python automatically finalizes an object, Python might start automatically clearing (*tp_clear*) the object and its referents (direct and indirect). Cleared objects are not guaranteed to be in a consistent state; a finalized object must be able to tolerate cleared referents.

Not

An object is not guaranteed to be automatically finalized before its destructor (*tp_dealloc*) is called. It is recommended to call *PyObject_CallFinalizerFromDealloc()* at the beginning of `tp_dealloc` to guarantee that the object is always finalized before destruction.

Not

The *tp_finalize* function can be called from any thread, although the *GIL* will be held.

Not

The `tp_finalize` function can be called during shutdown, after some global variables have been deleted. See the documentation of the `__del__()` method for details.

When Python finalizes an object, it behaves like the following algorithm:

1. Python might mark the object as *finalized*. Currently, Python always marks objects whose type supports garbage collection (i.e., the *Py_TPFLAGS_HAVE_GC* flag is set in *tp_flags*) and never marks other types of objects; this might change in a future version.
2. If the object is not marked as *finalized* and its `tp_finalize` finalizer function is non-`NULL`, the finalizer function is called.
3. If the finalizer function was called and the finalizer made the object reachable (i.e., there is a reference to the object and it is not a member of a *cyclic isolate*), then the finalizer is said to have *resurrected* the object. It is unspecified whether the finalizer can also resurrect the object by adding a new reference to the object that does not make it reachable, i.e., the object is (still) a member of a cyclic isolate.
4. If the finalizer resurrected the object, the object's pending destruction is canceled and the object's *finalized* mark might be removed if present. Currently, Python never removes the *finalized* mark; this might change in a future version.

Automatic finalization refers to any finalization performed by Python except via calls to *PyObject_CallFinalizer()* or *PyObject_CallFinalizerFromDealloc()*. No guarantees are made about when, if, or how often an object is automatically finalized, except:

- Python will not automatically finalize an object if it is reachable, i.e., there is a reference to it and it is not a member of a *cyclic isolate*.
- Python will not automatically finalize an object if finalizing it would not mark the object as *finalized*. Currently, this applies to objects whose type does not support garbage collection, i.e., the *Py_TPFLAGS_HAVE_GC* flag is not set. Such objects can still be manually finalized by calling *PyObject_CallFinalizer()* or *PyObject_CallFinalizerFromDealloc()*.
- Python will not automatically finalize any two members of a *cyclic isolate* concurrently.
- Python will not automatically finalize an object after it has automatically cleared (*tp_clear*) the object.
- If an object is a member of a *cyclic isolate*, Python will not automatically finalize it after automatically clearing (see *tp_clear*) any other member.
- Python will automatically finalize every member of a *cyclic isolate* before it automatically clears (see *tp_clear*) any of them.
- If Python is going to automatically clear an object (*tp_clear*), it will automatically finalize the object first.

Python currently only automatically finalizes objects that are members of a *cyclic isolate*, but future versions might finalize objects regularly before their destruction.

To manually finalize an object, do not call this function directly; call *PyObject_CallFinalizer()* or *PyObject_CallFinalizerFromDealloc()* instead.

tp_finalize should leave the current exception status unchanged. The recommended way to write a non-trivial finalizer is to back up the exception at the beginning by calling *PyErr_GetRaisedException()* and restore the exception at the end by calling *PyErr_SetRaisedException()*. If an exception is encountered in the middle of the finalizer, log and clear it with *PyErr_WriteUnraisable()* or *PyErr_FormatUnraisable()*. For example:

```
static void
foo_finalize(PyObject *self)
{
    // Save the current exception, if any.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    PyObject *exc = PyErr_GetRaisedException();

    // ...

    if (do_something_that_might_raise() != success_indicator) {
        PyErr_WriteUnraisable(self);
        goto done;
    }

done:
    // Restore the saved exception.  This silently discards any exception
    // raised above, so be sure to call PyErr_WriteUnraisable first if
    // necessary.
    PyErr_SetRaisedException(exc);
}
```

Inheritance:

This field is inherited by subtypes.

Added in version 3.4.

3.8 sürümünde değişti: Before version 3.8 it was necessary to set the *Py_TPFLAGS_HAVE_FINALIZE* flags bit in order for this field to be used. This is no longer required.

Ayrıca bakınız

- **PEP 442**: "Safe object finalization"
- *Object Life Cycle* for details about how this slot relates to other slots.
- *PyObject_CallFinalizer()*
- *PyObject_CallFinalizerFromDealloc()*

vectorcallfunc *PyTypeObject*.**tp_vectorcall**

A *vectorcall function* to use for calls of this type object (rather than instances). In other words, `tp_vectorcall` can be used to optimize `type.__call__`, which typically returns a new instance of *type*.

As with any vectorcall function, if `tp_vectorcall` is `NULL`, the *tp_call* protocol (`Py_TYPE(type)->tp_call`) is used instead.

Not

The *vectorcall protocol* requires that the vectorcall function has the same behavior as the corresponding `tp_call`. This means that `type->tp_vectorcall` must match the behavior of `Py_TYPE(type)->tp_call`.

Specifically, if *type* uses the default metaclass, `type->tp_vectorcall` must behave the same as *PyType_Type*`->tp_call`, which:

- calls `type->tp_new`,
- if the result is a subclass of *type*, calls `type->tp_init` on the result of `tp_new`, and
- returns the result of `tp_new`.

Typically, `tp_vectorcall` is overridden to optimize this process for specific *tp_new* and *tp_init*. When doing this for user-subclassable types, note that both can be overridden (using `__new__()` and `__init__()`, respectively).

Inheritance:

This field is never inherited.

Added in version 3.9: (the field exists since 3.8 but it's only used since 3.9)

unsigned char *PyTypeObject*.**tp_watched**

Internal. Do not use.

Added in version 3.12.

13.4.6 Static Types

Traditionally, types defined in C code are *static*, that is, a static *PyTypeObject* structure is defined directly in code and initialized using *PyType_Ready()*.

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state.

Also, since *PyTypeObject* is only part of the *Limited API* as an opaque struct, any extension modules using static types must be compiled for a specific Python minor version.

13.4.7 Heap Types

An alternative to *static types* is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's `class` statement. Heap types have the *Py_TPFLAGS_HEAPTYPE* flag set.

This is done by filling a *PyType_Spec* structure and calling *PyType_FromSpec()*, *PyType_FromSpecWithBases()*, *PyType_FromModuleAndSpec()*, or *PyType_FromMetaclass()*.

13.4.8 Number Object Structures

type **PyNumberMethods**

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Number Protocol* section.

Here is the structure definition:

```
typedef struct {
     binaryfunc nb_add;
     binaryfunc nb_subtract;
     binaryfunc nb_multiply;
     binaryfunc nb_remainder;
     binaryfunc nb_divmod;
     ternaryfunc nb_power;
     unaryfunc nb_negative;
     unaryfunc nb_positive;
     unaryfunc nb_absolute;
     inquiry nb_bool;
     unaryfunc nb_invert;
     binaryfunc nb_lshift;
     binaryfunc nb_rshift;
     binaryfunc nb_and;
     binaryfunc nb_xor;
     binaryfunc nb_or;
     unaryfunc nb_int;
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    void *nb_reserved;
    unaryfunc nb_float;

    binaryfunc nb_inplace_add;
    binaryfunc nb_inplace_subtract;
    binaryfunc nb_inplace_multiply;
    binaryfunc nb_inplace_remainder;
    ternaryfunc nb_inplace_power;
    binaryfunc nb_inplace_lshift;
    binaryfunc nb_inplace_rshift;
    binaryfunc nb_inplace_and;
    binaryfunc nb_inplace_xor;
    binaryfunc nb_inplace_or;

    binaryfunc nb_floor_divide;
    binaryfunc nb_true_divide;
    binaryfunc nb_inplace_floor_divide;
    binaryfunc nb_inplace_true_divide;

    unaryfunc nb_index;

    binaryfunc nb_matrix_multiply;
    binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;
```

Not

Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return `Py_NotImplemented`, if another error occurred they must return `NULL` and set an exception.

Not

The *nb_reserved* field should always be `NULL`. It was previously called `nb_long`, and was renamed in Python 3.0.1.

binaryfunc *PyNumberMethods*.**nb_add**

binaryfunc *PyNumberMethods*.**nb_subtract**

binaryfunc *PyNumberMethods*.**nb_multiply**

binaryfunc *PyNumberMethods*.**nb_remainder**

binaryfunc *PyNumberMethods*.**nb_divmod**

ternaryfunc *PyNumberMethods*.**nb_power**

unaryfunc *PyNumberMethods*.**nb_negative**

unaryfunc *PyNumberMethods*.**nb_positive**

unaryfunc *PyNumberMethods*.**nb_absolute**

inquiry *PyNumberMethods*.**nb_bool**

unaryfunc *PyNumberMethods*.**nb_invert**

binaryfunc *PyNumberMethods*.**nb_lshift**

binaryfunc *PyNumberMethods*.**nb_rshift**

binaryfunc *PyNumberMethods*.**nb_and**

binaryfunc *PyNumberMethods*.**nb_xor**

binaryfunc *PyNumberMethods*.**nb_or**

unaryfunc *PyNumberMethods*.**nb_int**

void **PyNumberMethods*.**nb_reserved**

unaryfunc *PyNumberMethods*.**nb_float**

binaryfunc *PyNumberMethods*.**nb_inplace_add**

binaryfunc *PyNumberMethods*.**nb_inplace_subtract**

binaryfunc *PyNumberMethods*.**nb_inplace_multiply**

binaryfunc *PyNumberMethods*.**nb_inplace_remainder**

ternaryfunc *PyNumberMethods*.**nb_inplace_power**

binaryfunc *PyNumberMethods*.**nb_inplace_lshift**

binaryfunc *PyNumberMethods*.**nb_inplace_rshift**

binaryfunc *PyNumberMethods*.**nb_inplace_and**

binaryfunc *PyNumberMethods*.**nb_inplace_xor**

binaryfunc *PyNumberMethods*.**nb_inplace_or**

binaryfunc *PyNumberMethods*.**nb_floor_divide**

binaryfunc *PyNumberMethods*.**nb_true_divide**

binaryfunc *PyNumberMethods*.**nb_inplace_floor_divide**

binaryfunc *PyNumberMethods*.**nb_inplace_true_divide**

unaryfunc *PyNumberMethods*.**nb_index**

binaryfunc *PyNumberMethods*.**nb_matrix_multiply**

binaryfunc *PyNumberMethods*.**nb_inplace_matrix_multiply**

13.4.9 Mapping Object Structures

type **PyMappingMethods**

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

lenfunc *PyMappingMethods*.**mp_length**

This function is used by *PyMapping_Size()* and *PyObject_Size()*, and has the same signature. This slot may be set to `NULL` if the object has no defined length.

binaryfunc *PyMappingMethods*.**mp_subscript**

This function is used by *PyObject_GetItem()* and *PySequence_GetSlice()*, and has the same signature as `PyObject_GetItem()`. This slot must be filled for the *PyMapping_Check()* function to return `1`, it can be `NULL` otherwise.

objobjargproc *PyMappingMethods*.**mp_ass_subscript**

This function is used by *PyObject_SetItem()*, *PyObject_DelItem()*, *PySequence_SetSlice()* and *PySequence_DelSlice()*. It has the same signature as `PyObject_SetItem()`, but *v* can also be set to `NULL` to delete an item. If this slot is `NULL`, the object does not support item assignment and deletion.

13.4.10 Sequence Object Structures

type **PySequenceMethods**

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

lenfunc *PySequenceMethods*.**sq_length**

This function is used by *PySequence_Size()* and *PyObject_Size()*, and has the same signature. It is also used for handling negative indices via the *sq_item* and the *sq_ass_item* slots.

binaryfunc *PySequenceMethods*.**sq_concat**

This function is used by *PySequence_Concat()* and has the same signature. It is also used by the `+` operator, after trying the numeric addition via the *nb_add* slot.

ssizeargfunc *PySequenceMethods*.**sq_repeat**

This function is used by *PySequence_Repeat()* and has the same signature. It is also used by the `*` operator, after trying numeric multiplication via the *nb_multiply* slot.

ssizeargfunc *PySequenceMethods*.**sq_item**

This function is used by *PySequence_GetItem()* and has the same signature. It is also used by *PyObject_GetItem()*, after trying the subscription via the *mp_subscript* slot. This slot must be filled for the *PySequence_Check()* function to return `1`, it can be `NULL` otherwise.

Negative indexes are handled as follows: if the *sq_length* slot is filled, it is called and the sequence length is used to compute a positive index which is passed to *sq_item*. If `sq_length` is `NULL`, the index is passed as is to the function.

ssizeobjargproc *PySequenceMethods*.**sq_ass_item**

This function is used by *PySequence_SetItem()* and has the same signature. It is also used by *PyObject_SetItem()* and *PyObject_DelItem()*, after trying the item assignment and deletion via the *mp_ass_subscript* slot. This slot may be left to `NULL` if the object does not support item assignment and deletion.

objobjproc *PySequenceMethods*.**sq_contains**

This function may be used by *PySequence_Contains()* and has the same signature. This slot may be left to `NULL`, in this case `PySequence_Contains()` simply traverses the sequence until it finds a match.

binaryfunc *PySequenceMethods*.**sq_inplace_concat**

This function is used by *PySequence_InPlaceConcat()* and has the same signature. It should modify its first operand, and return it. This slot may be left to `NULL`, in this case `PySequence_InPlaceConcat()` will fall back to *PySequence_Concat()*. It is also used by the augmented assignment `+=`, after trying numeric in-place addition via the *nb_inplace_add* slot.

ssizeargfunc *PySequenceMethods*.**sq_inplace_repeat**

This function is used by *PySequence_InPlaceRepeat()* and has the same signature. It should modify its first operand, and return it. This slot may be left to `NULL`, in this case `PySequence_InPlaceRepeat()` will fall back to *PySequence_Repeat()*. It is also used by the augmented assignment `*=`, after trying numeric in-place multiplication via the *nb_inplace_multiply* slot.

13.4.11 Buffer Object Structures

type **PyBufferProcs**

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

getbufferproc *PyBufferProcs*.**bf_getbuffer**

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps:

(1) Check if the request can be met. If not, raise `BufferError`, set `view->obj` to `NULL` and return `-1`.

(2) Fill in the requested fields.

(3) Increment an internal counter for the number of exports.

(4) Set `view->obj` to *exporter* and increment `view->obj`.

(5) Return `0`.

If *exporter* is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets `view->obj` to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, `view->obj` will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the *Py_buffer* structure belongs to the exporter and must remain valid until there are no consumers left. *format*, *shape*, *strides*, *suboffsets* and *internal* are read-only for the consumer.

PyBuffer_FillInfo() provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject_GetBuffer() is the interface for the consumer that wraps this function.

releasebufferproc *PyBufferProcs*.**bf_releasebuffer**

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, *PyBufferProcs.bf_releasebuffer* may be `NULL`. Otherwise, a standard implementation of this function will take these optional steps:

(1) Decrement an internal counter for the number of exports.

(2) If the counter is `0`, free all memory associated with *view*.

The exporter MUST use the *internal* field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the *view* argument.

This function MUST NOT decrement `view->obj`, since that is done automatically in *PyBuffer_Release()* (this scheme is useful for breaking reference cycles).

PyBuffer_Release() is the interface for the consumer that wraps this function.

13.4.12 Async Object Structures

Added in version 3.5.

type **PyAsyncMethods**

This structure holds pointers to the functions required to implement *awaitable* and *asynchronous iterator* objects.

Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
    sendfunc am_send;
} PyAsyncMethods;
```

unaryfunc *PyAsyncMethods*.**am_await**

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an *iterator*, i.e. *PyIter_Check()* must return `1` for it.

This slot may be set to `NULL` if an object is not an *awaitable*.

unaryfunc *PyAsyncMethods*.**am_aiter**

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an *asynchronous iterator* object. See `__anext__()` for details.

This slot may be set to `NULL` if an object does not implement asynchronous iteration protocol.

unaryfunc *PyAsyncMethods*.**am_anext**

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an *awaitable* object. See `__anext__()` for details. This slot may be set to `NULL`.

sendfunc *PyAsyncMethods*.**am_send**

The signature of this function is:

```
PySendResult am_send(PyObject *self, PyObject *arg, PyObject **result);
```

See *PyIter_Send()* for details. This slot may be set to `NULL`.

Added in version 3.10.

13.4.13 Slot Type typedefs

typedef *PyObject* *(***allocfunc**)(*PyTypeObject* *cls, *Py_ssize_t* nitems)

Bir parçası Kararlı ABI. The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with *ob_refcnt* set to `1` and *ob_type* set to the type argument. If the type's *tp_itemsize* is non-zero, the object's *ob_size* field should be initialized to *nitems* and the length of the allocated memory block should be `tp_basicsize + nitems*tp_itemsize`, rounded up to a multiple of `sizeof(void*)`; otherwise, *nitems* is not used and the length of the block should be *tp_basicsize*.

This function should not do any other instance initialization, not even to allocate additional memory; that should be done by *tp_new*.

typedef void (*__destructor__)(*PyObject**)

Bir parçası Kararlı ABI.

typedef void (*__freefunc__)(void*)

See *tp_free*.

typedef *PyObject* *(*__newfunc__)(*PyTypeObject**, *PyObject**, *PyObject**)

Bir parçası Kararlı ABI. See *tp_new*.

typedef int (*__initproc__)(*PyObject**, *PyObject**, *PyObject**)

Bir parçası Kararlı ABI. See *tp_init*.

typedef *PyObject* *(*__reprfunc__)(*PyObject**)

Bir parçası Kararlı ABI. See *tp_repr*.

typedef *PyObject* *(*__getattrfunc__)(*PyObject* *self, char *attr)

Bir parçası Kararlı ABI. Return the value of the named attribute for the object.

typedef int (*__setattrfunc__)(*PyObject* *self, char *attr, *PyObject* *value)

Bir parçası Kararlı ABI. Set the value of the named attribute for the object. The value argument is set to `NULL` to delete the attribute.

typedef *PyObject* *(*__getattrofunc__)(*PyObject* *self, *PyObject* *attr)

Bir parçası Kararlı ABI. Return the value of the named attribute for the object.

See *tp_getattro*.

typedef int (*__setattrofunc__)(*PyObject* *self, *PyObject* *attr, *PyObject* *value)

Bir parçası Kararlı ABI. Set the value of the named attribute for the object. The value argument is set to `NULL` to delete the attribute.

See *tp_setattro*.

typedef *PyObject* *(*__descrgetfunc__)(*PyObject**, *PyObject**, *PyObject**)

Bir parçası Kararlı ABI. See *tp_descr_get*.

typedef int (*__descrsetfunc__)(*PyObject**, *PyObject**, *PyObject**)

Bir parçası Kararlı ABI. See *tp_descr_set*.

typedef *Py_hash_t* (*__hashfunc__)(*PyObject**)

Bir parçası Kararlı ABI. See *tp_hash*.

typedef *PyObject* *(*__richcmpfunc__)(*PyObject**, *PyObject**, int)

Bir parçası Kararlı ABI. See *tp_richcompare*.

typedef *PyObject* *(*__getiterfunc__)(*PyObject**)

Bir parçası Kararlı ABI. See *tp_iter*.

typedef *PyObject* *(*__iternextfunc__)(*PyObject**)

Bir parçası Kararlı ABI. See *tp_iternext*.

typedef *Py_ssize_t* (*__lenfunc__)(*PyObject**)

Bir parçası Kararlı ABI.

typedef int (*__getbufferproc__)(*PyObject**, *Py_buffer**, int)

Bir parçası Kararlı ABI *3.12 sürümünden beri.*

typedef void (*__releasebufferproc__)(*PyObject**, *Py_buffer**)

Bir parçası Kararlı ABI *3.12 sürümünden beri.*

typedef *PyObject* *(*__unaryfunc__)(*PyObject**)

Bir parçası Kararlı ABI.

typedef *PyObject* *(***binaryfunc**)(*PyObject**, *PyObject**)
Bir parçası Kararlı ABI.

typedef *PySendResult* (***sendfunc**)(*PyObject**, *PyObject**, *PyObject*****)
See *am_send*.

typedef *PyObject* *(***ternaryfunc**)(*PyObject**, *PyObject**, *PyObject**)
Bir parçası Kararlı ABI.

typedef *PyObject* *(***ssizeargfunc**)(*PyObject**, *Py_ssize_t*)
Bir parçası Kararlı ABI.

typedef int (***ssizeobjargproc**)(*PyObject**, *Py_ssize_t*, *PyObject**)
Bir parçası Kararlı ABI.

typedef int (***objobjproc**)(*PyObject**, *PyObject**)
Bir parçası Kararlı ABI.

typedef int (***objobjargproc**)(*PyObject**, *PyObject**, *PyObject**)
Bir parçası Kararlı ABI.

13.4.14 Examples

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see defining-new-types and new-types-topics.

A basic *static type*:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

```
static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    "mymod.MyObject",               /* tp_name */
    sizeof(MyObject),               /* tp_basicsize */
    0,                              /* tp_itemsize */
    (destructor)myobj_dealloc,      /* tp_dealloc */
    0,                              /* tp_vectorcall_offset */
    0,                              /* tp_getattr */
    0,                              /* tp_setattr */
    0,                              /* tp_as_async */
    (reprfunc)myobj_repr,           /* tp_repr */
    0,                              /* tp_as_number */
    0,                              /* tp_as_sequence */
    0,                              /* tp_as_mapping */
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    0,                                  /* tp_hash */
    0,                                  /* tp_call */
    0,                                  /* tp_str */
    0,                                  /* tp_getattro */
    0,                                  /* tp_setattro */
    0,                                  /* tp_as_buffer */
    0,                                  /* tp_flags */
    PyDoc_STR("My objects"),            /* tp_doc */
    0,                                  /* tp_traverse */
    0,                                  /* tp_clear */
    0,                                  /* tp_richcompare */
    0,                                  /* tp_weaklistoffset */
    0,                                  /* tp_iter */
    0,                                  /* tp_iternext */
    0,                                  /* tp_methods */
    0,                                  /* tp_members */
    0,                                  /* tp_getset */
    0,                                  /* tp_base */
    0,                                  /* tp_dict */
    0,                                  /* tp_descr_get */
    0,                                  /* tp_descr_set */
    0,                                  /* tp_dictoffset */
    0,                                  /* tp_init */
    0,                                  /* tp_alloc */
    myobj_new,                          /* tp_new */
};
```

A type that supports weakrefs, instance dicts, and hashing:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE |
         Py_TPFLAGS_HAVE_GC | Py_TPFLAGS_MANAGED_DICT |
         Py_TPFLAGS_MANAGED_WEAKREF,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
    .tp_hash = (hashfunc)myobj_hash,
    .tp_richcompare = PyBaseObject_Type.tp_richcompare,
};
```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func) using *Py_TPFLAGS_DISALLOW_INSTANTIATION* flag:

```
typedef struct {
    PyUnicodeObject raw;
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
    char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL,  // set to &PyUnicode_Type in module init
    .tp_doc = PyDoc_STR("my custom str"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_DISALLOW_INSTANTIATION,
    .tp_repr = (reprfunc)myobj_repr,
};
```

The simplest *static type* with fixed-length instances:

```
typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest *static type* with variable-length instances:

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};
```

13.5 Supporting Cyclic Garbage Collection

Python's support for detecting and collecting garbage which involves circular references requires support from object types which are "containers" for other objects which may also be containers. Types which do not store references to other objects, or which only store references to atomic types (such as numbers or strings), do not need to provide any explicit support for garbage collection.

To create a container type, the *tp_flags* field of the type object must include the *Py_TPFLAGS_HAVE_GC* and provide an implementation of the *tp_traverse* handler. If instances of the type are mutable, a *tp_clear* implementation must also be provided.

Py_TPFLAGS_HAVE_GC
: Objects with a type with this flag set must conform with the rules documented here. For convenience these objects will be referred to as container objects.

Constructors for container types must conform to two rules:

1. The memory for the object must be allocated using *PyObject_GC_New* or *PyObject_GC_NewVar*.
2. Once all the fields which may contain references to other containers are initialized, it must call *PyObject_GC_Track()*.

Similarly, the deallocator for the object must conform to a similar pair of rules:

1. Before fields which refer to other containers are invalidated, `PyObject_GC_UnTrack()` must be called.
2. The object's memory must be deallocated using `PyObject_GC_Del()`.

> **Uyarı**
>
> If a type adds the Py_TPFLAGS_HAVE_GC, then it *must* implement at least a `tp_traverse` handler or explicitly use one from its subclass or subclasses.
>
> When calling `PyType_Ready()` or some of the APIs that indirectly call it like `PyType_FromSpecWithBases()` or `PyType_FromSpec()` the interpreter will automatically populate the `tp_flags`, `tp_traverse` and `tp_clear` fields if the type inherits from a class that implements the garbage collector protocol and the child class does *not* include the `Py_TPFLAGS_HAVE_GC` flag.

PyObject_GC_New(TYPE, typeobj)

Analogous to `PyObject_New` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

Do not call this directly to allocate memory for an object; call the type's `tp_alloc` slot instead.

When populating a type's `tp_alloc` slot, `PyType_GenericAlloc()` is preferred over a custom function that simply calls this macro.

Memory allocated by this macro must be freed with `PyObject_GC_Del()` (usually called via the object's `tp_free` slot).

> **Ayrıca bakınız**
>
> - `PyObject_GC_Del()`
> - `PyObject_New`
> - `PyType_GenericAlloc()`
> - `tp_alloc`

PyObject_GC_NewVar(TYPE, typeobj, size)

Analogous to `PyObject_NewVar` but for container objects with the `Py_TPFLAGS_HAVE_GC` flag set.

Do not call this directly to allocate memory for an object; call the type's `tp_alloc` slot instead.

When populating a type's `tp_alloc` slot, `PyType_GenericAlloc()` is preferred over a custom function that simply calls this macro.

Memory allocated by this macro must be freed with `PyObject_GC_Del()` (usually called via the object's `tp_free` slot).

> **Ayrıca bakınız**
>
> - `PyObject_GC_Del()`
> - `PyObject_NewVar`
> - `PyType_GenericAlloc()`
> - `tp_alloc`

PyObject ***PyUnstable_Object_GC_NewWithExtraData**(*PyTypeObject* *type, size_t extra_size)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Analogous to `PyObject_GC_New` but allocates *extra_size* bytes at the end of the object (at offset `tp_basicsize`). The allocated memory is initialized to zeros, except for the `Python object header`.

The extra data will be deallocated with the object, but otherwise it is not managed by Python.

Memory allocated by this function must be freed with `PyObject_GC_Del()` (usually called via the object's `tp_free` slot).

Uyarı

The function is marked as unstable because the final mechanism for reserving extra data after an instance is not yet decided. For allocating a variable number of fields, prefer using `PyVarObject` and `tp_itemsize` instead.

Added in version 3.12.

PyObject_GC_Resize(TYPE, op, newsize)

Resize an object allocated by `PyObject_NewVar`. Returns the resized object of type `TYPE*` (refers to any C type) or `NULL` on failure.

op must be of type `PyVarObject*` and must not be tracked by the collector yet. *newsize* must be of type `Py_ssize_t`.

void **PyObject_GC_Track**(*PyObject* *op)

Bir parçası Kararlı ABI. Adds the object *op* to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the `tp_traverse` handler become valid, usually near the end of the constructor.

int **PyObject_IS_GC**(*PyObject* *obj)

Returns non-zero if the object implements the garbage collector protocol, otherwise returns 0.

The object cannot be tracked by the garbage collector if this function returns 0.

int **PyObject_GC_IsTracked**(*PyObject* *op)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Returns 1 if the object type of *op* implements the GC protocol and *op* is being currently tracked by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_tracked()`.

Added in version 3.9.

int **PyObject_GC_IsFinalized**(*PyObject* *op)

Bir parçası Kararlı ABI *3.9 sürümünden beri.* Returns 1 if the object type of *op* implements the GC protocol and *op* has been already finalized by the garbage collector and 0 otherwise.

This is analogous to the Python function `gc.is_finalized()`.

Added in version 3.9.

void **PyObject_GC_Del**(void *op)

Bir parçası Kararlı ABI. Releases memory allocated to an object using `PyObject_GC_New` or `PyObject_GC_NewVar`.

Do not call this directly to free an object's memory; call the type's `tp_free` slot instead.

Do not use this for memory allocated by `PyObject_New`, `PyObject_NewVar`, or related allocation functions; use `PyObject_Free()` instead.

Ayrıca bakınız

- *PyObject_Free()* is the non-GC equivalent of this function.
- *PyObject_GC_New*
- *PyObject_GC_NewVar*
- *PyType_GenericAlloc()*
- *tp_free*

void **PyObject_GC_UnTrack**(void *op)

Bir parçası Kararlı ABI. Remove the object *op* from the set of container objects tracked by the collector. Note that *PyObject_GC_Track()* can be called again on this object to add it back to the set of tracked objects. The deallocator (*tp_dealloc* handler) should call this for the object before any of the fields used by the *tp_traverse* handler become invalid.

3.8 sürümünde değişti: The `_PyObject_GC_TRACK()` and `_PyObject_GC_UNTRACK()` macros have been removed from the public C API.

The *tp_traverse* handler accepts a function parameter of this type:

typedef int (***visitproc**)(*PyObject* *object, void *arg)

Bir parçası Kararlı ABI. Type of the visitor function passed to the *tp_traverse* handler. The function should be called with an object to traverse as *object* and the third parameter to the *tp_traverse* handler as *arg*. The Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The *tp_traverse* handler must have the following type:

typedef int (***traverseproc**)(*PyObject* *self, *visitproc* visit, void *arg)

Bir parçası Kararlı ABI. Traversal function for a container object. Implementations must call the *visit* function for each object directly contained by *self*, with the parameters to *visit* being the contained object and the *arg* value passed to the handler. The *visit* function must not be called with a `NULL` object argument. If *visit* returns a non-zero value that value should be returned immediately.

To simplify writing *tp_traverse* handlers, a *Py_VISIT()* macro is provided. In order to use this macro, the *tp_traverse* implementation must name its arguments exactly *visit* and *arg*:

Py_VISIT(o)

If the *PyObject** *o* is not `NULL`, call the *visit* callback, with arguments *o* and *arg*. If *visit* returns a non-zero value, then return it. Using this macro, *tp_traverse* handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The *tp_clear* handler must be of the *inquiry* type, or `NULL` if the object is immutable.

typedef int (***inquiry**)(*PyObject* *self)

Bir parçası Kararlı ABI. Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after calling this method (don't just call *Py_DECREF()* on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

13.5.1 Controlling the Garbage Collector State

The C-API provides the following functions for controlling garbage collection runs.

Py_ssize_t **PyGC_Collect**(void)

Bir parçası Kararlı ABI. Perform a full garbage collection, if the garbage collector is enabled. (Note that `gc.collect()` runs it unconditionally.)

Returns the number of collected + unreachable objects which cannot be collected. If the garbage collector is disabled or already collecting, returns `0` immediately. Errors during garbage collection are passed to `sys.unraisablehook`. This function does not raise exceptions.

int **PyGC_Enable**(void)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Enable the garbage collector: similar to `gc.enable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Added in version 3.10.

int **PyGC_Disable**(void)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Disable the garbage collector: similar to `gc.disable()`. Returns the previous state, 0 for disabled and 1 for enabled.

Added in version 3.10.

int **PyGC_IsEnabled**(void)

Bir parçası Kararlı ABI *3.10 sürümünden beri.* Query the state of the garbage collector: similar to `gc.isenabled()`. Returns the current state, 0 for disabled and 1 for enabled.

Added in version 3.10.

13.5.2 Querying Garbage Collector State

The C-API provides the following interface for querying information about the garbage collector.

void **PyUnstable_GC_VisitObjects**(*gcvisitobjects_t* callback, void *arg)

Bu *Kararsız API*. Bu, küçük (minor) sürümlerde uyarı olmadan değişebilir.

Run supplied *callback* on all live GC-capable objects. *arg* is passed through to all invocations of *callback*.

Uyarı

If new objects are (de)allocated by the callback it is undefined if they will be visited.

Garbage collection is disabled during operation. Explicitly running a collection in the callback may lead to undefined behaviour e.g. visiting the same objects multiple times or not at all.

Added in version 3.12.

typedef int (***gcvisitobjects_t**)(*PyObject* *object, void *arg)

Type of the visitor function to be passed to *`PyUnstable_GC_VisitObjects()`*. *arg* is the same as the *arg* passed to `PyUnstable_GC_VisitObjects`. Return `1` to continue iteration, return `0` to stop iteration. Other return values are reserved for now so behavior on returning anything else is undefined.

Added in version 3.12.

BÖLÜM 14

API and ABI Versioning

14.1 Build-time version constants

CPython exposes its version number in the following macros. Note that these correspond to the version code is **built** with. See `Py_Version` for the version used at **run time**.

See *C API Stability* for a discussion of API and ABI stability across versions.

PY_MAJOR_VERSION

The `3` in `3.4.1a2`.

PY_MINOR_VERSION

The `4` in `3.4.1a2`.

PY_MICRO_VERSION

The `1` in `3.4.1a2`.

PY_RELEASE_LEVEL

The `a` in `3.4.1a2`. This can be `0xA` for alpha, `0xB` for beta, `0xC` for release candidate or `0xF` for final.

PY_RELEASE_SERIAL

The `2` in `3.4.1a2`. Zero for final releases.

PY_VERSION_HEX

The Python version number encoded in a single integer. See `Py_PACK_FULL_VERSION()` for the encoding details.

Use this for numeric comparisons, for example, `#if PY_VERSION_HEX > = ...`.

14.2 Run-time version

const unsigned long **Py_Version**

Bir parçası Kararlı ABI *3.11 sürümünden beri.* The Python runtime version number encoded in a single constant integer. See `Py_PACK_FULL_VERSION()` for the encoding details. This contains the Python version used at run time.

Use this for numeric comparisons, for example, `if (Py_Version > = ...)`.

Added in version 3.11.

14.3 Bit-packing macros

uint32_t **Py_PACK_FULL_VERSION**(int major, int minor, int micro, int release_level, int release_serial)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Return the given version, encoded as a single 32-bit integer with the following structure:

Argument	No. of bits	Bit mask	Bit shift	Example values	
				`3.4.1a2`	`3.10.0`
major	8	`0xFF000000`	24	`0x03`	`0x03`
minor	8	`0x00FF0000`	16	`0x04`	`0x0A`
micro	8	`0x0000FF00`	8	`0x01`	`0x00`
release_level	4	`0x000000F0`	4	`0xA`	`0xF`
release_serial	4	`0x0000000F`	0	`0x2`	`0x0`

For example:

Version	`Py_PACK_FULL_VERSION` arguments	Encoded version
`3.4.1a2`	`(3, 4, 1, 0xA, 2)`	`0x030401a2`
`3.10.0`	`(3, 10, 0, 0xF, 0)`	`0x030a00f0`

Out-of range bits in the arguments are ignored. That is, the macro can be defined as:

```
#ifndef Py_PACK_FULL_VERSION
#define Py_PACK_FULL_VERSION(X, Y, Z, LEVEL, SERIAL) ( \
   (((X) & 0xff) << 24) |                              \
   (((Y) & 0xff) << 16) |                              \
   (((Z) & 0xff) << 8) |                               \
   (((LEVEL) & 0xf) << 4) |                            \
   (((SERIAL) & 0xf) << 0))
#endif
```

`Py_PACK_FULL_VERSION` is primarily a macro, intended for use in `#if` directives, but it is also available as an exported function.

Added in version 3.14.

uint32_t **Py_PACK_VERSION**(int major, int minor)

Bir parçası Kararlı ABI *3.14 sürümünden beri.* Equivalent to `Py_PACK_FULL_VERSION(major, minor, 0, 0, 0)`. The result does not correspond to any Python release, but is useful in numeric comparisons.

Added in version 3.14.

BÖLÜM 15

Monitoring C API

Added in version 3.13.

An extension may need to interact with the event monitoring system. Subscribing to events and registering callbacks can be done via the Python API exposed in `sys.monitoring`.

BÖLÜM 16

Generating Execution Events

The functions below make it possible for an extension to fire monitoring events as it emulates the execution of Python code. Each of these functions accepts a `PyMonitoringState` struct which contains concise information about the activation state of events, as well as the event arguments, which include a `PyObject*` representing the code object, the instruction offset and sometimes additional, event-specific arguments (see `sys.monitoring` for details about the signatures of the different event callbacks). The `codelike` argument should be an instance of `types.CodeType` or of a type that emulates it.

The VM disables tracing when firing an event, so there is no need for user code to do that.

Monitoring functions should not be called with an exception set, except those listed below as working with the current exception.

type **PyMonitoringState**

Representation of the state of an event type. It is allocated by the user while its contents are maintained by the monitoring API functions described below.

All of the functions below return 0 on success and -1 (with an exception set) on error.

See `sys.monitoring` for descriptions of the events.

int **PyMonitoring_FirePyStartEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `PY_START` event.

int **PyMonitoring_FirePyResumeEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `PY_RESUME` event.

int **PyMonitoring_FirePyReturnEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *retval)

Fire a `PY_RETURN` event.

int **PyMonitoring_FirePyYieldEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *retval)

Fire a `PY_YIELD` event.

int **PyMonitoring_FireCallEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *callable, *PyObject* *arg0)

Fire a `CALL` event.

int **PyMonitoring_FireLineEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, int lineno)

Fire a `LINE` event.

int **PyMonitoring_FireJumpEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *target_offset)

Fire a `JUMP` event.

int **PyMonitoring_FireBranchLeftEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *target_offset)

Fire a `BRANCH_LEFT` event.

int **PyMonitoring_FireBranchRightEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *target_offset)

Fire a `BRANCH_RIGHT` event.

int **PyMonitoring_FireCReturnEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *retval)

Fire a `C_RETURN` event.

int **PyMonitoring_FirePyThrowEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `PY_THROW` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FireRaiseEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `RAISE` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FireCRaiseEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `C_RAISE` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FireReraiseEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `RERAISE` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FireExceptionHandledEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire an `EXCEPTION_HANDLED` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FirePyUnwindEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset)

Fire a `PY_UNWIND` event with the current exception (as returned by *`PyErr_GetRaisedException()`*).

int **PyMonitoring_FireStopIterationEvent**(*PyMonitoringState* *state, *PyObject* *codelike, int32_t offset, *PyObject* *value)

Fire a `STOP_ITERATION` event. If `value` is an instance of `StopIteration`, it is used. Otherwise, a new `StopIteration` instance is created with `value` as its argument.

16.1 Managing the Monitoring State

Monitoring states can be managed with the help of monitoring scopes. A scope would typically correspond to a python function.

int **PyMonitoring_EnterScope**(*PyMonitoringState* *state_array, uint64_t *version, const uint8_t *event_types, *Py_ssize_t* length)

Enter a monitored scope. `event_types` is an array of the event IDs for events that may be fired from the scope. For example, the ID of a `PY_START` event is the value `PY_MONITORING_EVENT_PY_START`, which is numerically equal to the base-2 logarithm of `sys.monitoring.events.PY_START`. `state_array` is an array with a monitoring state entry for each event in `event_types`, it is allocated by the user but populated by `PyMonitoring_EnterScope()` with information about the activation state of the event. The size of `event_types` (and hence also of `state_array`) is given in `length`.

The `version` argument is a pointer to a value which should be allocated by the user together with `state_array` and initialized to 0, and then set only by `PyMonitoring_EnterScope()` itself. It allows this function to determine whether event states have changed since the previous call, and to return quickly if they have not.

The scopes referred to here are lexical scopes: a function, class or method. `PyMonitoring_EnterScope()` should be called whenever the lexical scope is entered. Scopes can be reentered, reusing the same *state_array* and *version*, in situations like when emulating a recursive Python function. When a code-like's execution is paused, such as when emulating a generator, the scope needs to be exited and re-entered.

The macros for *event_types* are:

Macro	Event
PY_MONITORING_EVENT_BRANCH_LEFT	BRANCH_LEFT
PY_MONITORING_EVENT_BRANCH_RIGHT	BRANCH_RIGHT
PY_MONITORING_EVENT_CALL	CALL
PY_MONITORING_EVENT_C_RAISE	C_RAISE
PY_MONITORING_EVENT_C_RETURN	C_RETURN
PY_MONITORING_EVENT_EXCEPTION_HANDLED	EXCEPTION_HANDLED
PY_MONITORING_EVENT_INSTRUCTION	INSTRUCTION
PY_MONITORING_EVENT_JUMP	JUMP
PY_MONITORING_EVENT_LINE	LINE
PY_MONITORING_EVENT_PY_RESUME	PY_RESUME
PY_MONITORING_EVENT_PY_RETURN	PY_RETURN
PY_MONITORING_EVENT_PY_START	PY_START
PY_MONITORING_EVENT_PY_THROW	PY_THROW
PY_MONITORING_EVENT_PY_UNWIND	PY_UNWIND
PY_MONITORING_EVENT_PY_YIELD	PY_YIELD
PY_MONITORING_EVENT_RAISE	RAISE
PY_MONITORING_EVENT_RERAISE	RERAISE
PY_MONITORING_EVENT_STOP_ITERATION	STOP_ITERATION

int **PyMonitoring_ExitScope**(void)

Exit the last scope that was entered with `PyMonitoring_EnterScope()`.

int **PY_MONITORING_IS_INSTRUMENTED_EVENT**(uint8_t ev)

Return true if the event corresponding to the event ID *ev* is a local event.

Added in version 3.13.

3.14 sürümünden beri kullanım dışı: This function is *soft deprecated*.

EK A

Sözlük

>>>
: The default Python prompt of the *interactive* shell. Often seen for code examples which can be executed interactively in the interpreter.

...
: Şunlara başvurabilir:

  - The default Python prompt of the *interactive* shell when entering the code for an indented code block, when within a pair of matching left and right delimiters (parentheses, square brackets, curly braces or triple quotes), or after specifying a decorator.
  - The three dots form of the Ellipsis object.

soyut temel sınıf
: Soyut temel sınıflar *duck-typing* 'i, `hasattr()` gibi diğer teknikler beceriksiz veya tamamen yanlış olduğunda arayüzleri tanımlamanın bir yolunu sağlayarak tamamlar (örneğin sihirli yöntemlerle). ABC'ler, bir sınıftan miras almayan ancak yine de `isinstance()` ve `issubclass()` tarafından tanınan sınıflar olan sanal alt sınıfları tanıtır; `abc` modül belgelerine bakın. Python comes with many built-in ABCs for data structures (in the `collections.abc` module), numbers (in the `numbers` module), streams (in the `io` module), import finders and loaders (in the `importlib.abc` module). `abc` modülü ile kendi ABC'lerinizi oluşturabilirsiniz.

annotate function
: A function that can be called to retrieve the *annotations* of an object. This function is accessible as the `__annotate__` attribute of functions, classes, and modules. Annotate functions are a subset of *evaluate functions*.

dipnot
: Bir değişkenle, bir sınıf niteliğiyle veya bir fonksiyon parametresiyle veya bir dönüş değeriyle ilişkilendirilen, gelenek olarak *type hint* biçiminde kullanılan bir etiket.

  Annotations of local variables cannot be accessed at runtime, but annotations of global variables, class attributes, and functions can be retrieved by calling `annotationlib.get_annotations()` on modules, classes, and functions, respectively.

  See *variable annotation*, *function annotation*, **PEP 484**, **PEP 526**, and **PEP 649**, which describe this functionality. Also see annotations-howto for best practices on working with annotations.

argüman
: Fonksiyon çağrılırken bir *function* 'a (veya *method*) geçirilen bir değer. İki tür argüman vardır:

- *keyword argument*: bir işlev çağrısında bir tanımlayıcının (ör. `ad =`) önüne geçen veya bir sözlükte `**` ile başlayan bir değer olarak geçirilen bir argüman. Örneğin, `3` ve `5`, aşağıdaki `complex()`: çağrılarında anahtar kelimenin argümanleridir:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

- *positional argument*: anahtar kelime argümanı olmayan bir argüman. Konumsal argümanler, bir argüman listesinin başında görünebilir ve/veya `*` ile başlayan bir *iterable* öğesinin öğeleri olarak iletilebilir. Örneğin, `3` ve `5`, aşağıdaki çağrılarda konumsal argümanlerdir:

```
complex(3, 5)
complex(*(3, 5))
```

Argümanler, bir fonksiyon gövdesindeki adlandırılmış yerel değişkenlere atanır. Bu atamayı yöneten kurallar için calls bölümüne bakın. Sözdizimsel olarak, bir argümanı temsil etmek için herhangi bir ifade kullanılabilir; değerlendirilen değer yerel değişkene atanır.

Ayrıca *parameter* sözlüğü girişine, the difference between arguments and parameters hakkındaki SSS sorusuna ve **PEP 362** 'ye bakın.

asenkron bağlam yöneticisi
An object which controls the environment seen in an `async with` statement by defining `__aenter__()` and `__aexit__()` methods. Introduced by **PEP 492**.

asenkron jeneratör
asynchronous generator iterator döndüren bir işlev. Bir `async for` döngüsünde kullanılabilen bir dizi değer üretmek için `yield` ifadeleri içermesi dışında `async def` ile tanımlanmış bir eşyordam işlevine benziyor.

Genellikle bir asenkron üreteç işlevine atıfta bulunur, ancak bazı bağlamlarda bir *asynchronous generator iterator* 'e karşılık gelebilir. Amaçlanan anlamın net olmadığı durumlarda, tam terimlerin kullanılması belirsizliği önler.

Bir asenkron üretici fonksiyonu, `await` ifadelerinin yanı sıra `async for` ve `async with` ifadeleri içerebilir.

asenkron jeneratör yineleyici
An object created by an *asynchronous generator* function.

This is an *asynchronous iterator* which when called using the `__anext__()` method returns an awaitable object which will execute the body of the asynchronous generator function until the next `yield` expression.

Each `yield` temporarily suspends processing, remembering the execution state (including local variables and pending try-statements). When the *asynchronous generator iterator* effectively resumes with another awaitable returned by `__anext__()`, it picks up where it left off. See **PEP 492** and **PEP 525**.

eşzamansız yinelenebilir
An object, that can be used in an `async for` statement. Must return an *asynchronous iterator* from its `__aiter__()` method. Introduced by **PEP 492**.

asenkron yineleyici
An object that implements the `__aiter__()` and `__anext__()` methods. `__anext__()` must return an *awaitable* object. `async for` resolves the awaitables returned by an asynchronous iterator's `__anext__()` method until it raises a `StopAsyncIteration` exception. Introduced by **PEP 492**.

attached thread state
A *thread state* that is active for the current OS thread.

When a *thread state* is attached, the OS thread has access to the full Python C API and can safely invoke the bytecode interpreter.

Unless a function explicitly notes otherwise, attempting to call the C API without an attached thread state will result in a fatal error or undefined behavior. A thread state can be attached and detached explicitly by the user through the C API, or implicitly by the runtime, including during blocking C calls and by the bytecode interpreter in between calls.

On most builds of Python, having an attached thread state implies that the caller holds the *GIL* for the current interpreter, so only one OS thread can have an attached thread state at a given moment. In *free-threaded* builds of Python, threads can concurrently hold an attached thread state, allowing for true parallelism of the bytecode interpreter.

nitelik
Noktalı ifadeler kullanılarak adıyla başvurulan bir nesneyle ilişkili değer. Örneğin, *o* nesnesinin *a* özniteliği varsa, bu nesneye *o.a* olarak başvurulur.

Bir nesneye, eğer nesne izin veriyorsa, örneğin `setattr()` kullanarak, adı identifiers tarafından tanımlandığı gibi tanımlayıcı olmayan bir öznitelik vermek mümkündür. Böyle bir özniteliğe noktalı bir ifade kullanılarak erişilemez ve bunun yerine `getattr()` ile alınması gerekir.

beklenebilir
An object that can be used in an `await` expression. Can be a *coroutine* or an object with an `__await__()` method. See also **PEP 492**.

BDFL
Benevolent Dictator For Life, namı diğer Guido van Rossum, Python'un yaratıcısı.

ikili dosya
A *file object* able to read and write *bytes-like objects*. Examples of binary files are files opened in binary mode (`'rb'`, `'wb'` or `'rb+'`), `sys.stdin.buffer`, `sys.stdout.buffer`, and instances of `io.BytesIO` and `gzip.GzipFile`.

Ayrıca `str` nesnelerini okuyabilen ve yazabilen bir dosya nesnesi için *text file* 'a bakın.

ödünç alınan referans
In Python's C API, a borrowed reference is a reference to an object, where the code using the object does not own the reference. It becomes a dangling pointer if the object is destroyed. For example, a garbage collection can remove the last *strong reference* to the object and so destroy it.

borrowed reference üzerinde *`Py_INCREF()`* çağırmak, nesnenin ödünç alınanın son kullanımından önce yok edilemediği durumlar dışında, onu yerinde bir *strong reference* 'a dönüştürmek için tavsiye edilir. referans. *`Py_NewRef()`* işlevi, yeni bir *strong reference* oluşturmak için kullanılabilir.

bayt benzeri nesne
Buffer Protocol 'i destekleyen ve bir C-*contiguous* arabelleğini dışa aktarabilen bir nesne. Bu, tüm `bytes`, `bytearray` ve `array.array` nesnelerinin yanı sıra birçok yaygın `memoryview` nesnesini içerir. Bayt benzeri nesneler, ikili verilerle çalışan çeşitli işlemler için kullanılabilir; bunlara sıkıştırma, ikili dosyaya kaydetme ve bir soket üzerinden gönderme dahildir.

Bazı işlemler, değişken olması için ikili verilere ihtiyaç duyar. Belgeler genellikle bunlara "okuma-yazma bayt benzeri nesneler" olarak atıfta bulunur. Örnek değiştirilebilir arabellek nesneleri `bytearray` ve bir `bytearray` `memoryview` içerir. Diğer işlemler, ikili verilerin değişmez nesnelerde ("salt okunur bayt benzeri nesneler") depolanmasını gerektirir; bunların örnekleri arasında `bytes` ve bir `bytes` nesnesinin `memoryview` bulunur.

bayt kodu
Python kaynak kodu, bir Python programının CPython yorumlayıcısındaki dahili temsili olan bayt kodunda derlenir. Bayt kodu ayrıca `.pyc` dosyalarında önbelleğe alınır, böylece aynı dosyanın ikinci kez çalıştırılması daha hızlı olur (kaynaktan bayt koduna yeniden derleme önlenebilir). Bu "ara dilin", her bir bayt koduna karşılık gelen makine kodunu yürüten bir *sanal makine* üzerinde çalıştığı söylenir. Bayt kodlarının farklı Python sanal makineleri arasında çalışması veya Python sürümleri arasında kararlı olması beklenmediğini unutmayın.

Bayt kodu talimatlarının bir listesi bytecodes dokümanında bulunabilir.

çağırılabilir
Bir çağrılabilir, muhtemelen bir dizi argümanla (bkz. *argument*) ve aşağıdaki sözdizimiyle çağrılabilen bir nesnedir:

```
callable(argument1, argument2, argumentN)
```

Bir *fonksiyon* ve uzantısı olarak bir *metot* bir çağrılabilirdir. `__call__()` yöntemini uygulayan bir sınıf örneği de bir çağrılabilirdir.

geri çağırmak
Gelecekte bir noktada yürütülecek bir argüman olarak iletilen bir alt program işlevi.

sınıf
Kullanıcı tanımlı nesneler oluşturmak için bir şablon. Sınıf tanımları normalde sınıfın örnekleri üzerinde çalışan yöntem tanımlarını içerir.

sınıf değişkeni
Bir sınıfta tanımlanmış ve yalnızca sınıf düzeyinde (yani sınıfın bir örneğinde değil) değiştirilmesi amaçlanan bir değişken.

closure variable
A *free variable* referenced from a *nested scope* that is defined in an outer scope rather than being resolved at runtime from the globals or builtin namespaces. May be explicitly defined with the `nonlocal` keyword to allow write access, or implicitly defined if the variable is only being read.

For example, in the `inner` function in the following code, both `x` and `print` are *free variables*, but only `x` is a *closure variable*:

```
def outer():
    x = 0
    def inner():
        nonlocal x
        x += 1
        print(x)
    return inner
```

Due to the `codeobject.co_freevars` attribute (which, despite its name, only includes the names of closure variables rather than listing all referenced free variables), the more general *free variable* term is sometimes used even when the intended meaning is to refer specifically to closure variables.

karmaşık sayı
Tüm sayıların bir reel kısım ve bir sanal kısım toplamı olarak ifade edildiği bilinen gerçek sayı sisteminin bir uzantısı. Hayali sayılar, hayali birimin gerçek katlarıdır (`-1` 'in karekökü), genellikle matematikte `i` veya mühendislikte `j` ile yazılır. Python, bu son gösterimle yazılan karmaşık sayılar için yerleşik desteğe sahiptir; hayali kısım bir `j` son ekiyle yazılır, örneğin `3+1j`. `math` modülünün karmaşık eş değerlerine erişmek için `cmath` kullanın. Karmaşık sayıların kullanımı oldukça gelişmiş bir matematiksel özelliktir. Onlara olan ihtiyacın farkında değilseniz, onları güvenle görmezden gelebileceğiniz neredeyse kesindir.

context
This term has different meanings depending on where and how it is used. Some common meanings:

- The temporary state or environment established by a *context manager* via a `with` statement.
- The collection of keyvalue bindings associated with a particular `contextvars.Context` object and accessed via `ContextVar` objects. Also see *context variable*.
- A `contextvars.Context` object. Also see *current context*.

context management protocol
The `__enter__()` and `__exit__()` methods called by the `with` statement. See **PEP 343**.

bağlam yöneticisi
An object which implements the *context management protocol* and controls the environment seen in a `with` statement. See **PEP 343**.

bağlam değişkeni
A variable whose value depends on which context is the *current context*. Values are accessed via `contextvars.ContextVar` objects. Context variables are primarily used to isolate state between concurrent asynchronous tasks.

bitişik
Bir arabellek, *C-bitişik* veya *Fortran bitişik* ise tam olarak bitişik olarak kabul edilir. Sıfır boyutlu arabellekler C ve Fortran bitişiktir. Tek boyutlu dizilerde, öğeler sıfırdan başlayarak artan dizinler sırasına göre bellekte

yan yana yerleştirilmelidir. Çok boyutlu C-bitişik dizilerde, öğeleri bellek adresi sırasına göre ziyaret ederken son dizin en hızlı şekilde değişir. Ancak, Fortran bitişik dizilerinde, ilk dizin en hızlı şekilde değişir.

eşyordam
Eşyordamlar, altyordamların daha genelleştirilmiş bir biçimidir. Alt programlara bir noktada girilir ve başka bir noktada çıkılır. Eşyordamlar birçok farklı noktada girilebilir, çıkılabilir ve devam ettirilebilir. `async def` ifadesi ile uygulanabilirler. Ayrıca bakınız **PEP 492**.

eşyordam işlevi
Bir *coroutine* nesnesi döndüren bir işlev. Bir eşyordam işlevi `async def` ifadesiyle tanımlanabilir ve `await`, `async for` ve `async with` anahtar kelimelerini içerebilir. Bunlar **PEP 492** tarafından tanıtıldı.

CPython
Python programlama dilinin python.org üzerinde dağıtıldığı şekliyle kurallı uygulaması. "CPython" terimi, gerektiğinde bu uygulamayı Jython veya IronPython gibi diğerlerinden ayırmak için kullanılır.

current context
The *context* (`contextvars.Context` object) that is currently used by `ContextVar` objects to access (get or set) the values of *context variables*. Each thread has its own current context. Frameworks for executing asynchronous tasks (see `asyncio`) associate each task with a context which becomes the current context whenever the task starts or resumes execution.

cyclic isolate
A subgroup of one or more objects that reference each other in a reference cycle, but are not referenced by objects outside the group. The goal of the *cyclic garbage collector* is to identify these groups and break the reference cycles so that the memory can be reclaimed.

dekoratör
Genellikle `@wrapper` sözdizimi kullanılarak bir işlev dönüşümü olarak uygulanan, başka bir işlevi döndüren bir işlev. Dekoratörler için yaygın örnekler şunlardır: `classmethod()` ve `staticmethod()`.

Dekoratör sözdizimi yalnızca sözdizimsel şekerdir, aşağıdaki iki işlev tanımı anlamsal olarak eş değerdir:

```
def f(arg):
    ...
f = staticmethod(f)

@staticmethod
def f(arg):
    ...
```

Aynı kavram sınıflar için de mevcuttur, ancak orada daha az kullanılır. Dekoratörler hakkında daha fazla bilgi için function definitions ve class definitions belgelerine bakın.

tanımlayıcı
Any object which defines the methods `__get__()`, `__set__()`, or `__delete__()`. When a class attribute is a descriptor, its special binding behavior is triggered upon attribute lookup. Normally, using *a.b* to get, set or delete an attribute looks up the object named *b* in the class dictionary for *a*, but if *b* is a descriptor, the respective descriptor method gets called. Understanding descriptors is a key to a deep understanding of Python because they are the basis for many features including functions, methods, properties, class methods, static methods, and reference to super classes.

Tanımlayıcıların yöntemleri hakkında daha fazla bilgi için, bkz. descriptors veya Descriptor How To Guide.

sözlük
An associative array, where arbitrary keys are mapped to values. The keys can be any object with `__hash__()` and `__eq__()` methods. Called a hash in Perl.

sözlük anlama
Öğelerin tümünü veya bir kısmını yinelenebilir bir şekilde işlemenin ve sonuçları içeren bir sözlük döndürmenin kompakt bir yolu. `results = {n: n ** 2 for range(10)}`, `n ** 2` değerine eşlenmiş `n` anahtarını içeren bir sözlük oluşturur. Bkz. comprehensions.

sözlük görünümü
: `dict.keys()`, `dict.values()` ve `dict.items()` 'den döndürülen nesnelere sözlük görünümleri denir. Sözlüğün girişleri üzerinde dinamik bir görünüm sağlarlar; bu, sözlük değiştiğinde görünümün bu değişiklikleri yansıttığı anlamına gelir. Sözlük görünümünü tam liste olmaya zorlamak için `list(dictview)` kullanın. Bakınız dict-views.

belge dizisi
: A string literal which appears as the first expression in a class, function or module. While ignored when the suite is executed, it is recognized by the compiler and put into the `__doc__` attribute of the enclosing class, function or module. Since it is available via introspection, it is the canonical place for documentation of the object.

ördek yazma
: Doğru arayüze sahip olup olmadığını belirlemek için bir nesnenin türüne bakmayan bir programlama stili; bunun yerine, yöntem veya nitelik basitçe çağrılır veya kullanılır ("Ördek gibi görünüyorsa ve ördek gibi vaklıyorsa, ördek olmalıdır.") İyi tasarlanmış kod, belirli türlerden ziyade arayüzleri vurgulayarak, polimorfik ikameye izin vererek esnekliğini artırır. Ördek yazma, `type()` veya `isinstance()` kullanan testleri önler. (Ancak, ördek yazmanın *abstract base class* ile tamamlanabileceğini unutmayın.) Bunun yerine, genellikle `hasattr()` testleri veya *EAFP* programlamasını kullanır.

dunder
: An informal short-hand for "double underscore", used when talking about a *special method*. For example, `__init__` is often pronounced "dunder init".

EAFP
: Af dilemek izin almaktan daha kolaydır. Bu yaygın Python kodlama stili, geçerli anahtarların veya niteliklerin varlığını varsayar ve varsayımın yanlış çıkması durumunda istisnaları yakalar. Bu temiz ve hızlı stil, birçok `try` ve `except` ifadesinin varlığı ile karakterize edilir. Teknik, C gibi diğer birçok dilde ortak olan *LBYL* stiliyle çelişir.

evaluate function
: A function that can be called to evaluate a lazily evaluated attribute of an object, such as the value of type aliases created with the `type` statement.

ifade (değer döndürür)
: Bir değere göre değerlendirilebilecek bir sözdizimi parçası. Başka bir deyişle, bir ifade, tümü bir değer döndüren sabit değerler, adlar, öznitelik erişimi, işleçler veya işlev çağrıları gibi ifade öğelerinin bir toplamıdır. Diğer birçok dilin aksine, tüm dil yapıları ifade değildir. Ayrıca `while` gibi kullanılamayan *ifadeler* de vardır. Atamalar da değer döndürmeyen ifadelerdir (statement).

uzatma modülü
: Çekirdekle ve kullanıcı koduyla etkileşim kurmak için Python'un C API'sini kullanan, C veya C++ ile yazılmış bir modül.

f-string
f-strings
: String literals prefixed with `f` or `F` are commonly called "f-strings" which is short for formatted string literals. See also **PEP 498**.

dosya nesnesi
: An object exposing a file-oriented API (with methods such as `read()` or `write()`) to an underlying resource. Depending on the way it was created, a file object can mediate access to a real on-disk file or to another type of storage or communication device (for example standard input/output, in-memory buffers, sockets, pipes, etc.). File objects are also called *file-like objects* or *streams*.

  Aslında üç dosya nesnesi kategorisi vardır: ham *binary files*, arabelleğe alınmış *binary files* ve *text files*. Arayüzleri `io` modülünde tanımlanmıştır. Bir dosya nesnesi yaratmanın kurallı yolu `open()` işlevini kullanmaktır.

dosya benzeri nesne
: *dosya nesnesi* ile eşanlamlıdır.

dosya sistemi kodlaması ve hata işleyicisi
: Python tarafından işletim sistemindeki baytların kodunu çözmek ve Unicode'u işletim sistemine kodlamak için kullanılan kodlama ve hata işleyici.

Dosya sistemi kodlaması, 128'in altındaki tüm baytların kodunu başarıyla çözmeyi garanti etmelidir. Dosya sistemi kodlaması bu garantiyi sağlayamazsa, API işlevleri `UnicodeError` değerini yükseltebilir.

`sys.getfilesystemencoding()` ve `sys.getfilesystemencodeerrors()` işlevleri, dosya sistemi kodlamasını ve hata işleyicisini almak için kullanılabilir.

filesystem encoding and error handler Python başlangıcında *`PyConfig_Read()`* işleviyle yapılandırılır: bkz. *`filesystem_encoding`* ve *`filesystem_errors`* üyeleri *`PyConfig`*.

Ayrıca bkz. *locale encoding*.

bulucu
İçe aktarılmakta olan bir modül için *loader* 'ı bulmaya çalışan bir nesne.

There are two types of finder: *meta path finders* for use with `sys.meta_path`, and *path entry finders* for use with `sys.path_hooks`.

See finders-and-loaders and `importlib` for much more detail.

kat bölümü
En yakın tam sayıya yuvarlayan matematiksel bölme. Kat bölme operatörü `//` şeklindedir. Örneğin, `11 // 4` ifadesi, gerçek yüzer bölme tarafından döndürülen `2.75` değerinin aksine `2` olarak değerlendirilir. `(-11) // 4` 'ün `-3` olduğuna dikkat edin, çünkü bu `-2.75` yuvarlatılmış *aşağı*. Bakınız **PEP 238**.

free threading
A threading model where multiple threads can run Python bytecode simultaneously within the same interpreter. This is in contrast to the *global interpreter lock* which allows only one thread to execute Python bytecode at a time. See **PEP 703**.

free variable
Formally, as defined in the language execution model, a free variable is any variable used in a namespace which is not a local variable in that namespace. See *closure variable* for an example. Pragmatically, due to the name of the `codeobject.co_freevars` attribute, the term is also sometimes used as a synonym for *closure variable*.

fonksiyon
Bir arayana bir değer döndüren bir dizi ifade. Ayrıca, gövdenin yürütülmesinde kullanılabilen sıfır veya daha fazla *argüman* iletilebilir. Ayrıca *parameter*, *method* ve function bölümüne bakın.

fonksiyon açıklaması
Bir işlev parametresinin veya dönüş değerinin *ek açıklaması*.

İşlev ek açıklamaları genellikle *type hints* için kullanılır: örneğin, bu fonksiyonun iki `int` argüman alması ve ayrıca bir `int` dönüş değerine sahip olması beklenir

```
def sum_two_numbers(a: int, b: int) -> int:
   return a + b
```

İşlev açıklama sözdizimi function bölümünde açıklanmaktadır.

Bu işlevi açıklayan *variable annotation* ve **PEP 484** 'e bakın. Ek açıklamalarla çalışmaya ilişkin en iyi uygulamalar için ayrıca annotations-howto konusuna bakın.

__future__
Bir future ifadesi, `from __future__ import <feature>`, derleyiciyi, Python'un gelecekteki bir sürümünde standart hale gelecek olan sözdizimini veya semantiği kullanarak mevcut modülü derlemeye yönlendirir. `__future__` modülü, *feature*'ın olası değerlerini belgeler. Bu modülü içe aktararak ve değişkenlerini değerlendirerek, dile ilk kez yeni bir özelliğin ne zaman eklendiğini ve ne zaman varsayılan olacağını (ya da yaptığını) görebilirsiniz:

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

çöp toplama
Artık kullanılmadığında belleği boşaltma işlemi. Python, referans sayımı ve referans döngülerini algılayıp kı-

rabilen bir döngüsel çöp toplayıcı aracılığıyla çöp toplama gerçekleştirir. Çöp toplayıcı `gc` modülü kullanılarak kontrol edilebilir.

jeneratör
Bir *generator iterator* döndüren bir işlev. Bir for döngüsünde kullanılabilen bir dizi değer üretmek için `yield` ifadeleri içermesi veya `next()` işleviyle birer birer alınabilmesi dışında normal bir işleve benziyor.

Genellikle bir üretici işlevine atıfta bulunur, ancak bazı bağlamlarda bir *jeneratör yineleyicisine* atıfta bulunabilir. Amaçlanan anlamın net olmadığı durumlarda, tam terimlerin kullanılması belirsizliği önler.

jeneratör yineleyici
Bir *generator* işlevi tarafından oluşturulan bir nesne.

Each `yield` temporarily suspends processing, remembering the execution state (including local variables and pending try-statements). When the *generator iterator* resumes, it picks up where it left off (in contrast to functions which start fresh on every invocation).

jeneratör ifadesi
An *expression* that returns an *iterator*. It looks like a normal expression followed by a `for` clause defining a loop variable, range, and an optional `if` clause. The combined expression generates values for an enclosing function:

```
>>> sum(i*i for i in range(10))         # sum of squares 0, 1, 4, ... 81
285
```

genel işlev
Farklı türler için aynı işlemi uygulayan birden çok işlevden oluşan bir işlev. Bir çağrı sırasında hangi uygulamanın kullanılması gerektiği, gönderme algoritması tarafından belirlenir.

Ayrıca *single dispatch* sözlük girdisine, `functools.singledispatch()` dekoratörüne ve **PEP 443** 'e bakın.

genel tip
Parametrelendirilebilen bir *type*; tipik olarak bir konteyner sınıfı, örneğin `list` veya `dict`. *type hint* ve *annotation* için kullanılır.

Daha fazla ayrıntı için generic allias types, **PEP 483**, **PEP 484**, **PEP 585** ve `typing` modülüne bakın.

GIL
Bakınız *global interpreter lock*.

genel tercüman kilidi
CPython yorumlayıcısı tarafından aynı anda yalnızca bir iş parçacığının Python *bytecode* 'u yürütmesini sağlamak için kullanılan mekanizma. Bu, nesne modelini (`dict` gibi kritik yerleşik türler dahil) eşzamanlı erişime karşı örtük olarak güvenli hale getirerek CPython uygulamasını basitleştirir. Tüm yorumlayıcıyı kilitlemek, çok işlemcili makinelerin sağladığı paralelliğin çoğu pahasına, yorumlayıcının çok iş parçacıklı olmasını kolaylaştırır.

Bununla birlikte, standart veya üçüncü taraf bazı genişletme modülleri, sıkıştırma veya karma gibi hesaplama açısından yoğun görevler yaparken GIL'yi serbest bırakacak şekilde tasarlanmıştır. Ayrıca, GIL, G/Ç yaparken her zaman serbest bırakılır.

As of Python 3.13, the GIL can be disabled using the `--disable-gil` build configuration. After building Python with this option, code must be run with `-X gil =0` or after setting the `PYTHON_GIL =0` environment variable. This feature enables improved performance for multi-threaded applications and makes it easier to use multi-core CPUs efficiently. For more details, see **PEP 703**.

In prior versions of Python's C API, a function might declare that it requires the GIL to be held in order to use it. This refers to having an *attached thread state*.

karma tabanlı pyc
Geçerliliğini belirlemek için ilgili kaynak dosyanın son değiştirilme zamanı yerine karma değerini kullanan bir bayt kodu önbellek dosyası. Bakınız pyc-invalidation.

yıkanabilir
An object is *hashable* if it has a hash value which never changes during its lifetime (it needs a `__hash__()`

method), and can be compared to other objects (it needs an `__eq__()` method). Hashable objects which compare equal must have the same hash value.

Hashability, bir nesneyi bir sözlük anahtarı ve bir set üyesi olarak kullanılabilir hale getirir, çünkü bu veri yapıları hash değerini dahili olarak kullanır.

Python'un değişmez yerleşik nesnelerinin çoğu, yıkanabilir; değiştirilebilir kaplar (listeler veya sözlükler gibi) değildir; değişmez kaplar (tüpler ve donmuş kümeler gibi) yalnızca öğelerinin yıkanabilir olması durumunda yıkanabilirdir. Kullanıcı tanımlı sınıfların örnekleri olan nesneler varsayılan olarak hash edilebilirdir. Hepsi eşit olmayanı karşılaştırır (kendileriyle hariç) ve hash değerleri `id()` 'lerinden türetilir.

BOŞTA
Python için Entegre Geliştirme Ortamı. idle, Python'un standart dağıtımıyla birlikte gelen temel bir düzenleyici ve yorumlayıcı ortamıdır.

immortal
Immortal objects are a CPython implementation detail introduced in **PEP 683**.

If an object is immortal, its *reference count* is never modified, and therefore it is never deallocated while the interpreter is running. For example, `True` and `None` are immortal in CPython.

Immortal objects can be identified via `sys._is_immortal()`, or via *`PyUnstable_IsImmortal()`* in the C API.

değişmez
Sabit değeri olan bir nesne. Değişmez nesneler arasında sayılar, dizeler ve demetler bulunur. Böyle bir nesne değiştirilemez. Farklı bir değerin saklanması gerekiyorsa yeni bir nesne oluşturulmalıdır. Örneğin bir sözlükte anahtar olarak, sabit bir karma değerinin gerekli olduğu yerlerde önemli bir rol oynarlar.

içe aktarım yolu
İçe aktarılacak modüller için *path based finder* tarafından aranan konumların (veya *path entries*) listesi. İçe aktarma sırasında, bu konum listesi genellikle `sys.path` adresinden gelir, ancak alt paketler için üst paketin `__path__` özelliğinden de gelebilir.

içe aktarma
Bir modüldeki Python kodunun başka bir modüldeki Python koduna sunulması süreci.

içe aktarıcı
Bir modülü hem bulan hem de yükleyen bir nesne; hem bir *finder* hem de *loader* nesnesi.

etkileşimli
Python has an interactive interpreter which means you can enter statements and expressions at the interpreter prompt, immediately execute them and see their results. Just launch `python` with no arguments (possibly by selecting it from your computer's main menu). It is a very powerful way to test out new ideas or inspect modules and packages (remember `help(x)`). For more on interactive mode, see tut-interac.

yorumlanmış
Python, derlenmiş bir dilin aksine yorumlanmış bir dildir, ancak bayt kodu derleyicisinin varlığı nedeniyle ayrım bulanık olabilir. Bu, kaynak dosyaların daha sonra çalıştırılacak bir yürütülebilir dosya oluşturmadan doğrudan çalıştırılabileceği anlamına gelir. Yorumlanan diller genellikle derlenmiş dillerden daha kısa bir geliştirme/hata ayıklama döngüsüne sahiptir, ancak programları genellikle daha yavaş çalışır. Ayrıca bkz. *interactive*.

tercüman kapatma
Kapatılması istendiğinde, Python yorumlayıcısı, modüller ve çeşitli kritik iç yapılar gibi tahsis edilen tüm kaynakları kademeli olarak serbest bıraktığı özel bir aşamaya girer. Ayrıca *garbage collector* için birkaç çağrı yapar. Bu, kullanıcı tanımlı yıkıcılarda veya zayıf referans geri aramalarında kodun yürütülmesini tetikleyebilir. Kapatma aşamasında yürütülen kod, dayandığı kaynaklar artık çalışmayabileceğinden çeşitli istisnalarla karşılaşabilir (yaygın örnekler kütüphane modülleri veya uyarı makineleridir).

Yorumlayıcının kapatılmasının ana nedeni, `__main__` modülünün veya çalıştırılan betiğin yürütmeyi bitirmiş olmasıdır.

yinelenebilir
An object capable of returning its members one at a time. Examples of iterables include all sequence types (such

as `list`, `str`, and `tuple`) and some non-sequence types like `dict`, *file objects*, and objects of any classes you define with an `__iter__()` method or with a `__getitem__()` method that implements *sequence* semantics.

Iterables can be used in a `for` loop and in many other places where a sequence is needed (`zip()`, `map()`, …). When an iterable object is passed as an argument to the built-in function `iter()`, it returns an iterator for the object. This iterator is good for one pass over the set of values. When using iterables, it is usually not necessary to call `iter()` or deal with iterator objects yourself. The `for` statement does that automatically for you, creating a temporary unnamed variable to hold the iterator for the duration of the loop. See also *iterator*, *sequence*, and *generator*.

yineleyici
An object representing a stream of data. Repeated calls to the iterator's `__next__()` method (or passing it to the built-in function `next()`) return successive items in the stream. When no more data are available a `StopIteration` exception is raised instead. At this point, the iterator object is exhausted and any further calls to its `__next__()` method just raise `StopIteration` again. Iterators are required to have an `__iter__()` method that returns the iterator object itself so every iterator is also iterable and may be used in most places where other iterables are accepted. One notable exception is code which attempts multiple iteration passes. A container object (such as a `list`) produces a fresh new iterator each time you pass it to the `iter()` function or use it in a `for` loop. Attempting this with an iterator will just return the same exhausted iterator object used in the previous iteration pass, making it appear like an empty container.

Daha fazla bilgi typeiter içinde bulunabilir.

CPython uygulama ayrıntısı: CPython does not consistently apply the requirement that an iterator define `__iter__()`. And also please note that the free-threading CPython does not guarantee the thread-safety of iterator operations.

anahtar işlev
Anahtar işlevi veya harmanlama işlevi, sıralama veya sıralama için kullanılan bir değeri döndüren bir çağrılabilir. Örneğin, `locale.strxfrm()`, yerel ayara özgü sıralama kurallarının farkında olan bir sıralama anahtarı üretmek için kullanılır.

Python'daki bir dizi araç, öğelerin nasıl sıralandığını veya gruplandırıldığını kontrol etmek için temel işlevleri kabul eder. Bunlar `min()`, `max()`, `sorted()`, `list.sort()`, `heapq.merge()`, `heapq.nsmallest()`, `heapq.nlargest()` ve `itertools.groupby()`.

Bir tuş fonksiyonu oluşturmanın birkaç yolu vardır. Örneğin. `str.lower()` yöntemi, büyük/küçük harfe duyarlı olmayan sıralamalar için bir anahtar fonksiyonu işlevi görebilir. Alternatif olarak, `lambda r: (r[0], r[2])` gibi bir `lambda` ifadesinden bir anahtar işlevi oluşturulabilir. Ayrıca, `attrgetter()`, `itemgetter()` ve `methodcaller()` fonksiyonları üç anahtar fonksiyon kurucularıdır. Anahtar işlevlerin nasıl oluşturulacağı ve kullanılacağına ilişkin örnekler için Sorting HOW TO bölümüne bakın.

anahtar kelime argümanı
Bakınız *argument*.

lambda
İşlev çağrıldığında değerlendirilen tek bir *expression* 'dan oluşan anonim bir satır içi işlev. Bir lambda işlevi oluşturmak için sözdizimi `lambda [parametreler]: ifade` şeklindedir

LBYL
Zıplamadan önce Bak. Bu kodlama stili, arama veya arama yapmadan önce ön koşulları açıkça test eder. Bu stil, *EAFP* yaklaşımıyla çelişir ve birçok `if` ifadesinin varlığı ile karakterize edilir.

Çok iş parçacıklı bir ortamda, LBYL yaklaşımı "bakan" ve "sıçrayan" arasında bir yarış koşulu getirme riskini taşıyabilir. Örneğin, `if key in mapping: return mapping[key]` kodu, testten sonra, ancak aramadan önce başka bir iş parçacığı *eşlemeden key* kaldırırsa başarısız olabilir. Bu sorun, kilitlerle veya EAFP yaklaşımı kullanılarak çözülebilir.

lexical analyzer
Formal name for the *tokenizer*; see *token*.

liste
A built-in Python *sequence*. Despite its name it is more akin to an array in other languages than to a linked list since access to elements is $O(1)$.

liste anlama
Bir dizideki öğelerin tümünü veya bir kısmını işlemenin ve sonuçları içeren bir liste döndürmenin kompakt bir yolu. `sonuç = ['{:#04x}'.format(x) for range(256) if x % 2 == 0]`, dizinde çift onaltılık sayılar (0x..) içeren bir diziler listesi oluşturur. 0 ile 255 arasındadır. `if` yan tümcesi isteğe bağlıdır. Atlanırsa, "aralık(256)" içindeki tüm öğeler işlenir.

yükleyici
An object that loads a module. It must define the `exec_module()` and `create_module()` methods to implement the `Loader` interface. A loader is typically returned by a *finder*. See also:

- finders-and-loaders
- `importlib.abc.Loader`
- **PEP 302**

yerel kodlama
Unix'te, LC_CTYPE yerel ayarının kodlamasıdır. `locale.setlocale(locale.LC_CTYPE, new_locale)` ile ayarlanabilir.

Windows'ta bu, ANSI kod sayfasıdır (ör. `"cp1252"`).

Android ve VxWorks'te Python, yerel kodlama olarak `"utf-8"` kullanır.

`locale.getencoding()` can be used to get the locale encoding.

Ayrıca *filesystem encoding and error handler* 'ne bakın.

sihirli yöntem
special method için gayri resmi bir eşanlamlı.

haritalama
Keyfi anahtar aramalarını destekleyen ve `Mapping` veya `MutableMapping` collections-abstract-base-classes içinde belirtilen yöntemleri uygulayan bir kapsayıcı nesnesi. Örnekler arasında `dict`, `collections.defaultdict`, `collections.OrderedDict` ve `collections.Counter` sayılabilir.

meta yol bulucu
Bir *finder*, `sys.meta_path` aramasıyla döndürülür. Meta yol bulucular, *yol girişi bulucuları* ile ilişkilidir, ancak onlardan farklıdır.

Meta yol bulucuların uyguladığı yöntemler için `importlib.abc.MetaPathFinder` bölümüne bakın.

metasınıf
Bir sınıfın sınıfı. Sınıf tanımları, bir sınıf adı, bir sınıf sözlüğü ve temel sınıfların bir listesini oluşturur. Metasınıf, bu üç argümanı almaktan ve sınıfı oluşturmaktan sorumludur. Çoğu nesne yönelimli programlama dili, varsayılan bir uygulama sağlar. Python'u özel yapan şey, özel metasınıflar oluşturmanın mümkün olmasıdır. Çoğu kullanıcı bu araca hiçbir zaman ihtiyaç duymaz, ancak ihtiyaç duyulduğunda, metasınıflar güçlü ve zarif çözümler sağlayabilir. Nitelik erişimini günlüğe kaydetmek, iş parçacığı güvenliği eklemek, nesne oluşturmayı izlemek, tekilleri uygulamak ve diğer birçok görev için kullanılmışlardır.

Daha fazla bilgi metaclasses içinde bulunabilir.

metot
Bir sınıf gövdesi içinde tanımlanan bir işlev. Bu sınıfın bir örneğinin özniteliği olarak çağrılırsa, yöntem örnek nesnesini ilk *argument* (genellikle `self` olarak adlandırılır) olarak alır. Bkz. *function* ve *nested scope*.

metot kalite sıralaması
Method Resolution Order is the order in which base classes are searched for a member during lookup. See python_2.3_mro for details of the algorithm used by the Python interpreter since the 2.3 release.

modül
Python kodunun kuruluş birimi olarak hizmet eden bir nesne. Modüller, rastgele Python nesneleri içeren bir ad alanına sahiptir. Modüller, *importing* işlemiyle Python'a yüklenir.

Ayrıca bakınız *package*.

modül özelliği
Bir modülü yüklemek için kullanılan içe aktarmayla ilgili bilgileri içeren bir ad alanı. Bir `importlib.machinery.ModuleSpec` örneği.

See also module-specs.

MRO
Bakınız *metot çözüm sırası*.

değiştirilebilir
Değiştirilebilir (mutable) nesneler değerlerini değiştirebilir ancak `idlerini` koruyabilirler. Ayrıca bkz. *immutable*.

adlandırılmış demet
"named tuple" terimi, demetten miras alan ve dizinlenebilir öğelerine de adlandırılmış nitelikler kullanılarak erişilebilen herhangi bir tür veya sınıf için geçerlidir. Tür veya sınıfın başka özellikleri de olabilir.

Çeşitli yerleşik türler, `time.localtime()` ve `os.stat()` tarafından döndürülen değerler de dahil olmak üzere, tanımlama grupları olarak adlandırılır. Başka bir örnek `sys.float_info`:

```
>>> sys.float_info[1]                   # indexed access
1024
>>> sys.float_info.max_exp              # named field access
1024
>>> isinstance(sys.float_info, tuple)   # kind of tuple
True
```

Some named tuples are built-in types (such as the above examples). Alternatively, a named tuple can be created from a regular class definition that inherits from `tuple` and that defines named fields. Such a class can be written by hand, or it can be created by inheriting `typing.NamedTuple`, or with the factory function `collections.namedtuple()`. The latter techniques also add some extra methods that may not be found in hand-written or built-in named tuples.

ad alanı
Değişkenin saklandığı yer. Ad alanları sözlükler olarak uygulanır. Nesnelerde (yöntemlerde) yerel, genel ve yerleşik ad alanlarının yanı sıra iç içe ad alanları vardır. Ad alanları, adlandırma çakışmalarını önleyerek modülerliği destekler. Örneğin, `builtins.open` ve `os.open()` işlevleri ad alanlarıyla ayırt edilir. Ad alanları, hangi modülün bir işlevi uyguladığını açıkça belirterek okunabilirliğe ve sürdürülebilirliğe de yardımcı olur. Örneğin, `random.seed()` veya `itertools.islice()` yazmak, bu işlevlerin sırasıyla `random` ve `itertools` modülleri tarafından uygulandığını açıkça gösterir.

ad alanı paketi
A *package* which serves only as a container for subpackages. Namespace packages may have no physical representation, and specifically are not like a *regular package* because they have no `__init__.py` file.

Namespace packages allow several individually installable packages to have a common parent package. Otherwise, it is recommended to use a *regular package*.

For more information, see **PEP 420** and reference-namespace-package.

Ayrıca bkz. *module*.

iç içe kapsam
Kapsamlı bir tanımdaki bir değişkene atıfta bulunma yeteneği. Örneğin, başka bir fonksiyonun içinde tanımlanan bir fonksiyon, dış fonksiyondaki değişkenlere atıfta bulunabilir. İç içe kapsamların varsayılan olarak yalnızca başvuru için çalıştığını ve atama için çalışmadığını unutmayın. Yerel değişkenler en içteki kapsamda hem okur hem de yazar. Benzer şekilde, global değişkenler global ad alanını okur ve yazar. `nonlocal`, dış kapsamlara yazmaya izin verir.

yeni stil sınıf
Old name for the flavor of classes now used for all class objects. In earlier Python versions, only new-style classes could use Python's newer, versatile features like `__slots__`, descriptors, properties, `__getattribute__()`, class methods, and static methods.

obje
Durum (öznitelikler veya değer) ve tanımlanmış davranış (yöntemler) içeren herhangi bir veri. Ayrıca herhangi bir *yeni tarz sınıfın* nihai temel sınıfı.

optimized scope
A scope where target local variable names are reliably known to the compiler when the code is compiled, allowing optimization of read and write access to these names. The local namespaces for functions, generators, coroutines, comprehensions, and generator expressions are optimized in this fashion. Note: most interpreter optimizations are applied to all scopes, only those relying on a known set of local and nonlocal variable names are restricted to optimized scopes.

paket
Alt modüller veya yinelemeli olarak alt paketler içerebilen bir Python *module*. Teknik olarak bir paket, `__path__` özniteliğine sahip bir Python modülüdür.

Ayrıca bkz. *regular package* ve *namespace package*.

parametre
Bir *function* (veya yöntem) tanımında, işlevin kabul edebileceği bir *argument* (veya bazı durumlarda, argümanlar) belirten adlandırılmış bir varlık. Beş çeşit parametre vardır:

- *positional-or-keyword*: *pozisyonel* veya bir *keyword argümanı* olarak iletilebilen bir argüman belirtir. Bu, varsayılan parametre türüdür, örneğin aşağıdakilerde *foo* ve *bar*:

```
def func(foo, bar=None): ...
```

- *positional-only*: yalnızca konuma göre sağlanabilen bir argüman belirtir. Yalnızca konumsal parametreler, onlardan sonra fonksiyon tanımının parametre listesine bir `/` karakteri eklenerek tanımlanabilir, örneğin aşağıdakilerde *posonly1* ve *posonly2*:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

- *keyword-only*: sadece anahtar kelime ile sağlanabilen bir argüman belirtir. Yalnızca anahtar kelime (keyword-only) parametreleri, onlardan önceki fonksiyon tanımının parametre listesine tek bir değişken konumlu parametre veya çıplak `*` dahil edilerek tanımlanabilir, örneğin aşağıdakilerde *kw_only1* ve *kw_only2*:

```
def func(arg, *, kw_only1, kw_only2): ...
```

- *var-positional*: keyfi bir pozisyonel argüman dizisinin sağlanabileceğini belirtir (diğer parametreler tarafından zaten kabul edilmiş herhangi bir konumsal argümana ek olarak). Böyle bir parametre, parametre adının başına `*` eklenerek tanımlanabilir, örneğin aşağıdakilerde *args*:

```
def func(*args, **kwargs): ...
```

- *var-keyword*: keyfi olarak birçok anahtar kelime argümanının sağlanabileceğini belirtir (diğer parametreler tarafından zaten kabul edilen herhangi bir anahtar kelime argümanına ek olarak). Böyle bir parametre, parametre adının başına `**`, örneğin yukarıdaki örnekte *kwargs* eklenerek tanımlanabilir.

Parametreler, hem isteğe bağlı hem de gerekli argümanleri ve ayrıca bazı isteğe bağlı bağımsız değişkenler için varsayılan değerleri belirtebilir.

Ayrıca bkz. *argüman*, argümanlar ve parametreler arasındaki fark, `inspect.Parameter`, function ve **PEP 362**.

yol girişi
path based finder içe aktarma modüllerini bulmak için başvurduğu *import path* üzerindeki tek bir konum.

yol girişi bulucu
Bir *finder* `sys.path_hooks` (yani bir *yol giriş kancası*) üzerinde bir çağrılabilir tarafından döndürülür ve *path entry* verilen modüllerin nasıl bulunacağını bilir.

Yol girişi bulucularının uyguladığı yöntemler için `importlib.abc.PathEntryFinder` bölümüne bakın.

yol giriş kancası
A callable on the `sys.path_hooks` list which returns a *path entry finder* if it knows how to find modules on a specific *path entry*.

yol tabanlı bulucu
Modüller için bir *import path* arayan varsayılan *meta yol bulucudan* biri.

yol benzeri nesne
Bir dosya sistemi yolunu temsil eden bir nesne. Yol benzeri bir nesne, bir yolu temsil eden bir `str` veya `bytes` nesnesi veya `os.PathLike` protokolünü uygulayan bir nesnedir. `os.PathLike` protokolünü destekleyen bir nesne, `os.fspath()` işlevi çağrılarak bir `str` veya `bytes` dosya sistemi yoluna dönüştürülebilir; `os.fsdecode()` ve `os.fsencode()`, bunun yerine sırasıyla `str` veya `bytes` sonucunu garanti etmek için kullanılabilir. **PEP 519** tarafından tanıtıldı.

PEP
Python Geliştirme Önerisi. PEP, Python topluluğuna bilgi sağlayan veya Python veya süreçleri ya da ortamı için yeni bir özelliği açıklayan bir tasarım belgesidir. PEP'ler, önerilen özellikler için özlü bir teknik şartname ve bir gerekçe sağlamalıdır.

PEP'lerin, önemli yeni özellikler önermek, bir sorun hakkında topluluk girdisi toplamak ve Python'a giren tasarım kararlarını belgelemek için birincil mekanizmalar olması amaçlanmıştır. PEP yazarı, topluluk içinde fikir birliği oluşturmaktan ve muhalif görüşleri belgelemekten sorumludur.

Bakınız **PEP 1**.

kısım
PEP 420 içinde tanımlandığı gibi, bir ad alanı paketine katkıda bulunan tek bir dizindeki (muhtemelen bir zip dosyasında depolanan) bir dizi dosya.

konumsal argüman
Bakınız *argument*.

geçici API
Geçici bir API, standart kitaplığın geriye dönük uyumluluk garantilerinden kasıtlı olarak hariç tutulan bir API'dir. Bu tür arayüzlerde büyük değişiklikler beklenmese de, geçici olarak işaretlendikleri sürece, çekirdek geliştiriciler tarafından gerekli görüldüğü takdirde geriye dönük uyumsuz değişiklikler (arayüzün kaldırılmasına kadar ve buna kadar) meydana gelebilir. Bu tür değişiklikler karşılıksız yapılmayacaktır - bunlar yalnızca API'nin eklenmesinden önce gözden kaçan ciddi temel kusurlar ortaya çıkarsa gerçekleşecektir.

Geçici API'ler için bile, geriye dönük uyumsuz değişiklikler "son çare çözümü" olarak görülür - tanımlanan herhangi bir soruna geriye dönük uyumlu bir çözüm bulmak için her türlü girişimde bulunulacaktır.

Bu süreç, standart kitaplığın, uzun süreler boyunca sorunlu tasarım hatalarına kilitlenmeden zaman içinde gelişmeye devam etmesini sağlar. Daha fazla ayrıntı için bkz. **PEP 411**.

geçici paket
Bakınız *provisional API*.

Python 3000
Python 3.x sürüm satırının takma adı (uzun zaman önce sürüm 3'ün piyasaya sürülmesi uzak bir gelecekte olduğu zaman ortaya çıktı.) Bu aynı zamanda "Py3k" olarak da kısaltılır.

Pythonic
Diğer dillerde ortak kavramları kullanarak kod uygulamak yerine Python dilinin en yaygın deyimlerini yakından takip eden bir fikir veya kod parçası. Örneğin, Python'da yaygın bir deyim, bir `for` ifadesi kullanarak yinelenebilir bir öğenin tüm öğeleri üzerinde döngü oluşturmaktır. Diğer birçok dilde bu tür bir yapı yoktur, bu nedenle Python'a aşina olmayan kişiler bazen bunun yerine sayısal bir sayaç kullanır:

```
for i in range(len(food)):
    print(food[i])
```

Temizleyicinin aksine, Pythonic yöntemi:

```
for piece in food:
    print(piece)
```

nitelikli isim
: **PEP 3155** içinde tanımlandığı gibi, bir modülün genel kapsamından o modülde tanımlanan bir sınıfa, işleve veya yönteme giden "yolu" gösteren noktalı ad. Üst düzey işlevler ve sınıflar için nitelikli ad, nesnenin adıyla aynıdır:

```
>>> class C:
...     class D:
...         def meth(self):
...             pass
...
>>> C.__qualname__
'C'
>>> C.D.__qualname__
'C.D'
>>> C.D.meth.__qualname__
'C.D.meth'
```

Modüllere atıfta bulunmak için kullanıldığında, *tam nitelenmiş ad*, herhangi bir üst paket de dahil olmak üzere, modüle giden tüm noktalı yol anlamına gelir, örn. `email.mime.text`:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

referans sayısı
: The number of references to an object. When the reference count of an object drops to zero, it is deallocated. Some objects are *immortal* and have reference counts that are never modified, and therefore the objects are never deallocated. Reference counting is generally not visible to Python code, but it is a key element of the *CPython* implementation. Programmers can call the `sys.getrefcount()` function to return the reference count for a particular object.

In *CPython*, reference counts are not considered to be stable or well-defined values; the number of references to an object, and how that number is affected by Python code, may be different between versions.

sürekli paketleme
: `__init__.py` dosyası içeren bir dizin gibi geleneksel bir *package*.

Ayrıca bkz. *ad alanı paketi*.

REPL
: An acronym for the "read–eval–print loop", another name for the *interactive* interpreter shell.

__slots__
: Örnek öznitelikleri için önceden yer bildirerek ve örnek sözlüklerini ortadan kaldırarak bellekten tasarruf sağlayan bir sınıf içindeki bildirim. Popüler olmasına rağmen, tekniğin doğru olması biraz zor ve en iyi, bellek açısından kritik bir uygulamada çok sayıda örneğin bulunduğu nadir durumlar için ayrılmıştır.

dizi
: An *iterable* which supports efficient element access using integer indices via the `__getitem__()` special method and defines a `__len__()` method that returns the length of the sequence. Some built-in sequence types are `list`, `str`, `tuple`, and `bytes`. Note that `dict` also supports `__getitem__()` and `__len__()`, but is considered a mapping rather than a sequence because the lookups use arbitrary *hashable* keys rather than integers.

The `collections.abc.Sequence` abstract base class defines a much richer interface that goes beyond just `__getitem__()` and `__len__()`, adding `count()`, `index()`, `__contains__()`, and `__reversed__()`. Types that implement this expanded interface can be registered explicitly using `register()`. For more documentation on sequence methods generally, see Common Sequence Operations.

anlamak
: Öğelerin tümünü veya bir kısmını yinelenebilir bir şekilde işlemenin ve sonuçlarla birlikte bir küme döndürmenin kompakt bir yolu. `results = {c for c in 'abracadabra' if c not in 'abc'}`, `{'r', 'd'}` dizelerini oluşturur. Bakınız comprehensions.

tek sevk
Uygulamanın tek bir argüman türüne göre seçildiği bir *generic function* gönderimi biçimi.

parçalamak
Genellikle bir *sequence* 'nin bir bölümünü içeren bir nesne. Bir dilim, örneğin `variable_name[1:3:5]` 'de olduğu gibi, birkaç tane verildiğinde, sayılar arasında iki nokta üst üste koyarak, `[]` alt simge gösterimi kullanılarak oluşturulur. Köşeli ayraç (alt simge) gösterimi, dahili olarak `slice` nesnelerini kullanır.

soft deprecated
A soft deprecated API should not be used in new code, but it is safe for already existing code to use it. The API remains documented and tested, but will not be enhanced further.

Soft deprecation, unlike normal deprecation, does not plan on removing the API and will not emit warnings.

See PEP 387: Soft Deprecation.

özel metod
Toplama gibi bir tür üzerinde belirli bir işlemi yürütmek için Python tarafından örtük olarak çağrılan bir yöntem. Bu tür yöntemlerin çift alt çizgi ile başlayan ve biten adları vardır. Özel yöntemler specialnames içinde belgelenmiştir.

standard library
The collection of *packages*, *modules* and *extension modules* distributed as a part of the official Python interpreter package. The exact membership of the collection may vary based on platform, available system libraries, or other criteria. Documentation can be found at library-index.

See also `sys.stdlib_module_names` for a list of all possible standard library module names.

ifade (değer döndürmez)
Bir ifade, bir paketin parçasıdır (kod "bloğu"). Bir ifade, bir *expression* veya `if`, `while` veya `for` gibi bir anahtar kelimeye sahip birkaç yapıdan biridir.

static type checker
An external tool that reads Python code and analyzes it, looking for issues such as incorrect types. See also *type hints* and the `typing` module.

stdlib
An abbreviation of *standard library*.

güçlü referans
In Python's C API, a strong reference is a reference to an object which is owned by the code holding the reference. The strong reference is taken by calling *`Py_INCREF()`* when the reference is created and released with *`Py_DECREF()`* when the reference is deleted.

`Py_NewRef()` fonksiyonu, bir nesneye güçlü bir başvuru oluşturmak için kullanılabilir. Genellikle *`Py_DECREF()`* fonksiyonu, bir referansın sızmasını önlemek için güçlü referans kapsamından çıkmadan önce güçlü referansta çağrılmalıdır.

Ayrıca bkz. *ödünç alınan referans*.

t-string
t-strings
String literals prefixed with `t` or `T` are commonly called "t-strings" which is short for template string literals.

yazı çözümleme
Python'da bir dize, bir Unicode kod noktaları dizisidir (`U+0000–U+10FFFF` aralığında). Bir dizeyi depolamak veya aktarmak için, bir bayt dizisi olarak seri hale getirilmesi gerekir.

Bir dizeyi bir bayt dizisi halinde seri hale getirmek "kodlama (encoding)" olarak bilinir ve dizeyi bayt dizisinden yeniden oluşturmak "kod çözme (decoding)" olarak bilinir.

Toplu olarak "metin kodlamaları" olarak adlandırılan çeşitli farklı metin serileştirme kodekleri vardır.

yazı dosyası
A *file object* `str` nesnelerini okuyabilir ve yazabilir. Çoğu zaman, bir metin dosyası aslında bir bayt yönelimli veri akışına erişir ve otomatik olarak *text encoding* işler. Metin dosyalarına örnek olarak metin modunda açılan dosyalar (`'r'` veya `'w'`), `sys.stdin`, `sys.stdout` ve `io.StringIO` örnekleri verilebilir.

Ayrıca *ikili dosyaları* okuyabilen ve yazabilen bir dosya nesnesi için *bayt benzeri nesnelere* bakın.

thread state
The information used by the *CPython* runtime to run in an OS thread. For example, this includes the current exception, if any, and the state of the bytecode interpreter.

Each thread state is bound to a single OS thread, but threads may have many thread states available. At most, one of them may be *attached* at once.

An *attached thread state* is required to call most of Python's C API, unless a function explicitly documents otherwise. The bytecode interpreter only runs under an attached thread state.

Each thread state belongs to a single interpreter, but each interpreter may have many thread states, including multiple for the same OS thread. Thread states from multiple interpreters may be bound to the same thread, but only one can be *attached* in that thread at any given moment.

See *Thread State and the Global Interpreter Lock* for more information.

token
A small unit of source code, generated by the lexical analyzer (also called the *tokenizer*). Names, numbers, strings, operators, newlines and similar are represented by tokens.

The `tokenize` module exposes Python's lexical analyzer. The `token` module contains information on the various types of tokens.

üç tırnaklı dize
Üç tırnak işareti (") veya kesme işareti (') ile sınırlanan bir dize. Tek tırnaklı dizelerde bulunmayan herhangi bir işlevsellik sağlamasalar da, birkaç nedenden dolayı faydalıdırlar. bir dizeye çıkışsız tek ve çift tırnak eklemeniz gerekir ve bunlar, devam karakterini kullanmadan birden çok satıra yayılabilir, bu da onları özellikle belge dizileri yazarken kullanışlı hale getirir.

tip
The type of a Python object determines what kind of object it is; every object has a type. An object's type is accessible as its `__class__` attribute or can be retrieved with `type(obj)`.

tip takma adı
Bir tanımlayıcıya tür atanarak oluşturulan, bir tür için eş anlamlı.

Tür takma adları, *tür ipuçlarını* basitleştirmek için kullanışlıdır. Örneğin:

```
def remove_gray_shades(
        colors: list[tuple[int, int, int]]) -> list[tuple[int, int, int]]:
    pass
```

bu şekilde daha okunaklı hale getirilebilir:

```
Color = tuple[int, int, int]

def remove_gray_shades(colors: list[Color]) -> list[Color]:
    pass
```

Bu işlevi açıklayan `typing` ve **PEP 484** bölümlerine bakın.

tür ipucu
Bir değişken, bir sınıf niteliği veya bir işlev parametresi veya dönüş değeri için beklenen türü belirten bir *ek açıklama*.

Type hints are optional and are not enforced by Python but they are useful to *static type checkers*. They can also aid IDEs with code completion and refactoring.

Genel değişkenlerin, sınıf özniteliklerinin ve işlevlerin tür ipuçlarına, yerel değişkenlere değil, `typing.get_type_hints()` kullanılarak erişilebilir.

Bu işlevi açıklayan `typing` ve **PEP 484** bölümlerine bakın.

evrensel yeni satırlar
Aşağıdakilerin tümünün bir satırın bitişi olarak kabul edildiği metin akışlarını yorumlamanın bir yolu: Unix satır sonu kuralı `\n'`, Windows kuralı `'\r\n'`, ve eski Macintosh kuralı `'\r'`. Ek bir kullanım için **PEP 278** ve **PEP 3116** ve ayrıca `bytes.splitlines()` bakın.

değişken açıklama
Bir değişkenin veya bir sınıf özniteliğinin *ek açıklaması*.

Bir değişkene veya sınıf niteliğine açıklama eklerken atama isteğe bağlıdır:

```
class C:
    field: 'annotation'
```

Değişken açıklamaları genellikle *tür ipuçları* için kullanılır: örneğin, bu değişkenin `int` değerlerini alması beklenir:

```
count: int = 0
```

Değişken açıklama sözdizimi annassign bölümünde açıklanmıştır.

Bu işlevi açıklayan; *function annotation*, **PEP 484** ve **PEP 526** bölümlerine bakın. Ek açıklamalarla çalışmaya ilişkin en iyi uygulamalar için ayrıca bkz. annotations-howto.

sanal ortam
Python kullanıcılarının ve uygulamalarının, aynı sistem üzerinde çalışan diğer Python uygulamalarının davranışına müdahale etmeden Python dağıtım paketlerini kurmasına ve yükseltmesine olanak tanıyan, işbirliği içinde yalıtılmış bir çalışma zamanı ortamı.

Ayrıca bakınız `venv`.

sanal makine
Tamamen yazılımla tanımlanmış bir bilgisayar. Python'un sanal makinesi, bayt kodu derleyicisi tarafından yayınlanan *bytecode* 'u çalıştırır.

walrus operator
A light-hearted way to refer to the assignment expression operator `:=` because it looks a bit like a walrus if you turn your head.

Python'un Zen'i
Dili anlamaya ve kullanmaya yardımcı olan Python tasarım ilkeleri ve felsefelerinin listesi. Liste, etkileşimli komut isteminde "`import this`" yazarak bulunabilir.

EK B

About this documentation

Python's documentation is generated from reStructuredText sources using Sphinx, a documentation generator originally created for Python and now maintained as an independent project.

Dokümantasyonun ve araç zincirinin geliştirilmesi, tıpkı Python'un kendisi gibi tamamen gönüllü bir çabadır. Katkıda bulunmak istiyorsanız, nasıl yapacağınıza ilişkin bilgi için lütfen reporting-bugs sayfasına göz atın. Yeni gönüllülere her zaman açığız!

Destekleri için teşekkürler:

- Fred L. Drake, Jr., the creator of the original Python documentation toolset and author of much of the content;
- Docutils projesi, reStructuredText ve Docutils paketini oluşturdukları için;
- Fredrik Lundh, Sphinx'in pek çok iyi fikir edindiği Alternatif Python Referansı projesi için.

B.1 Contributors to the Python documentation

Birçok kişi Python diline, Python standart kütüphanesine ve Python dokümantasyonuna katkıda bulunmuştur. Katkıda bulunanların kısmi bir listesi için Python kaynak dağıtımında Misc/ACKS dosyasına bakın.

Python topluluğunun girdileri ve katkıları sayesinde böyle harika bir dokümantasyona sahibiz – Teşekkürler!

EK C

Tarihçe ve Lisans

C.1 Yazılımın tarihçesi

Python was created in the early 1990s by Guido van Rossum at Stichting Mathematisch Centrum (CWI, see https://www.cwi.nl) in the Netherlands as a successor of a language called ABC. Guido remains Python's principal author, although it includes many contributions from others.

In 1995, Guido continued his work on Python at the Corporation for National Research Initiatives (CNRI, see https://www.cnri.reston.va.us) in Reston, Virginia where he released several versions of the software.

In May 2000, Guido and the Python core development team moved to BeOpen.com to form the BeOpen PythonLabs team. In October of the same year, the PythonLabs team moved to Digital Creations, which became Zope Corporation. In 2001, the Python Software Foundation (PSF, see https://www.python.org/psf/) was formed, a non-profit organization created specifically to own Python-related Intellectual Property. Zope Corporation was a sponsoring member of the PSF.

All Python releases are Open Source (see https://opensource.org for the Open Source Definition). Historically, most, but not all, Python releases have also been GPL-compatible; the table below summarizes the various releases.

Yayın	Şundan türedi:	Yıl	Sahibi	GPL-compatible? (1)
0.9.0'dan 1.2'ye	n/a	1991-1995	CWI	evet
1.3 'dan 1.5.2'ye	1.2	1995-1999	CNRI	evet
1.6	1.5.2	2000	CNRI	hayır
2.0	1.6	2000	BeOpen.com	hayır
1.6.1	1.6	2001	CNRI	yes (2)
2.1	2.0+1.6.1	2001	PSF	hayır
2.0.1	2.0+1.6.1	2001	PSF	evet
2.1.1	2.1+2.0.1	2001	PSF	evet
2.1.2	2.1.1	2002	PSF	evet
2.1.3	2.1.2	2002	PSF	evet
2.2 ve üzeri	2.1.1	2001-Günümüz	PSF	evet

Not

(1) GPL-compatible doesn't mean that we're distributing Python under the GPL. All Python licenses, unlike the GPL, let you distribute a modified version without making your changes open source. The GPL-compatible

licenses make it possible to combine Python with other software that is released under the GPL; the others don't.

(2) According to Richard Stallman, 1.6.1 is not GPL-compatible, because its license has a choice of law clause. According to CNRI, however, Stallman's lawyer has told CNRI's lawyer that 1.6.1 is "not incompatible" with the GPL.

Bu yayınları mümkün kılmak için Guido'nun yönetimi altında çalışan birçok gönüllüye teşekkürler.

C.2 Python'a erişmek veya başka bir şekilde kullanmak için şartlar ve koşullar

Python software and documentation are licensed under the Python Software Foundation License Version 2.

Starting with Python 3.8.6, examples, recipes, and other code in the documentation are dual licensed under the PSF License Version 2 and the *Zero-Clause BSD license*.

Python'a dahil edilen bazı yazılımlar farklı lisanslar altındadır. Lisanslar, bu lisansa giren kodla listelenir. Bu lisansların eksik listesi için bkz. *Tüzel Yazılımlar için Lisanslar ve Onaylar*.

C.2.1 PYTHON SOFTWARE FOUNDATION LICENSE VERSION 2

```
1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"), and
   the Individual or Organization ("Licensee") accessing and otherwise using this
   software ("Python") in source or binary form and its associated documentation.

2. Subject to the terms and conditions of this License Agreement, PSF hereby
   grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce,
   analyze, test, perform and/or display publicly, prepare derivative works,
   distribute, and otherwise use Python alone or in any derivative
   version, provided, however, that PSF's License Agreement and PSF's notice of
   copyright, i.e., "Copyright © 2001 Python Software Foundation; All Rights
   Reserved" are retained in Python alone or in any derivative version
   prepared by Licensee.

3. In the event Licensee prepares a derivative work that is based on or
   incorporates Python or any part thereof, and wants to make the
   derivative work available to others as provided herein, then Licensee hereby
   agrees to include in any such work a brief summary of the changes made to␣
↪Python.

4. PSF is making Python available to Licensee on an "AS IS" basis.
   PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED.  BY WAY OF
   EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
   WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
   USE OF PYTHON WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON
   FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF
   MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON, OR ANY DERIVATIVE
   THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

6. This License Agreement will automatically terminate upon a material breach of
   its terms and conditions.

7. Nothing in this License Agreement shall be deemed to create any relationship
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
   of agency, partnership, or joint venture between PSF and Licensee.  This License
   Agreement does not grant permission to use PSF trademarks or trade name in a
   trademark sense to endorse or promote products or services of Licensee, or any
   third party.

8. By copying, installing or otherwise using Python, Licensee agrees
   to be bound by the terms and conditions of this License Agreement.
```

C.2.2 PYTHON 2.0 İÇİN BEOPEN.COM LİSANS SÖZLEŞMESİ

BEOPEN PYTHON AÇIK KAYNAK LİSANS SÖZLEŞMESİ SÜRÜM 1

```
1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at
   160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization
   ("Licensee") accessing and otherwise using this software in source or binary
   form and its associated documentation ("the Software").

2. Subject to the terms and conditions of this BeOpen Python License Agreement,
   BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license
   to reproduce, analyze, test, perform and/or display publicly, prepare derivative
   works, distribute, and otherwise use the Software alone or in any derivative
   version, provided, however, that the BeOpen Python License is retained in the
   Software, alone or in any derivative version prepared by Licensee.

3. BeOpen is making the Software available to Licensee on an "AS IS" basis.
   BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED.  BY WAY OF
   EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
   WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
   USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR
   ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING,
   MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF
   ADVISED OF THE POSSIBILITY THEREOF.

5. This License Agreement will automatically terminate upon a material breach of
   its terms and conditions.

6. This License Agreement shall be governed by and interpreted in all respects
   by the law of the State of California, excluding conflict of law provisions.
   Nothing in this License Agreement shall be deemed to create any relationship of
   agency, partnership, or joint venture between BeOpen and Licensee.  This License
   Agreement does not grant permission to use BeOpen trademarks or trade names in a
   trademark sense to endorse or promote products or services of Licensee, or any
   third party.  As an exception, the "BeOpen Python" logos available at
   http://www.pythonlabs.com/logos.html may be used according to the permissions
   granted on that web page.

7. By copying, installing or otherwise using the software, Licensee agrees to be
   bound by the terms and conditions of this License Agreement.
```

C.2.3 PYTHON 1.6.1 İÇİN CNRI LİSANS ANLAŞMASI

```
1. This LICENSE AGREEMENT is between the Corporation for National Research
   Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191
   ("CNRI"), and the Individual or Organization ("Licensee") accessing and
   otherwise using Python 1.6.1 software in source or binary form and its
   associated documentation.

2. Subject to the terms and conditions of this License Agreement, CNRI hereby
   grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce,
   analyze, test, perform and/or display publicly, prepare derivative works,
   distribute, and otherwise use Python 1.6.1 alone or in any derivative version,
   provided, however, that CNRI's License Agreement and CNRI's notice of copyright,
   i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All
   Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version
   prepared by Licensee.  Alternately, in lieu of CNRI's License Agreement,
   Licensee may substitute the following text (omitting the quotes): "Python 1.6.1
   is made available subject to the terms and conditions in CNRI's License
   Agreement.  This Agreement together with Python 1.6.1 may be located on the
   internet using the following unique, persistent identifier (known as a handle):
   1895.22/1013.  This Agreement may also be obtained from a proxy server on the
   internet using the following URL: http://hdl.handle.net/1895.22/1013".

3. In the event Licensee prepares a derivative work that is based on or
   incorporates Python 1.6.1 or any part thereof, and wants to make the derivative
   work available to others as provided herein, then Licensee hereby agrees to
   include in any such work a brief summary of the changes made to Python 1.6.1.

4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis.  CNRI
   MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED.  BY WAY OF EXAMPLE,
   BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY
   OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF
   PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR
   ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF
   MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE
   THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

6. This License Agreement will automatically terminate upon a material breach of
   its terms and conditions.

7. This License Agreement shall be governed by the federal intellectual property
   law of the United States, including without limitation the federal copyright
   law, and, to the extent such U.S. federal law does not apply, by the law of the
   Commonwealth of Virginia, excluding Virginia's conflict of law provisions.
   Notwithstanding the foregoing, with regard to derivative works based on Python
   1.6.1 that incorporate non-separable material that was previously distributed
   under the GNU General Public License (GPL), the law of the Commonwealth of
   Virginia shall govern this License Agreement only as to issues arising under or
   with respect to Paragraphs 4, 5, and 7 of this License Agreement.  Nothing in
   this License Agreement shall be deemed to create any relationship of agency,
   partnership, or joint venture between CNRI and Licensee.  This License Agreement
   does not grant permission to use CNRI trademarks or trade name in a trademark
   sense to endorse or promote products or services of Licensee, or any third
   party.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
8. By clicking on the "ACCEPT" button where indicated, or by copying, installing
   or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and
   conditions of this License Agreement.
```

C.2.4 0.9.0 ARASI 1.2 PYTHON İÇİN CWI LİSANS SÖZLEŞMESİ

```
Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The
Netherlands.  All rights reserved.

Permission to use, copy, modify, and distribute this software and its
documentation for any purpose and without fee is hereby granted, provided that
the above copyright notice appear in all copies and that both that copyright
notice and this permission notice appear in supporting documentation, and that
the name of Stichting Mathematisch Centrum or CWI not be used in advertising or
publicity pertaining to distribution of the software without specific, written
prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS
SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO
EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT
OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE,
DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS
SOFTWARE.
```

C.2.5 ZERO-CLAUSE BSD LICENSE FOR CODE IN THE PYTHON DOCUMENTATION

```
Permission to use, copy, modify, and/or distribute this software for any
purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH
REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT,
INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM
LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR
OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR
PERFORMANCE OF THIS SOFTWARE.
```

C.3 Tüzel Yazılımlar için Lisanslar ve Onaylar

Bu bölüm, Python dağıtımına dahil edilmiş üçüncü taraf yazılımlar için tamamlanmamış ancak büyüyen bir lisans ve onay listesidir.

C.3.1 Mersenne Twister'ı

`random` modülünün altyapısını oluşturan `_random` C uzantısı, http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/MT2002/emt19937ar.html adresinden indirilen kodu temel alır. Orijinal koddan kelimesi kelimesine yorumlar aşağıdadır:

```
A C-program for MT19937, with initialization improved 2002/1/26.
Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init_genrand(seed)
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
or init_by_array(init_key, key_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura,
All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

 1. Redistributions of source code must retain the above copyright
    notice, this list of conditions and the following disclaimer.

 2. Redistributions in binary form must reproduce the above copyright
    notice, this list of conditions and the following disclaimer in the
    documentation and/or other materials provided with the distribution.

 3. The names of its contributors may not be used to endorse or promote
    products derived from this software without specific prior written
    permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED.  IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.


Any feedback is very welcome.
http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html
email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)
```

C.3.2 Soketler

`socket` modülü, https://www.wide.ad.jp/ adresindeki WIDE Projesi'nden ayrı kaynak dosyalarında kodlanan `getaddrinfo()` ve `getnameinfo()` fonksiyonlarını kullanır.

```
Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project.
All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.
3. Neither the name of the project nor the names of its contributors
   may be used to endorse or promote products derived from this software
   without specific prior written permission.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED.  IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

C.3.3 Asenkron soket hizmetleri

The `test.support.asynchat` and `test.support.asyncore` modules contain the following notice:

```
Copyright 1996 by Sam Rushing

                        All Rights Reserved

Permission to use, copy, modify, and distribute this software and
its documentation for any purpose and without fee is hereby
granted, provided that the above copyright notice appear in all
copies and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of Sam
Rushing not be used in advertising or publicity pertaining to
distribution of the software without specific, written prior
permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE,
INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN
NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR
CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS
OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT,
NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN
CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.
```

C.3.4 Çerez yönetimi

`http.cookies` modülü aşağıdaki uyarıyı içerir:

```
Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>

               All Rights Reserved

Permission to use, copy, modify, and distribute this software
and its documentation for any purpose and without fee is hereby
granted, provided that the above copyright notice appear in all
copies and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of
Timothy O'Malley  not be used in advertising or publicity
pertaining to distribution of the software without specific, written
prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR
ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,
WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR
PERFORMANCE OF THIS SOFTWARE.
```

C.3.5 Çalıştırma izleme

`trace` modülü aşağıdaki uyarıyı içerir:

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...
err...  reserved and offered to the public under the terms of the
Python 2.2 license.
Author: Zooko O'Whielacronx
http://zooko.com/
mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.
Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.


Permission to use, copy, modify, and distribute this Python software and
its associated documentation for any purpose without fee is hereby
granted, provided that the above copyright notice appears in all copies,
and that both that copyright notice and this permission notice appear in
supporting documentation, and that the name of neither Automatrix,
Bioreason or Mojam Media be used in advertising or publicity pertaining to
distribution of the software without specific, written prior permission.
```

C.3.6 UUencode ve UUdecode fonksiyonları

The `uu` codec contains the following notice:

```
Copyright 1994 by Lance Ellinghouse
Cathedral City, California Republic, United States of America.
                       All Rights Reserved
Permission to use, copy, modify, and distribute this software and its
documentation for any purpose and without fee is hereby granted,
provided that the above copyright notice appear in all copies and that
both that copyright notice and this permission notice appear in
supporting documentation, and that the name of Lance Ellinghouse
not be used in advertising or publicity pertaining to distribution
of the software without specific, written prior permission.
LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO
THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND
FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN
ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT
OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:
- Use binascii module to do the actual line-by-line conversion
  between ascii and binary. This results in a 1000-fold speedup. The C
  version is still 5 times faster, though.
- Arguments more compliant with Python standard
```

C.3.7 XML Uzaktan Yordam Çağrıları

`xmlrpc.client` modülü aşağıdaki uyarıyı içerir:

```
    The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB
Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its
associated documentation, you agree that you have read, understood,
and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and
its associated documentation for any purpose and without fee is
hereby granted, provided that the above copyright notice appears in
all copies, and that both that copyright notice and this permission
notice appear in supporting documentation, and that the name of
Secret Labs AB or the author not be used in advertising or publicity
pertaining to distribution of the software without specific, written
prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD
TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-
ABILITY AND FITNESS.  IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR
BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY
DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,
WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS
ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE
OF THIS SOFTWARE.
```

C.3.8 test_epoll

`test.test_epoll` modülü aşağıdaki uyarıyı içerir:

```
Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
The above copyright notice and this permission notice shall be
included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE
LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION
OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION
WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

C.3.9 kqueue seçin

`select` modülü, kqueue arayüzü için aşağıdaki uyarıyı içerir:

```
Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes
All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED.  IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

C.3.10 SipHash24

`Python/pyhash.c` dosyası, Dan Bernstein'ın SipHash24 algoritmasının Marek Majkowski uygulamasını içerir. Burada aşağıdaki not yer alır:

```
<MIT License>
Copyright (c) 2013  Marek Majkowski <marek@popcount.org>

Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
</MIT License>

Original location:
   https://github.com/majek/csiphash/

Solution inspired by code from:
   Samuel Neves (supercop/crypto_auth/siphash24/little)
   djb (supercop/crypto_auth/siphash24/little2)
   Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)
```

C.3.11 strtod ve dtoa

C double'larının dizelere ve dizelerden dönüştürülmesi için dtoa ve strtod C fonksiyonlarını sağlayan `Python/dtoa.c` dosyası, şu anda https://web.archive.org/web/20220517033456/http://www.netlib.org/fp/dtoa.c 'den erişilebilen David M. Gay tarafından aynı adlı dosyadan türetilmiştir. 16 Mart 2009'da alınan orijinal dosya aşağıdaki telif hakkı ve lisans bildirimini içerir:

```
/****************************************************************
 *
 * The author of this software is David M. Gay.
 *
 * Copyright (c) 1991, 2000, 2001 by Lucent Technologies.
 *
 * Permission to use, copy, modify, and distribute this software for any
 * purpose without fee is hereby granted, provided that this entire notice
 * is included in all copies of any software which is or includes a copy
 * or modification of this software and in all copies of the supporting
 * documentation for such software.
 *
 * THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
 * WARRANTY.  IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY
 * REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY
 * OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.
 *
 ***************************************************************/
```

C.3.12 OpenSSL

The modules `hashlib`, `posix` and `ssl` use the OpenSSL library for added performance if made available by the operating system. Additionally, the Windows and macOS installers for Python may include a copy of the OpenSSL libraries, so we include a copy of the OpenSSL license here. For the OpenSSL 3.0 release, and later releases derived from that, the Apache License v2 applies:

```
                                 Apache License
                           Version 2.0, January 2004
                        https://www.apache.org/licenses/

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. Definitions.

   "License" shall mean the terms and conditions for use, reproduction,
   and distribution as defined by Sections 1 through 9 of this document.

   "Licensor" shall mean the copyright owner or entity authorized by
   the copyright owner that is granting the License.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
   "Legal Entity" shall mean the union of the acting entity and all
   other entities that control, are controlled by, or are under common
   control with that entity. For the purposes of this definition,
   "control" means (i) the power, direct or indirect, to cause the
   direction or management of such entity, whether by contract or
   otherwise, or (ii) ownership of fifty percent (50%) or more of the
   outstanding shares, or (iii) beneficial ownership of such entity.

   "You" (or "Your") shall mean an individual or Legal Entity
   exercising permissions granted by this License.

   "Source" form shall mean the preferred form for making modifications,
   including but not limited to software source code, documentation
   source, and configuration files.

   "Object" form shall mean any form resulting from mechanical
   transformation or translation of a Source form, including but
   not limited to compiled object code, generated documentation,
   and conversions to other media types.

   "Work" shall mean the work of authorship, whether in Source or
   Object form, made available under the License, as indicated by a
   copyright notice that is included in or attached to the work
   (an example is provided in the Appendix below).

   "Derivative Works" shall mean any work, whether in Source or Object
   form, that is based on (or derived from) the Work and for which the
   editorial revisions, annotations, elaborations, or other modifications
   represent, as a whole, an original work of authorship. For the purposes
   of this License, Derivative Works shall not include works that remain
   separable from, or merely link (or bind by name) to the interfaces of,
   the Work and Derivative Works thereof.

   "Contribution" shall mean any work of authorship, including
   the original version of the Work and any modifications or additions
   to that Work or Derivative Works thereof, that is intentionally
   submitted to Licensor for inclusion in the Work by the copyright owner
   or by an individual or Legal Entity authorized to submit on behalf of
   the copyright owner. For the purposes of this definition, "submitted"
   means any form of electronic, verbal, or written communication sent
   to the Licensor or its representatives, including but not limited to
   communication on electronic mailing lists, source code control systems,
   and issue tracking systems that are managed by, or on behalf of, the
   Licensor for the purpose of discussing and improving the Work, but
   excluding communication that is conspicuously marked or otherwise
   designated in writing by the copyright owner as "Not a Contribution."

   "Contributor" shall mean Licensor and any individual or Legal Entity
   on behalf of whom a Contribution has been received by Licensor and
   subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of
   this License, each Contributor hereby grants to You a perpetual,
   worldwide, non-exclusive, no-charge, royalty-free, irrevocable
   copyright license to reproduce, prepare Derivative Works of,
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
   publicly display, publicly perform, sublicense, and distribute the
   Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of
   this License, each Contributor hereby grants to You a perpetual,
   worldwide, non-exclusive, no-charge, royalty-free, irrevocable
   (except as stated in this section) patent license to make, have made,
   use, offer to sell, sell, import, and otherwise transfer the Work,
   where such license applies only to those patent claims licensable
   by such Contributor that are necessarily infringed by their
   Contribution(s) alone or by combination of their Contribution(s)
   with the Work to which such Contribution(s) was submitted. If You
   institute patent litigation against any entity (including a
   cross-claim or counterclaim in a lawsuit) alleging that the Work
   or a Contribution incorporated within the Work constitutes direct
   or contributory patent infringement, then any patent licenses
   granted to You under this License for that Work shall terminate
   as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the
   Work or Derivative Works thereof in any medium, with or without
   modifications, and in Source or Object form, provided that You
   meet the following conditions:

   (a) You must give any other recipients of the Work or
       Derivative Works a copy of this License; and

   (b) You must cause any modified files to carry prominent notices
       stating that You changed the files; and

   (c) You must retain, in the Source form of any Derivative Works
       that You distribute, all copyright, patent, trademark, and
       attribution notices from the Source form of the Work,
       excluding those notices that do not pertain to any part of
       the Derivative Works; and

   (d) If the Work includes a "NOTICE" text file as part of its
       distribution, then any Derivative Works that You distribute must
       include a readable copy of the attribution notices contained
       within such NOTICE file, excluding those notices that do not
       pertain to any part of the Derivative Works, in at least one
       of the following places: within a NOTICE text file distributed
       as part of the Derivative Works; within the Source form or
       documentation, if provided along with the Derivative Works; or,
       within a display generated by the Derivative Works, if and
       wherever such third-party notices normally appear. The contents
       of the NOTICE file are for informational purposes only and
       do not modify the License. You may add Your own attribution
       notices within Derivative Works that You distribute, alongside
       or as an addendum to the NOTICE text from the Work, provided
       that such additional attribution notices cannot be construed
       as modifying the License.

   You may add Your own copyright statement to Your modifications and
   may provide additional or different license terms and conditions
   for use, reproduction, or distribution of Your modifications, or
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
   for any such Derivative Works as a whole, provided Your use,
   reproduction, and distribution of the Work otherwise complies with
   the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise,
   any Contribution intentionally submitted for inclusion in the Work
   by You to the Licensor shall be under the terms and conditions of
   this License, without any additional terms or conditions.
   Notwithstanding the above, nothing herein shall supersede or modify
   the terms of any separate license agreement you may have executed
   with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade
   names, trademarks, service marks, or product names of the Licensor,
   except as required for reasonable and customary use in describing the
   origin of the Work and reproducing the content of the NOTICE file.

7. Disclaimer of Warranty. Unless required by applicable law or
   agreed to in writing, Licensor provides the Work (and each
   Contributor provides its Contributions) on an "AS IS" BASIS,
   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or
   implied, including, without limitation, any warranties or conditions
   of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A
   PARTICULAR PURPOSE. You are solely responsible for determining the
   appropriateness of using or redistributing the Work and assume any
   risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory,
   whether in tort (including negligence), contract, or otherwise,
   unless required by applicable law (such as deliberate and grossly
   negligent acts) or agreed to in writing, shall any Contributor be
   liable to You for damages, including any direct, indirect, special,
   incidental, or consequential damages of any character arising as a
   result of this License or out of the use or inability to use the
   Work (including but not limited to damages for loss of goodwill,
   work stoppage, computer failure or malfunction, or any and all
   other commercial damages or losses), even if such Contributor
   has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing
   the Work or Derivative Works thereof, You may choose to offer,
   and charge a fee for, acceptance of support, warranty, indemnity,
   or other liability obligations and/or rights consistent with this
   License. However, in accepting such obligations, You may act only
   on Your own behalf and on Your sole responsibility, not on behalf
   of any other Contributor, and only if You agree to indemnify,
   defend, and hold each Contributor harmless for any liability
   incurred by, or claims asserted against, such Contributor by reason
   of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS
```

C.3.13 expat

The `pyexpat` extension is built using an included copy of the expat sources unless the build is configured `--with-system-expat`:

```
Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd
                               and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:

The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT.
IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY
CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT,
TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE
SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

C.3.14 libffi

`ctypes` modülünün altyapsını oluşturan `_ctypes` C uzantısı, `--with-system-libffi` olarak yapılandırılmadığı sürece libffi kaynaklarının dahil edildiği bir kopya kullanılarak oluşturulur:

```
Copyright (c) 1996-2008  Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:

The above copyright notice and this permission notice shall be included
in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT.  IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT
HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY,
WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER
DEALINGS IN THE SOFTWARE.
```

C.3.15 zlib

`zlib` uzantısı, sistemde bulunan zlib sürümü derleme için kullanılamayacak kadar eskiyse, zlib kaynaklarının dahil edildiği bir kopya kullanılarak oluşturulur:

```
Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied
warranty.  In no event will the authors be held liable for any damages
arising from the use of this software.

Permission is granted to anyone to use this software for any purpose,
including commercial applications, and to alter it and redistribute it
freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not
   claim that you wrote the original software. If you use this software
   in a product, an acknowledgment in the product documentation would be
   appreciated but is not required.

2. Altered source versions must be plainly marked as such, and must not be
   misrepresented as being the original software.

3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly        Mark Adler
jloup@gzip.org          madler@alumni.caltech.edu
```

C.3.16 cfuhash

`tracemalloc` tarafından kullanılan hash tablosunun uygulanması cfuhash projesine dayanmaktadır:

```
Copyright (c) 2005 Don Owens
All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

  * Redistributions of source code must retain the above copyright
    notice, this list of conditions and the following disclaimer.

  * Redistributions in binary form must reproduce the above
    copyright notice, this list of conditions and the following
    disclaimer in the documentation and/or other materials provided
    with the distribution.

  * Neither the name of the author nor the names of its
    contributors may be used to endorse or promote products derived
    from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT,
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
(INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR
SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
OF THE POSSIBILITY OF SUCH DAMAGE.
```

C.3.17 libmpdec

The `_decimal` C extension underlying the `decimal` module is built using an included copy of the libmpdec library unless the build is configured `--with-system-libmpdec`:

```
Copyright (c) 2008-2020 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
ARE DISCLAIMED.  IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
SUCH DAMAGE.
```

C.3.18 W3C C14N test paketi

`test` paketindeki C14N 2.0 test paketi (`Lib/test/xmltestdata/c14n-20/`), https://www.w3.org/TR/xml-c14n2-testcases/ adresindeki W3C web sitesinden alınmıştır ve 3 maddeli BSD lisansı altında dağıtılmaktadır:

```
Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang),
All Rights Reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:

* Redistributions of works must retain the original copyright notice,
  this list of conditions and the following disclaimer.
* Redistributions in binary form must reproduce the original copyright
  notice, this list of conditions and the following disclaimer in the
  documentation and/or other materials provided with the distribution.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
* Neither the name of the W3C nor the names of its contributors may be
  used to endorse or promote products derived from this work without
  specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

C.3.19 mimalloc

MIT License:

```
Copyright (c) 2018-2021 Microsoft Corporation, Daan Leijen

Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all
copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR
IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE
AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER
LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE
SOFTWARE.
```

C.3.20 asyncio

Parts of the `asyncio` module are incorporated from uvloop 0.16, which is distributed under the MIT license:

```
Copyright (c) 2015-2021 MagicStack Inc.  http://magic.io

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
"Software"), to deal in the Software without restriction, including
without limitation the rights to use, copy, modify, merge, publish,
distribute, sublicense, and/or sell copies of the Software, and to
permit persons to whom the Software is furnished to do so, subject to
the following conditions:

The above copyright notice and this permission notice shall be
included in all copies or substantial portions of the Software.
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND,
EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF
MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND
NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE
LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION
OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION
WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```

C.3.21 Global Unbounded Sequences (GUS)

The file `Python/qsbr.c` is adapted from FreeBSD's "Global Unbounded Sequences" safe memory reclamation scheme in subr_smr.c. The file is distributed under the 2-Clause BSD License:

```
Copyright (c) 2019,2020 Jeffrey Roberson <jeff@FreeBSD.org>

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
1. Redistributions of source code must retain the above copyright
   notice unmodified, this list of conditions, and the following
   disclaimer.
2. Redistributions in binary form must reproduce the above copyright
   notice, this list of conditions and the following disclaimer in the
   documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR
IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES
OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED.
IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

C.3.22 Zstandard bindings

Zstandard bindings in `Modules/_zstd` and `Lib/compression/zstd` are based on code from the pyzstd library, copyright Ma Lin and contributors. The pyzstd code is distributed under the 3-Clause BSD License:

```
Copyright (c) 2020-present, Ma Lin and contributors.
All rights reserved.

Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this
   list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice,
   this list of conditions and the following disclaimer in the documentation
   and/or other materials provided with the distribution.

3. Neither the name of the copyright holder nor the names of its
```

(sonraki sayfaya devam)

(önceki sayfadan devam)

```
   contributors may be used to endorse or promote products derived from
   this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS"
AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE
DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE
FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR
SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER
CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY,
OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

EK D

Telif Hakkı

Python ve bu dokümantasyon:

Copyright © 2001 Python Software Foundation. All rights reserved.

Telif Hakkı © 2000 BeOpen.com. Tüm hakları saklıdır.

Telif Hakkı © 1995-2000 Ulusal Araştırma Girişimleri Kurumu. Tüm hakları saklıdır.

Telif Hakkı © 1991-1995 Stichting Mathematisch Centrum. Tüm hakları saklıdır.

Bütün lisans ve izin bilgileri için *Tarihçe ve Lisans* 'a göz atın.

Kaynakça

[win] `PyExc_WindowsError` is only defined on Windows; protect code that uses this by testing that the preprocessor macro `MS_WINDOWS` is defined.

Dizin

Alfabetik olmayan

. . ., **367**
    ellipsis literal, 367
>>>, **367**
__all__ (*package variable*), 82
__dict__ (*module attribute*), 203
__doc__ (*module attribute*), 203
__file__ (*module attribute*), 203, 204
__future__, **373**
__import__
    built-in function, 83
__loader__ (*module attribute*), 203
__main__
    module, 12, 231, 246, 247
__name__ (*module attribute*), 203
__package__ (*module attribute*), 203
__PYVENV_LAUNCHER__, 270, 276
__slots__, **381**
_frozen (*C struct*), 85
_inittab (*C struct*), 86
_inittab.initfunc (*C member*), 86
_inittab.name (*C member*), 86
_Py_c_diff (*C function*), 155
_Py_c_neg (*C function*), 155
_Py_c_pow (*C function*), 155
_Py_c_prod (*C function*), 155
_Py_c_quot (*C function*), 155
_Py_c_sum (*C function*), 155
_Py_NoneStruct (*C var*), 299
_PyBytes_Resize (*C function*), 158
_PyCode_GetExtra (*C function*), 201
_PyCode_SetExtra (*C function*), 201
_PyEval_RequestCodeExtraIndex (*C function*), 201
_PyFrameEvalFunction (*C type*), 244
_PyInterpreterFrame (*C struct*), 219
_PyInterpreterState_GetEvalFrameFunc (*C function*), 244
_PyInterpreterState_SetEvalFrameFunc (*C function*), 244
_PyObject_GetDictPtr (*C function*), 109
_PyObject_New (*C function*), 297
_PyObject_NewVar (*C function*), 297
_PyTuple_Resize (*C function*), 182
_thread
    module, 240

A

abort (*C function*), 82
abs
    built-in function, 120
ad alanı, **378**
ad alanı paketi, **378**
adlandırılmış demet, **378**
allocfunc (*C type*), 348
anahtar işlev, **376**
anahtar kelime argümanı, **376**
anlamak, **381**
annotate function, **367**
argüman, **367**
argv (*in module sys*), 236, 269
ascii
    built-in function, 109
asenkron bağlam yöneticisi, **368**
asenkron jeneratör, **368**
asenkron jeneratör yineleyici, **368**
asenkron yineleyici, **368**
attached thread state, **368**

B

bağlam değişkeni, **370**
bağlam yöneticisi, **370**
bayt benzeri nesne, **369**
bayt kodu, **369**
BDFL, **369**
beklenebilir, **369**
belge dizisi, **372**
binaryfunc (*C type*), 349
bitişik, **370**
BOŞTA, **375**
buffer interface
    (see buffer protocol), 127
buffer object
    (see buffer protocol), 127
buffer protocol, 127
built-in function
    __import__, 83

    abs, 120
    ascii, 109
    bytes, 110
    classmethod, 307
    compile, 84
    divmod, 120
    float, 122
    hash, 110, 324
    int, 122
    len, 111, 123, 125, 184, 188, 192
    pow, 120, 122
    repr, 109, 323
    staticmethod, 307
    tuple, 124, 186
    type, 110
builtins
    module, 12, 231, 246, 247
bulucu, **373**
bytearray
    object, 158
bytes
    built-in function, 110
    object, 156

C

calloc (*C function*), 285
Capsule
    object, 215
C-contiguous, 130, 370
classmethod
    built-in function, 307
cleanup functions, 82
close (*in module os*), 247
closure variable, **370**
CO_ASYNC_GENERATOR (*C macro*), 200
CO_COROUTINE (*C macro*), 200
CO_FUTURE_ABSOLUTE_IMPORT (*C macro*), 200
CO_FUTURE_ANNOTATIONS (*C macro*), 200
CO_FUTURE_DIVISION (*C macro*), 200
CO_FUTURE_GENERATOR_STOP (*C macro*), 200
CO_FUTURE_PRINT_FUNCTION (*C macro*), 200
CO_FUTURE_UNICODE_LITERALS (*C macro*), 200
CO_FUTURE_WITH_STATEMENT (*C macro*), 200
CO_GENERATOR (*C macro*), 200
CO_HAS_DOCSTRING (*C macro*), 200
CO_ITERABLE_COROUTINE (*C macro*), 200
CO_METHOD (*C macro*), 200
CO_NESTED (*C macro*), 200
CO_NEWLOCALS (*C macro*), 200
CO_OPTIMIZED (*C macro*), 200
CO_VARARGS (*C macro*), 200
CO_VARKEYWORDS (*C macro*), 200
code object, 196
Common Vulnerabilities and Exposures
    CVE 2008-5983, 236
compile
    built-in function, 84
complex number
    object, 154
context, **370**
context management protocol, **370**
contiguous, 130
copyright (*in module sys*), 236
CPython, **371**
current context, **371**
cyclic isolate, **371**

Ç

çağırılabilir, **369**
çöp toplama, **373**

D

değişken açıklama, **384**
değişmez, **375**
değiştirilebilir, **378**
dekoratör, **371**
descrgetfunc (*C type*), 349
descrsetfunc (*C type*), 349
destructor (*C type*), 349
dictionary
    object, 186
dipnot, **367**
divmod
    built-in function, 120
dizi, **381**
dosya benzeri nesne, **372**
dosya nesnesi, **372**
dosya sistemi kodlaması ve hata işleyicisi, **372**
dunder, **372**

E

EAFP, **372**
EOFError (*built-in exception*), 202
eşyordam, **371**
eşyordam işlevi, **371**
eşzamansız yinelenebilir, **368**
etkileşimli, **375**
evaluate function, **372**
evrensel yeni satırlar, **384**
exc_info (*in module sys*), 10
executable (*in module sys*), 235
exit (*C function*), 82

F

f-string, **372**
f-strings, **372**
file
    object, 202
float
    built-in function, 122
floating-point
    object, 152
fonksiyon, **373**
fonksiyon açıklaması, **373**
Fortran contiguous, 130, 370

free (*C function*), 285
free threading, **373**
free variable, **373**
freefunc (*C type*), 349
freeze utility, 85
frozenset
    object, 191
function
    object, 192

G

gcvisitobjects_t (*C type*), 356
geçici API, **380**
geçici paket, **380**
genel işlev, **374**
genel tercüman kilidi, **374**
genel tip, **374**
geri çağırmak, **370**
getattrfunc (*C type*), 349
getattrofunc (*C type*), 349
getbufferproc (*C type*), 349
getiterfunc (*C type*), 349
getter (*C type*), 312
GIL, **374**
global interpreter lock, 237
güçlü referans, **382**

H

haritalama, **377**
hash
    built-in function, 110, 324
hashfunc (*C type*), 349

İ

iç içe kapsam, **378**
içe aktarıcı, **375**
içe aktarım yolu, **375**
içe aktarma, **375**
ifade (*değer döndürmez*), **382**
ifade (*değer döndürür*), **372**
ikili dosya, **369**
immortal, **375**
incr_item(), 11
initproc (*C type*), 349
inquiry (*C type*), 355
instancemethod
    object, 195
int
    built-in function, 122
integer
    object, 142
interpreter lock, 237
iternextfunc (*C type*), 349

J

jeneratör, **374**
jeneratör ifadesi, **374**
jeneratör yineleyici, **374**

K

karma tabanlı pyc, **374**
karmaşık sayı, **370**
kat bölümü, **373**
KeyboardInterrupt (*built-in exception*), 61
kısım, **380**
konumsal argüman, **380**

L

lambda, **376**
LBYL, **376**
len
    built-in function, 111, 123, 125, 184, 188, 192
lenfunc (*C type*), 349
lexical analyzer, **376**
list
    object, 184
liste, **376**
liste anlama, **377**
lock, interpreter, 237
long integer
    object, 142
LONG_MAX (*C macro*), 144

M

magic
    metot, 377
main(), 234, 236, 269
malloc (*C function*), 285
mapping
    object, 186
memoryview
    object, 213
meta yol bulucu, **377**
metasınıf, **377**
METH_CLASS (*C macro*), 307
METH_COEXIST (*C macro*), 308
METH_FASTCALL (*C macro*), 307
METH_KEYWORDS (*C macro*), 306
METH_METHOD (*C macro*), 307
METH_NOARGS (*C macro*), 307
METH_O (*C macro*), 307
METH_STATIC (*C macro*), 307
METH_VARARGS (*C macro*), 306
method
    object, 195
MethodType (*in module types*), 192, 195
metot, **377**
    magic, 377
    special, 382
metot kalite sıralaması, **377**
module
    __main__, 12, 231, 246, 247
    _thread, 240
    builtins, 12, 231, 246, 247

    object, 203
    search path, 12, 231, 235
    signal, 61
    sys, 12, 231, 246, 247
modules (*in module sys*), 82, 231
ModuleType (*in module types*), 203
modül, **377**
modül özelliği, **378**
MRO, **378**

N

newfunc (*C type*), 349
nitelik, **369**
nitelikli isim, **381**
None
    object, 142
numeric
    object, 142

O

obje, **379**
object
    bytearray, 158
    bytes, 156
    Capsule, 215
    code, 196
    complex number, 154
    dictionary, 186
    file, 202
    floating-point, 152
    frozenset, 191
    function, 192
    instancemethod, 195
    integer, 142
    list, 184
    long integer, 142
    mapping, 186
    memoryview, 213
    method, 195
    module, 203
    None, 142
    numeric, 142
    sequence, 156
    set, 191
    tuple, 181
    type, 6, 135
objobjargproc (*C type*), 350
objobjproc (*C type*), 350
optimized scope, **379**
ortam değişkeni
    __PYVENV_LAUNCHER__, 270, 276
    PATH, 12
    PYTHON_CPU_COUNT, 274
    PYTHON_FROZEN_MODULES, 273
    PYTHON_GIL, 374
    PYTHON_PERF_JIT_SUPPORT, 278
    PYTHON_PRESITE, 277
    PYTHONCOERCECLOCALE, 282
    PYTHONDEBUG, 229, 276
    PYTHONDEVMODE, 271
    PYTHONDONTWRITEBYTECODE, 229, 279
    PYTHONDUMPREFS, 271
    PYTHONDUMPREFSFILE, 271
    PYTHONEXECUTABLE, 276
    PYTHONFAULTHANDLER, 272
    PYTHONHASHSEED, 229, 273
    PYTHONHOME, 12, 229, 237, 273
    PYTHONINSPECT, 229, 273
    PYTHONINTMAXSTRDIGITS, 274
    PYTHONIOENCODING, 277
    PYTHONLEGACYWINDOWSFSENCODING, 230, 267
    PYTHONLEGACYWINDOWSSTDIO, 230, 274
    PYTHONMALLOC, 286, 290, 292, 293
    PYTHONMALLOCSTATS, 274, 286
    PYTHONNODEBUGRANGES, 271
    PYTHONNOUSERSITE, 230, 279
    PYTHONOPTIMIZE, 230, 275
    PYTHONPATH, 12, 229, 275
    PYTHONPERFSUPPORT, 278
    PYTHONPLATLIBDIR, 274
    PYTHONPROFILEIMPORTTIME, 273
    PYTHONPYCACHEPREFIX, 276
    PYTHONSAFEPATH, 270
    PYTHONTRACEMALLOC, 278
    PYTHONUNBUFFERED, 231, 270
    PYTHONUTF8, 267, 282
    PYTHONVERBOSE, 231, 279
    PYTHONWARNINGS, 279
OverflowError (*built-in exception*), 144, 145

Ö

ödünç alınan referans, **369**
ördek yazma, **372**
özel metod, **382**

P

package variable
    __all__, 82
paket, **379**
parametre, **379**
parçalamak, **382**
PATH, 12
path
    module search, 12, 231, 235
path (*in module sys*), 12, 231, 235
PEP, **380**
platform (*in module sys*), 235
pow
    built-in function, 120, 122
Py_ABS (*C macro*), 4
Py_AddPendingCall (*C function*), 248
Py_ALWAYS_INLINE (*C macro*), 4
Py_ASNATIVEBYTES_ALLOW_INDEX (*C macro*), 148
Py_ASNATIVEBYTES_BIG_ENDIAN (*C macro*), 148
Py_ASNATIVEBYTES_DEFAULTS (*C macro*), 148

Py_ASNATIVEBYTES_LITTLE_ENDIAN (*C macro*), 148
Py_ASNATIVEBYTES_NATIVE_ENDIAN (*C macro*), 148
Py_ASNATIVEBYTES_REJECT_NEGATIVE (*C macro*), 148
Py_ASNATIVEBYTES_UNSIGNED_BUFFER (*C macro*), 148
Py_AtExit (*C function*), 82
Py_AUDIT_READ (*C macro*), 309
Py_AuditHookFunction (*C type*), 82
Py_BEGIN_ALLOW_THREADS (*C macro*), 238, 242
Py_BEGIN_CRITICAL_SECTION (*C macro*), 255
Py_BEGIN_CRITICAL_SECTION2 (*C macro*), 256
Py_BEGIN_CRITICAL_SECTION2_MUTEX (*C macro*), 256
Py_BEGIN_CRITICAL_SECTION_MUTEX (*C macro*), 255
Py_BLOCK_THREADS (*C macro*), 242
Py_buffer (*C type*), 128
Py_buffer.buf (*C member*), 128
Py_buffer.format (*C member*), 128
Py_buffer.internal (*C member*), 129
Py_buffer.itemsize (*C member*), 128
Py_buffer.len (*C member*), 128
Py_buffer.ndim (*C member*), 128
Py_buffer.obj (*C member*), 128
Py_buffer.readonly (*C member*), 128
Py_buffer.shape (*C member*), 128
Py_buffer.strides (*C member*), 129
Py_buffer.suboffsets (*C member*), 129
Py_BuildValue (*C function*), 94
Py_BytesMain (*C function*), 232
Py_BytesWarningFlag (*C var*), 228
Py_CHARMASK (*C macro*), 5
Py_CLEANUP_SUPPORTED (*C macro*), 91
Py_CLEAR (*C function*), 51
Py_CompileString (*C function*), 45, 46
Py_CompileStringExFlags (*C function*), 45
Py_CompileStringFlags (*C function*), 45
Py_CompileStringObject (*C function*), 45
Py_complex (*C type*), 154
Py_complex.imag (*C member*), 154
Py_complex.real (*C member*), 154
Py_CONSTANT_ELLIPSIS (*C macro*), 106
Py_CONSTANT_EMPTY_BYTES (*C macro*), 106
Py_CONSTANT_EMPTY_STR (*C macro*), 106
Py_CONSTANT_EMPTY_TUPLE (*C macro*), 106
Py_CONSTANT_FALSE (*C macro*), 106
Py_CONSTANT_NONE (*C macro*), 106
Py_CONSTANT_NOT_IMPLEMENTED (*C macro*), 106
Py_CONSTANT_ONE (*C macro*), 106
Py_CONSTANT_TRUE (*C macro*), 106
Py_CONSTANT_ZERO (*C macro*), 106
PY_CXX_CONST (*C macro*), 93
Py_DEBUG (*C macro*), 12
Py_DebugFlag (*C var*), 228
Py_DecodeLocale (*C function*), 78
Py_DECREF (*C function*), 7, 50
Py_DecRef (*C function*), 51
Py_DEPRECATED (*C macro*), 5
Py_DontWriteBytecodeFlag (*C var*), 229
Py_Ellipsis (*C var*), 213
Py_EncodeLocale (*C function*), 79
Py_END_ALLOW_THREADS (*C macro*), 238, 242
Py_END_CRITICAL_SECTION (*C macro*), 256
Py_END_CRITICAL_SECTION2 (*C macro*), 256
Py_EndInterpreter (*C function*), 247
Py_EnterRecursiveCall (*C function*), 64
Py_EQ (*C macro*), 334
Py_eval_input (*C var*), 46
Py_Exit (*C function*), 82
Py_ExitStatusException (*C function*), 265
Py_False (*C var*), 152
Py_FatalError (*C function*), 82
Py_FatalError(), 236
Py_fclose (*C function*), 80
Py_FdIsInteractive (*C function*), 77
Py_file_input (*C var*), 46
Py_Finalize (*C function*), 232
Py_FinalizeEx (*C function*), 82, 231, 232, 247, 248
Py_fopen (*C function*), 80
Py_FrozenFlag (*C var*), 229
Py_GE (*C macro*), 334
Py_GenericAlias (*C function*), 226
Py_GenericAliasType (*C var*), 226
Py_GetArgcArgv (*C function*), 283
Py_GetBuildInfo (*C function*), 236
Py_GetCompiler (*C function*), 236
Py_GetConstant (*C function*), 105
Py_GetConstantBorrowed (*C function*), 106
Py_GetCopyright (*C function*), 235
Py_GETENV (*C macro*), 5
Py_GetExecPrefix (*C function*), 12, 234
Py_GetPath (*C function*), 12, 235
Py_GetPath(), 234
Py_GetPlatform (*C function*), 235
Py_GetPrefix (*C function*), 12, 234
Py_GetProgramFullPath (*C function*), 12, 235
Py_GetProgramName (*C function*), 234
Py_GetPythonHome (*C function*), 237
Py_GetVersion (*C function*), 235
Py_GT (*C macro*), 334
Py_hash_t (*C type*), 98
Py_HashBuffer (*C function*), 99
Py_HashPointer (*C function*), 98
Py_HashRandomizationFlag (*C var*), 229
Py_IgnoreEnvironmentFlag (*C var*), 229
Py_INCREF (*C function*), 7, 49
Py_IncRef (*C function*), 51
Py_Initialize (*C function*), 12, 231, 247
Py_Initialize(), 234
Py_InitializeEx (*C function*), 231
Py_InitializeFromConfig (*C function*), 231
Py_InitializeFromInitConfig (*C function*), 260
Py_InspectFlag (*C var*), 229

Py_InteractiveFlag (*C var*), 229
Py_Is (*C function*), 304
Py_IS_TYPE (*C function*), 304
Py_IsFalse (*C function*), 304
Py_IsFinalizing (*C function*), 232
Py_IsInitialized (*C function*), 12, 232
Py_IsNone (*C function*), 304
Py_IsolatedFlag (*C var*), 229
Py_IsTrue (*C function*), 304
Py_LE (*C macro*), 334
Py_LeaveRecursiveCall (*C function*), 65
Py_LegacyWindowsFSEncodingFlag (*C var*), 230
Py_LegacyWindowsStdioFlag (*C var*), 230
Py_LIMITED_API (*C macro*), 16
Py_LT (*C macro*), 334
Py_Main (*C function*), 232
PY_MAJOR_VERSION (*C macro*), 357
Py_MARSHAL_VERSION (*C macro*), 86
Py_MAX (*C macro*), 5
Py_MEMBER_SIZE (*C macro*), 5
PY_MICRO_VERSION (*C macro*), 357
Py_MIN (*C macro*), 5
PY_MINOR_VERSION (*C macro*), 357
Py_mod_create (*C macro*), 205
Py_mod_exec (*C macro*), 206
Py_MOD_GIL_NOT_USED (*C macro*), 206
Py_MOD_GIL_USED (*C macro*), 206
Py_mod_gil (*C macro*), 206
Py_MOD_MULTIPLE_INTERPRETERS_NOT_SUPPORTED (*C macro*), 206
Py_MOD_MULTIPLE_INTERPRETERS_SUPPORTED (*C macro*), 206
Py_mod_multiple_interpreters (*C macro*), 206
Py_MOD_PER_INTERPRETER_GIL_SUPPORTED (*C macro*), 206
PY_MONITORING_EVENT_BRANCH_LEFT (*C macro*), 364
PY_MONITORING_EVENT_BRANCH_RIGHT (*C macro*), 364
PY_MONITORING_EVENT_C_RAISE (*C macro*), 364
PY_MONITORING_EVENT_C_RETURN (*C macro*), 364
PY_MONITORING_EVENT_CALL (*C macro*), 364
PY_MONITORING_EVENT_EXCEPTION_HANDLED (*C macro*), 364
PY_MONITORING_EVENT_INSTRUCTION (*C macro*), 364
PY_MONITORING_EVENT_JUMP (*C macro*), 364
PY_MONITORING_EVENT_LINE (*C macro*), 364
PY_MONITORING_EVENT_PY_RESUME (*C macro*), 364
PY_MONITORING_EVENT_PY_RETURN (*C macro*), 364
PY_MONITORING_EVENT_PY_START (*C macro*), 364
PY_MONITORING_EVENT_PY_THROW (*C macro*), 364
PY_MONITORING_EVENT_PY_UNWIND (*C macro*), 364
PY_MONITORING_EVENT_PY_YIELD (*C macro*), 364
PY_MONITORING_EVENT_RAISE (*C macro*), 364
PY_MONITORING_EVENT_RERAISE (*C macro*), 364
PY_MONITORING_EVENT_STOP_ITERATION (*C macro*), 364
PY_MONITORING_IS_INSTRUMENTED_EVENT (*C function*), 365
Py_NE (*C macro*), 334
Py_NewInterpreter (*C function*), 247
Py_NewInterpreterFromConfig (*C function*), 246
Py_NewRef (*C function*), 50
Py_NO_INLINE (*C macro*), 5
Py_None (*C var*), 142
Py_NoSiteFlag (*C var*), 230
Py_NotImplemented (*C var*), 106
Py_NoUserSiteDirectory (*C var*), 230
Py_OpenCodeHookFunction (*C type*), 202
Py_OptimizeFlag (*C var*), 230
Py_PACK_FULL_VERSION (*C function*), 358
Py_PACK_VERSION (*C function*), 358
Py_PreInitialize (*C function*), 267
Py_PreInitializeFromArgs (*C function*), 267
Py_PreInitializeFromBytesArgs (*C function*), 267
Py_PRINT_RAW (*C macro*), 106, 203
Py_QuietFlag (*C var*), 231
Py_READONLY (*C macro*), 309
Py_REFCNT (*C function*), 49
Py_RELATIVE_OFFSET (*C macro*), 309
PY_RELEASE_LEVEL (*C macro*), 357
PY_RELEASE_SERIAL (*C macro*), 357
Py_ReprEnter (*C function*), 65
Py_ReprLeave (*C function*), 65
Py_RETURN_FALSE (*C macro*), 152
Py_RETURN_NONE (*C macro*), 142
Py_RETURN_NOTIMPLEMENTED (*C macro*), 106
Py_RETURN_RICHCOMPARE (*C macro*), 334
Py_RETURN_TRUE (*C macro*), 152
Py_RunMain (*C function*), 233
Py_SET_REFCNT (*C function*), 49
Py_SET_SIZE (*C function*), 305
Py_SET_TYPE (*C function*), 305
Py_SetProgramName (*C function*), 234
Py_SetPythonHome (*C function*), 237
Py_SETREF (*C macro*), 51
Py_SIZE (*C function*), 305
Py_single_input (*C var*), 46
PY_SSIZE_T_MAX (*C macro*), 145
Py_ssize_t (*C type*), 10
Py_STRINGIFY (*C macro*), 5
Py_T_BOOL (*C macro*), 311
Py_T_BYTE (*C macro*), 311
Py_T_CHAR (*C macro*), 311
Py_T_DOUBLE (*C macro*), 311
Py_T_FLOAT (*C macro*), 311
Py_T_INT (*C macro*), 311
Py_T_LONG (*C macro*), 311
Py_T_LONGLONG (*C macro*), 311
Py_T_OBJECT_EX (*C macro*), 311
Py_T_PYSSIZET (*C macro*), 311
Py_T_SHORT (*C macro*), 311
Py_T_STRING (*C macro*), 311
Py_T_STRING_INPLACE (*C macro*), 311

Py_T_UBYTE (*C macro*), 311
Py_T_UINT (*C macro*), 311
Py_T_ULONG (*C macro*), 311
Py_T_ULONGLONG (*C macro*), 311
Py_T_USHORT (*C macro*), 311
Py_tp_token (*C macro*), 142
Py_TP_USE_SPEC (*C macro*), 142
Py_TPFLAGS_BASE_EXC_SUBCLASS (*C macro*), 328
Py_TPFLAGS_BASETYPE (*C macro*), 326
Py_TPFLAGS_BYTES_SUBCLASS (*C macro*), 328
Py_TPFLAGS_DEFAULT (*C macro*), 327
Py_TPFLAGS_DICT_SUBCLASS (*C macro*), 328
Py_TPFLAGS_DISALLOW_INSTANTIATION (*C macro*), 328
Py_TPFLAGS_HAVE_FINALIZE (*C macro*), 328
Py_TPFLAGS_HAVE_GC (*C macro*), 326
Py_TPFLAGS_HAVE_VECTORCALL (*C macro*), 328
Py_TPFLAGS_HEAPTYPE (*C macro*), 326
Py_TPFLAGS_IMMUTABLETYPE (*C macro*), 328
Py_TPFLAGS_ITEMS_AT_END (*C macro*), 327
Py_TPFLAGS_LIST_SUBCLASS (*C macro*), 328
Py_TPFLAGS_LONG_SUBCLASS (*C macro*), 328
Py_TPFLAGS_MANAGED_DICT (*C macro*), 327
Py_TPFLAGS_MANAGED_WEAKREF (*C macro*), 327
Py_TPFLAGS_MAPPING (*C macro*), 329
Py_TPFLAGS_METHOD_DESCRIPTOR (*C macro*), 327
Py_TPFLAGS_READY (*C macro*), 326
Py_TPFLAGS_READYING (*C macro*), 326
Py_TPFLAGS_SEQUENCE (*C macro*), 329
Py_TPFLAGS_TUPLE_SUBCLASS (*C macro*), 328
Py_TPFLAGS_TYPE_SUBCLASS (*C macro*), 328
Py_TPFLAGS_UNICODE_SUBCLASS (*C macro*), 328
Py_TPFLAGS_VALID_VERSION_TAG (*C macro*), 329
Py_tracefunc (*C type*), 249
Py_True (*C var*), 152
Py_tss_NEEDS_INIT (*C macro*), 252
Py_tss_t (*C type*), 252
Py_TYPE (*C function*), 304
Py_UCS1 (*C type*), 160
Py_UCS2 (*C type*), 160
Py_UCS4 (*C type*), 160
Py_uhash_t (*C type*), 98
Py_UNBLOCK_THREADS (*C macro*), 242
Py_UnbufferedStdioFlag (*C var*), 231
Py_UNICODE (*C type*), 180
Py_UNICODE_IS_HIGH_SURROGATE (*C function*), 162
Py_UNICODE_IS_LOW_SURROGATE (*C function*), 162
Py_UNICODE_IS_SURROGATE (*C function*), 162
Py_UNICODE_ISALNUM (*C function*), 162
Py_UNICODE_ISALPHA (*C function*), 162
Py_UNICODE_ISDECIMAL (*C function*), 162
Py_UNICODE_ISDIGIT (*C function*), 162
Py_UNICODE_ISLINEBREAK (*C function*), 161
Py_UNICODE_ISLOWER (*C function*), 161
Py_UNICODE_ISNUMERIC (*C function*), 162
Py_UNICODE_ISPRINTABLE (*C function*), 162
Py_UNICODE_ISSPACE (*C function*), 161
Py_UNICODE_ISTITLE (*C function*), 161
Py_UNICODE_ISUPPER (*C function*), 161
Py_UNICODE_JOIN_SURROGATES (*C function*), 162
Py_UNICODE_REPLACEMENT_CHARACTER (*C macro*), 171
Py_UNICODE_TODECIMAL (*C function*), 162
Py_UNICODE_TODIGIT (*C function*), 162
Py_UNICODE_TOLOWER (*C function*), 162
Py_UNICODE_TONUMERIC (*C function*), 162
Py_UNICODE_TOTITLE (*C function*), 162
Py_UNICODE_TOUPPER (*C function*), 162
Py_UNREACHABLE (*C macro*), 5
Py_UNUSED (*C macro*), 6
Py_VaBuildValue (*C function*), 96
PY_VECTORCALL_ARGUMENTS_OFFSET (*C macro*), 116
Py_VerboseFlag (*C var*), 231
PY_VERSION_HEX (*C macro*), 357
Py_Version (*C var*), 357
Py_VISIT (*C macro*), 355
Py_XDECREF (*C function*), 11, 50
Py_XINCREF (*C function*), 50
Py_XNewRef (*C function*), 50
Py_XSETREF (*C macro*), 51
PyAIter_Check (*C function*), 126
PyAnySet_Check (*C function*), 191
PyAnySet_CheckExact (*C function*), 191
PyArg_Parse (*C function*), 92
PyArg_ParseTuple (*C function*), 92
PyArg_ParseTupleAndKeywords (*C function*), 92
PyArg_UnpackTuple (*C function*), 93
PyArg_ValidateKeywordArguments (*C function*), 92
PyArg_VaParse (*C function*), 92
PyArg_VaParseTupleAndKeywords (*C function*), 92
PyASCIIObject (*C type*), 160
PyAsyncMethods (*C type*), 348
PyAsyncMethods.am_aiter (*C member*), 348
PyAsyncMethods.am_anext (*C member*), 348
PyAsyncMethods.am_await (*C member*), 348
PyAsyncMethods.am_send (*C member*), 348
PyBaseObject_Type (*C var*), 304
PyBool_Check (*C function*), 152
PyBool_FromLong (*C function*), 152
PyBool_Type (*C var*), 152
PyBUF_ANY_CONTIGUOUS (*C macro*), 130
PyBUF_C_CONTIGUOUS (*C macro*), 130
PyBUF_CONTIG (*C macro*), 131
PyBUF_CONTIG_RO (*C macro*), 131
PyBUF_F_CONTIGUOUS (*C macro*), 130
PyBUF_FORMAT (*C macro*), 129
PyBUF_FULL (*C macro*), 131
PyBUF_FULL_RO (*C macro*), 131
PyBUF_INDIRECT (*C macro*), 130
PyBUF_MAX_NDIM (*C macro*), 129
PyBUF_ND (*C macro*), 130
PyBUF_READ (*C macro*), 213
PyBUF_RECORDS (*C macro*), 131
PyBUF_RECORDS_RO (*C macro*), 131

PyBUF_SIMPLE (*C macro*), 130
PyBUF_STRIDED (*C macro*), 131
PyBUF_STRIDED_RO (*C macro*), 131
PyBUF_STRIDES (*C macro*), 130
PyBUF_WRITABLE (*C macro*), 129
PyBUF_WRITE (*C macro*), 213
PyBuffer_FillContiguousStrides (*C function*), 133
PyBuffer_FillInfo (*C function*), 133
PyBuffer_FromContiguous (*C function*), 133
PyBuffer_GetPointer (*C function*), 133
PyBuffer_IsContiguous (*C function*), 133
PyBuffer_Release (*C function*), 132
PyBuffer_SizeFromFormat (*C function*), 133
PyBuffer_ToContiguous (*C function*), 133
PyBufferProcs (*C type*), 127, 347
PyBufferProcs.bf_getbuffer (*C member*), 347
PyBufferProcs.bf_releasebuffer (*C member*), 347
PyByteArray_AS_STRING (*C function*), 159
PyByteArray_AsString (*C function*), 159
PyByteArray_Check (*C function*), 158
PyByteArray_CheckExact (*C function*), 158
PyByteArray_Concat (*C function*), 159
PyByteArray_FromObject (*C function*), 158
PyByteArray_FromStringAndSize (*C function*), 158
PyByteArray_GET_SIZE (*C function*), 159
PyByteArray_Resize (*C function*), 159
PyByteArray_Size (*C function*), 159
PyByteArray_Type (*C var*), 158
PyByteArrayObject (*C type*), 158
PyBytes_AS_STRING (*C function*), 157
PyBytes_AsString (*C function*), 157
PyBytes_AsStringAndSize (*C function*), 157
PyBytes_Check (*C function*), 156
PyBytes_CheckExact (*C function*), 156
PyBytes_Concat (*C function*), 158
PyBytes_ConcatAndDel (*C function*), 158
PyBytes_FromFormat (*C function*), 156
PyBytes_FromFormatV (*C function*), 157
PyBytes_FromObject (*C function*), 157
PyBytes_FromString (*C function*), 156
PyBytes_FromStringAndSize (*C function*), 156
PyBytes_GET_SIZE (*C function*), 157
PyBytes_Join (*C function*), 158
PyBytes_Size (*C function*), 157
PyBytes_Type (*C var*), 156
PyBytesObject (*C type*), 156
PyCallable_Check (*C function*), 119
PyCallIter_Check (*C function*), 211
PyCallIter_New (*C function*), 211
PyCallIter_Type (*C var*), 211
PyCapsule (*C type*), 215
PyCapsule_CheckExact (*C function*), 216
PyCapsule_Destructor (*C type*), 215
PyCapsule_GetContext (*C function*), 216
PyCapsule_GetDestructor (*C function*), 216
PyCapsule_GetName (*C function*), 216
PyCapsule_GetPointer (*C function*), 216
PyCapsule_Import (*C function*), 216
PyCapsule_IsValid (*C function*), 217
PyCapsule_New (*C function*), 216
PyCapsule_SetContext (*C function*), 217
PyCapsule_SetDestructor (*C function*), 217
PyCapsule_SetName (*C function*), 217
PyCapsule_SetPointer (*C function*), 217
PyCell_Check (*C function*), 196
PyCell_GET (*C function*), 196
PyCell_Get (*C function*), 196
PyCell_New (*C function*), 196
PyCell_SET (*C function*), 196
PyCell_Set (*C function*), 196
PyCell_Type (*C var*), 196
PyCellObject (*C type*), 196
PyCF_ALLOW_TOP_LEVEL_AWAIT (*C macro*), 46
PyCF_ONLY_AST (*C macro*), 46
PyCF_OPTIMIZED_AST (*C macro*), 46
PyCF_TYPE_COMMENTS (*C macro*), 46
PyCFunction (*C type*), 305
PyCFunction_New (*C function*), 308
PyCFunction_NewEx (*C function*), 308
PyCFunctionFast (*C type*), 305
PyCFunctionFastWithKeywords (*C type*), 306
PyCFunctionWithKeywords (*C type*), 305
PyCMethod (*C type*), 306
PyCMethod_New (*C function*), 308
PyCode_Addr2Line (*C function*), 197
PyCode_Addr2Location (*C function*), 197
PyCode_AddWatcher (*C function*), 198
PyCode_Check (*C function*), 196
PyCode_ClearWatcher (*C function*), 198
PyCode_GetCellvars (*C function*), 198
PyCode_GetCode (*C function*), 198
PyCode_GetFreevars (*C function*), 198
PyCode_GetNumFree (*C function*), 196
PyCode_GetVarnames (*C function*), 198
PyCode_New (*C function*), 197
PyCode_NewEmpty (*C function*), 197
PyCode_NewWithPosOnlyArgs (*C function*), 197
PyCode_Type (*C var*), 196
PyCode_WatchCallback (*C type*), 198
PyCodec_BackslashReplaceErrors (*C function*), 102
PyCodec_Decode (*C function*), 100
PyCodec_Decoder (*C function*), 101
PyCodec_Encode (*C function*), 100
PyCodec_Encoder (*C function*), 101
PyCodec_IgnoreErrors (*C function*), 101
PyCodec_IncrementalDecoder (*C function*), 101
PyCodec_IncrementalEncoder (*C function*), 101
PyCodec_KnownEncoding (*C function*), 100
PyCodec_LookupError (*C function*), 101
PyCodec_NameReplaceErrors (*C function*), 102
PyCodec_Register (*C function*), 100
PyCodec_RegisterError (*C function*), 101

PyCodec_ReplaceErrors (*C function*), 101
PyCodec_StreamReader (*C function*), 101
PyCodec_StreamWriter (*C function*), 101
PyCodec_StrictErrors (*C function*), 101
PyCodec_Unregister (*C function*), 100
PyCodec_XMLCharRefReplaceErrors (*C function*), 102
PyCodeEvent (*C type*), 198
PyCodeObject (*C type*), 196
PyCompactUnicodeObject (*C type*), 160
PyCompilerFlags (*C struct*), 46
PyCompilerFlags.cf_feature_version (*C member*), 46
PyCompilerFlags.cf_flags (*C member*), 46
PyComplex_AsCComplex (*C function*), 156
PyComplex_Check (*C function*), 155
PyComplex_CheckExact (*C function*), 155
PyComplex_FromCComplex (*C function*), 155
PyComplex_FromDoubles (*C function*), 155
PyComplex_ImagAsDouble (*C function*), 156
PyComplex_RealAsDouble (*C function*), 155
PyComplex_Type (*C var*), 155
PyComplexObject (*C type*), 155
PyConfig (*C type*), 268
PyConfig_Clear (*C function*), 269
PyConfig_Get (*C function*), 262
PyConfig_GetInt (*C function*), 262
PyConfig_InitIsolatedConfig (*C function*), 268
PyConfig_InitPythonConfig (*C function*), 268
PyConfig_Names (*C function*), 262
PyConfig._pystats (*C member*), 279
PyConfig_Read (*C function*), 269
PyConfig_Set (*C function*), 262
PyConfig_SetArgv (*C function*), 268
PyConfig_SetBytesArgv (*C function*), 268
PyConfig_SetBytesString (*C function*), 268
PyConfig_SetString (*C function*), 268
PyConfig_SetWideStringList (*C function*), 268
PyConfig.argv (*C member*), 269
PyConfig.base_exec_prefix (*C member*), 270
PyConfig.base_executable (*C member*), 270
PyConfig.base_prefix (*C member*), 270
PyConfig.buffered_stdio (*C member*), 270
PyConfig.bytes_warning (*C member*), 270
PyConfig.check_hash_pycs_mode (*C member*), 271
PyConfig.code_debug_ranges (*C member*), 270
PyConfig.configure_c_stdio (*C member*), 271
PyConfig.cpu_count (*C member*), 274
PyConfig.dev_mode (*C member*), 271
PyConfig.dump_refs (*C member*), 271
PyConfig.dump_refs_file (*C member*), 271
PyConfig.exec_prefix (*C member*), 271
PyConfig.executable (*C member*), 272
PyConfig.faulthandler (*C member*), 272
PyConfig.filesystem_encoding (*C member*), 272
PyConfig.filesystem_errors (*C member*), 272
PyConfig.hash_seed (*C member*), 273
PyConfig.home (*C member*), 273
PyConfig.import_time (*C member*), 273
PyConfig.inspect (*C member*), 273
PyConfig.install_signal_handlers (*C member*), 273
PyConfig.int_max_str_digits (*C member*), 273
PyConfig.interactive (*C member*), 273
PyConfig.isolated (*C member*), 274
PyConfig.legacy_windows_stdio (*C member*), 274
PyConfig.malloc_stats (*C member*), 274
PyConfig.module_search_paths (*C member*), 275
PyConfig.module_search_paths_set (*C member*), 275
PyConfig.optimization_level (*C member*), 275
PyConfig.orig_argv (*C member*), 275
PyConfig.parse_argv (*C member*), 275
PyConfig.parser_debug (*C member*), 275
PyConfig.pathconfig_warnings (*C member*), 276
PyConfig.perf_profiling (*C member*), 278
PyConfig.platlibdir (*C member*), 274
PyConfig.prefix (*C member*), 276
PyConfig.program_name (*C member*), 276
PyConfig.pycache_prefix (*C member*), 276
PyConfig.pythonpath_env (*C member*), 275
PyConfig.quiet (*C member*), 276
PyConfig.run_command (*C member*), 276
PyConfig.run_filename (*C member*), 276
PyConfig.run_module (*C member*), 277
PyConfig.run_presite (*C member*), 277
PyConfig.safe_path (*C member*), 269
PyConfig.show_ref_count (*C member*), 277
PyConfig.site_import (*C member*), 277
PyConfig.skip_source_first_line (*C member*), 277
PyConfig.stdio_encoding (*C member*), 277
PyConfig.stdio_errors (*C member*), 277
PyConfig.stdlib_dir (*C member*), 278
PyConfig.tracemalloc (*C member*), 278
PyConfig.use_environment (*C member*), 278
PyConfig.use_frozen_modules (*C member*), 272
PyConfig.use_hash_seed (*C member*), 273
PyConfig.use_system_logger (*C member*), 278
PyConfig.user_site_directory (*C member*), 278
PyConfig.verbose (*C member*), 279
PyConfig.warn_default_encoding (*C member*), 270
PyConfig.warnoptions (*C member*), 279
PyConfig.write_bytecode (*C member*), 279
PyConfig.xoptions (*C member*), 279
PyContext (*C type*), 221
PyContext_AddWatcher (*C function*), 221
PyContext_CheckExact (*C function*), 221
PyContext_ClearWatcher (*C function*), 221
PyContext_Copy (*C function*), 221
PyContext_CopyCurrent (*C function*), 221
PyContext_Enter (*C function*), 221
PyContext_Exit (*C function*), 221

PyContext_New (*C function*), 221
PyContext_Type (*C var*), 221
PyContext_WatchCallback (*C type*), 222
PyContextEvent (*C type*), 222
PyContextToken (*C type*), 221
PyContextToken_CheckExact (*C function*), 221
PyContextToken_Type (*C var*), 221
PyContextVar (*C type*), 221
PyContextVar_CheckExact (*C function*), 221
PyContextVar_Get (*C function*), 222
PyContextVar_New (*C function*), 222
PyContextVar_Reset (*C function*), 222
PyContextVar_Set (*C function*), 222
PyContextVar_Type (*C var*), 221
PyCoro_CheckExact (*C function*), 220
PyCoro_New (*C function*), 220
PyCoro_Type (*C var*), 220
PyCoroObject (*C type*), 220
PyDate_Check (*C function*), 223
PyDate_CheckExact (*C function*), 223
PyDate_FromDate (*C function*), 224
PyDate_FromTimestamp (*C function*), 226
PyDateTime_Check (*C function*), 223
PyDateTime_CheckExact (*C function*), 223
PyDateTime_Date (*C type*), 222
PyDateTime_DATE_GET_FOLD (*C function*), 225
PyDateTime_DATE_GET_HOUR (*C function*), 225
PyDateTime_DATE_GET_MICROSECOND (*C function*), 225
PyDateTime_DATE_GET_MINUTE (*C function*), 225
PyDateTime_DATE_GET_SECOND (*C function*), 225
PyDateTime_DATE_GET_TZINFO (*C function*), 225
PyDateTime_DateTime (*C type*), 223
PyDateTime_DateTimeType (*C var*), 223
PyDateTime_DateType (*C var*), 223
PyDateTime_Delta (*C type*), 223
PyDateTime_DELTA_GET_DAYS (*C function*), 225
PyDateTime_DELTA_GET_MICROSECONDS (*C function*), 226
PyDateTime_DELTA_GET_SECONDS (*C function*), 225
PyDateTime_DeltaType (*C var*), 223
PyDateTime_FromDateAndTime (*C function*), 224
PyDateTime_FromDateAndTimeAndFold (*C function*), 224
PyDateTime_FromTimestamp (*C function*), 226
PyDateTime_GET_DAY (*C function*), 225
PyDateTime_GET_MONTH (*C function*), 224
PyDateTime_GET_YEAR (*C function*), 224
PyDateTime_TIME_GET_FOLD (*C function*), 225
PyDateTime_TIME_GET_HOUR (*C function*), 225
PyDateTime_TIME_GET_MICROSECOND (*C function*), 225
PyDateTime_TIME_GET_MINUTE (*C function*), 225
PyDateTime_TIME_GET_SECOND (*C function*), 225
PyDateTime_TIME_GET_TZINFO (*C function*), 225
PyDateTime_Time (*C type*), 223
PyDateTime_TimeType (*C var*), 223
PyDateTime_TimeZone_UTC (*C var*), 223
PyDateTime_TZInfoType (*C var*), 223
PyDelta_Check (*C function*), 223
PyDelta_CheckExact (*C function*), 224
PyDelta_FromDSU (*C function*), 224
PyDescr_IsData (*C function*), 211
PyDescr_NewClassMethod (*C function*), 211
PyDescr_NewGetSet (*C function*), 211
PyDescr_NewMember (*C function*), 211
PyDescr_NewMethod (*C function*), 211
PyDescr_NewWrapper (*C function*), 211
PyDict_AddWatcher (*C function*), 190
PyDict_Check (*C function*), 186
PyDict_CheckExact (*C function*), 186
PyDict_Clear (*C function*), 186
PyDict_ClearWatcher (*C function*), 190
PyDict_Contains (*C function*), 186
PyDict_ContainsString (*C function*), 186
PyDict_Copy (*C function*), 186
PyDict_DelItem (*C function*), 186
PyDict_DelItemString (*C function*), 186
PyDict_GetItem (*C function*), 187
PyDict_GetItemRef (*C function*), 187
PyDict_GetItemString (*C function*), 187
PyDict_GetItemStringRef (*C function*), 187
PyDict_GetItemWithError (*C function*), 187
PyDict_Items (*C function*), 188
PyDict_Keys (*C function*), 188
PyDict_Merge (*C function*), 189
PyDict_MergeFromSeq2 (*C function*), 189
PyDict_New (*C function*), 186
PyDict_Next (*C function*), 188
PyDict_Pop (*C function*), 188
PyDict_PopString (*C function*), 188
PyDict_SetDefault (*C function*), 187
PyDict_SetDefaultRef (*C function*), 187
PyDict_SetItem (*C function*), 186
PyDict_SetItemString (*C function*), 186
PyDict_Size (*C function*), 188
PyDict_Type (*C var*), 186
PyDict_Unwatch (*C function*), 190
PyDict_Update (*C function*), 189
PyDict_Values (*C function*), 188
PyDict_Watch (*C function*), 190
PyDict_WatchCallback (*C type*), 190
PyDict_WatchEvent (*C type*), 190
PyDictObject (*C type*), 186
PyDictProxy_New (*C function*), 186
PyDoc_STR (*C macro*), 6
PyDoc_STRVAR (*C macro*), 6
PyEllipsis_Type (*C var*), 213
PyErr_BadArgument (*C function*), 55
PyErr_BadInternalCall (*C function*), 56
PyErr_CheckSignals (*C function*), 61
PyErr_Clear (*C function*), 10, 11, 53
PyErr_DisplayException (*C function*), 54
PyErr_ExceptionMatches (*C function*), 11, 58
PyErr_Fetch (*C function*), 58
PyErr_Format (*C function*), 54

PyErr_FormatUnraisable (*C function*), 54
PyErr_FormatV (*C function*), 54
PyErr_GetExcInfo (*C function*), 60
PyErr_GetHandledException (*C function*), 59
PyErr_GetRaisedException (*C function*), 58
PyErr_GivenExceptionMatches (*C function*), 58
PyErr_NewException (*C function*), 62
PyErr_NewExceptionWithDoc (*C function*), 62
PyErr_NoMemory (*C function*), 55
PyErr_NormalizeException (*C function*), 59
PyErr_Occurred (*C function*), 10, 57
PyErr_Print (*C function*), 54
PyErr_PrintEx (*C function*), 53
PyErr_ResourceWarning (*C function*), 57
PyErr_Restore (*C function*), 59
PyErr_SetExcFromWindowsErr (*C function*), 55
PyErr_SetExcFromWindowsErrWithFilename (*C function*), 56
PyErr_SetExcFromWindowsErrWithFilenameObject (*C function*), 56
PyErr_SetExcFromWindowsErrWithFilenameObjects (*C function*), 56
PyErr_SetExcInfo (*C function*), 60
PyErr_SetFromErrno (*C function*), 55
PyErr_SetFromErrnoWithFilename (*C function*), 55
PyErr_SetFromErrnoWithFilenameObject (*C function*), 55
PyErr_SetFromErrnoWithFilenameObjects (*C function*), 55
PyErr_SetFromWindowsErr (*C function*), 55
PyErr_SetFromWindowsErrWithFilename (*C function*), 56
PyErr_SetHandledException (*C function*), 60
PyErr_SetImportError (*C function*), 56
PyErr_SetImportErrorSubclass (*C function*), 56
PyErr_SetInterrupt (*C function*), 61
PyErr_SetInterruptEx (*C function*), 61
PyErr_SetNone (*C function*), 55
PyErr_SetObject (*C function*), 54
PyErr_SetRaisedException (*C function*), 58
PyErr_SetString (*C function*), 10, 54
PyErr_SyntaxLocation (*C function*), 56
PyErr_SyntaxLocationEx (*C function*), 56
PyErr_SyntaxLocationObject (*C function*), 56
PyErr_WarnEx (*C function*), 57
PyErr_WarnExplicit (*C function*), 57
PyErr_WarnExplicitObject (*C function*), 57
PyErr_WarnFormat (*C function*), 57
PyErr_WriteUnraisable (*C function*), 54
PyEval_AcquireThread (*C function*), 245
PyEval_AcquireThread(), 240
PyEval_EvalCode (*C function*), 45
PyEval_EvalCodeEx (*C function*), 46
PyEval_EvalFrame (*C function*), 46
PyEval_EvalFrameEx (*C function*), 46
PyEval_GetBuiltins (*C function*), 99
PyEval_GetFrame (*C function*), 99
PyEval_GetFrameBuiltins (*C function*), 100
PyEval_GetFrameGlobals (*C function*), 100
PyEval_GetFrameLocals (*C function*), 100
PyEval_GetFuncDesc (*C function*), 100
PyEval_GetFuncName (*C function*), 100
PyEval_GetGlobals (*C function*), 99
PyEval_GetLocals (*C function*), 99
PyEval_InitThreads (*C function*), 240
PyEval_InitThreads(), 231
PyEval_MergeCompilerFlags (*C function*), 46
PyEval_ReleaseThread (*C function*), 245
PyEval_ReleaseThread(), 240
PyEval_RestoreThread (*C function*), 238, 240
PyEval_RestoreThread(), 240
PyEval_SaveThread (*C function*), 238, 240
PyEval_SaveThread(), 240
PyEval_SetProfile (*C function*), 250
PyEval_SetProfileAllThreads (*C function*), 250
PyEval_SetTrace (*C function*), 250
PyEval_SetTraceAllThreads (*C function*), 250
PyExc_ArithmeticError (*C var*), 65
PyExc_AssertionError (*C var*), 65
PyExc_AttributeError (*C var*), 66
PyExc_BaseException (*C var*), 65
PyExc_BaseExceptionGroup (*C var*), 65
PyExc_BlockingIOError (*C var*), 66
PyExc_BrokenPipeError (*C var*), 66
PyExc_BufferError (*C var*), 66
PyExc_BytesWarning (*C var*), 71
PyExc_ChildProcessError (*C var*), 66
PyExc_ConnectionAbortedError (*C var*), 66
PyExc_ConnectionError (*C var*), 66
PyExc_ConnectionRefusedError (*C var*), 66
PyExc_ConnectionResetError (*C var*), 66
PyExc_DeprecationWarning (*C var*), 71
PyExc_EncodingWarning (*C var*), 71
PyExc_EnvironmentError (*C var*), 70
PyExc_EOFError (*C var*), 66
PyExc_Exception (*C var*), 65
PyExc_FileExistsError (*C var*), 66
PyExc_FileNotFoundError (*C var*), 66
PyExc_FloatingPointError (*C var*), 66
PyExc_FutureWarning (*C var*), 71
PyExc_GeneratorExit (*C var*), 67
PyExc_ImportError (*C var*), 67
PyExc_ImportWarning (*C var*), 71
PyExc_IndentationError (*C var*), 67
PyExc_IndexError (*C var*), 67
PyExc_InterruptedError (*C var*), 67
PyExc_IOError (*C var*), 70
PyExc_IsADirectoryError (*C var*), 67
PyExc_KeyboardInterrupt (*C var*), 67
PyExc_KeyError (*C var*), 67
PyExc_LookupError (*C var*), 67
PyExc_MemoryError (*C var*), 67
PyExc_ModuleNotFoundError (*C var*), 67
PyExc_NameError (*C var*), 67
PyExc_NotADirectoryError (*C var*), 67

PyExc_NotImplementedError (*C var*), 68
PyExc_OSError (*C var*), 68
PyExc_OverflowError (*C var*), 68
PyExc_PendingDeprecationWarning (*C var*), 71
PyExc_PermissionError (*C var*), 68
PyExc_ProcessLookupError (*C var*), 68
PyExc_PythonFinalizationError (*C var*), 68
PyExc_RecursionError (*C var*), 68
PyExc_ReferenceError (*C var*), 68
PyExc_ResourceWarning (*C var*), 71
PyExc_RuntimeError (*C var*), 68
PyExc_RuntimeWarning (*C var*), 71
PyExc_StopAsyncIteration (*C var*), 68
PyExc_StopIteration (*C var*), 68
PyExc_SyntaxError (*C var*), 68
PyExc_SyntaxWarning (*C var*), 71
PyExc_SystemError (*C var*), 68
PyExc_SystemExit (*C var*), 68
PyExc_TabError (*C var*), 69
PyExc_TimeoutError (*C var*), 69
PyExc_TypeError (*C var*), 69
PyExc_UnboundLocalError (*C var*), 69
PyExc_UnicodeDecodeError (*C var*), 69
PyExc_UnicodeEncodeError (*C var*), 69
PyExc_UnicodeError (*C var*), 69
PyExc_UnicodeTranslateError (*C var*), 69
PyExc_UnicodeWarning (*C var*), 71
PyExc_UserWarning (*C var*), 71
PyExc_ValueError (*C var*), 69
PyExc_Warning (*C var*), 71
PyExc_WindowsError (*C var*), 70
PyExc_ZeroDivisionError (*C var*), 69
PyException_GetArgs (*C function*), 63
PyException_GetCause (*C function*), 62
PyException_GetContext (*C function*), 62
PyException_GetTraceback (*C function*), 62
PyException_SetArgs (*C function*), 63
PyException_SetCause (*C function*), 62
PyException_SetContext (*C function*), 62
PyException_SetTraceback (*C function*), 62
PyExceptionClass_Check (*C function*), 62
PyExceptionClass_Name (*C function*), 62
PyFile_FromFd (*C function*), 202
PyFile_GetLine (*C function*), 202
PyFile_SetOpenCodeHook (*C function*), 202
PyFile_WriteObject (*C function*), 202
PyFile_WriteString (*C function*), 203
PyFloat_AS_DOUBLE (*C function*), 153
PyFloat_AsDouble (*C function*), 153
PyFloat_Check (*C function*), 153
PyFloat_CheckExact (*C function*), 153
PyFloat_FromDouble (*C function*), 153
PyFloat_FromString (*C function*), 153
PyFloat_GetInfo (*C function*), 153
PyFloat_GetMax (*C function*), 153
PyFloat_GetMin (*C function*), 153
PyFloat_Pack2 (*C function*), 154
PyFloat_Pack4 (*C function*), 154
PyFloat_Pack8 (*C function*), 154
PyFloat_Type (*C var*), 152
PyFloat_Unpack2 (*C function*), 154
PyFloat_Unpack4 (*C function*), 154
PyFloat_Unpack8 (*C function*), 154
PyFloatObject (*C type*), 152
PyFrame_Check (*C function*), 217
PyFrame_GetBack (*C function*), 217
PyFrame_GetBuiltins (*C function*), 218
PyFrame_GetCode (*C function*), 218
PyFrame_GetGenerator (*C function*), 218
PyFrame_GetGlobals (*C function*), 218
PyFrame_GetLasti (*C function*), 218
PyFrame_GetLineNumber (*C function*), 219
PyFrame_GetLocals (*C function*), 218
PyFrame_GetVar (*C function*), 218
PyFrame_GetVarString (*C function*), 218
PyFrame_Type (*C var*), 217
PyFrameLocalsProxy_Check (*C function*), 219
PyFrameLocalsProxy_Type (*C var*), 219
PyFrameObject (*C type*), 217
PyFrozenSet_Check (*C function*), 191
PyFrozenSet_CheckExact (*C function*), 191
PyFrozenSet_New (*C function*), 191
PyFrozenSet_Type (*C var*), 191
PyFunction_AddWatcher (*C function*), 194
PyFunction_Check (*C function*), 192
PyFunction_ClearWatcher (*C function*), 194
PyFunction_GET_ANNOTATIONS (*C function*), 193
PyFunction_GET_CLOSURE (*C function*), 193
PyFunction_GET_CODE (*C function*), 193
PyFunction_GET_DEFAULTS (*C function*), 193
PyFunction_GET_GLOBALS (*C function*), 193
PyFunction_GET_KW_DEFAULTS (*C function*), 193
PyFunction_GET_MODULE (*C function*), 193
PyFunction_GetAnnotations (*C function*), 193
PyFunction_GetClosure (*C function*), 193
PyFunction_GetCode (*C function*), 193
PyFunction_GetDefaults (*C function*), 193
PyFunction_GetGlobals (*C function*), 193
PyFunction_GetKwDefaults (*C function*), 193
PyFunction_GetModule (*C function*), 193
PyFunction_New (*C function*), 192
PyFunction_NewWithQualName (*C function*), 193
PyFunction_SetAnnotations (*C function*), 193
PyFunction_SetClosure (*C function*), 193
PyFunction_SetDefaults (*C function*), 193
PyFunction_SetVectorcall (*C function*), 193
PyFunction_Type (*C var*), 192
PyFunction_WatchCallback (*C type*), 194
PyFunction_WatchEvent (*C type*), 194
PyFunctionObject (*C type*), 192
PyGC_Collect (*C function*), 356
PyGC_Disable (*C function*), 356
PyGC_Enable (*C function*), 356
PyGC_IsEnabled (*C function*), 356
PyGen_Check (*C function*), 220
PyGen_CheckExact (*C function*), 220

PyGen_New (*C function*), 220
PyGen_NewWithQualName (*C function*), 220
PyGen_Type (*C var*), 220
PyGenObject (*C type*), 220
PyGetSetDef (*C type*), 312
PyGetSetDef.closure (*C member*), 312
PyGetSetDef.doc (*C member*), 312
PyGetSetDef.get (*C member*), 312
PyGetSetDef.name (*C member*), 312
PyGetSetDef.set (*C member*), 312
PyGILState_Check (*C function*), 242
PyGILState_Ensure (*C function*), 241
PyGILState_GetThisThreadState (*C function*), 242
PyGILState_Release (*C function*), 242
PyHASH_BITS (*C macro*), 98
PyHash_FuncDef (*C type*), 98
PyHash_FuncDef.hash (*C member*), 98
PyHash_FuncDef.hash_bits (*C member*), 98
PyHash_FuncDef.name (*C member*), 98
PyHash_FuncDef.seed_bits (*C member*), 98
PyHash_GetFuncDef (*C function*), 98
PyHASH_IMAG (*C macro*), 98
PyHASH_INF (*C macro*), 98
PyHASH_MODULUS (*C macro*), 98
PyHASH_MULTIPLIER (*C macro*), 98
PyImport_AddModule (*C function*), 83
PyImport_AddModuleObject (*C function*), 83
PyImport_AddModuleRef (*C function*), 83
PyImport_AppendInittab (*C function*), 85
PyImport_ExecCodeModule (*C function*), 84
PyImport_ExecCodeModuleEx (*C function*), 84
PyImport_ExecCodeModuleObject (*C function*), 84
PyImport_ExecCodeModuleWithPathnames (*C function*), 84
PyImport_ExtendInittab (*C function*), 86
PyImport_FrozenModules (*C var*), 85
PyImport_GetImporter (*C function*), 85
PyImport_GetMagicNumber (*C function*), 84
PyImport_GetMagicTag (*C function*), 85
PyImport_GetModule (*C function*), 85
PyImport_GetModuleDict (*C function*), 85
PyImport_Import (*C function*), 83
PyImport_ImportFrozenModule (*C function*), 85
PyImport_ImportFrozenModuleObject (*C function*), 85
PyImport_ImportModule (*C function*), 82
PyImport_ImportModuleAttr (*C function*), 86
PyImport_ImportModuleAttrString (*C function*), 86
PyImport_ImportModuleEx (*C function*), 82
PyImport_ImportModuleLevel (*C function*), 83
PyImport_ImportModuleLevelObject (*C function*), 83
PyImport_ImportModuleNoBlock (*C function*), 82
PyImport_ReloadModule (*C function*), 83
PyIndex_Check (*C function*), 122
PyInit_modulename (*C function*), 74
PyInitConfig (*C struct*), 258
PyInitConfig_AddModule (*C function*), 260
PyInitConfig_Create (*C function*), 258
PyInitConfig_Free (*C function*), 258
PyInitConfig_FreeStrList (*C function*), 259
PyInitConfig_GetError (*C function*), 258
PyInitConfig_GetExitCode (*C function*), 258
PyInitConfig_GetInt (*C function*), 259
PyInitConfig_GetStr (*C function*), 259
PyInitConfig_GetStrList (*C function*), 259
PyInitConfig_HasOption (*C function*), 259
PyInitConfig_SetInt (*C function*), 259
PyInitConfig_SetStr (*C function*), 259
PyInitConfig_SetStrList (*C function*), 259
PyInstanceMethod_Check (*C function*), 195
PyInstanceMethod_Function (*C function*), 195
PyInstanceMethod_GET_FUNCTION (*C function*), 195
PyInstanceMethod_New (*C function*), 195
PyInstanceMethod_Type (*C var*), 195
PyInterpreterConfig (*C type*), 246
PyInterpreterConfig_DEFAULT_GIL (*C macro*), 246
PyInterpreterConfig_OWN_GIL (*C macro*), 246
PyInterpreterConfig_SHARED_GIL (*C macro*), 246
PyInterpreterConfig.allow_daemon_threads (*C member*), 246
PyInterpreterConfig.allow_exec (*C member*), 246
PyInterpreterConfig.allow_fork (*C member*), 246
PyInterpreterConfig.allow_threads (*C member*), 246
PyInterpreterConfig.check_multi_interp_extensions (*C member*), 246
PyInterpreterConfig.gil (*C member*), 246
PyInterpreterConfig.use_main_obmalloc (*C member*), 246
PyInterpreterState (*C type*), 240
PyInterpreterState_Clear (*C function*), 243
PyInterpreterState_Delete (*C function*), 243
PyInterpreterState_Get (*C function*), 244
PyInterpreterState_GetDict (*C function*), 244
PyInterpreterState_GetID (*C function*), 244
PyInterpreterState_Head (*C function*), 251
PyInterpreterState_Main (*C function*), 251
PyInterpreterState_New (*C function*), 243
PyInterpreterState_Next (*C function*), 251
PyInterpreterState_ThreadHead (*C function*), 251
PyIter_Check (*C function*), 126
PyIter_Next (*C function*), 126
PyIter_NextItem (*C function*), 126
PyIter_Send (*C function*), 127
PyList_Append (*C function*), 185
PyList_AsTuple (*C function*), 185
PyList_Check (*C function*), 184

PyList_CheckExact (*C function*), 184
PyList_Clear (*C function*), 185
PyList_Extend (*C function*), 185
PyList_GET_ITEM (*C function*), 184
PyList_GET_SIZE (*C function*), 184
PyList_GetItem (*C function*), 9, 184
PyList_GetItemRef (*C function*), 184
PyList_GetSlice (*C function*), 185
PyList_Insert (*C function*), 185
PyList_New (*C function*), 184
PyList_Reverse (*C function*), 185
PyList_SET_ITEM (*C function*), 185
PyList_SetItem (*C function*), 7, 184
PyList_SetSlice (*C function*), 185
PyList_Size (*C function*), 184
PyList_Sort (*C function*), 185
PyList_Type (*C var*), 184
PyListObject (*C type*), 184
PyLong_AS_LONG (*C function*), 144
PyLong_AsDouble (*C function*), 146
PyLong_AsInt (*C function*), 144
PyLong_AsInt32 (*C function*), 146
PyLong_AsInt64 (*C function*), 146
PyLong_AsLong (*C function*), 144
PyLong_AsLongAndOverflow (*C function*), 144
PyLong_AsLongLong (*C function*), 145
PyLong_AsLongLongAndOverflow (*C function*), 145
PyLong_AsNativeBytes (*C function*), 147
PyLong_AsSize_t (*C function*), 145
PyLong_AsSsize_t (*C function*), 145
PyLong_AsUInt32 (*C function*), 146
PyLong_AsUInt64 (*C function*), 146
PyLong_AsUnsignedLong (*C function*), 145
PyLong_AsUnsignedLongLong (*C function*), 145
PyLong_AsUnsignedLongLongMask (*C function*), 146
PyLong_AsUnsignedLongMask (*C function*), 146
PyLong_AsVoidPtr (*C function*), 146
PyLong_Check (*C function*), 142
PyLong_CheckExact (*C function*), 142
PyLong_Export (*C function*), 151
PyLong_FreeExport (*C function*), 151
PyLong_FromDouble (*C function*), 143
PyLong_FromInt32 (*C function*), 143
PyLong_FromInt64 (*C function*), 143
PyLong_FromLong (*C function*), 143
PyLong_FromLongLong (*C function*), 143
PyLong_FromNativeBytes (*C function*), 144
PyLong_FromSize_t (*C function*), 143
PyLong_FromSsize_t (*C function*), 143
PyLong_FromString (*C function*), 143
PyLong_FromUInt32 (*C function*), 143
PyLong_FromUInt64 (*C function*), 143
PyLong_FromUnicodeObject (*C function*), 144
PyLong_FromUnsignedLong (*C function*), 143
PyLong_FromUnsignedLongLong (*C function*), 143
PyLong_FromUnsignedNativeBytes (*C function*), 144
PyLong_FromVoidPtr (*C function*), 144
PyLong_GetInfo (*C function*), 149
PyLong_GetNativeLayout (*C function*), 150
PyLong_GetSign (*C function*), 149
PyLong_IsNegative (*C function*), 149
PyLong_IsPositive (*C function*), 149
PyLong_IsZero (*C function*), 149
PyLong_Type (*C var*), 142
PyLongExport (*C struct*), 151
PyLongExport.digits (*C member*), 151
PyLongExport.ndigits (*C member*), 151
PyLongExport.negative (*C member*), 151
PyLongExport.value (*C member*), 151
PyLongLayout (*C struct*), 150
PyLongLayout.bits_per_digit (*C member*), 150
PyLongLayout.digit_endianness (*C member*), 150
PyLongLayout.digit_size (*C member*), 150
PyLongLayout.digits_order (*C member*), 150
PyLongObject (*C type*), 142
PyLongWriter (*C struct*), 151
PyLongWriter_Create (*C function*), 151
PyLongWriter_Discard (*C function*), 152
PyLongWriter_Finish (*C function*), 152
PyMapping_Check (*C function*), 125
PyMapping_DelItem (*C function*), 125
PyMapping_DelItemString (*C function*), 125
PyMapping_GetItemString (*C function*), 125
PyMapping_GetOptionalItem (*C function*), 125
PyMapping_GetOptionalItemString (*C function*), 125
PyMapping_HasKey (*C function*), 125
PyMapping_HasKeyString (*C function*), 126
PyMapping_HasKeyStringWithError (*C function*), 125
PyMapping_HasKeyWithError (*C function*), 125
PyMapping_Items (*C function*), 126
PyMapping_Keys (*C function*), 126
PyMapping_Length (*C function*), 125
PyMapping_SetItemString (*C function*), 125
PyMapping_Size (*C function*), 125
PyMapping_Values (*C function*), 126
PyMappingMethods (*C type*), 345
PyMappingMethods.mp_ass_subscript (*C member*), 346
PyMappingMethods.mp_length (*C member*), 345
PyMappingMethods.mp_subscript (*C member*), 345
PyMarshal_ReadLastObjectFromFile (*C function*), 87
PyMarshal_ReadLongFromFile (*C function*), 86
PyMarshal_ReadObjectFromFile (*C function*), 87
PyMarshal_ReadObjectFromString (*C function*), 87
PyMarshal_ReadShortFromFile (*C function*), 87
PyMarshal_WriteLongToFile (*C function*), 86
PyMarshal_WriteObjectToFile (*C function*), 86
PyMarshal_WriteObjectToString (*C function*), 86

PyMem_Calloc (*C function*), 287
PyMem_Del (*C function*), 288
PYMEM_DOMAIN_MEM (*C macro*), 291
PYMEM_DOMAIN_OBJ (*C macro*), 291
PYMEM_DOMAIN_RAW (*C macro*), 291
PyMem_Free (*C function*), 288
PyMem_GetAllocator (*C function*), 291
PyMem_Malloc (*C function*), 287
PyMem_New (*C macro*), 288
PyMem_RawCalloc (*C function*), 287
PyMem_RawFree (*C function*), 287
PyMem_RawMalloc (*C function*), 286
PyMem_RawRealloc (*C function*), 287
PyMem_Realloc (*C function*), 288
PyMem_Resize (*C macro*), 288
PyMem_SetAllocator (*C function*), 291
PyMem_SetupDebugHooks (*C function*), 292
PyMemAllocatorDomain (*C type*), 291
PyMemAllocatorEx (*C type*), 290
PyMember_GetOne (*C function*), 309
PyMember_SetOne (*C function*), 309
PyMemberDef (*C type*), 308
PyMemberDef.doc (*C member*), 308
PyMemberDef.flags (*C member*), 308
PyMemberDef.name (*C member*), 308
PyMemberDef.offset (*C member*), 308
PyMemberDef.type (*C member*), 308
PyMemoryView_Check (*C function*), 214
PyMemoryView_FromBuffer (*C function*), 213
PyMemoryView_FromMemory (*C function*), 213
PyMemoryView_FromObject (*C function*), 213
PyMemoryView_GET_BASE (*C function*), 214
PyMemoryView_GET_BUFFER (*C function*), 214
PyMemoryView_GetContiguous (*C function*), 213
PyMethod_Check (*C function*), 195
PyMethod_Function (*C function*), 195
PyMethod_GET_FUNCTION (*C function*), 195
PyMethod_GET_SELF (*C function*), 195
PyMethod_New (*C function*), 195
PyMethod_Self (*C function*), 195
PyMethod_Type (*C var*), 195
PyMethodDef (*C type*), 306
PyMethodDef.ml_doc (*C member*), 306
PyMethodDef.ml_flags (*C member*), 306
PyMethodDef.ml_meth (*C member*), 306
PyMethodDef.ml_name (*C member*), 306
PyMODINIT_FUNC (*C macro*), 74
PyModule_Add (*C function*), 208
PyModule_AddFunctions (*C function*), 209
PyModule_AddIntConstant (*C function*), 209
PyModule_AddIntMacro (*C macro*), 209
PyModule_AddObject (*C function*), 209
PyModule_AddObjectRef (*C function*), 208
PyModule_AddStringConstant (*C function*), 209
PyModule_AddStringMacro (*C macro*), 209
PyModule_AddType (*C function*), 209
PyModule_Check (*C function*), 203
PyModule_CheckExact (*C function*), 203
PyModule_Create (*C function*), 207
PyModule_Create2 (*C function*), 207
PyModule_ExecDef (*C function*), 207
PyModule_FromDefAndSpec (*C function*), 207
PyModule_FromDefAndSpec2 (*C function*), 207
PyModule_GetDef (*C function*), 203
PyModule_GetDict (*C function*), 203
PyModule_GetFilename (*C function*), 204
PyModule_GetFilenameObject (*C function*), 203
PyModule_GetName (*C function*), 203
PyModule_GetNameObject (*C function*), 203
PyModule_GetState (*C function*), 203
PyModule_New (*C function*), 203
PyModule_NewObject (*C function*), 203
PyModule_SetDocString (*C function*), 210
PyModule_Type (*C var*), 203
PyModuleDef (*C type*), 204
PyModuleDef_Init (*C function*), 75
PyModuleDef_Slot (*C type*), 205
PyModuleDef_Slot.slot (*C member*), 205
PyModuleDef_Slot.value (*C member*), 205
PyModuleDef.m_base (*C member*), 204
PyModuleDef.m_clear (*C member*), 205
PyModuleDef.m_doc (*C member*), 204
PyModuleDef.m_free (*C member*), 205
PyModuleDef.m_methods (*C member*), 204
PyModuleDef.m_name (*C member*), 204
PyModuleDef.m_size (*C member*), 204
PyModuleDef.m_slots (*C member*), 204
PyModuleDef.m_slots.m_reload (*C member*), 205
PyModuleDef.m_traverse (*C member*), 205
PyMonitoring_EnterScope (*C function*), 362
PyMonitoring_ExitScope (*C function*), 364
PyMonitoring_FireBranchLeftEvent (*C function*), 362
PyMonitoring_FireBranchRightEvent (*C function*), 362
PyMonitoring_FireCallEvent (*C function*), 361
PyMonitoring_FireCRaiseEvent (*C function*), 362
PyMonitoring_FireCReturnEvent (*C function*), 362
PyMonitoring_FireExceptionHandledEvent (*C function*), 362
PyMonitoring_FireJumpEvent (*C function*), 361
PyMonitoring_FireLineEvent (*C function*), 361
PyMonitoring_FirePyResumeEvent (*C function*), 361
PyMonitoring_FirePyReturnEvent (*C function*), 361
PyMonitoring_FirePyStartEvent (*C function*), 361
PyMonitoring_FirePyThrowEvent (*C function*), 362
PyMonitoring_FirePyUnwindEvent (*C function*), 362
PyMonitoring_FirePyYieldEvent (*C function*), 361
PyMonitoring_FireRaiseEvent (*C function*), 362

PyMonitoring_FireReraiseEvent (*C function*), 362
PyMonitoring_FireStopIterationEvent (*C function*), 362
PyMonitoringState (*C type*), 361
PyMutex (*C type*), 254
PyMutex_IsLocked (*C function*), 254
PyMutex_Lock (*C function*), 254
PyMutex_Unlock (*C function*), 254
PyNumber_Absolute (*C function*), 120
PyNumber_Add (*C function*), 120
PyNumber_And (*C function*), 121
PyNumber_AsSsize_t (*C function*), 122
PyNumber_Check (*C function*), 120
PyNumber_Divmod (*C function*), 120
PyNumber_Float (*C function*), 122
PyNumber_FloorDivide (*C function*), 120
PyNumber_Index (*C function*), 122
PyNumber_InPlaceAdd (*C function*), 121
PyNumber_InPlaceAnd (*C function*), 122
PyNumber_InPlaceFloorDivide (*C function*), 121
PyNumber_InPlaceLshift (*C function*), 122
PyNumber_InPlaceMatrixMultiply (*C function*), 121
PyNumber_InPlaceMultiply (*C function*), 121
PyNumber_InPlaceOr (*C function*), 122
PyNumber_InPlacePower (*C function*), 121
PyNumber_InPlaceRemainder (*C function*), 121
PyNumber_InPlaceRshift (*C function*), 122
PyNumber_InPlaceSubtract (*C function*), 121
PyNumber_InPlaceTrueDivide (*C function*), 121
PyNumber_InPlaceXor (*C function*), 122
PyNumber_Invert (*C function*), 120
PyNumber_Long (*C function*), 122
PyNumber_Lshift (*C function*), 121
PyNumber_MatrixMultiply (*C function*), 120
PyNumber_Multiply (*C function*), 120
PyNumber_Negative (*C function*), 120
PyNumber_Or (*C function*), 121
PyNumber_Positive (*C function*), 120
PyNumber_Power (*C function*), 120
PyNumber_Remainder (*C function*), 120
PyNumber_Rshift (*C function*), 121
PyNumber_Subtract (*C function*), 120
PyNumber_ToBase (*C function*), 122
PyNumber_TrueDivide (*C function*), 120
PyNumber_Xor (*C function*), 121
PyNumberMethods (*C type*), 343
PyNumberMethods.nb_absolute (*C member*), 344
PyNumberMethods.nb_add (*C member*), 344
PyNumberMethods.nb_and (*C member*), 345
PyNumberMethods.nb_bool (*C member*), 344
PyNumberMethods.nb_divmod (*C member*), 344
PyNumberMethods.nb_float (*C member*), 345
PyNumberMethods.nb_floor_divide (*C member*), 345
PyNumberMethods.nb_index (*C member*), 345
PyNumberMethods.nb_inplace_add (*C member*), 345
PyNumberMethods.nb_inplace_and (*C member*), 345
PyNumberMethods.nb_inplace_floor_divide (*C member*), 345
PyNumberMethods.nb_inplace_lshift (*C member*), 345
PyNumberMethods.nb_inplace_matrix_multiply (*C member*), 345
PyNumberMethods.nb_inplace_multiply (*C member*), 345
PyNumberMethods.nb_inplace_or (*C member*), 345
PyNumberMethods.nb_inplace_power (*C member*), 345
PyNumberMethods.nb_inplace_remainder (*C member*), 345
PyNumberMethods.nb_inplace_rshift (*C member*), 345
PyNumberMethods.nb_inplace_subtract (*C member*), 345
PyNumberMethods.nb_inplace_true_divide (*C member*), 345
PyNumberMethods.nb_inplace_xor (*C member*), 345
PyNumberMethods.nb_int (*C member*), 345
PyNumberMethods.nb_invert (*C member*), 345
PyNumberMethods.nb_lshift (*C member*), 345
PyNumberMethods.nb_matrix_multiply (*C member*), 345
PyNumberMethods.nb_multiply (*C member*), 344
PyNumberMethods.nb_negative (*C member*), 344
PyNumberMethods.nb_or (*C member*), 345
PyNumberMethods.nb_positive (*C member*), 344
PyNumberMethods.nb_power (*C member*), 344
PyNumberMethods.nb_remainder (*C member*), 344
PyNumberMethods.nb_reserved (*C member*), 345
PyNumberMethods.nb_rshift (*C member*), 345
PyNumberMethods.nb_subtract (*C member*), 344
PyNumberMethods.nb_true_divide (*C member*), 345
PyNumberMethods.nb_xor (*C member*), 345
PyObject (*C type*), 303
PyObject_ASCII (*C function*), 109
PyObject_AsFileDescriptor (*C function*), 202
PyObject_Bytes (*C function*), 110
PyObject_Call (*C function*), 117
PyObject_CallFinalizer (*C function*), 303
PyObject_CallFinalizerFromDealloc (*C function*), 303
PyObject_CallFunction (*C function*), 118
PyObject_CallFunctionObjArgs (*C function*), 118
PyObject_CallMethod (*C function*), 118
PyObject_CallMethodNoArgs (*C function*), 118
PyObject_CallMethodObjArgs (*C function*), 118
PyObject_CallMethodOneArg (*C function*), 119
PyObject_CallNoArgs (*C function*), 117

PyObject_CallObject (*C function*), 118
PyObject_Calloc (*C function*), 289
PyObject_CallOneArg (*C function*), 118
PyObject_CheckBuffer (*C function*), 132
PyObject_ClearManagedDict (*C function*), 112
PyObject_ClearWeakRefs (*C function*), 215
PyObject_CopyData (*C function*), 133
PyObject_Del (*C function*), 299
PyObject_DelAttr (*C function*), 108
PyObject_DelAttrString (*C function*), 108
PyObject_DelItem (*C function*), 111
PyObject_DelItemString (*C function*), 111
PyObject_Dir (*C function*), 111
PyObject_Format (*C function*), 109
PyObject_Free (*C function*), 289
PyObject_GC_Del (*C function*), 354
PyObject_GC_IsFinalized (*C function*), 354
PyObject_GC_IsTracked (*C function*), 354
PyObject_GC_New (*C macro*), 353
PyObject_GC_NewVar (*C macro*), 353
PyObject_GC_Resize (*C macro*), 354
PyObject_GC_Track (*C function*), 354
PyObject_GC_UnTrack (*C function*), 355
PyObject_GenericGetAttr (*C function*), 108
PyObject_GenericGetDict (*C function*), 108
PyObject_GenericHash (*C function*), 99
PyObject_GenericSetAttr (*C function*), 108
PyObject_GenericSetDict (*C function*), 109
PyObject_GetAIter (*C function*), 111
PyObject_GetArenaAllocator (*C function*), 293
PyObject_GetAttr (*C function*), 107
PyObject_GetAttrString (*C function*), 107
PyObject_GetBuffer (*C function*), 132
PyObject_GetItem (*C function*), 111
PyObject_GetItemData (*C function*), 112
PyObject_GetIter (*C function*), 111
PyObject_GetOptionalAttr (*C function*), 107
PyObject_GetOptionalAttrString (*C function*), 108
PyObject_GetTypeData (*C function*), 111
PyObject_HasAttr (*C function*), 107
PyObject_HasAttrString (*C function*), 107
PyObject_HasAttrStringWithError (*C function*), 107
PyObject_HasAttrWithError (*C function*), 107
PyObject_Hash (*C function*), 110
PyObject_HashNotImplemented (*C function*), 110
PyObject_HEAD (*C macro*), 304
PyObject_HEAD_INIT (*C macro*), 305
PyObject_Init (*C function*), 297
PyObject_InitVar (*C function*), 297
PyObject_IS_GC (*C function*), 354
PyObject_IsInstance (*C function*), 110
PyObject_IsSubclass (*C function*), 110
PyObject_IsTrue (*C function*), 110
PyObject_Length (*C function*), 111
PyObject_LengthHint (*C function*), 111
PyObject_Malloc (*C function*), 289
PyObject_New (*C macro*), 297
PyObject_NewVar (*C macro*), 298
PyObject_Not (*C function*), 110
PyObject_Print (*C function*), 107
PyObject_Realloc (*C function*), 289
PyObject_Repr (*C function*), 109
PyObject_RichCompare (*C function*), 109
PyObject_RichCompareBool (*C function*), 109
PyObject_SelfIter (*C function*), 111
PyObject_SetArenaAllocator (*C function*), 293
PyObject_SetAttr (*C function*), 108
PyObject_SetAttrString (*C function*), 108
PyObject_SetItem (*C function*), 111
PyObject_Size (*C function*), 111
PyObject_Str (*C function*), 109
PyObject_Type (*C function*), 110
PyObject_TypeCheck (*C function*), 110
PyObject_VAR_HEAD (*C macro*), 304
PyObject_Vectorcall (*C function*), 119
PyObject_VectorcallDict (*C function*), 119
PyObject_VectorcallMethod (*C function*), 119
PyObject_VisitManagedDict (*C function*), 112
PyObjectArenaAllocator (*C type*), 293
PyObject.ob_refcnt (*C member*), 303
PyObject.ob_type (*C member*), 303
PyOS_AfterFork (*C function*), 78
PyOS_AfterFork_Child (*C function*), 78
PyOS_AfterFork_Parent (*C function*), 77
PyOS_BeforeFork (*C function*), 77
PyOS_CheckStack (*C function*), 78
PyOS_double_to_string (*C function*), 97
PyOS_FSPath (*C function*), 77
PyOS_getsig (*C function*), 78
PyOS_InputHook (*C var*), 44
PyOS_ReadlineFunctionPointer (*C var*), 44
PyOS_setsig (*C function*), 78
PyOS_sighandler_t (*C type*), 78
PyOS_snprintf (*C function*), 96
PyOS_stricmp (*C function*), 97
PyOS_string_to_double (*C function*), 97
PyOS_strnicmp (*C function*), 97
PyOS_strtol (*C function*), 96
PyOS_strtoul (*C function*), 96
PyOS_vsnprintf (*C function*), 96
PyPreConfig (*C type*), 265
PyPreConfig_InitIsolatedConfig (*C function*), 265
PyPreConfig_InitPythonConfig (*C function*), 265
PyPreConfig.allocator (*C member*), 265
PyPreConfig.coerce_c_locale (*C member*), 266
PyPreConfig.coerce_c_locale_warn (*C member*), 266
PyPreConfig.configure_locale (*C member*), 266
PyPreConfig.dev_mode (*C member*), 266
PyPreConfig.isolated (*C member*), 266
PyPreConfig.legacy_windows_fs_encoding (*C member*), 266
PyPreConfig.parse_argv (*C member*), 267

PyPreConfig.use_environment (*C member*), 267
PyPreConfig.utf8_mode (*C member*), 267
PyProperty_Type (*C var*), 211
PyRefTracer (*C type*), 251
PyRefTracer_CREATE (*C var*), 251
PyRefTracer_DESTROY (*C var*), 251
PyRefTracer_GetTracer (*C function*), 251
PyRefTracer_SetTracer (*C function*), 251
PyRun_AnyFile (*C function*), 43
PyRun_AnyFileEx (*C function*), 43
PyRun_AnyFileExFlags (*C function*), 43
PyRun_AnyFileFlags (*C function*), 43
PyRun_File (*C function*), 45
PyRun_FileEx (*C function*), 45
PyRun_FileExFlags (*C function*), 45
PyRun_FileFlags (*C function*), 45
PyRun_InteractiveLoop (*C function*), 44
PyRun_InteractiveLoopFlags (*C function*), 44
PyRun_InteractiveOne (*C function*), 44
PyRun_InteractiveOneFlags (*C function*), 44
PyRun_SimpleFile (*C function*), 44
PyRun_SimpleFileEx (*C function*), 44
PyRun_SimpleFileExFlags (*C function*), 44
PyRun_SimpleString (*C function*), 43
PyRun_SimpleStringFlags (*C function*), 43
PyRun_String (*C function*), 45
PyRun_StringFlags (*C function*), 45
PySendResult (*C type*), 127
PySeqIter_Check (*C function*), 211
PySeqIter_New (*C function*), 211
PySeqIter_Type (*C var*), 211
PySequence_Check (*C function*), 123
PySequence_Concat (*C function*), 123
PySequence_Contains (*C function*), 124
PySequence_Count (*C function*), 123
PySequence_DelItem (*C function*), 123
PySequence_DelSlice (*C function*), 123
PySequence_Fast (*C function*), 124
PySequence_Fast_GET_ITEM (*C function*), 124
PySequence_Fast_GET_SIZE (*C function*), 124
PySequence_Fast_ITEMS (*C function*), 124
PySequence_GetItem (*C function*), 9, 123
PySequence_GetSlice (*C function*), 123
PySequence_In (*C function*), 124
PySequence_Index (*C function*), 124
PySequence_InPlaceConcat (*C function*), 123
PySequence_InPlaceRepeat (*C function*), 123
PySequence_ITEM (*C function*), 124
PySequence_Length (*C function*), 123
PySequence_List (*C function*), 124
PySequence_Repeat (*C function*), 123
PySequence_SetItem (*C function*), 123
PySequence_SetSlice (*C function*), 123
PySequence_Size (*C function*), 123
PySequence_Tuple (*C function*), 124
PySequenceMethods (*C type*), 346
PySequenceMethods.sq_ass_item (*C member*), 346
PySequenceMethods.sq_concat (*C member*), 346
PySequenceMethods.sq_contains (*C member*), 346
PySequenceMethods.sq_inplace_concat (*C member*), 346
PySequenceMethods.sq_inplace_repeat (*C member*), 346
PySequenceMethods.sq_item (*C member*), 346
PySequenceMethods.sq_length (*C member*), 346
PySequenceMethods.sq_repeat (*C member*), 346
PySet_Add (*C function*), 192
PySet_Check (*C function*), 191
PySet_CheckExact (*C function*), 191
PySet_Clear (*C function*), 192
PySet_Contains (*C function*), 192
PySet_Discard (*C function*), 192
PySet_GET_SIZE (*C function*), 192
PySet_New (*C function*), 191
PySet_Pop (*C function*), 192
PySet_Size (*C function*), 192
PySet_Type (*C var*), 191
PySetObject (*C type*), 191
PySignal_SetWakeupFd (*C function*), 61
PySlice_AdjustIndices (*C function*), 213
PySlice_Check (*C function*), 212
PySlice_GetIndices (*C function*), 212
PySlice_GetIndicesEx (*C function*), 212
PySlice_New (*C function*), 212
PySlice_Type (*C var*), 212
PySlice_Unpack (*C function*), 213
PyState_AddModule (*C function*), 210
PyState_FindModule (*C function*), 210
PyState_RemoveModule (*C function*), 211
PyStatus (*C type*), 264
PyStatus_Error (*C function*), 264
PyStatus_Exception (*C function*), 264
PyStatus_Exit (*C function*), 264
PyStatus_IsError (*C function*), 265
PyStatus_IsExit (*C function*), 265
PyStatus_NoMemory (*C function*), 264
PyStatus_Ok (*C function*), 264
PyStatus.err_msg (*C member*), 264
PyStatus.exitcode (*C member*), 264
PyStatus.func (*C member*), 264
PyStructSequence_Desc (*C type*), 183
PyStructSequence_Desc.doc (*C member*), 183
PyStructSequence_Desc.fields (*C member*), 183
PyStructSequence_Desc.n_in_sequence (*C member*), 183
PyStructSequence_Desc.name (*C member*), 183
PyStructSequence_Field (*C type*), 183
PyStructSequence_Field.doc (*C member*), 183
PyStructSequence_Field.name (*C member*), 183
PyStructSequence_GET_ITEM (*C function*), 183
PyStructSequence_GetItem (*C function*), 183
PyStructSequence_InitType (*C function*), 182
PyStructSequence_InitType2 (*C function*), 182
PyStructSequence_New (*C function*), 183

PyStructSequence_NewType (*C function*), 182
PyStructSequence_SET_ITEM (*C function*), 184
PyStructSequence_SetItem (*C function*), 183
PyStructSequence_UnnamedField (*C var*), 183
PySys_AddAuditHook (*C function*), 81
PySys_Audit (*C function*), 81
PySys_AuditTuple (*C function*), 81
PySys_FormatStderr (*C function*), 81
PySys_FormatStdout (*C function*), 81
PySys_GetObject (*C function*), 80
PySys_GetXOptions (*C function*), 81
PySys_ResetWarnOptions (*C function*), 80
PySys_SetArgv (*C function*), 236
PySys_SetArgvEx (*C function*), 236
PySys_SetObject (*C function*), 80
PySys_WriteStderr (*C function*), 81
PySys_WriteStdout (*C function*), 80
Python 3000, **380**
Python Geliştirme Önerileri
    PEP 1, 380
    PEP 7, 3, 6
    PEP 238, 373
    PEP 278, 384
    PEP 302, 377
    PEP 343, 370
    PEP 353, 10
    PEP 362, 368, 379
    PEP 383, 168, 169
    PEP 387, 15, 16
    PEP 393, 159
    PEP 411, 380
    PEP 420, 378, 380
    PEP 442, 302, 342
    PEP 443, 374
    PEP 446, 80
    PEP 451, 205
    PEP 456, 98
    PEP 483, 374
    PEP 484, 367, 373, 374, 383, 384
    PEP 489, 73, 74, 246
    PEP 492, 368, 369, 371
    PEP 498, 372
    PEP 519, 380
    PEP 523, 219, 244, 245
    PEP 525, 368
    PEP 526, 367, 384
    PEP 528, 230, 274
    PEP 529, 169, 230
    PEP 538, 282
    PEP 539, 252
    PEP 540, 282
    PEP 552, 271
    PEP 554, 248
    PEP 578, 81
    PEP 585, 374
    PEP 587, 263
    PEP 590, 115
    PEP 623, 159
    PEP 0626#out-of-process-debuggers-and-profilers, 197
    PEP 634, 329
    PEP 649, 367
    PEP 667, 99, 219
    PEP 0683, 50, 375
    PEP 684, 240, 248
    PEP 703, 373, 374
    PEP 741, 257
    PEP 3116, 384
    PEP 3119, 110
    PEP 3121, 204
    PEP 3147, 85
    PEP 3151, 69
    PEP 3155, 381
PYTHON_ABI_VERSION (*C macro*), 207
PYTHON_API_VERSION (*C macro*), 207
PYTHON_CPU_COUNT, 274
PYTHON_FROZEN_MODULES, 273
PYTHON_GIL, 374
PYTHON_PERF_JIT_SUPPORT, 278
PYTHON_PRESITE, 277
PYTHONCOERCECLOCALE, 282
PYTHONDEBUG, 229, 276
PYTHONDEVMODE, 271
PYTHONDONTWRITEBYTECODE, 229, 279
PYTHONDUMPREFS, 271
PYTHONDUMPREFSFILE, 271
PYTHONEXECUTABLE, 276
PYTHONFAULTHANDLER, 272
PYTHONHASHSEED, 229, 273
PYTHONHOME, 12, 229, 237, 273
PYTHONINSPECT, 229, 273
PYTHONINTMAXSTRDIGITS, 274
PYTHONIOENCODING, 277
Pythonic, **380**
PYTHONLEGACYWINDOWSFSENCODING, 230, 267
PYTHONLEGACYWINDOWSSTDIO, 230, 274
PYTHONMALLOC, 286, 290, 292, 293
PYTHONMALLOCSTATS, 274, 286
PYTHONNODEBUGRANGES, 271
PYTHONNOUSERSITE, 230, 279
PYTHONOPTIMIZE, 230, 275
PYTHONPATH, 12, 229, 275
PYTHONPERFSUPPORT, 278
PYTHONPLATLIBDIR, 274
PYTHONPROFILEIMPORTTIME, 273
PYTHONPYCACHEPREFIX, 276
PYTHONSAFEPATH, 270
PYTHONTRACEMALLOC, 278
Python'un Zen'i, **384**
PYTHONUNBUFFERED, 231, 270
PYTHONUTF8, 267, 282
PYTHONVERBOSE, 231, 279
PYTHONWARNINGS, 279
PyThread_create_key (*C function*), 253
PyThread_delete_key (*C function*), 253
PyThread_delete_key_value (*C function*), 254

PyThread_get_key_value (*C function*), 254
PyThread_ReInitTLS (*C function*), 254
PyThread_set_key_value (*C function*), 253
PyThread_tss_alloc (*C function*), 252
PyThread_tss_create (*C function*), 253
PyThread_tss_delete (*C function*), 253
PyThread_tss_free (*C function*), 252
PyThread_tss_get (*C function*), 253
PyThread_tss_is_created (*C function*), 253
PyThread_tss_set (*C function*), 253
PyThreadState (*C type*), 237, 240
PyThreadState_Clear (*C function*), 243
PyThreadState_Delete (*C function*), 243
PyThreadState_DeleteCurrent (*C function*), 243
PyThreadState_EnterTracing (*C function*), 244
PyThreadState_Get (*C function*), 241
PyThreadState_GetDict (*C function*), 245
PyThreadState_GetFrame (*C function*), 243
PyThreadState_GetID (*C function*), 243
PyThreadState_GetInterpreter (*C function*), 243
PyThreadState_GetUnchecked (*C function*), 241
PyThreadState_LeaveTracing (*C function*), 244
PyThreadState_New (*C function*), 243
PyThreadState_Next (*C function*), 252
PyThreadState_SetAsyncExc (*C function*), 245
PyThreadState_Swap (*C function*), 241
PyThreadState.interp (*C member*), 240
PyTime_AsSecondsDouble (*C function*), 103
PyTime_Check (*C function*), 223
PyTime_CheckExact (*C function*), 223
PyTime_FromTime (*C function*), 224
PyTime_FromTimeAndFold (*C function*), 224
PyTime_MAX (*C var*), 102
PyTime_MIN (*C var*), 102
PyTime_Monotonic (*C function*), 102
PyTime_MonotonicRaw (*C function*), 103
PyTime_PerfCounter (*C function*), 102
PyTime_PerfCounterRaw (*C function*), 103
PyTime_t (*C type*), 102
PyTime_Time (*C function*), 102
PyTime_TimeRaw (*C function*), 103
PyTimeZone_FromOffset (*C function*), 224
PyTimeZone_FromOffsetAndName (*C function*), 224
PyTrace_C_CALL (*C var*), 250
PyTrace_C_EXCEPTION (*C var*), 250
PyTrace_C_RETURN (*C var*), 250
PyTrace_CALL (*C var*), 249
PyTrace_EXCEPTION (*C var*), 250
PyTrace_LINE (*C var*), 250
PyTrace_OPCODE (*C var*), 250
PyTrace_RETURN (*C var*), 250
PyTraceMalloc_Track (*C function*), 294
PyTraceMalloc_Untrack (*C function*), 294
PyTuple_Check (*C function*), 181
PyTuple_CheckExact (*C function*), 181
PyTuple_GET_ITEM (*C function*), 181
PyTuple_GET_SIZE (*C function*), 181
PyTuple_GetItem (*C function*), 181
PyTuple_GetSlice (*C function*), 181
PyTuple_New (*C function*), 181
PyTuple_Pack (*C function*), 181
PyTuple_SET_ITEM (*C function*), 182
PyTuple_SetItem (*C function*), 7, 182
PyTuple_Size (*C function*), 181
PyTuple_Type (*C var*), 181
PyTupleObject (*C type*), 181
PyType_AddWatcher (*C function*), 136
PyType_Check (*C function*), 135
PyType_CheckExact (*C function*), 135
PyType_ClearCache (*C function*), 135
PyType_ClearWatcher (*C function*), 136
PyType_Freeze (*C function*), 140
PyType_FromMetaclass (*C function*), 139
PyType_FromModuleAndSpec (*C function*), 139
PyType_FromSpec (*C function*), 140
PyType_FromSpecWithBases (*C function*), 140
PyType_GenericAlloc (*C function*), 137
PyType_GenericNew (*C function*), 137
PyType_GetBaseByToken (*C function*), 138
PyType_GetDict (*C function*), 136
PyType_GetFlags (*C function*), 135
PyType_GetFullyQualifiedName (*C function*), 137
PyType_GetModule (*C function*), 138
PyType_GetModuleByDef (*C function*), 138
PyType_GetModuleName (*C function*), 137
PyType_GetModuleState (*C function*), 138
PyType_GetName (*C function*), 137
PyType_GetQualName (*C function*), 137
PyType_GetSlot (*C function*), 138
PyType_GetTypeDataSize (*C function*), 112
PyType_HasFeature (*C function*), 136
PyType_IS_GC (*C function*), 136
PyType_IsSubtype (*C function*), 137
PyType_Modified (*C function*), 136
PyType_Ready (*C function*), 137
PyType_Slot (*C type*), 141
PyType_Slot.pfunc (*C member*), 141
PyType_Slot.slot (*C member*), 141
PyType_Spec (*C type*), 140
PyType_Spec.basicsize (*C member*), 140
PyType_Spec.flags (*C member*), 141
PyType_Spec.itemsize (*C member*), 140
PyType_Spec.name (*C member*), 140
PyType_Spec.slots (*C member*), 141
PyType_Type (*C var*), 135
PyType_Watch (*C function*), 136
PyType_WatchCallback (*C type*), 136
PyTypeObject (*C type*), 135
PyTypeObject.tp_alloc (*C member*), 338
PyTypeObject.tp_as_async (*C member*), 323
PyTypeObject.tp_as_buffer (*C member*), 325
PyTypeObject.tp_as_mapping (*C member*), 324
PyTypeObject.tp_as_number (*C member*), 324
PyTypeObject.tp_as_sequence (*C member*), 324
PyTypeObject.tp_base (*C member*), 335
PyTypeObject.tp_bases (*C member*), 339

PyTypeObject.tp_basicsize (*C member*), 319
PyTypeObject.tp_cache (*C member*), 339
PyTypeObject.tp_call (*C member*), 324
PyTypeObject.tp_clear (*C member*), 331
PyTypeObject.tp_dealloc (*C member*), 320
PyTypeObject.tp_del (*C member*), 340
PyTypeObject.tp_descr_get (*C member*), 336
PyTypeObject.tp_descr_set (*C member*), 336
PyTypeObject.tp_dict (*C member*), 336
PyTypeObject.tp_dictoffset (*C member*), 337
PyTypeObject.tp_doc (*C member*), 330
PyTypeObject.tp_finalize (*C member*), 340
PyTypeObject.tp_flags (*C member*), 325
PyTypeObject.tp_free (*C member*), 338
PyTypeObject.tp_getattr (*C member*), 323
PyTypeObject.tp_getattro (*C member*), 325
PyTypeObject.tp_getset (*C member*), 335
PyTypeObject.tp_hash (*C member*), 324
PyTypeObject.tp_init (*C member*), 337
PyTypeObject.tp_is_gc (*C member*), 339
PyTypeObject.tp_itemsize (*C member*), 319
PyTypeObject.tp_iter (*C member*), 335
PyTypeObject.tp_iternext (*C member*), 335
PyTypeObject.tp_members (*C member*), 335
PyTypeObject.tp_methods (*C member*), 335
PyTypeObject.tp_mro (*C member*), 339
PyTypeObject.tp_name (*C member*), 319
PyTypeObject.tp_new (*C member*), 338
PyTypeObject.tp_repr (*C member*), 323
PyTypeObject.tp_richcompare (*C member*), 333
PyTypeObject.tp_setattr (*C member*), 323
PyTypeObject.tp_setattro (*C member*), 325
PyTypeObject.tp_str (*C member*), 324
PyTypeObject.tp_subclasses (*C member*), 339
PyTypeObject.tp_traverse (*C member*), 330
PyTypeObject.tp_vectorcall (*C member*), 342
PyTypeObject.tp_vectorcall_offset (*C member*), 322
PyTypeObject.tp_version_tag (*C member*), 340
PyTypeObject.tp_watched (*C member*), 343
PyTypeObject.tp_weaklist (*C member*), 340
PyTypeObject.tp_weaklistoffset (*C member*), 334
PyTZInfo_Check (*C function*), 224
PyTZInfo_CheckExact (*C function*), 224
PyUnicode_1BYTE_DATA (*C function*), 160
PyUnicode_1BYTE_KIND (*C macro*), 160
PyUnicode_2BYTE_DATA (*C function*), 160
PyUnicode_2BYTE_KIND (*C macro*), 160
PyUnicode_4BYTE_DATA (*C function*), 160
PyUnicode_4BYTE_KIND (*C macro*), 160
PyUnicode_Append (*C function*), 166
PyUnicode_AppendAndDel (*C function*), 166
PyUnicode_AsASCIIString (*C function*), 174
PyUnicode_AsCharmapString (*C function*), 175
PyUnicode_AsEncodedString (*C function*), 171
PyUnicode_AsLatin1String (*C function*), 174
PyUnicode_AsMBCSString (*C function*), 175
PyUnicode_AsRawUnicodeEscapeString (*C function*), 174
PyUnicode_AsUCS4 (*C function*), 167
PyUnicode_AsUCS4Copy (*C function*), 168
PyUnicode_AsUnicodeEscapeString (*C function*), 173
PyUnicode_AsUTF8 (*C function*), 172
PyUnicode_AsUTF8AndSize (*C function*), 171
PyUnicode_AsUTF8String (*C function*), 171
PyUnicode_AsUTF16String (*C function*), 173
PyUnicode_AsUTF32String (*C function*), 172
PyUnicode_AsWideChar (*C function*), 170
PyUnicode_AsWideCharString (*C function*), 170
PyUnicode_BuildEncodingMap (*C function*), 166
PyUnicode_Check (*C function*), 160
PyUnicode_CHECK_INTERNED (*C function*), 178
PyUnicode_CheckExact (*C function*), 160
PyUnicode_Compare (*C function*), 177
PyUnicode_CompareWithASCIIString (*C function*), 178
PyUnicode_Concat (*C function*), 176
PyUnicode_Contains (*C function*), 178
PyUnicode_CopyCharacters (*C function*), 167
PyUnicode_Count (*C function*), 177
PyUnicode_DATA (*C function*), 160
PyUnicode_Decode (*C function*), 171
PyUnicode_DecodeASCII (*C function*), 174
PyUnicode_DecodeCharmap (*C function*), 174
PyUnicode_DecodeCodePageStateful (*C function*), 175
PyUnicode_DecodeFSDefault (*C function*), 169
PyUnicode_DecodeFSDefaultAndSize (*C function*), 169
PyUnicode_DecodeLatin1 (*C function*), 174
PyUnicode_DecodeLocale (*C function*), 168
PyUnicode_DecodeLocaleAndSize (*C function*), 168
PyUnicode_DecodeMBCS (*C function*), 175
PyUnicode_DecodeMBCSStateful (*C function*), 175
PyUnicode_DecodeRawUnicodeEscape (*C function*), 174
PyUnicode_DecodeUnicodeEscape (*C function*), 173
PyUnicode_DecodeUTF7 (*C function*), 173
PyUnicode_DecodeUTF7Stateful (*C function*), 173
PyUnicode_DecodeUTF8 (*C function*), 171
PyUnicode_DecodeUTF8Stateful (*C function*), 171
PyUnicode_DecodeUTF16 (*C function*), 173
PyUnicode_DecodeUTF16Stateful (*C function*), 173
PyUnicode_DecodeUTF32 (*C function*), 172
PyUnicode_DecodeUTF32Stateful (*C function*), 172
PyUnicode_EncodeCodePage (*C function*), 175
PyUnicode_EncodeFSDefault (*C function*), 169
PyUnicode_EncodeLocale (*C function*), 168
PyUnicode_Equal (*C function*), 177
PyUnicode_EqualToUTF8 (*C function*), 178

PyUnicode_EqualToUTF8AndSize (*C function*), 177
PyUnicode_Fill (*C function*), 167
PyUnicode_Find (*C function*), 176
PyUnicode_FindChar (*C function*), 177
PyUnicode_Format (*C function*), 178
PyUnicode_FromEncodedObject (*C function*), 166
PyUnicode_FromFormat (*C function*), 163
PyUnicode_FromFormatV (*C function*), 166
PyUnicode_FromKindAndData (*C function*), 163
PyUnicode_FromObject (*C function*), 166
PyUnicode_FromOrdinal (*C function*), 166
PyUnicode_FromString (*C function*), 163
PyUnicode_FromStringAndSize (*C function*), 163
PyUnicode_FromWideChar (*C function*), 170
PyUnicode_FSConverter (*C function*), 169
PyUnicode_FSDecoder (*C function*), 169
PyUnicode_GET_LENGTH (*C function*), 160
PyUnicode_GetDefaultEncoding (*C function*), 166
PyUnicode_GetLength (*C function*), 166
PyUnicode_InternFromString (*C function*), 178
PyUnicode_InternInPlace (*C function*), 178
PyUnicode_IS_ASCII (*C function*), 161
PyUnicode_IS_READY (*C function*), 181
PyUnicode_IsIdentifier (*C function*), 161
PyUnicode_Join (*C function*), 176
PyUnicode_KIND (*C function*), 160
PyUnicode_MAX_CHAR_VALUE (*C function*), 161
PyUnicode_New (*C function*), 163
PyUnicode_Partition (*C function*), 176
PyUnicode_READ (*C function*), 161
PyUnicode_READ_CHAR (*C function*), 161
PyUnicode_ReadChar (*C function*), 167
PyUnicode_READY (*C function*), 180
PyUnicode_Replace (*C function*), 177
PyUnicode_Resize (*C function*), 167
PyUnicode_RichCompare (*C function*), 178
PyUnicode_RPartition (*C function*), 176
PyUnicode_RSplit (*C function*), 176
PyUnicode_Split (*C function*), 176
PyUnicode_Splitlines (*C function*), 176
PyUnicode_Substring (*C function*), 167
PyUnicode_Tailmatch (*C function*), 176
PyUnicode_Translate (*C function*), 175
PyUnicode_Type (*C var*), 159
PyUnicode_WRITE (*C function*), 161
PyUnicode_WriteChar (*C function*), 167
PyUnicodeDecodeError_Create (*C function*), 63
PyUnicodeDecodeError_GetEncoding (*C function*), 63
PyUnicodeDecodeError_GetEnd (*C function*), 64
PyUnicodeDecodeError_GetObject (*C function*), 63
PyUnicodeDecodeError_GetReason (*C function*), 64
PyUnicodeDecodeError_GetStart (*C function*), 63
PyUnicodeDecodeError_SetEnd (*C function*), 64
PyUnicodeDecodeError_SetReason (*C function*), 64
PyUnicodeDecodeError_SetStart (*C function*), 63
PyUnicodeEncodeError_GetEncoding (*C function*), 63
PyUnicodeEncodeError_GetEnd (*C function*), 64
PyUnicodeEncodeError_GetObject (*C function*), 63
PyUnicodeEncodeError_GetReason (*C function*), 64
PyUnicodeEncodeError_GetStart (*C function*), 63
PyUnicodeEncodeError_SetEnd (*C function*), 64
PyUnicodeEncodeError_SetReason (*C function*), 64
PyUnicodeEncodeError_SetStart (*C function*), 63
PyUnicodeIter_Type (*C var*), 159
PyUnicodeObject (*C type*), 160
PyUnicodeTranslateError_GetEnd (*C function*), 64
PyUnicodeTranslateError_GetObject (*C function*), 63
PyUnicodeTranslateError_GetReason (*C function*), 64
PyUnicodeTranslateError_GetStart (*C function*), 63
PyUnicodeTranslateError_SetEnd (*C function*), 64
PyUnicodeTranslateError_SetReason (*C function*), 64
PyUnicodeTranslateError_SetStart (*C function*), 63
PyUnicodeWriter (*C type*), 179
PyUnicodeWriter_Create (*C function*), 179
PyUnicodeWriter_DecodeUTF8Stateful (*C function*), 180
PyUnicodeWriter_Discard (*C function*), 179
PyUnicodeWriter_Finish (*C function*), 179
PyUnicodeWriter_Format (*C function*), 180
PyUnicodeWriter_WriteASCII (*C function*), 179
PyUnicodeWriter_WriteChar (*C function*), 179
PyUnicodeWriter_WriteRepr (*C function*), 180
PyUnicodeWriter_WriteStr (*C function*), 180
PyUnicodeWriter_WriteSubstring (*C function*), 180
PyUnicodeWriter_WriteUCS4 (*C function*), 180
PyUnicodeWriter_WriteUTF8 (*C function*), 179
PyUnicodeWriter_WriteWideChar (*C function*), 179
PyUnstable, 15
PyUnstable_AtExit (*C function*), 233
PyUnstable_Code_GetExtra (*C function*), 201
PyUnstable_Code_GetFirstFree (*C function*), 196
PyUnstable_Code_New (*C function*), 197
PyUnstable_Code_NewWithPosOnlyArgs (*C function*), 197
PyUnstable_Code_SetExtra (*C function*), 201
PyUnstable_EnableTryIncRef (*C function*), 114
PyUnstable_Eval_RequestCodeExtraIndex (*C function*), 201
PyUnstable_Exc_PrepReraiseStar (*C function*),

63
PyUnstable_GC_VisitObjects (*C function*), 356
PyUnstable_InterpreterFrame_GetCode (*C function*), 219
PyUnstable_InterpreterFrame_GetLasti (*C function*), 219
PyUnstable_InterpreterFrame_GetLine (*C function*), 219
PyUnstable_IsImmortal (*C function*), 113
PyUnstable_Long_CompactValue (*C function*), 150
PyUnstable_Long_IsCompact (*C function*), 150
PyUnstable_Module_SetGIL (*C function*), 210
PyUnstable_Object_ClearWeakRefsNoCallbacks (*C function*), 215
PyUnstable_Object_EnableDeferredRefcount (*C function*), 112
PyUnstable_Object_GC_NewWithExtraData (*C function*), 353
PyUnstable_Object_IsUniquelyReferenced (*C function*), 115
PyUnstable_Object_IsUniqueReferencedTemporary (*C function*), 112
PyUnstable_PerfMapState_Fini (*C function*), 104
PyUnstable_PerfMapState_Init (*C function*), 103
PyUnstable_TryIncRef (*C function*), 113
PyUnstable_Type_AssignVersionTag (*C function*), 138
PyUnstable_WritePerfMapEntry (*C function*), 103
PyVarObject (*C type*), 303
PyVarObject_HEAD_INIT (*C macro*), 305
PyVarObject.ob_size (*C member*), 303
PyVectorcall_Call (*C function*), 117
PyVectorcall_Function (*C function*), 117
PyVectorcall_NARGS (*C function*), 116
PyWeakref_Check (*C function*), 214
PyWeakref_CheckProxy (*C function*), 214
PyWeakref_CheckRef (*C function*), 214
PyWeakref_GET_OBJECT (*C function*), 215
PyWeakref_GetObject (*C function*), 214
PyWeakref_GetRef (*C function*), 214
PyWeakref_IsDead (*C function*), 215
PyWeakref_NewProxy (*C function*), 214
PyWeakref_NewRef (*C function*), 214
PyWideStringList (*C type*), 264
PyWideStringList_Append (*C function*), 264
PyWideStringList_Insert (*C function*), 264
PyWideStringList.items (*C member*), 264
PyWideStringList.length (*C member*), 264
PyWrapper_New (*C function*), 212

R

READ_RESTRICTED (*C macro*), 310
READONLY (*C macro*), 310
realloc (*C function*), 285
referans sayısı, **381**
releasebufferproc (*C type*), 349
REPL, **381**
repr
    built-in function, 109, 323
reprfunc (*C type*), 349
RESTRICTED (*C macro*), 310
richcmpfunc (*C type*), 349

S

sanal makine, **384**
sanal ortam, **384**
search
    path, module, 12, 231, 235
sendfunc (*C type*), 350
sequence
    object, 156
set
    object, 191
set_all(), 8
setattrfunc (*C type*), 349
setattrofunc (*C type*), 349
setswitchinterval (*in module sys*), 237
setter (*C type*), 312
SIGINT (*C macro*), 61
sınıf, **370**
sınıf değişkeni, **370**
SIZE_MAX (*C macro*), 145
signal
    module, 61
sihirli yöntem, **377**
soft deprecated, **382**
soyut temel sınıf, **367**
sözlük, **371**
sözlük anlama, **371**
sözlük görünümü, **372**
special
    metot, 382
ssizeargfunc (*C type*), 350
ssizeobjargproc (*C type*), 350
standard library, **382**
static type checker, **382**
staticmethod
    built-in function, 307
stderr (*in module sys*), 246, 247
stdin (*in module sys*), 246, 247
stdlib, **382**
stdout (*in module sys*), 246, 247
strerror (*C function*), 55
string
    PyObject_Str (*C function*), 109
structmember.h, 312
sum_list(), 9
sum_sequence(), 9, 10
sürekli paketleme, **381**
sys
    module, 12, 231, 246, 247
SystemError (*built-in exception*), 203, 204

T

t-string, **382**
t-strings, **382**

T_BOOL (*C macro*), 312
T_BYTE (*C macro*), 312
T_CHAR (*C macro*), 312
T_DOUBLE (*C macro*), 312
T_FLOAT (*C macro*), 312
T_INT (*C macro*), 312
T_LONG (*C macro*), 312
T_LONGLONG (*C macro*), 312
T_NONE (*C macro*), 312
T_OBJECT (*C macro*), 312
T_OBJECT_EX (*C macro*), 312
T_PYSSIZET (*C macro*), 312
T_SHORT (*C macro*), 312
T_STRING (*C macro*), 312
T_STRING_INPLACE (*C macro*), 312
T_UBYTE (*C macro*), 312
T_UINT (*C macro*), 312
T_ULONG (*C macro*), 312
T_ULONGULONG (*C macro*), 312
T_USHORT (*C macro*), 312
tanımlayıcı, **371**
tek sevk, **382**
tercüman kapatma, **375**
ternaryfunc (*C type*), 350
thread state, **383**
tip, **383**
tip takma adı, **383**
token, **383**
traverseproc (*C type*), 355
tuple
    built-in function, 124, 186
    object, 181
tür ipucu, **383**
type
    built-in function, 110
    object, 6, 135

U

ULONG_MAX (*C macro*), 145
unaryfunc (*C type*), 349
USE_STACKCHECK (*C macro*), 78
uzatma modülü, **372**

Ü

üç tırnaklı dize, **383**

V

vectorcallfunc (*C type*), 116
version (*in module sys*), 235, 236
visitproc (*C type*), 355

W

walrus operator, **384**
WRITE_RESTRICTED (*C macro*), 310

Y

yazı çözümleme, **382**
yazı dosyası, **382**
yeni stil sınıf, **378**
yerel kodlama, **377**
yıkanabilir, **374**
yinelenebilir, **375**
yineleyici, **376**
yol benzeri nesne, **380**
yol giriş kancası, **380**
yol girişi, **379**
yol girişi bulucu, **379**
yol tabanlı bulucu, **380**
yorumlanmış, **375**
yükleyici, **377**